## **Test Your Persistence Layer**

Spring provides you a small but interesting set of tools that help you start only your persistence layer or the entire application, manage transactions in your test cases, and prefill your database with a set of test data.

## **Define your Test**

If you annotate your test class with @SpringBootTest, your entire application with all dependencies and its standard configuration will get started before your test gets executed.

If you annotate your test class with @DataJpaTest, you only start the parts of your application that are relevant for JPA. These are the repository implementations and the configuration and instantiation of the EntityManager and your DataSource.

By default, the @DataJpaTest replaces your database with an inmemory database. You can avoid this replacement by annotating your class with @AutoConfigureTestDatabase and setting the replace attribute to NONE.

## **Managing Transactions**

All tests annotated with @DataJpaTest automatically manage a transactional context. By default, they start a transaction before executing the test case and roll it back afterward.

You can change that by annotating your test classes or methods with with @Commit or with @Rollback(false).