

Genesys Administrator Extension

Deployment Guide

Genesys Administrator 8.5.2

### **Table of Contents**

Genesys Administrator Extension Deployment Guide	5
Overview	5
Solution Deployment	9
Operational Parameter Management	11
Audio Resource Management	12
Configuration Object Management	13
Auditing	14
Architecture	14
Database Size Requirements	18
Setting Up Genesys Administrator Extension	20
Deploying Genesys Administrator Extension	23
Configuring GAX Properties	51
Coordinating Simultaneous Changes to Data	54
Configuring ADDP Connections	55
Prerequisites for Genesys Administrator Extension Modules	56
Configuring System Security	66
Configuring the Auditing Feature	79
Plug-ins	81
Managing Plug-ins	82
Upgrading GAX	90
Customizing the GAX Homepage	96
Cleaning the GAX Database After a Tenant is Deleted	97
Accessing Genesys Administrator Extension	99
Logging In	99
Logging In Remotely	101
Logging In to Genesys Administrator from GAX	102
Logging Out	103
Starting and Stopping GAX	103
Troubleshooting	5
Plug-in Issues	105

Required Permissions	105
Deployment Issues	106
Running Out of Memory	106
Tomcat Issues	107
Browser Issues	108
Role Privileges	111
General	111
GA Direct Login Integration	112
Operational Parameter Management	11
Solution Deployment	9
Configuration Object Management	13
Agent Management	142
Bulk Operations	143
Audio Resources Management—Tenant	0
Audio Resources Management—System	0
Centralized Log	145
Configuration Options	147
Mandatory Options	148
general Section	148
security Section	151
asd Section	152
arm Section	153
ga Section	156
log Section	157
clog Section	161
opm Section	162
Product Alert	163
Change History	165

#### Genesys Administrator Extension Deployment Guide

Genesys Administrator Extension (GAX), part of the Genesys Framework, is a web-based graphical user interface (GUI) that provides advanced administrative and operational functionality that is targeted to Hosted Service Providers as well as Enterprise customers.

This document contains the following information:

#### **Overview**

Solution Deployment Configuration Object Management Architecture

#### **Setting up GAX**

Deployment Task Summary Managing Plug-ins Upgrading GAX

#### **Accessing GAX**

Logging In Logging in to Genesys Administrator from GAX

#### **Troubleshooting**

Including:

Required Permissions Memory Issues Browser Issues

#### **GAX Role Privileges**

Including:

Operational Parameter Management Solution Deployment Configuration Object Management

---

#### **GAX Configuration Options**

Including:

general Section arm Section log Section

...

#### Overview

This chapter provides a brief description of Genesys Administrator Extension and its architecture.

This chapter contains the following sections:

- Genesys Administrator Extension
- Architecture
- Database Size Requirements

#### **Genesys Administrator Extension**

Genesys Administrator Extension (GAX) is an application that provides advanced administrative capabilities to both technical and business users of Genesys contact centers. Currently, the following GAX core modules are supported:

- Solution Deployment
- · Operational Parameter Management
- Audio Resource Management
- Configuration Object Management
- GAX/Genesys Administrator Single-Sign-on

Genesys Administrator Extension also supports plug-in resources from other Genesys products, such as Pulse and GVP Reporting. Refer to Plug-in Management for more information.

The following subsections describe some of the features of the GAX interface.

#### **Tenant Filtering**

GAX comprises a set of modules that are selected and viewed in a browser interface. Each of the modules enables you to filter the information that you view about the applications that you have configured and deployed in the Genesys environment.

In a multi-tenant environment, GAX enables you to filter your views by a single tenant or by multiple tenants. By default, when you log in the view is of your default tenant. You can use the tenant selector to change the view so that you can view by one or more tenants.

#### Filtering and Sorting Lists and Tables

All lists and tables in the GAX interface can be sorted by clicking on the column headings. Tables and lists can also be filtered by appropriate criteria, for example:

- Tenant
- Date
- Date range
- Name
- Deployed by
- Deployed date

#### **Field Auto-completion**

All fields in the GAX interface that have predefined values support auto-completion. When you start to enter a value in the field, GAX searches for an existing value in the database and completes the entry. You can override auto-completion by continuing to enter the value. You can accept the auto-completion value by pressing **Enter**.

#### Localization

GAX supports the installation of multiple language packs for the user interface. You can choose to configure one default language across all GAX instances, while each user can select a different language. Default and user-specific language selection is done in the Profile menu. See Profile Menu in GAX Help for more information.

You can install language packs by using the plug-in installation procedure. See Installing Plug-ins with the Software Installation Wizard for more information, or refer to the Help pages by clicking the Help button in GAX (also available here).

#### Important

Product translation is limited to contents of this product only. Display data coming from other products might appear in English.

Overview Solution Deployment

#### **Solution Deployment**

Solution Deployment enables you to fully deploy solution definitions and installation packages (IPs) to remote locations. This includes installation and configuration of all of the necessary applications and updates to existing multi-Tenant applications, where appropriate.

Genesys Deployment Agent (GDA) is required to deploy solution definitions and IPs.

#### **Important**

GDA does not support multiple concurrent deployments on the same host. Therefore, multiple users cannot deploy a solution by using GAX on the same host at the same time that GDA is deploying. This limitation has always existed for GDA.

A solution definition consists of none, one, or multiple IPs for Genesys components. For Hosted Provider Edition, the IPs to be deployed must be primarily related to Tenant objects, and should contain object definitions, access permissions, and role privileges.

A solution definition consists of an XML file that defines the steps to install, upgrade, or configure IPs and system configurations to successfully deploy a solution. For information about authoring solution definition files, see Authoring Solution Definitions.

Solution Deployment can make changes to Tenant objects in Configuration Server, perform installations of IPs, or execute external scripts, such as database scripts.

You can also define a list of trusted URLs, called whitelisted hosts, to and from which the IPs are sent and retrieved. Use the **host\_whitelist** and **host\_whitelist\_enabled** options, as described in the security section.

For each deployed solution, from the Deployed Solutions window, you can export a file that contains the properties, summary, and actions for auditing purposes.

#### Important

Not all browsers enable you to use filenames that are not US-ASCII compatible; therefore, Genesys recommends that you use only filenames that are US-ASCII compatible.

Overview Solution Deployment

#### **Defined Privileges**

Roles and their privileges are imported into GAX during the upload of an installation package (IP). All privileges that are defined in the metadata of the IP are imported into the GAX database. Privileges are defined as task elements in the metadata XML of the IP.

#### **Solution Definition File Version Tracking**

During normal use, solution definition files (also called solution package definitions, or SPDs) are added, upgraded, revised, and removed. Solution Deployment supports versioning, auditing, and tracking of changes of SPDs from within the GAX interface. The tracking report can be exported to a CSV file for use outside of GAX.

Solution Deployment enables you to view and access past versions of SPDs. You can also add custom comments and notes to any version.

You can filter and sort the SPD history by one or more of the following criteria:

- Solution—Group results by deployed solutions.
- Tenant—Group results by Tenant and select a subset of a Tenant or Tenants by solution and version.
- Date—Group results by date range.
- Result—Group by successful and failed deployments.

You can generate reports for both individual solutions as well as for individual Tenants.

You can configure the reports by specific criteria, including the following parameters:

- Solution Definition name
- Solution Definition version
- Tenant name
- Profile
- Date deployed
- Deployed by (name of the individual who performed the deployment)
- Result of deployment (Success, Fail, Unknown)
- Latest (true or false)
- Application name (IP Xref)

#### Protection Against External XML Entity Injection Protection

GAX includes XML validation to protect against external XML entity injection. This validation rejects any XML file that includes the external entity definition DOCTYPE.

#### **External Script Support**

Solution Deployment passes arguments to external scripts when executing them, and can receive back results from the execution of a script. For example, if you have a script to create a new virtual host by using the VMware API, you can specify a name or naming convention from within an SPD. You will then receive confirmation that the creation was successful and the name of the new host that was created.

#### **Operational Parameter Management**

Operational Parameter Management enables the creation of parameters that can be used in parameterized routing strategies, in which the values of the parameters are defined at runtime and integrated into the call flow. In most cases, parameter creation and assignment proceeds as follows:

- 1. The Solution Provider defines the parameters by specifying the type of parameter and a name that can be referenced in a strategy.
- 2. The Solution Provider groups parameters into a Parameter Group Template. A parameter can be associated with one or more templates.
- 3. The Solution Provider deploys Parameter Group Templates to one or more Tenants.
- 4. The Tenant administrator, or a user with the appropriate roles and permissions, then enters values for the parameters in the Parameter Group, enabling control of active strategies. Genesys Administrator Extension stores those values in the Configuration Database as part of a Transaction object.
- 5. The Universal Routing Server Application object (or any other interaction routing application, such as GVP) executes a routing strategy to read those values and integrate them into the call flow. Orchestration Server and GVP Media Server Application objects are also supported.

#### **Routing Strategies**

In select cases, a Tenant may create its own routing strategy. The Solution Provider then grants the Tenant permission to define parameters and create the group templates. The Solution Provider must provide the Tenant with all of the required privileges to create parameters, group templates, and deploy groups (refer to Role Privileges).

#### **Parameters**

Operational Parameter Management can be used to update a parameter group after it has been deployed. You can add, remove, re-order, and modify parameters that have already been deployed to a parameter group. All modifications are tracked as part of the audit trail.

Objects and strategies can be associated with specific Parameter Group Templates to ensure that they are not deployed with the incorrect objects or strategies. Operational Parameter Management provides a view of all of the objects and strategies that are associated with a specific Parameter Group so that you know where the objects are used, including information about Tenant ownership and associated applications and scripts.

You can specify the application type or the specific application object for which the Parameter Group Template is compatible. If the type is set, it becomes a permanent attribute of the application. If there are multiple simple-routing-type routing scripts in the system, you can specify that only one matches the Parameter Group Template and is therefore compatible, rather than all scripts of a type.

When you create the Parameter Group Template, you can select an existing application of a particular type to associate the Parameter Group Template with the application. This ensures that the correct applications are deployed at deployment time.

#### **GVP**

Operational Parameter Management can be used to deploy parameters that can be used by Genesys Voice Platform (GVP) and other VXML applications. You can use Operational Parameter Management to deploy a set of parameters to create a new Configuration Layer object that is associated with a specified VXML application that is used by GVP.

#### **Orchestration Applications**

Operational Parameter Management can also be used to deploy parameters that can be used by Orchestration Applications (SCXML).

#### **Audio Resource Management**

Genesys Administrator Extension provides an interface for Audio Resource Management. This enables you to manage audio resources for both announcements and music files. This

module also enables the conversion of audio files (.wav using PCM encoding), and the deployment of audio files to Media Servers throughout the network.

#### **Important**

Audio Resource Management supports only WAV files that use PCM encoding. If you use non-PCM encoded files, there might be conversion artifacts, or the conversion might fail completely.

You can create Personalities to help you organize which files belong to a particular speaker. For example, you might have a personality called <code>John</code> that uses dialog spoken in English by a male speaker. Or, you might have a personality called <code>Marie</code> that uses dialog spoken in French by a female speaker.

You can upload two types of audio resources:

- Announcements—These are files that contain spoken dialog that will be played for customers. For example, you might have an announcement file that tells customers about your business hours.
- Music—These are files that play music for customers. For example, you might have a music file that plays music for customers who are about to be transferred to an Agent.

The **Audio Resources** window in Genesys Administrator Extension (GAX) is a unified list of your personalities and audio resources. For each audio resource, GAX displays the following:

- A logo to indicate whether the file has been designated as Announcement or Music.
- The name of the audio resource.
- The Audio Resource ID (ARID).
- Additional columns, one for each personality, to indicate which personality is using this audio resource.

#### **Configuration Object Management**

Configuration Object Management is responsible for the general management of configuration objects on your system.

Overview Auditing

#### **Configuration Manager**

The **Configuration Manager** window enables the creation and management of system-level configuration objects such as Alarm Conditions, Business Attributes, Hosts, and more. Refer to the Configuration Manager topic in the Genesys Administrator Extension Help for more information.

#### **Agents Window**

The Agents window consolidates all aspects of agent management into a streamlined interface. From one window, you can:

- create agents and their associated objects such as Agent Logins, DNs, and Places.
- edit agent information.
- copy, delete, and enable/disable agents, one at a time or in bulk.

Refer to the Agents topic in the Genesys Administrator Extension Help for more information.

#### **Auditing**

The auditing feature writes data to Message Server about activities in Operational Parameter Management and Solution Definitions, and Message Server writes the data to the Genesys Log database. Auditing data is made available to the GAX user by selecting the **History** option in the **Related** menu in the panel of certain items in the GAX user interface. The auditing feature reads the information from the Log database and enables you to view the change history of objects such as Personalities and Parameter Groups.

See Configuring the Auditing Feature for more information.

#### **Architecture**

This section describes the architecture of Genesys Administrator Extension as it resides in the User Interface Layer of the Genesys Framework, and the architecture and connections within a Genesys Administrator Extension configuration.


#### **User Interface Layer**

Genesys Administrator Extension resides in the User Interaction Layer of the Genesys Framework. This Layer provides comprehensive user interfaces to:

Overview Architecture

- · Configure, monitor, and control the management environment.
- Perform specific tasks related to Solution Deployment, Operational Parameter Management, Audio Resource Management, and Account Management.

The figure below illustrates how the User Interaction Layer is positioned within the Framework architecture.



Framework Architecture

Refer to the Framework Deployment Guide for more information about Framework architecture as a whole.

#### **Functions**

The User Interaction Layer provides centralized web-based functionality and interfaces for the following:

- Remote deployment of Genesys components by using the Genesys Deployment Agent (a Management Layer component).
- Configuration, monitoring, and control of applications and solutions.

Overview Architecture

#### **Architecture**

The browser-based Genesys Administrator Extension includes a comprehensive user interface to perform tasks that are related to Solution Deployment, Operational Parameter Management, Audio Resource Management, and Configuration Object Management.

Currently, Genesys Administrator and Genesys Administrator Extension are the only components in the User Interaction Layer.

#### Genesys Administrator Extension:

- Communicates with the Configuration Server (a Configuration Layer component) to exchange configuration data.
- Communicates with the Solution Control Server (a Management Layer component) to exchange status, operations, and control information.
- Depending on the solutions that are deployed in the system, Genesys Administrator Extension might also communicate with other back-end servers to retrieve solutionspecific information.
- Uses the GAX Database to store configuration information and other data, such as operational parameter templates and audio resource metadata.
- Uses Sound eXchange (SoX) to encode audio files.
- Sends encoded audio files to the Audio Resource Manager (ARM) Storage. From the ARM storage, the ARM Web Server distributes them to GVP Media Servers.
- Uploads IPs to Solution Deployment storage.
- Displays logs from the Centralized Log Database.

#### **Important**

Both TCP/IP v4 and TCP/IP v6 communications are supported between GAX and other Genesys components.

#### **Configurations**

You can deploy Genesys Administrator Extension as a single instance, or you can deploy multiple instances of GAX in a load-balanced environment to support High-Availability (HA).


Tip

As GAX is a web application, it does not support the typical Genesys HA model of Primary/Backup instances.

Overview Architecture

To support HA, you must deploy multiple active instances of GAX that connect to a common configuration environment and share common resources. For example, you can have multiple instances of GAX that connect to the same Configuration Database and DB Server.

The figure below provides an example of a GAX deployment in an HA environment. A load balancer distributes traffic to three or more GAX instances. Each GAX instance is connected to a common GAX database (see Database High Availability for more information on database HA).



To provide HA functionality, a load-balancer and at least two instances of an application server (AS) are required. The load-balancer distributes the load to all nodes.

To use the configuration described above, follow the instructions for Deploying Genesys Administrator Extension for each GAX instance. In Setup Mode, choose **Existing Deployment** and specify the same information for Configuration Database and DB Server for each GAX instance that you set up.

#### **Important**

If multiple GAX instances are using the same database, you must ensure that all GAX plug-ins work with the schema version of the database. For example, if you have two GAX instances with different plug-in versions that use different schema versions, you might encounter problems.

#### **Database High-Availability**

Databases that are supported by GAX have their own HA functionality. Refer to the documentation specific to your database for information on how to configure the database for HA.

#### **Database Size Requirements**

To help you plan to manage your space requirements for audio resources, this section provides information about space allocation for a 100-tenant system with an average of 100 announcement files per segment, including personalities.

#### **Original Audio Resource Files**

The space required for the original audio resource files that are uploaded by tenants can be calculated as:

```
Original Files Storage Requirements = <# of tenants> x <avg # of announcement files> x <avg file size>
```

For example, if you have 100 tenants with 100 audio files of an average size of 3 MB you would have to calculate 30 GB of space for just the original audio files:

```
Original Files Storage Requirements = 
100 x 100 x 3 MB = 
30,000 MB = 30 GB
```

#### **Processed Audio Resource Files**

The original files are stored both in the database and on the disk (unless database storage is turned off by using the configuration options). The processed files are located only on the disk. Therefore, the raw storage that is required on the disk can be calculated as:

Processed Files Storage Requirements = ((<# of tenants> x <# of announcement files> x <avg file size>) / <compression factor>) x (<# of conversion formats>)

In the example with 100 tenants, the requirement for Processed files is also 30 GB:

Processed Files Storage Requirements =

```
((100 x 100 x 3 MB) / 3) x (3) =
30,000 MB = 30 GB
```

#### **Reserved Space**

For the database, which holds only the original files, additional space should be reserved to allow for short time peaks and better database performance. Genesys recommends that 50% (1.5 times) of additional space should be reserved for this purpose:

```
Database Size Requirements = <Original Files Storage Requirements> x
<reserve percentage>
```

In this example, the suggested database space requirement is:

```
Database Size Requirements = 30 GB x 1.5 = 45 GB
```

Your disk space requirement should also include reserved space to prevent degraded performance, which can occur if drives become too full.

Genesys recommends that the reserved space allocation is 25% (1.25) of the actual raw requirements:

```
Disk Size Requirements = (<Original Files Storage Requirements> +
<Processed Files Storage Requirements>) x <reserve percentage>
```

Therefore, in total, for the original files, the converted files, and reserved space, 75 GB are required:

```
Disk Size Requirements = (30 \text{ GB} + 3 \text{ 0 GB}) \times 1.25 = 75 \text{ GB}
```

#### Setting Up Genesys Administrator Extension

This chapter describes how to install and configure Genesys Administrator Extension. It also describes the prerequisites and other information for setting up Genesys Administrator Extension to perform the tasks that are described in the Overview chapter.

#### **Overview**

Genesys Administrator Extension is deployed with a web application server and can be accessed by using a web browser. It does not have to be deployed in the same environment with Genesys Administrator and nothing needs to be installed on client machines.

#### **Important**

GAX is normally deployed in a multiple tenant environment; however, single-tenant environment deployment is supported as of version 8.1.2. If you deploy GAX in a single-tenant environment, the Tenant Management features and filtering are not applicable.

#### **Prerequisites**

Before you deploy Genesys Administrator Extension, you should review the planning information in the Framework Deployment Guide. This will help you to deploy Genesys Administrator Extension and other components of Management Framework in a manner that is most appropriate to your situation.

To use the Role-based Access Control feature, Configuration Server 8.1.x or higher is required.

#### **Important**

To avoid issues with role assignments, you should upgrade the application, metadata, and the roles to the new type when you migrate to the latest version of GAX or perform a fresh install (see Upgrading to the latest Genesys Administrator Extension for Management Framework 8.1.1 or higher).

Refer to the Genesys Supported Operating Environment Reference Guide for information on which operating environments are supported by GAX.

In addition, each module of GAX might have additional prerequisites. Refer to Prerequisites for Genesys Administrator Extension Modules for more information.

#### **Browser Requirements**

Refer to the Genesys Supported Operating Environment Reference Guide for information on which web browsers are supported by GAX. Although GAX supports all major browsers, it is optimized for Google Chrome.

If you use Microsoft Internet Explorer or Safari, see Browser Issues for troubleshooting information specific to your browser.

Genesys Administrator Extension is designed to be viewed at a minimum screen resolution of 1024x768, although higher resolutions are recommended. If you are working in 1024x768 mode, maximize your browser to ensure that you can see all of the interface. In addition, all windows of the browser must be set to a resolution of 1024x768 or greater.

#### Required Permissions and Role Privileges

Genesys Administrator Extension uses a permission-based mechanism and a role-based access control system to protect your data. Before installing and using Genesys Administrator Extension, ensure that all users have the necessary access permissions and role privileges to do their work. The following are examples of scenarios that require permissions:

- A user must have Update permission on his or her User object to set and save his or her user preferences in Genesys Administrator Extension.
- To log in to Genesys Administrator Extension, a user must have Read permission on his or her User object, Read and Execute permissions on his or her Tenant object, and Read and Execute permissions on the Genesys Administrator Extension client Application object. These permissions are usually assigned by adding the users to access groups.

There are no role privileges required to log in to GAX. However, GAX-specific functions might require additional role privileges to be enabled. Refer to Role Privileges for more information about role privileges.

#### **Deploying Multiple Instances of GAX with Shared Resources**

GAX is a web application. As such, you can deploy multiple active instances of GAX behind a web load balancer to support both High Availability (HA) and load balancing. Note that this setup is different than the typical Genesys HA model that features Primary/Backup servers.

If you deploy multiple active GAX instances, the load balancer evenly distributes traffic among all instances in the cluster. If one instance fails, the load balancer redirects traffic to the remaining instances. In the meantime, Local Control Agent (LCA) auto-restarts the failed instance.

#### **Important**

If a GAX instance fails, users who are logged in to that instance must log in again to GAX. The load balancer redirects these login requests to the remaining active GAX instances.

You can also install multiple instances of GAX to take advantage of the GAX plug-in architecture. Each instance of GAX can be deployed with a different combination of plug-ins.

In either scenario, the multiple instances of GAX share the same data resources, such as Configuration Server, the GAX database, and audio resources, but are executed independently by different users on different hosts.

See the Architecture page for more information.

### Minimum Required Firewall Permissions and Settings for GAX Deployment

Your firewall must allow incoming connections on the http and https ports. (for example 8080, 80, 433, and so on, based on your setup). The application server can listen on more than one port at once.

You must allow outgoing connections to allow GAX to establish connections; however, you can restrict the connections to networks that contain the following components:

- GDA hosts
- Databases
- Genesys configuration layer servers: Configuration Server, Message Server, and Solution Control Server

### Minimum Required File System Permissions and Settings for GAX Deployment

The GAX operating system user is the user that runs the GAX process. The GAX operating system user must be the owner of the folder where it is deployed and must have the following permissions:

- Write permission on the log file folder
- Read/write access to the folder configured for ARM

#### **Deploying Genesys Administrator Extension**

This page describes how to install and deploy Genesys Administrator Extension. Before beginning your installation, ensure that you have met the prerequisites listed in Prerequisites. If you plan to install any of the modules in Genesys Administrator Extension, refer to Prerequisites for Genesys Administrator Extension Modules before using them.

Genesys Administrator Extension can be deployed via Setup Mode or the command line.

#### **Important**

- Although Configuration Server might support more database types, GAX only supports the following database types: Oracle, Microsoft SQL Server, and PostgreSQL.
- Do not connect GAX to a Configuration Server Proxy; connect it to Configuration Server only.
   Configuration Server Proxy does not support some functionality that is required by GAX.
- Although Management Framework supports various operating systems, GAX can only deploy Configuration Server and Database Server on Windows Server 2003/2008/2012 or Red Hat Enterprise Linux 5.5/6.x. See Prerequisites for more information on operating systems that are supported by GAX.

#### **Deploying Genesys Administrator Extension via Setup Mode**

Setup Mode can set up new instances of GAX to connect to an existing Management Framework deployment. You can also use Setup Mode to install and configure new Genesys deployments. In the latter scenario, Setup Mode will install GAX, Configuration Server, and DB Server (where applicable). After these components are installed, you can use the installation package (IP) management features of GAX to deploy other installation packages.

If you are using Setup Mode to install GAX for the first time, you must be a local user on the machine on which GAX will be installed. You are considered a local user if you are using this machine in person or via a remote desktop connection. After the set up is completed, the local user account is no longer used for subsequent installations.

#### Warning

Any interruption in the Setup Mode process might result in only partial and incomplete configuration of your environment. A complete restart of the setup process is needed. If you encounter an interruption while deploying GAX using Setup Mode, first reset Configuration Server (for example, stop any running Configuration Server processes) and your environment (for example, reset the Configuration Database) to their initial values. Then restart Setup Mode from scratch.

The following table describes how to deploy GAX via Setup Mode.

#### Set up the database

#### Important

In Setup mode, results of executing SQL statements that contain the <code>drop</code> keyword are ignored, although they are still logged by GAX. This is because some databases return errors when dropping tables or views; you can ignore these errors. If required, you can find the errors in the logs of the GAX server.

Choose one of the following database types:

#### **Oracle**

#### [+] Click to show section

## Setting up the Genesys Administrator Extension database (for Oracle)

**Purpose:** To set up the Oracle 11g R2 or Oracle 12c database that is used by Genesys Administrator Extension.

#### **Steps**

- 1. Refer to the Oracle documentation to install the Oracle Database Management System on the host machine.
- 2. Use the following SQL commands to create the users and ensure that they do not have excessive permissions:

```
create user <username> identified by <password>;
grant connect, resource to <username>;
alter user <username> quota 10M on USERS;
```

#### **Important**

The above quota value is an example. Consult the Oracle documentation to determine the correct quota value for your system.

- 3. If you are setting up a new Configuration Server, perform the following steps on the Configuration Server host:
  - Run the Oracle Net Configuration Assistant.
  - Select Local Net Service Name Configuration to create an entry in the tnsnames.ora file to map the Local Net Service Name to the host, port, and SID (System ID) used by the database.

**Important** 

The Local Net Service Name must be the same as the SID in order for Setup Mode in GAX to work properly.

 The ORACLE\_HOME environment variable must be set to the installation directory of the Oracle database client.

Refer to the Oracle documentation for additional details on completing this step.

#### (Optional) Enable UTF-8 character encoding for Oracle databases

To enable UTF-8 character encoding for Oracle databases in Genesys Administrator Extension, you must ensure that:

- Configuration Server 8.1.2 or higher is installed.
- UTF-8 string encoding is enabled on Configuration Server 8.1.2 or higher.

The database character set must be set to **AL32UTF8** to support the use of UTF-8 character encoding. To verify the character set, use the following SQL command:

```
SELECT * FROM NLS DATABASE PARAMETERS;
```

In the response, if NLS\_CHARACTERSET is set to AL32UTF8, no additional actions are required. Otherwise, refer to the Oracle support guide for more information about character set migration:

http://docs.oracle.com/cd/B28359\_01/server.111/b28298/ch11charsetmig.htm

#### Warning

Character-set migration is a non-reversible process. Incorrect data conversion can lead to data corruption, so always perform a full backup of the database before attempting to migrate the data to a new character set.

#### **Important**

In most cases, a full export and import is recommended to properly convert all data to a new character set.

#### Microsoft SQL

#### [+] Click to show section

## Setting up the Genesys Administrator Extension database (for Microsoft SQL Server)

**Purpose:** To set up the Microsoft SQL Server 2008/2012 database that is used by Genesys Administrator Extension.

#### **Steps**

- Refer to the Microsoft SQL Server documentation to create the Microsoft SQL Server Database for GAX.
- 2. Start SQL Server Management Studio.
- 3. Connect to Microsoft SQL Server as sa.
  - · Server type: Database Engine
  - Server name: Local
  - Authentication: SQL Server Authentication
- 4. Create a login and password for the GAX database. For example: gax850admin with the password password.
- 5. Create the GAX database (for example, gax850) by using the login to make this login the owner of the database.

#### **Important**

When you create the login, uncheck the **Enforce** password policy check box.

- 6. Verify that you can connect to the database with the login that you created:
  - Server type: Database Engine
  - Server name: Local
  - Authentication: SQL Server Authentication

#### **PostgreSQL**

#### [+] Click to show section

## Setting up the Genesys Administrator Extension database (for PostgreSQL)

**Purpose:** To set up the PostgreSQL database that is used by Genesys Administrator Extension.

#### **Steps**

#### **Important**

It is recommended to use PostgreSQL version 9.1.x.

- Refer to the PostgreSQL 9.1 documentation to create the PostgreSQL Database for GAX.
- 2. Start pgAdmin.
- 3. Select the PostgreSQL 9.1 connection and connect to the PostgreSQL database with the following user name: postgres.

#### **Important**

If a PostgreSQL 9.1 connection is not available, you can create it by clicking **Add Server**.

4. Create a login and password for the GAX database.

For example: gax850admin with the password password.

You can execute queries by clicking **Query Tool**. For example:

```
CREATE USER gax WITH PASSWORD 'gax850admin' CREATEDB;
```

5. Create the GAX database (for example, gax850) by using the login created in Step 4 to make this login the owner of the database.

```
create database gax850 owner gax;
```

- 6. Connect to the database with the login that you created in Step 4.
- 7. Perform the following steps if you are setting up a new Configuration Server:

- You must update the DBMS configuration file pg\_hba.conf to allow the client to connect to the database.
- Issue the command pg\_ctl reload to complete the update of the DBMS configuration file.

#### **Important**

- The PostgreSQL driver LIBPQ.dll must be installed on the host where Database Server is installed.
- The PATH environment variable must be set to the bin directory of PostgreSQL.

#### Set up the host

#### Setting up the host for Genesys Administrator Extension server

#### **Steps**

1. If Java Server JRE 6, 7, or 8 is not already installed on the host machine where Genesys Administrator Extension will be installed, install it now by downloading it from the following website:

http://www.oracle.com/technetwork/java/javase/downloads/index.html

Refer to the Oracle documentation for more information on how to install the tar.gz package.

#### Important

GAX only supports the 64-bit version of Oracle Java HotSpot Server VM.

- 2. Set the following environment variables for your host, as follows:
  - a. Linux

#### Insert the following lines into the /etc/profile file:

- export JRE\_HOME=/usr/lib/java/jre-<version of Java downloaded>/jre
- export PATH = \$PATH: /usr/lib/java/jre-<version of Java downloaded>/jre/bin

Log out and log in again to activate the new environment variables in the current session.

- b. Windows
  - Create a new System Variable named <u>JRE\_HOME</u> and use the path that was used during installation as the value (for example, C:\Programs\Java\jre1.6.0 23).
  - Edit the Path variable and append C:\Programs\Java\
     jre1.6.0 23\bin to the existing value.
- 3. Install Local Control Agent on this host. For detailed instructions, refer to the Framework Deployment Guide.

#### Install the GAX server on a host

#### Linux

#### [+] Click to show section

### Installing Genesys Administrator Extension server on a Linux host

#### **Prerequisites**

 The environment variable for JRE\_HOME has been configured (see Step 2 of Setting up the host for Genesys Administrator Extension server).

#### **Steps**

- 1. Copy the IP to the host machine.
- 2. Navigate to the folder to which you copied the IP, and change the permissions of the installation file by entering the following command:

```
chmod 755 install.sh
```

3. Run the installation file to extract and copy the necessary files by entering the following command:

```
./install.sh
```

#### **Important**

When you install Genesys Administrator Extension, you might receive the following error message that indicates that installation was unsuccessful:

Unable to find configuration information. Either you have not used configuration wizards and the GCTISetup.ini file was not created or the file is corrupted.

Ignore this message; Genesys Administrator Extension was installed successfully.

- 4. Navigate to the folder in which you installed GAX and run the gax startup.sh file.
- 5. Install the Genesys Deployment Agent on port 5000 of this host. Follow the instructions in the Framework Deployment Guide, but when asked to provide installation information for Local Control Agent, provide dummy values for now. After Configuration Server is installed, you can go back and install LCA with the correct values or change them manually.

#### **Important**

The GAX installer creates a setenv.sh file that enables you to adjust the memory settings for GAX. The setenv.sh file defines the memory (RAM) settings for GAX to 1024 MB. You can change the memory setting in the setenv.sh file to a different value. If you enable TLS encryption, ensure that you make the following updates to the setenv.sh file. The setenv.sh file contains the following lines:

```
# Uncomment the following lines only if you are going to use
TLS. Don't forget to set the correct path and password.
#export JAVA_OPTS="$JAVA_OPTS -Djavax.net.ssl.trustStore=
/path_to_jre/jre6/lib/security/cacerts"
#export JAVA_OPTS="$JAVA_OPTS -
Djavax.net.ssl.trustStorePassword=secret password"
```

```
# This line defines the memory (RAM) settings for GAX. If you have more RAM available for GAX, adjust both values accordingly export JAVA_OPTS="$JAVA_OPTS -Xms1024m -Xmx1024M"

# Uncomment following line to activate psdk.logs, it's recommended to let this option deactivated
#export JAVA_OPTS=%JAVA_OPTS% -
Dcom.genesyslab.platform.commons.log.loggerFactory=
com.genesyslab.platform.commons.log.Log4JLoggerFactoryImpl
# Enable this option for SSL Debugging
#export JAVA_OPTS=%JAVA_OPTS% -Djavax.net.debug=all
```

Follow the instructions in the first line by uncommenting the indicated lines below it and setting the path and password.

• You must create a trust store and set the trust store path accordingly. See Transport Layer Security for more information.

#### **Windows**

#### [+] Click to show section

### Install Genesys Administrator Extension server on a Windows Server host

#### **Prerequisites**

 The environment variable for JRE\_HOME has been configured (see Step 2 of Setting up the host for Genesys Administrator Extension server).

#### **Steps**

- 1. Copy the IP to the host machine.
- 2. Run the **setup.exe** installation file to extract and copy the necessary files.

If there is an existing installation of GAX on the host, the installer will display a dialog box that prompts you to confirm whether or not you want to maintain the existing installation.

- 3. Navigate to the folder in which you installed GAX and run the **gax\_startup.bat** file.
- 4. Install the Genesys Deployment Agent on port 5000 of this host. Follow the instructions in the Framework Deployment Guide, but when asked to provide installation information for Local Control Agent, provide dummy values for now. After Configuration Server is installed, you can go back and install LCA with the correct values or change them manually.

#### **Important**

The GAX installer creates a setenv.bat file that enables you to adjust the memory settings for GAX. The setenv.bat file defines the memory (RAM) settings for GAX to 1024 MB. You can change the memory setting in the setnev.bat file to a different value. If you enable TLS encryption, ensure that you make the following updates to the setenv.bat file. The setenv.bat file contains the following lines:

```
REM Uncomment the following lines only if you are going to use TLS. Don't forget to set the correct path and password.

REM set JAVA_OPTS=%JAVA_OPTS% -Djavax.net.ssl.trustStore=
"C:\Program Files\Java\jre6\lib\security\cacerts"

REM set JAVA_OPTS=%JAVA_OPTS% -
Djavax.net.ssl.trustStorePassword=secret password
```

Follow the instructions in the first line by uncommenting the indicated lines below it and setting the path and password.

 You must create a trust store and set the trust store path accordingly. See Transport Layer Security for more information.

#### **Deploy GAX**

#### **Deploy GAX (Existing Management Framework Deployment)**

[+] Click to show section

## Deploying Genesys Administrator Extension (Existing Management Framework Deployment)

**Purpose:** To deploy GAX into an existing deployment of Management Framework.

#### **Prerequisites**

- Management Framework is deployed and configured.
- The host property of the Configuration Server application is set.

#### Steps

1. Connect to GAX locally by opening a supported web browser and navigating to the location of your GAX host (for example: http://localhost:8080/gax/).

#### **Important**

Setup Mode is accessible only through a local connection. You cannot use Setup Mode if you connect remotely to the GAX host.

- 2. Select the **Username** field and enter root. By default, there is no password.
- 3. Click Log In.
- 4. Choose Connect to an Existing Deployment.
- 5. You must provide configuration information about the existing Management Framework deployment. This screen pre-populates with existing details about the deployment, such as:
  - Primary Configuration Server Host
  - Port number
  - Default Client Application Name
  - Username
  - Password

If there are any errors, GAX prompts you to re-enter the configuration information.

- 6. Click Next.
- 7. Associate this instance of GAX with an Application object. Do one of the following:

**Important** 

When you are first installing GAX, be sure to use an Application object that is based on the template from the GAX IP.

- To use an existing Application object, select the Application object from the list. If the Host object on which the object is configured has the same Host name or IP address as the current GAX instance, the Application object is highlighted as **recommended**.
- To create a new Application object, provide the following information in the corresponding fields:
  - Administrator Extension Application Object Name—The name of the Application object to create.
  - Template—The application template to use.

This creates an application of type Genesys Administrator. If the Host object does not exist, it is automatically created.

- Click Next.
- 9. GAX prompts you to enter configuration information for the GAX database. This screen pre-populates with existing details that might be stored in Configuration Server. You must provide the following configuration information:
  - Database Server Type
  - Database Host
  - Port (numeric only)
  - Database Name
  - Username
  - Password
- 10. Click Next.
- 11. GAX verifies the database version and creates (or updates) the database access configuration. If an error occurs, an error message displays and you can either cancel or restart the deployment process.
- 12. Click Finish.
- 13. GAX restarts to finish the setup operation. When it is done, GAX displays the login screen and you can login to GAX.

#### Deploy GAX 8.5.000.65 or Later and Management Framework 8.5.x/8.1.x

#### [+] Click to show section

# Deploying Genesys Administrator Extension 8.5.000.65 or Later and Management Framework 8.5.x/8.1.x

**Purpose:** To deploy GAX 8.5.000.65 (or later) and Management Framework 8.5.x or 8.1.x.

#### **Prerequisites**

- Genesys Deployment Agent (GDA) must be installed on port 5000 on the server that will run Configuration Server and Database Server.
- The installation packages for Configuration Server and Database Server (required for Management Framework 8.1.x only) are in a location accessible to the GAX host machine.
- You are familiar with the prerequisites for deploying Management Framework. Refer to the Management Framework documentation for more information.

#### **Steps**

1. Connect to GAX locally by opening a supported web browser and navigating to the location of your GAX host (for example: http://localhost:8080/gax/).

#### **Important**

Setup Mode is accessible only through a local connection. You cannot use Setup Mode if you connect remotely to the GAX host.

- 2. Select the **Username** field and enter root. By default, there is no password.
- 3. Click Log In.
- 4. Choose Install a New Deployment.
- 5. In the **Configuration Server Installation Package Path** field, enter the path to the Configuration Server installation package .zip file (Windows) or tar.gz file (Linux). The file must contain the **ip** and **Templates** directories.
- 6. Click Next.
- 7. (This step only appears if you are using an installation package for Configuration Server 8.1.x or lower.)
  - In the Database Server Installation Package Path field, enter the path to the

Database Server installation package .zip file (Windows) or tar.gz file (Linux). The file must contain the **ip** and **Templates** directories. When you are done, click **Next**.

- 8. In the **Configuration Server Details** section, provide the following information. Some fields are populated by default values.
  - Installation Path on Target Host—The installation path to which Configuration Server will be installed.
  - Primary Configuration Server Host—Enter the name of the Primary Configuration Server host.
  - Port—Enter the port number for the Primary Configuration Server.
  - Target Host OS Type—Select the operating system used by the target host.

# **Important**

Although Management Framework supports various operating systems, GAX can only deploy Configuration Server and Database Server on Windows Server 2003/2008/2012 or Red Hat Enterprise Linux 5.5/6.x. See Prerequisites for more information on operating systems that are supported by GAX.

- **Management Port**—Enter the port number for the Management Port.
- 9. Click Next.
- 10. (This step only appears if you are using an installation package for Configuration Server 8.5.x or higher.)
  - In the **Configuration Server License Path** field, enter the path to the Configuration Server license file and then click **Next**.
- 11. (Optional) Click the **Install Backup Configuration Server** check box to install a Backup Configuration Server. You must provide the following information:
  - Backup Configuration Server Host—Enter the name of the Backup Configuration Server host.
  - **Port**—Enter the port number for the Backup Configuration Server.
  - Management Port—Enter the port number for the Backup Management Port.
- 12. Click Next.
- 13. (This step only appears if you are using an installation package for Configuration Server 8.1.x or earlier.)
  - In the **Database Server Details** section, provide the following information. Some fields are populated by default values.
    - Installation Path on Target Host—The installation path to which Database Server will be installed.

• **Port**—Enter the port number for the database.

When you are done, click **Next**.

- 14. In the **Configuration Server Database** section, provide the following information. Some fields are populated by default values.
  - Database Server Type—Select the database type to be used by GAX: Oracle, PostgreSQL, or MS SQL Server.
  - Database Host—Enter the name of the database host.
  - **Port**—Enter the port number for the database.
  - **Database Name**—Enter the name of the database.
  - **Username**—Enter the user name to use when accessing the database.
  - Password—Enter the password to use when accessing the database.

### **Important**

GAX uses default values for some deployment parameters. These default values are not presented to the user. If you want to override these default values, you must edit the following file in the \conf directory: asd\_hostinfo.properties, asd\_silentini\_<IP Nick Name>.properties

- 15. Click Next.
- 16. A progress indicator displays while GAX performs the deployment. If an error occurs, an error message displays and you can either cancel or restart the deployment process.
- 17. Click Next.
- 18. In the **Application Object Details** section, provide the following information.
  - Administrator Extension Application Object Name—Enter the name of the GAX Application object.
- 19. Click Next.
- In the Administrator Extension Database Details section, provide the following information. Some fields are populated by default values.
  - Database Server Type—Select the database type to be used by the GAX database: Oracle, PostgreSQL, or MS SQL Server.
  - Database Host—Enter the name of the GAX database host.
  - **Port**—Enter the port number for the GAX database.
  - Database Name—Enter the name of the GAX database.
  - **Username**—Enter the user name to use when accessing the GAX database.
  - Password—Enter the password to use when accessing the GAX database.
- Click Next.

- 22. GAX verifies the database version and creates (or updates) the database access configuration. If an error occurs, an error message displays and you can either cancel or restart the deployment process.
- 23. Click Finish.
- 24. GAX restarts to finish the setup operation. When it is done, GAX displays the login screen and you can login to GAX.

### **Important**

To complete deployment of Management Framework, you might have to install and configure License Reporting Manager.

### **Important**

Setup Mode reads SQL script files from IPs and executes them on the target database through a JDBC connection. SQL script files should follow these rules:

- 1. <Script> ::= {[<Statement>] | [<Delimiter>] | [<Comment>]}
  A script consists of a sequence of statements or comments, with or
  without delimiters in between.

A multi-line comment starts with "/\*" and ends with "\*/".

- 3. < Delimiter > ::= "qo"|"/"|";"
- An instance of go or / is a strong delimiter which delimits any statements.

An instance of ; is a weak delimiter which delimits all other statements except <CreateProcedure>.

- 4. <Quotations> ::= '{<any\_character>}'|"{<any\_character>}"
  Quotations can appear inside a statement. Any characters inside
  quotations are not treated as a statement, delimiter, or comment.
- 5. <Statement> ::= <CreateProcedure>|<SimpleStatement>
  <CreateProcedure>::="CREATE PROCEDURE"|"CREATE OR REPLACE

PROCEDURE"{<any\_character>|<Quotations>}"go"|"/"|<EOF>
<SimpleStatement>::="INSERT"|"UPDATE"|"DELETE"|"DROP"|"CREATE"|"ALTER"|"COMMIA create procedure statement must be specifically delimited by a strong delimiter.

A simple statement can be delimited by a delimiter, a comment, or another statement.

6. All keywords are case insensitive.

# Deploy GAX 8.5.000.58 or Earlier and Management Framework 8.1.x

### [+] Click to show section

### **Important**

This procedure describes how to use Setup Mode to deploy GAX 8.5.000.58 (or earlier) and Management Framework 8.1.x. If you want to deploy Management Framework 8.5.x, you must use GAX 8.5.000.65 or later and refer to the section above - Deploy GAX 8.5.000.65 or Later and Management Framework 8.5.x./8.1.x.

Deploying Genesys Administrator Extension
8.5.000.58 or Earlier and Management Framework
8.1.x

**Purpose:** To deploy GAX 8.5.000.58 (or earlier) and Management Framework 8.1.x.

#### **Prerequisites**

- Genesys Deployment Agent (GDA) must be installed on port 5000 on the server that will run Configuration Server and Database Server.
- The installation packages for Configuration Server and Database Server are in a location accessible to the GAX host machine.
- You are familiar with the prerequisites for deploying Management Framework. Refer to the Management Framework documentation for more information.

#### **Steps**

1. Connect to GAX locally by opening a supported web browser and navigating to the location of your GAX host (for example: http://localhost:8080/gax/).

### **Important**

Setup Mode is accessible only through a local connection. You cannot use Setup Mode if you connect remotely to the GAX host.

- 2. Select the **Username** field and enter root. By default, there is no password.
- 3. Click Log In.
- 4. Choose Install a New Deployment.
- 5. In the **Installation Packages** pane, provide the following information:
  - Configuration Server IP Path—Enter the path to the Configuration Server installation package .zip file (Windows) or tar.gz file (Linux). The file must contain the ip and Templates directories.
  - Database Server IP Path—Enter the path to the Database Server installation package .zip file (Windows) or tar.gz file (Linux). The file must contain the ip and Templates directories.
- 6. Click Next.
- 7. In the **Configuration Server Details** section, provide the following information. Some fields are populated by default values.
  - Installation Path on Target Host—The installation path to which Configuration Server will be installed.
  - Primary Configuration Server Host—Enter the name of the Primary Configuration Server host.
  - **Port**—Enter the port number for the Primary Configuration Server.
  - Target Host OS Type—Select the operating system used by the target host.

# **Important**

Although Management Framework supports various operating systems, GAX can only deploy Configuration Server and Database Server on Windows Server 2003/2008/2012 or Red Hat Enterprise Linux 5.5/6. See Prerequisites for more information on operating systems that are supported by GAX.

- Management Port—Enter the port number for the Management Port.
- 8. Click Next.
- 9. (Optional) Click the **Install Backup Configuration Server** check box to install a Backup Configuration Server. You must provide the following information:
  - Backup Configuration Server Host—Enter the name of the Backup Configuration Server host.
  - Port—Enter the port number for the Backup Configuration Server.
  - Management Port—Enter the port number for the Backup Management Port.
- 10. Click Next.
- 11. In the **Database Server Details** section, provide the following information. Some fields are populated by default values.
  - Installation Path on Target Host—The installation path to which Database Server will be installed.
  - **Port**—Enter the port number for the database.
- 12. Click Next.
- 13. In the **Configuration Server Database** section, provide the following information. Some fields are populated by default values.
  - Database Server Type—Select the database type to be used by GAX: Oracle, PostgreSQL, or MS SQL Server.
  - Database Host—Enter the name of the database host.
  - **Port**—Enter the port number for the database.
  - Database Name—Enter the name of the database.
  - **Username**—Enter the user name to use when accessing the database.
  - **Password**—Enter the password to use when accessing the database.

# **Important**

GAX uses default values for some deployment parameters. These default values are not presented to the user. If you want to override these default values, you must edit the following file in the \conf directory: asd\_hostinfo.properties, asd\_silentini\_<IP Nick Name>.properties

- 14. A progress indicator displays while GAX performs the deployment. If an error occurs, an error message displays and you can either cancel or restart the deployment process.
- 15. Click Next.
- 16. In the **Configuration Server Details** section, provide the following information.

- Administrator Extension Application Object Name—Enter the name of the GAX Application object.
- 17. Click Next.
- 18. In the **Administrator Extension Database Details** section, provide the following information. Some fields are populated by default values.
  - Database Server Type—Select the database type to be used by the GAX database: Oracle, PostgreSQL, or MS SQL Server.
  - **Database Host**—Enter the name of the GAX database host.
  - Port—Enter the port number for the GAX database.
  - **Database Name**—Enter the name of the GAX database.
  - Username—Enter the user name to use when accessing the GAX database.
  - Password—Enter the password to use when accessing the GAX database.
- 19. Click Next.
- 20. GAX verifies the database version and creates (or updates) the database access configuration. If an error occurs, an error message displays and you can either cancel or restart the deployment process.
- 21. Click Finish.
- 22. GAX restarts to finish the setup operation. When it is done, GAX displays the login screen and you can login to GAX.

#### End

### **Important**

statements.

Setup Mode reads SQL script files from IPs and executes them on the target database through a JDBC connection. SQL script files should follow these rules:

- 1. <Script> ::= {[<Statement>] | [<Delimiter>] | [<Comment>]}
  A script consists of a sequence of statements or comments, with or
  without delimiters in between.

A multi-line comment starts with "/\*" and ends with "\*/".

3. < Delimiter > ::= "go"|"/"|";" An instance of go or / is a strong delimiter which delimits any

An instance of ; is a weak delimiter which delimits all other

statements except <CreateProcedure>.

- 4. <Quotations> ::= '{<any\_character>}'|"{<any\_character>}"
  Quotations can appear inside a statement. Any characters inside
  quotations are not treated as a statement, delimiter, or comment.
- 5. <Statement> ::= <CreateProcedure>|<SimpleStatement> <CreateProcedure>::="CREATE PROCEDURE"|"CREATE OR REPLACE PROCEDURE"{<any\_character>|<Quotations>}"go"|"/"|<EOF> <SimpleStatement>::="INSERT"|"UPDATE"|"DELETE"|"DROP"|"CREATE"|"ALTER"|"COMMIA create procedure statement must be specifically delimited by a strong delimiter.

  A simple statement can be delimited by a delimiter, a comment, or
- 6. All keywords are case insensitive.

### **Add SCS Connection**

another statement.

GAX must have a connection to Solution Control Server (SCS) for the System Dashboard to function.

# Adding a Connection to SCS from GAX

### **Prerequisites**

Solution Control Server is installed and configured.

#### **Steps**

- 1. In GAX, go to Configuration Manager.
- 2. Hover over the **Environment** icon and select **Applications** in the pop-up list.
- 3. In the **Applications** list, open the Application object for GAX.
- 4. In the GAX Application object details window, click the **Connections** tab.
- Click Add.
- In the pop-up window, enter information about the connection to SCS. Refer to the procedure "Creating Application Objects" on the Applications page for more information.
- Click OK.

- 8. Click Save.
- Restart GAX.

# **Deploying GAX via the Command Line**

You can also deploy GAX (with or without Management Framework) via the command line by using a setup file to provide deployment instructions. This feature is useful for situations in which you cannot access the GAX host via a remote desktop connection.

Choose a procedure below.

[+] Deploy GAX into existing Management Framework deployment

# Deploying GAX via the Command Line (Existing Management Framework Deployment)

**Purpose:** To deploy GAX via the command line into an existing Management Framework deployment.

### **Prerequisites**

You have completed the following procedures:

- Set up the database
- Set up the host
- Install the GAX server on a host
- The host property of the Configuration Server application is set.

### **Steps**

1. Create a setup file to provide deployment instructions for the command-line argument. The setup file must contain the following content:

```
Configuration_Server_Host=
Configuration_Server_Port=
Default_Client_Application_Name=
Configuration_Server_Username=
Configuration_Server_Password=
Application_Object_Name=
Database_Server_Type=
```

```
Database_Host=
Database_Port=
Database_Name=
Database_Username=
Database Password=
```

### The following is an example of a completed setup file:

```
Configuration_Server_Host=192.168.0.1
Configuration_Server_Port=2020
Default_Client_Application_Name=default
Configuration_Server_Username=default
Configuration_Server_Password=password
Application_Object_Name=GAX_APP
Database_Server_Type=Oracle
Database_Host=135.17.176.99
Database_Port=1521
Database_Name=GAX_DB
Database_Username=gax_admin
Database_Password=password
```

# **Important**

- You must provide a valid value for each parameter in the setup file.
- For Database\_Server\_Type only the following values are valid: oracle, mssql, or postgre.
- 2. Enter the following command in a command-line window, replacing <setup\_file\_name> with the name of the file you created in Step 1: java -jar gax.war -setup gax <setup\_file\_name>

### [+] Deploy GAX and Management Framework

**Important** 

You can only deploy Management Framework 8.5.x if you are using GAX 8.5.000.65 or later. GAX 8.5.000.58 or earlier can only deploy Management Framework 8.1.x.

# Deploying GAX and Management Framework via the Command Line

**Purpose:** To deploy GAX and Management Framework via the command line.

### **Prerequisites**

You have completed the following procedures:

- Set up the database
- · Set up the host
- · Install the GAX server on a host
- You are familiar with the prerequisites for deploying Management Framework. Refer to the Management Framework documentation for more information.

#### **Steps**

 Create a setup file to provide deployment instructions for the command-line argument. The setup file must contain the following content:

```
#MF settings
Configuration_Server_IP=
Database_Server_IP=(Use this line only for Management Framework 8.1.x o
MF_Installation_Path=
Configuration_Server_Licence_File=(Use this line only for Management Fr
Configuration_Server_Host=
Configuration_Server_Port=
Configuration_Server_OS=
Configuration_Server_OS_Bit=
Configuration_Server_Management_Port=
Database_Server_Port=(Use this line only for Management Framework 8.1.x
Install_Backup_Configuration_Server=
Backup_Configuration_Server_Host=(Optional)
Backup_Configuration_Server_Port=(Optional)
```

```
Backup Configuration Server Management Port=(Optional)
Configuration Server Database Type=
Configuration Server Database Host=
Configuration Server Database Port=
Configuration Server Database Name=
Configuration Server Database Username=
Configuration Server Database Password=
#GAX settings
Default Client Application Name=
Configuration Server Username=
Configuration Server Password=
Application Object Name=
Database Server Type=
Database Host=
Database Port=
Database Name=
Database Username=
Database Password=
```

### The following are examples of completed setup files.

#### **Management Framework 8.1.x (Windows)**

```
#MF settings
Configuration Server IP=C:\\GAX\\CS64mt.zip
Database Server IP=C:\\GAX\\DB64.zip
MF Installation Path=C:\\genesys\\GCTI\\
Configuration Server Host=cs primary host
Configuration Server Port=2020
Configuration Server OS=CFGWindowsServer2008
Configuration Server OS Bit=64
Configuration Server Management Port=2021
Database Server Port=4040
Install Backup Configuration Server=true
Backup Configuration Server Host=cs backup host
Backup Configuration Server Port=7020
Backup Configuration Server Management Port=7021
Configuration Server Database Type=Oracle
Configuration Server Database Host=cs db host
Configuration Server Database Port=1521
```

```
Configuration_Server_Database_Name=cs_db
Configuration_Server_Database_Username=default
Configuration_Server_Database_Password=password

#GAX settings
Default_Client_Application_Name=default
Configuration_Server_Username=default
Configuration_Server_Password=password
Application_Object_Name=GAX_8.5
Database_Server_Type=Oracle
Database_Host=gaxdb_host
Database_Port=1521
Database_Name=gaxdb
Database_Username=default
Database_Password=password
```

### Management Framework 8.5.x (Linux)

```
#MF settings
Configuration Server IP=/opt/genesys/cs850linux64.tar.gz
MF Installation Path=/home/genesys/GCTI/
Configuration Server Licence File=/opt/genesys/license.dat
Configuration Server Host=cs primary host
Configuration Server Port=2020
Configuration Server OS=CFGRedHatLinux
Configuration Server OS Bit=64
Configuration Server Management Port=2021
Install Backup Configuration Server=true
Backup Configuration Server Host=cs backup host
Backup Configuration Server Port=7020
Backup Configuration Server Management Port=7021
Configuration Server Database Type=Oracle
Configuration Server Database Host=cs db host
Configuration Server Database Port=1521
Configuration Server Database Name=cs db
Configuration Server Database Username=default
Configuration Server Database Password=password
#GAX settings
Default Client Application Name=default
Configuration Server Username=default
```

```
Configuration_Server_Password=password
Application_Object_Name=GAX_8.5
Database_Server_Type=Oracle
Database_Host=gaxdb_host
Database_Port=1521
Database_Name=gaxdb
Database_Username=default
Database_Password=password
```

### **Important**

- You must provide a valid value for each parameter in the setup file, unless it is marked as optional.
- For Database\_Server\_Type, only the following values are valid: oracle, mssql, or postgre.
- For Configuration\_Server\_OS, only the following values are valid: CFGRedHatLinux, CFGWinNT, CFGWindows2000, CFGWindowsServer2003, CFGWindowsServer2008. If you are using Windows Server 2012, you must use the CFGWindowsServer2008 value to prevent compatibility issues.
- For Configuration\_Server\_OS\_Bit, only the following values are valid: 32 or 64.
- Windows file paths should contain escaped backslashes. For example:
  - C:\\GAX\\CS85mt.zip.
- You must ensure that there are no trailing whitespace characters at the end of each parameter value line.
- 2. Enter the following command in a command-line window, replacing <setup\_file\_name> with the name of the file you created in Step 1:
   java -jar gax.war -setup mf-install <setup\_file\_name>

# **Configuring GAX Properties**

After GAX starts for the first time, it generates the following files and folders in the installation directory:

- conf/gax.properties
- webapp
- logs
- jsp

You can configure GAX by editing the <code>gax.properties</code> file. The options specified in the <code>gax.properties</code> file are used by GAX before it connects to Configuration Server. To set additional configuration options, see Configuration Options.

Tip

Click this link to read more general information about Javabased *.properties* files.

The following options can be configured:

Option	Description	Possible Values	Default Value
accesslog_enabled	Enables HTTP access logging	true, false	true
accesslog_filename	File name for the HTTP access log	valid filename	./logs/http- yyyy_mm_dd.log
accesslog_timezone	Time zone for the HTTP access log	Any valid timezone code (see Time Zones for a list).	GMT
accesslog_append	After GAX is restarted, specifies whether to append to existing HTTP access log	true, false	true

Option	Description	Possible Values	Default Value
accesslog_extended	Specifies whether to include extended information in the HTTP access log	true, false	false
accesslog_cookies	Specifies whether to include cookies in the HTTP access log	true, false	false
accesslog_retaindays	Specifices number of days to retain the HTTP access log	integer	90
app	Specifies the GAX Application object	Existing Application object name	
backup_port	Specifies the backup Configuration Server Port	integer	
backup_host	Specifies the backup Configuration Server Host, written as a Fully Qualified Domain Name (FQDN) or IP	Valid FQDN or IP	
<pre>enable_web_notification</pre>	Enables real-time notification if the configuration object currently being modified has been updated by another user while the current user was modifying it; that is, since the object's properties window was opened. See Coordinating Simultaneous Changes to Data.  Note: This feature is currently supported	true, false	false

Option	Description	Possible Values	Default Value
	only in the Configuration Manager view.		
host	Specifies the primary Configuration Server Host, written as a Fully Qualified Domain Name (FQDN) or IP	Valid FQDN or IP	
http_port	Defines the HTTP port	integer	8080
https_port	Defines the HTTPS port	integer	8443
keystore_path	Specifies the keystore path	Valid path	
keystore_password	Specifies the keystore password	Note: The password is encrypted and must not be modified directly. Instead, refer to Step 4 of Setting up HTTPS for use with Genesys Administrator Extension.	
max_cfg_connection	Specifies the maximum number of connections to allow from GAX to Configuration Server. To allow unlimited connections, set the value to -1.	-1 or any positive integer	200

Option	Description	Possible Values	Default Value
max_idle_time	Specifies the maximum idle time, in milliseconds, before automatic logout	integer	1000*60*60
port	Specifies the primary Configuration Server Port	integer	
root_url	Specifies the root URL (host:port/rootURL)		/gax
supported_protocol	Defines the protocol to use when communicating with the server	http/ https/ both	http

# **Coordinating Simultaneous Changes to Data**

Genesys Administrator is a web-based application, and so can support many users using it at the same time. To prevent users working on the same configuration object from overwriting the other's changes, GAX provides a real-time web notification service.

# **Important**

This feature is currently supported only in the Configuration Manager view.

With this feature, the first user to save their changes can do so, and a warning message is immediately sent to all other users modifying the same configuration object. Those other users can only refresh the page, which loses all of their changes, or view the object with their own changes. In the latter case, though, the users cannot save or apply the changes—they must transfer them to an updated copy of the object or save them to an external file for import later. Regardless of what option they choose, the users are unable to overwrite each other's changes when modifying the same object at the same time.

To enable this feature, set the **gax.properties** parameter **enable\_web\_notification** to true before restarting GAX.

# **Configuring ADDP Connections**

The Advanced Disconnection Detection Protocol (ADDP) is a Genesys proprietary add-on to the TCP/IP stack. It implements a periodic poll when no actual activity occurs over a given connection. If a configurable timeout expires without a response from the opposite process, the connection is considered lost.

Genesys recommends enabling ADDP on the links between any pair of Genesys components. ADDP helps detect a connection failure on both the client and the server side. For most connections, enabling detection on the client side only is sufficient and it reduces network traffic. However, Genesys strongly recommends that you use detection on both sides for all connections between Configuration Server and its clients (including Solution Control Interface), as well as between any two T-Servers.

Refer to the Framework Deployment Guide for more information on ADDP.

# **Using ADDP with GAX**

Genesys Administrator Extension supports ADDP connections to the following components:

- Configuration Server (ADDP always enabled)
- Message Server (ADDP enabled optionally through connection parameters)

At startup, GAX initiates a connection to Configuration Server with ADDP enabled using the following default values:

Local Timeout: 20Remote Timeout: 20

• Trace: On

After establishing the connection, GAX reads the ADDP parameters specified in the connection to Configuration Server, and if configured, the timeouts are reset dynamically based on the configured values (no re-connection is needed).

The ADDP parameters for Message Server are read from Configuration Server before the connection to Message Server is initialized. ADDP is not enabled on the connection to Message Server if configuration values are not defined.

Refer to the Genesys Administrator Extension Help for more information on configuring ADDP connections.

### **Important**

- The timeout values are adjusted based on the workload experienced by components with ADDP enabled. You can increase the timeout if the components are heavily loaded.
- You must restart GAX when an ADDP connection is severed. Restart GAX to re-establish the connection.

# **Prerequisites for Genesys Administrator Extension Modules**

This section describes prerequisites to be met before installing or using the functional modules of Genesys Administrator Extension. These are in addition to the basic prerequisites listed here, and are specific to the corresponding module.

### **Important**

Unless specified otherwise, all commands that are entered on a command line in this section should be issued as a root user (command prompt of #) or as a regular user (command prompt of \$).

# **Solution Deployment**

Before using Solution Deployment to deploy Solutions to local and remote hosts, you must ensure that the following prerequisites are met:

- Hosts are set up and running at the remote locations, and are running Local Control Agent (LCA) and Genesys Deployment Agent (GDA). Use the instructions in Genesys Administrator Extension Help.
- The following configuration options are defined on the **Options** tab of the Genesys Administrator Extension server Application object in the **asd** section:
  - silent\_ini\_path
  - local ip cache dir

Refer to Configuration Options for more information about these options.

- An appropriate SQL client is installed for solution definitions that include
   <os:execSQL> commands. You can use the following clients for each database type:
  - Oracle—SQL\*Plus
  - Microsoft SQL Server—sqlcmd
  - PostgreSQL—psql

# **Operational Parameter Management**

For the deployment of Parameter Groups, ensure that you have write permissions to the **Transactions** folder of the tenant on which the Parameter Group is deployed. You must also have write privileges for the **Voice Platform Profiles** folder to deploy the Voice application and/or write privileges for the **Routing Scripts** folder to deploy Genesys IRD or SCXML routing strategies.

There are no additional prerequisites for using Operational Parameter Management in Genesys Administrator Extension. However, ensure that your Interaction Routing Designer (IRD) routing strategies reference the **Transaction** objects correctly.

Operational Parameter Management works together with routing strategies, SCXML routing strategies, GVP voice applications, and Genesys Business Rules.

# **Important**

Operational Parameter Management does not load strategies on DNs or upload applications to application servers. You must do this manually for all parameterized objects.

# **Audio Resource Management**

# **Important**

 Internet Explorer does not support playing an audio file directly. You have to download the file and playback the file locally. Firefox cannot play µ-law and A-law audio codecs. Only PCM Audio codecs can be played in Firefox.  If you will be converting audio file formats, you must install SoX (Sound Exchange) before doing any conversions. Use the procedure under the appropriate tab below.

# **Setting up ARM on Linux**

Before using ARM on Linux, you must do the following:

1. Add the configuration option section **[arm]** and define the following configuration options on the **Options** tab of the Genesys Administrator Extension server Application object: **[+] Show options** 

### [arm]

- local announcement folder
- · local music folder
- · local\_os
- local\_path
- local sox path
- target\_announcement\_folder
- target music folder
- target\_os
- target\_path
- delete\_from\_db\_after\_processing

See Configuration Options for a detailed description of these options.

2. If you will be converting audio file formats, you must install SoX (Sound Exchange) before doing any conversions. For Linux, Genesys Administrator Extension supports SoX version 12 or higher. **[+] Show procedure** 

# **Installing SoX**

**Purpose:** To install SoX to enable conversion of audio resources to μ-law, a-law, and gsm formats. This procedure can be run at any time before or after Genesys Administrator Extension is installed.

### **Steps**

- 1. Download SoX for Linux. For more information, visit http://sox.sourceforge.net/Main/HomePage.
- 2. To install SoX on Linux, enter the following command at the # prompt:

yum install sox

### **Important**

The user of the host on which the GAX application is running must be configured to read and execute the sox binary.

3. Now you are ready to set up the ARM Runtime Web Server on Linux. [+] Show procedure

# Setting up the ARM Runtime Web Server on Linux

**Purpose:** To set up the target storage for Audio Resource Management by setting up a shared directory on an Apache web server on a Red Hat Enterprise Linux host. On this host, it creates a shared directory from which audio files are retrieved by Audio Resource Management, and to which Genesys Administrator Extension writes audio resource files as they are uploaded by users. The shared directory is accessible from the Genesys Administrator Extension host and is referred to as *target storage*.

# **Important**

The ARM Runtime Web Server is sometimes referred to as an ARM HTTP Proxy.

#### **Prerequisites**

- Genesys Administrator Extension Host is running.
- A dedicated host machine is available for the ARM Runtime Web Server.
- Media Server is available.

#### **Steps**

- 1. Set up your Network File System (NFS) to share data between Genesys Administrator Extension and the ARM Runtime Web Server.
  - a. (Linux) On the ARM Runtime Web Server, create the required folders and subfolders by entering the following commands at the # prompt:

```
mkdir /opt/genesys/arm
mkdir /opt/genesys/arm/music
```

mkdir /opt/genesys/arm/announcements

### **Important**

Ensure that the user of the host on which the GAX application is running is configured to read and write these directories. GAX treats all directories as local. If the target directory and the sub-directories reside physically on a remote host and are used as network directories, or mapped as a local drive, the user must have network access configured.

b. On the Genesys Administrator Extension host, open the /etc/exports in an editor and add the folder /opt/genesys/arm as a shared directory. When added, the file should contain the following line:

```
/opt/genesys/arm* (rw,sync)
```

To limit access to only certain machines, change the asterisk (\*) to the fully qualified domain name or address of the Genesys Administrator Extension host. If you have multiple Genesys Administrator Extension hosts in your environment, you can create one line per host.

3. On the ARM Runtime Web Server, make sure that NFS and the supporting portmap processes have started by entering the following commands at the # prompt:

```
chkconfig portmap on chkconfig nfs on
```

If necessary, you can manually start the processes by entering the following commands at the # prompt:

```
Solution nfs start
Solution portmap start
```

- 4. Mount the shared drive on the Genesys Administrator Extension host (or hosts) as follows:
  - a. On the host, create a new directory by entering the following command at the # prompt:

```
mkdir -p /mnt/arm/target
```

b. Open the file /etc/fstab in an editor and add the following line:

```
<address of the ARM Runtime Web Server>/opt/
genesys/arm
/mnt/arm/target nfs rsize=8192,wsize=8192,
timeo=14,intr
```

c. Mount the target manually by entering the following command at the # prompt:

```
mount /mnt/arm/target
```

The target is mounted automatically when the server restarts.

- 5. Install Apache Web Server as follows:
  - a. Install Apache by entering the following command at the # prompt:

```
yum install httpd
```

b. Make sure that Apache starts when the host starts by entering the following command at the # prompt:

```
chkconfig httpd on
```

Alternately, you can start Apache manually by entering the following command at the # prompt:

Solution httpd start

- c. Start or restart Apache to test that it works.
- 4. To have Apache serve the media files for the Media Server, open the file /etc/ httpd/conf/httpd.conf in an editor and make the following changes:

### Change This Line ...

#### ... to this Line

```
DocumentRoot "/var/www/ DocumentRoot "/opt/genesys/
html" arm"

<Directory "/var/www/ Spirectory "/opt/genesys/
html">
```

- 5. Update your Media Server configuration to use the ARM Runtime Web Server (address:http://<address of ARM Runtime Web Server>/) instead of the local file storage.
  - When integrating the Media Server for ARM, the following Media Control Platform configuration options must be modified:
    - To reduce the number of audio files searching attempts and promote efficiency at ARM Runtime Web Server, set msml/ play.usedefaultsearchorder to false.
    - To set the locations at the Services Site so that ARM Runtime Web Server can access announcement and music files, set the following options:

```
msml/play.basepath=http://<ARM Runtime Web
Server>
msml/play.musicbasepath=http://<ARM
Runtime Web Server>
```

For more information about these options and file naming for Play Treatment requests, refer to the Genesys Media Server 8.5 Deployment Guide.

# **Setting up ARM on Windows**

Before using ARM on Windows, you must do the following:

1. Add the configuration option section **[arm]** and define the following configuration options on the **Options** tab of the Genesys Administrator Extension server Application object: **[+] Show options** 

### [arm]

- · local announcement folder
- local\_music\_folder
- local os
- · local path
- local\_sox\_path
- target announcement folder
- target\_music\_folder
- target\_os
- delete from db after processing

See Configuration Options for a detailed description of the configuration options.

 If you will be converting audio file formats, you must install SoX (Sound Exchange) before doing any conversions. For Windows, GAX supports SoX version 14.3.1 or higher.
 Show procedure

# **Installing SoX**

**Purpose:** To install SoX to enable conversion of audio resources to μ-law, a-law, and gsm formats. This procedure can be run at any time before or after Genesys Administrator Extension is installed.

#### Steps

- 1. Download SoX for Windows. For more information, visit http://sox.sourceforge.net/Main/HomePage.
- 2. To install SoX on Windows Server, execute the installer application and install sox.exe into the following directory:

C:\Program Files\SoX\sox.exe

### **Important**

The user of the host on which the GAX application is running must be configured to read and execute the sox binary.

3. Now you are ready to set up a Network File System for ARM. [+] Show the procedure

# Setting up ARM Runtime Web Server on Windows

**Purpose:** To set up a Network File System (NFS) to share data between Genesys Administrator Extension and the ARM Runtime Web Server.

### **Important**

The ARM Runtime Web Server is sometimes referred to as an ARM HTTP Proxy.

### **Prerequisites**

- · Genesys Administrator Extension Host is running.
- A dedicated host machine is available for the ARM Runtime Web Server.
- Media Server is available.

### Steps

- 1. On the host designated as the Windows ARM Runtime Web Server, create the following required folders and subfolders:
  - C:\genesys\arm
  - C:\genesys\arm\music
- 2. C:\genesys\arm\announcements

On the ARM Runtime Web Server, share the arm folder on the network, as follows:

- a. Right-click the arm folder and select **Properties**.
- b. Click the **Sharing** tab and select **Share**.
- c. In the **Sharing** window, enter a name for the shared folder (for example, ARM), and then click **Add** and then **Share** to complete the sharing.

Now the drive is shared and can be accessed at \\host-name\arm.

3. On the GAX host, map the shared folder from the ARM Runtime Web Server (step 2) to, for example, the Z drive (**Z:**\), as follows:

### **Important**

The network mapped drive, such as Z:\, applies only to the user account that mapped the driver. GAX has to run and start under the same user account with which the network drive was mapped. Otherwise, GAX cannot access the files from the network drive.

- a. On the GAX host machine, click **Start**, and select **Computer**.
- b. In the **Tools** menu, select **Map network drive**.
- c. In the **Drive** list, select a drive to which to map the shared folder.
- d. In the Folder box, enter \\<host-name>\arm.
- e. Click Finish.
- 4. On the ARM Runtime Web Server, configure Internet Services Manager (IIS) to serve the C:\genesys\arm folder as the root directory for the new website, as follows:
  - a. Log on to the Web server computer as an Administrator.
  - b. Click Start, expand Settings, and click Control Panel.
  - c. Double-click **Administrative Tools**, and then double-click **Internet Services Manager**.
  - d. Click Action, expand New, and click Web Site.
  - e. After the Web Site Creation Wizard starts, click Next.
  - f. Enter a description for the Web site. This description is used internally to identify the Web site in IIS only.
  - g. Select the IP address to use for the site. If you select All (unassigned), the web site is accessible on all interfaces and all configured IP addresses.
  - h. Enter the TCP port number on which to publish the site.
  - i. Enter the Host Header name (the real name that is used to access this site).
  - j. Click Next.

- k. Do one of the following to specify the folder that contains the web site documents, and then click **Next**.
  - Enter the path to the folder.
  - Click Browse to select the folder.
- I. Select the access permissions for the web site, and then click **Next**.
- m. Click Finish.
- n. Right-click the web site you have created for ARM, and in the panel on the right side, click **Directory Browsing**, and click **Enable**.
- 5. Verify that you can access the web site at the following URL: http://<address of ARM Runtime Web Server:port>/<site name >.
- 6. In the GAX configuration options, set the **target\_path** option in the **[arm]** section to the mapped network folder from step 3, as follows:

```
[arm]
target_path = \\<host-name>\arm\
```

# **Configuring System Security**

GAX has many features that enhance your system security. This section discusses GAX security features and describes how to configure and/or use them.

# **Default Account Support**

Genesys uses a default user account. This is a special account that always has full privileges to all objects and can perform any action. This account ensures that there is always at least one account that enables the administrator to correct permissions and access issues if other administrative accounts are deleted, disabled, or otherwise compromised.

GAX supports the default user account. The default user account always has full access to all the functions that are specified for the GAX role, even if this account does not have any role privileges or explicit permissions specified. When the default account is created during the installation of Configuration Server, it has full control over all configuration objects; however, this account might be deleted or its permissions on objects might be revoked. If this happens, GAX cannot work around the permissions. The default account must have the permissions set to write objects in the Configuration Server.

Use the **default\_account\_dbid** option to configure the actual account to be used, and that has all privileges assigned, in case the original default user account is disabled for security reasons or has been deleted.

# **Transport Layer Security (TLS)**

GAX employs Transport Layer Security (TLS), a cryptographic protocol that provides security and data integrity for communications over networks such as the Internet. TLS encrypts the segments of network connections at the transport layer from end to end.

GAX supports TLS-enabled connections to the following Genesys servers:

- Configuration Server
- Solution Control Server
- Message Server
- Genesys Deployment Agent

GAX also supports TLS-enabled connections to the GAX database and the LRM database.

For the GAX database connection (either Oracle, Microsoft SQL Server, or PostgreSQL), the database driver and database must also support TLS. For information about configuring your GAX database, refer to the documentation that is specific to the database that you are using:

- Oracle: Oracle Database Advanced Security Administrator's Guide
- Microsoft SQL Server: Use the documentation that came with your database application.
- PostgreSQL: Use the documentation that came with your database application.

For information about TLS and detailed instructions about configuring secure connections, and creating and managing certificates, refer to the TLS section of the *Genesys Security Deployment Guide*.

Follow the instructions to create a certificate, assign that certificate to a Host object (which is required for Genesys Server to run in TLS mode), and configure the use of a secured port for the GAX application.

Next, import the server certificate to the trust storage for GAX to enable authentication for TLS connections.

By default, trust storage is in the JRE folder at the following location:

C:\Program Files\Java\jre6\lib\security\cacerts

The default password is "changeit".

Genesys recommends that you create a separate trust store for GAX.

[+] Create a trust store and import the certificates

# Creating a keystore and managing the trust store

**Purpose:** To create storage that is separate from the default keystores that come with Java.

Genesys recommends that you do not use the default keystores that are shipped with Java. To ensure a clean separation, you should create a separate storage. If you use a standard **cacert** file, you must re-import the certificates after each Java Virtual Machine (JVM) update.

The trust store should contain only the certificates of servers that GAX should trust. If a server sends GAX its certificate during a TLS handshake, GAX will search for a matching certificate in this keystore. If the certificate is found, the connection is accepted; otherwise, the connection is rejected.

### **Prerequisites**

- Your Keytool must be configured to your path.
- · You have JRE or JDK installed.

### **Steps**

1. To create an empty keystore, execute the following command lines on your shell:

```
keytool -genkey -alias initKey -keystore trusted.keystore -storetype jk
keytool -delete -alias initKey -keystore trusted.keystore
```

- Make the trusted.keystore file readable for the user that owns the GAX process.
- 3. Set a strong password on your keystore.
- 4. Add a certificate to the trust store by executing the following command line:

```
keytool -import -alias mssql -keystore trusted.keystore -file "cert/dem
```

#### Where:

- -alias corresponds to the certificate being imported; it can be an address within the trust store.
- -keystore specifies the keystore file.
- -file specifies the certificate to be imported.
- 5. To display the whole content of a keystore, execute the following command line:

```
keytool -list -keystore trusted.keystore
```

6. To display a specific certificate, execute the following command line:

```
keytool -list -v -alias mssql -keystore trusted.keystore
```

7. To delete a certificate from the keystore, execute the following command line:

```
keytool -delete -alias mssql -keystore trusted.keystore
```

### **Important**

Most systems have multiple trusted stores. You must always use the same store for GAX.

The following options must be set to configure the trust store location for GAX. The options also enable authentication on a global level for all connections that use a secured port.

On Linux or Windows, set these options by adding the following lines to the setenv.sh or setenv.bat script, respectively.

```
set JAVA_OPTS=%JAVA_OPTS% -Djavax.net.ssl.trustStore="D:\certificates\trusted set JAVA_OPTS=%JAVA_OPTS% -Djavax.net.ssl.trustStorePassword=changeit
```

If you have configured GAX to start as a service, add the following arguments in the **JavaServerStarter.ini** file:

```
-Djavax.net.ssl.trustStore="D:\certificates\trusted.keystore" -Djavax.net.ssl.trustStorePassword=changeit
```

# **Important**

GAX does not support Client Authentication. GAX will not authenticate itself by sending a certificate to the server.

### Secure Use of the Auto Detect Port

When GAX connects to the Auto Detect (Upgrade) port, the **trustStore** set by the **setenv.sh** or **setenv.bat** script is ignored. You must configure the trust store based on the settings of

the Auto Detect port. In addition, you usually must import the GAX certificate into the trust store.

### [+] Set up secure connection to Auto Detect port on Windows

#### On the GAX host:

- 1. Import the certificate into the Windows certificate store in Microsoft Management Console (MMC), under the same user that starts the GAX processes. If GAX runs under a local system account, there are several ways to import certificates to this local account. This is the most common:
  - Enter psexec.exe -i -s mmc.exe on the command line, and then import the certificate for the local system account user.
  - Enter psexec.exe -i -s certutil -f -user -p [password] importpfx [path to the certificate]

# **Important**

- psexec.exe with the -s flag executes the specified program under the system account.
- psexec is part of PSTools that you can download from http://technet.microsoft.com/en-US/sysinternals.
- On the Options tab of the GAX application object, in the [security] section, create a new option certificate and set its value to the thumbprint of the certificate that you imported in step 1.
- 3. Try to connect to the Configuration Server Auto Detect port and see if it works.

# Secure Socket Layer (SSL) Security

Genesys Administrator Extension supports Secure Socket Layer (SSL) communications between the GAX server and client-side connections using the web browser interface.

GAX can support connections through HTTP or HTTPS simultaneously. This is defined through configuration of the **supported\_protocol** parameter in the **gax.properties** file, which can be found in the **conf** directory of your GAX installation.

### [+] Set up HTTPS for use with GAX

# Setting up HTTPS for use with Genesys Administrator Extension

#### **Steps**

1. Create a keystore file to store the private key and certificate for the GAX server.

To create a self-signed certificate, execute the following command:

```
keytool -keystore keystore -alias gax -genkey -keyalg RSA
```

As prompted, enter the information required.

- 2. Start GAX in HTTP-only mode. In the gax.properties file, ensure supported\_protocol=http. This is set by default.
- 3. As a local user (whether in person or via a remote desktop connection), log in to GAX as the local user root.
- 4. Call the webservice API by entering the following in the address bar of your web browser (for example: http://localhost:8080/gax/api/system/setkeystorepassword?password={password}). The password is stored in an obscured fashion in the gax.properties file. The password specified must be the same as the password specified for the keystore (see Step 1, above). Alternately, use the following commands without a web browser:

```
curl -i --cookie-jar "./cookie.txt" -H "Content-Type:
application/json" -d
"{\"username\":\"root\",\"password\":\"\",\"isPasswordEncrypted\":\"fa
http://localhost:8080/gax/api/session/login
curl --cookie "./cookie.txt" http://localhost:8080/gax/api/
system/setkeystorepassword?password=password
```

- 5. Define the parameter https\_port in gax.properties with a port number. The usual default is 443. See Configuring GAX Properties for more information.
- 6. Update the parameter supported\_protocol in gax.properties with either https or both.

- 7. Define the parameter keystore\_path in gax.properties with the full path to the location of the keystore file.
- 8. Restart GAX in HTTPS mode.

# **TLS: Preparing Genesys Management Framework**

To enable GAX to connect securely to Genesys servers, you must configure the Genesys Framework as described in the *Genesys Security Deployment Guide*. Follow the instructions in this guide to create and manage certificates and make them usable within Genesys Framework.

# **Configuration Server**

You must meet the following conditions to create a secure connection to Configuration Server:

- 1. Create a an Auto Detect listening port for your Configuration Server with a certificate configured.
- 2. Configure the GAX Server to connect when it starts up to the Configuration Server Auto Detect port by setting the GAX Server -port property. In the **Start Info** tab of the GAX Server Properties dialog box, enter the following settings:
  - Working Directory: /path/gax
  - Command Line: ./startup.sh
  - Command Line Arguments: -host <host name> -port <auto detect port number> -app GAX\_Server

# **Message Server and Solution Control Server**

Both Message Server and Solution Control Server are configured the same way.

- 1. Create a Secured port for Message Server and Solution Control Server.
- 2. Configure the GAX Server to connect to Message Server and Solution Control Server by using the *specific* Secured ports that you have created. In the Properties dialog box for the server and in the Connections tab of the GAX Server dialog box, secured ports are displayed with a key symbol icon.
- 3. Restart GAX Server to connect over an encrypted session by using the secure ports.

### **Genesys Deployment Agent**

Genesys Deployment Agent (GDA) does not read its configuration from Configuration Server. TLS for GDA is activated by accessing the **[security]** section of the local gda.cfg file and setting the **gda-tls** option to a value of 1.

The **Application Options** tab of the related Host must also have a corresponding **[security]** section that contains the **gda-tls** option with the same value. The **gda-tls** option is not relevant for GDA runtime; it is read during the installation of LCA and GDA only. GAX reads the value of **gda-tls** to determine in what mode GDA is running, and to determine whether it should connect using TLS or not.

Therefore, these values must be kept synchronized. If the system administrator changes one of the values in the local file or in the Host **Application Options** tab, the other option must also be changed to enable GAX to connect correctly.

## Warning

Genesys strongly recommends that you use GDA version 8.5.x or higher. Earlier versions are not able to handle certificates that do not have CPD information.

#### Configuring mutual TLS between GAX and GDA

In mutual TLS, GAX and GDA each have a Certificate Authority (CA) configured, and exchange certificates which are authenticated by the other CA. The authentication occurs when a connection between GAX and GDA is established.

To support mutual TLS connection between GAX and GDA, you must do the following:

- Configure the GDA Application object with mutual TLS enabled, by adding the certificate, certificate-key, and trusted-ca parameters to the [security] section of the gda.cfg file. Refer to the following documents for additional information:
  - The "Configuring Secure Connections Between Genesys Deployment Agent and its Clients" section of the *Genesys Security Deployment Guide* for information about configuring TLS for GDA and an example of a gda.cfg file.
  - The TLS sections of the Genesys Security Deployment Guide for information about installing certificates on Windows and UNIX hosts.

- 2. Enable TLS on the Host object on which GDA is running, by setting **gda-tls** to 1 in the **[security]** section in the Annex of the Host object. GAX reads this option to determine if GDA is running in mutual-TLS mode.
- 3. Configure GAX to support TLS, as described in Transport Layer Security (TLS), above.
- 4. Configure a certificate and its private key for GAX in the GAX trusted store to add GAX authentication to GDA. Store these files in PKCS#12 format. This format defines an archive name, and is commonly used to bundle a private key with its certificate. GAX should store its Certificate Authority, certificate, and certificate key in the same trusted store as configured in step 3.
  - a. Create an archived file of the GAX certificate and its private key in the GAX keystore. For example:

```
openssl pkcs12 -inkey 04_test_priv_key.pem -in
04_test_cert.pem -export -out gaxcert.pfx
```

b. Import the archived file into the GAX keystore. For example:

```
keytool -importkeystore -destkeystore gax.keystore
-srckeystore "C:\GAX\TLS\Certificates\
test.us.genesyslab.com-HOST\repository\gaxcert.pfx" -
deststoretype JKS -srcstoretype pkcs12
```

## **Disabling Authentication for Certain Connections**

The configuring steps outlined above engage authentication for Configuration Server, Message Server, and Solution Control Server. If GAX uses the secure ports to connect to Message Server and Solution Control Server, both server-side certificates will automatically be validated against the trust storage.

In certain rare cases you might want to disable authentication for one of the connections. To do this, add the following line to the **Advanced** tab of the **Properties** dialog box for the connections:

```
"disableAuthentication=1"
```

Do not use white spaces. To separate this option from other options, use a semi-colon.

To disable TLS authentication for Configuration Server, add the following line to the following files:

• (Linux) setenv.sh:

JAVA OPTS="\$JAVA OPTS -Dgax.configserver.validate.cert=off"

• (Windows) setenv.bat:

set JAVA OPTS=%JAVA OPTS% -Dgax.configserver.validate.cert=off

### **Important**

- Connections to Message Server and Solution
   Control Server fail if GAX does not find the received
   certificate in the trust store, or if Message Server
   and Solution Control Server do not send a
   certificate.
- Connections also fail to Configuration Server and databases if they are configured for authentication and the certificate is not in the trust store.

## **TLS: Configuring the GAX Database**

You must configure your Oracle, Microsoft SQL, or PostgreSQL server to use TLS. In addition to the appropriate procedure below, refer to the documentation that came with your database for information on how to use TLS security.

[+] Configuring the GAX Oracle Database for TLS

## Configuring the GAX Database for TLS (Oracle)

#### **Prerequisites**

Setting up the Genesys Administrator database (for Oracle)

#### Steps

 Configure Oracle as described in the related database guides, and configure a TCPS listener.

- Set the level of TLS control on the DAP.
  - a. In the GAX section of the DAP, create an option that is named tls mode.
  - b. Specify one of the following values for the tls mode option:
    - off—No TLS will be used.
    - required—If a server does not support TLS, revoke the connection.
    - authentication—GAX will validate the server send-certificate with the local trust store.
    - <option not set>—Same as off.

### [+] Configuring the GAX MS SQL Database for TLS

# Configuring the GAX Database for TLS (Microsoft SQL Server)

#### **Prerequisites**

- Setting up the Genesys Administrator database (for Microsoft SQL Server).
- Ensure that you are using the latest JTDS driver (1.2.5 or later).

#### Steps

- 1. Configure Microsoft SQL Server as described in the related database guides.
- Set the level of TLS control on the DAP.
  - a. In the GAX section of the DAP, create an option that is named tls mode.
  - b. Specify one of the following values for the tls mode option:
    - off—Do not use TLS.
    - request—If the server supports TLS, it is used.
    - required—If the server does not support TLS, the connection is revoked.
    - authentication—GAX validates the server-send certificate against the local trust store.
    - <option not set>—Same as off.
- Verify that the configured port is identical to the TLS listener port of Microsoft SQL Server
- Due to an incompatibility between newer versions of Java and the Microsoft SQL Server driver, disable CBC Protection to enable GAX to connect to a Microsoft SQL Server database.
  - For Windows, add the following line to the setenv.bat file:

set JAVA OPTS=%JAVA OPTS% -Djsse.enableCBCProtection=false

For Linux, add the following line to the setenv.sh file:

JAVA OPTS="\$JAVA OPTS -Djsse.enableCBCProtection=false"

#### [+] Configuring the GAX PostgreSQL Database for TLS

# Configuring the GAX Database for TLS (PostgreSQL)

### **Prerequisites**

Setting up the Genesys Administrator database (for PostgreSQL).

#### **Steps**

- 1. Configure PostgreSQL as described in the related database guides.
- Set the level of TLS control on the DAP.
  - a. In the GAX section of the DAP, create an option that is named tls mode.
  - b. Specify one of the following values for the tls mode option:
    - off—Do not use TLS.
    - required—If the server does not support TLS, the connection is revoked.
    - authentication—GAX validates the server-send certificate with the local trust store.
    - <option not set>—Same as off.

## **Cross-site Scripting and Cookies**

You can configure your system to improve the protection of Genesys Administrator Extension against Cross-site Scripting (XSS) attacks by configuring the HttpOnly and Secure flags on your HTTP server to further enhance the existing GAX security. These flags tell browsers how to handle cookies.

Server-side cookies can be tagged with <code>HttpOnly</code> and <code>Secure</code> flags to tell the browser how to deal with them. To achieve a maximum level of security, administrators must make this configuration on the Application Server.

### **Securing Server-side Cookies**

#### **HttpOnly Flag**

Setting the HttpOnly flag on cookies forces the browser to prevent (disallow) scripts from accessing the cookies. This prevents JavaScript that might be introduced through an XSS attack into a browser page to access cookie data and send it to a different person. Stolen cookie data can also be used to hijack a browser session.

To setup and configure the <code>HttpOnly</code> flag, open and edit the <code>\$CATALINA\_HOME/conf/context.xml</code> file.

To set the HttpOnly flag, add the following attribute:

```
useHttpOnly="true"
```

#### The main tag should be:

```
<Context useHttpOnly="true">
```

Instead of: <Context>

When GAX is running on an embedded Jetty system, GAX automatically sets the HttpOnly flag on the JSESSIONID session cookie. You can turn off this flag by adding the following line in the gax.properties file:

```
session httponly = false
```

#### Secure Flag

With the Secure flag set, cookies are transmitted only from the browser to the server when the connection is secured by using the HTTPS protocol. This setting is applicable to HTTPS connections only. Therefore, you must configure GAX to use an HTTPS connector, not an HTTP connector.

To setup and configure the <code>HttpOnly</code> flag, open and edit the <code>\$CATALINA\_HOME/conf/server.xml</code> file.

To set the Secure flag, add the following attribute to the HTTPS connector:

```
secure="true"
```

The flag must not be applied to any non-HTTPS connectors. If you apply the flag to an HTTP connection, it will become unusable for Genesys Administrator Extension.

The following is an example of a valid connector:

```
<Connector port="8443" protocol="HTTP/1.1" SSLEnabled="true"
maxThreads="150" scheme="https" secure="true"
keystoreFile="/home/gcti/keystore.key" keystorePass="genesys"
clientAuth="false" sslProtocol="TLS" />
```

When GAX is running on an embedded Jetty system and **supported\_protocol** is set to https in **gax.properties**, GAX automatically sets the Secure flag on the JSESSIONID session cookie. You can turn off this flag by adding the following line to the **gax.properties** file:

```
session securecookies = false
```

## **Inactivity Timeout**

For security purposes, GAX can be configured to lock the application if an administrator has not used the keyboard or mouse for a period that you specify. All user input is blocked until the administrator provides login information to unlock the application. This feature ensures that no unauthorized user can access an unattended terminal that is running GAX.

Use the <code>inactivity\_timeout</code> option to specify the amount of time in minutes of administrator inactivity (no mouse or keyboard usage) that triggers application locking. If the administrator has been inactive longer than the number of minutes that are specified by the <code>inactivity\_timeout</code> option, the administrator must re-authenticate to be able to use the GAX application. A value of <code>0</code> disables this functionality.

GAX employs a keep-alive strategy to prevent *session* timeout; this ensures that GAX maintains your session even if the inactivity timeout feature locks the application and requires you to log in.

## **Configuring the Auditing Feature**

The auditing feature writes data to Message Server about activities in Operational Parameter Management and Solution Definitions, and Message Server writes the data to the Genesys Log database. Auditing data is made available to the GAX user by selecting the **History** option in the **Related** menu in the panel of certain items in the GAX user interface.

The auditing feature reads the information from the Log database and enables you to view the change history of objects such as Parameter Groups.

## **GAX Application**

Enable auditing by setting the value of the auditing option in the general section of the GAX Server application to true.

Next, in the general section of the GAX application, make the following configuration option settings:

- Set the number of switch-over attempts before GAX tries to switch-over to the redundant node to 1. To do this, set the value of the max\_switchovers option in the general section of the GAX application to 1. A value of 0 means switch-overs are disabled. Negative values allow an unlimited numbers of switch-overs, and, therefore, a continuous reconnect process if the server is unreachable. Setting a negative value is recommended for production systems.
- Set the number of connection attempts before GAX tries to switch over to the redundant node. To do this, set the value of the attempts option in the general section of the GAX application to 1.
- Set the timeout interval between connection attempts to Message Server. To do this, set the value of the warmstandby\_timeout option in the general section of the GAX application to any positive integer.
- Set the protocol timeout, which is the time in seconds after which GAX gives up attempting to connect. To do this, set the value of the timeout option in the general section of the GAX application to 30.

## Message Server

In the Message Server object, set the db\_storage option in the messages section to the value true.

If the db\_storage option is not set to true, Message Server does not save the audit data to its database.


## **Database Configuration**

To read the audit data from the Log Database, a DAP (Database Access Point) must be configured and connected to the GAX Server Application object. Configure the DAP in the same way that DAPs were configured for the GAX database. To identify the DAP role, set the value of the role option in the GAX section of the DAP to auditing.

You can now view auditing information in certain panels by clicking the **Related** button and selecting the **History** option.

## Plug-ins

Genesys Administrator Extension is deployed as a set of plug-ins into the GAX Core. This enables you to deploy only the functionality that you require, or to restrict the availability of certain functionality to users.



GAX is based on a hierarchical dependency system. The **gax-core** plug-in depends on the **gax-common** plug-in. The **gax-plugin-api** plug-in depends on the **gax-core** and **gax-common** plug-ins. All other GAX plug-ins depend on the **gax-plugin-api** and **gax-common** plug-ins.

The **gax-common** plug-in contains classes, such as error codes, exceptions, static utility classes, and interfaces, that are shared by both the **gax-core** and **gax-plugin-api** plug-ins. Most auditing related interfaces and objects are contained in the **gax-common** plug-in.

The **gax-core** plug-in manages all system-wide resources; therefore, all connections, threads, and stateful classes are contained in the **gax-core** plug-in.

The **gax-plugin-api** plug-in contains GAX functionalities that are used by other plug-ins. This plug-in contains generic configuration APIs, the base class of web access controller (BaseController), and other utility classes.

The **gax-webservice** plug-in contains all core web service interfaces that might be used in GAX.

### **Important**

If a plug-in contains configuration options, you must have write permissions on the GAX Application object for **SYSTEM**.

## **Managing Plug-ins**

The **Plug-in Management** screen displays all installed plug-ins in your GAX environment. To access the screen, navigate to **Administration > Plug-in Management**.

You can click on the name of a plug-in to view additional details, such as which server hosts the plug-in. Click **Plug-ins** to display more information, which displays in a new panel to the right:

- Name—The name of the plug-in
- **Version**—The version number of the plug-in.
- Language—The language used by the interface of the plug-in
- **Provider**—The name of the user or company that provided the plug-in
- **State**—This field can be set to **Enabled** or **Disabled**, depending on the status of the plug-in. See Enabling or disabling a plug-in in GAX for more information.

The following actions can be performed in the **Plug-in Management** area:

- Plug-ins can be installed.
  - If your GAX instance uses Jetty, see Installing Plug-ins with the Software Installation Wizard.
  - If your GAX instance uses Tomcat, or the plug-in is designed for GAX 8.1.3 or earlier, see Installing Legacy Plug-ins.

- Language packs can be installed. See Installing Language Packs for more information.
- Plug-in options can be modified. See Modifying plug-in settings for more information.
- Plug-ins can be enabled or disabled. See Enabling or disabling a plug-in in GAX for more information.
- Plug-ins can be removed. See Removing a plug-in from GAX for more information.

### Installing Plug-ins with the Software Installation Wizard

### **Important**

- The plug-in install profile automatically fetches GAX Application objects for selected Host objects.
- Plug-in options are merged into the affected GAX Application objects. See the Deployment Wizard tab in the Genesys Administrator Extension Help for detailed information.

### [+] Click here to show procedure

# Installing Plug-ins with the Software Installation Wizard

**Purpose:** To install plug-ins that are designed for GAX instances that use Jetty.

#### **Prerequisites**

- GAX is installed and deployed, as described in Deploying Genesys Administrator Extension.
- GAX has been started at least once.
- GDA is installed and running on the target machine.

#### **Steps**

- 1. In the **Installation Packages** panel, click **+**. A new panel called **Software Installation Wizard** opens to the right.
- 2. In the Software Installation Wizard panel, select a method for importing the plug-in:

### **Important**

If your installation package contains two or more templates, you must use the **Installation Package Upload (includes templates)** procedure.

0

- Installation Package Upload (includes templates)—Upload a ZIP file that contains an installation package and its associated templates. These files are typically provided by Genesys Technical Support.
- In the Software Installation Wizard panel, select Installation Package Upload (includes templates) and click Next.
- ii. The panel updates. Click **Choose File** to select the file to upload.
- iii. Click Finish.

0

- Installation Package Upload (template uploaded separately)—Upload an installation package and its associated template.
- i. In the Software Installation Wizard panel, select Installation Package Upload (template uploaded separately) and click Next.
- ii. The panel updates and displays three boxes—Upload a package, Upload an XML template, and Upload an APD template. Click Choose File in each field to select the file to upload.
  - Upload a package—A ZIP file that contains the installation package.
  - Upload an XML template—The XML template file for this installation package. This is the template that is referenced by the installation package description file. This file must not be modified from the version in the template directory.
  - Upload an APD template—The APD template file for this installation package. This is the template that is referenced by the installation package description file. This file must not be modified from the version in the template directory.
- iv. Click Finish.

0

 UNC Path to Mounted CD or Directory—Upload an installation package that is stored on a mounted CD or network directory.

- i. In the Software Installation Wizard panel, select UNC Path to Mounted CD or Directory and click Next.
- ii. In the text field, enter the path for where the installation package is stored.
- iii. Click **Next** to open the path.
- iv. The panel updates to display the installation package(s) that is found at the specified location. Click the check box(es) that is beside the installation package(s) to upload.
- v. Click Finish.

0

- UNC Path to an Existing Administrator Repository—Upload an installation package from an existing Genesys Administrator repository.
- In the Software Installation Wizard panel, select UNC Path to an Existing Administrator Repository and click Next.
- ii. In the text field, enter the path for the existing Genesys Administrator repository.
- iii. Click Next to open the path.
- iv. The panel updates to display the installation package(s) that is found at the specified location. Click the check box(es) that is beside the installation package(s) to upload.
- v. Click Finish.

0

- UNC Path to Zipped IPs through Support—Upload a .zip file provided by Genesys Customer Care that is stored on a mounted CD or network directory. This file contains an installation package and its associated templates.
- In the Software Installation Wizard panel, select UNC Path to Zipped IPs through Support and click Next.
- ii. In the text field, enter the path for where the IP is stored.
- iii. Click **Next** to open the path.
- iv. The panel updates to display the installation package(s) that is found at the specified location. Click the check box(es) that is beside the installation package(s) to upload.
- v. Click Finish.

## **Important**

When you upload a plug-in, GAX uses the template file (.tpl) to create an Application Template and extracts the default options for the plug-in. GAX stores these options in the database and merges them with the core GAX Application object upon deployment. During this

merge, only new options are added—existing key value pairs are not overridden.

- The file(s) upload from your file system to Genesys Administrator Extension and a
  progress bar displays to show the upload progress. The progress of the upload also
  displays in the Status column in the Installation Packages panel.
- 7. Deploy the plug-in by using the **Automated Deployment Wizard** (this method is also used to deploy installation packages). For more information, refer to the heading Deploy Installation Packages in the Genesys Administrator Extension Help.

### **Important**

- A green progress bar represents a successful upload for the installation package. A red progress bar represents a failed upload for the installation package. You can review which step failed in the Status field in the Installation Packages list.
- You cannot upload a plug-in to the repository if a version of the plug-in already exists in the repository. You must have the Replace IPs and SPDs privilege enabled to overwrite a plug-in in the repository.

## **Installing Legacy Plug-ins**

[+] Click here to show procedure

## **Installing Legacy Plug-ins**

**Purpose:** To install plug-ins that are designed for GAX 8.1.3 releases or earlier, or to install plug-ins for GAX instances that use Tomcat.

#### **Prerequisites**

The CATALINA\_HOME variable exists.

- The path <CATALINA\_HOME>/webapps/gax/WEB-INF/lib/ exists.
- GDA is installed and running on the target machine.

#### **Steps**

- 1. Install the plug-in as indicated in the procedure Installing Plug-ins with the Software Installation Wizard.
- 2. The installation process copies .jar files to the following folder: <CATALINA HOME>/webapps/gax/WEB-INF/lib/.
- 3. (Optional) If you are using GAX with Jetty, you must copy the plug-in's .jar files to <GAX FOLDER>/webapp/WEB-INF/lib.
- 4. Restart GAX.

### Installing Language Packs

[+] Click here to show procedure

## **Installing Language Packs**

#### **Steps**

- 1. Copy the Language Pack IP to the host machine.
- 2. Stop GAX (if it is running).
- 3. Run the **setup.exe** (Windows) or **install.sh** (Linux) installation file.
- 4. Follow the prompts in the installer to install the Language Pack.
- Restart GAX.

### Important

Product translation is limited to contents of this product only. Display data coming from other products might appear in English.

See the Genesys Administrator Extension Help for more information on how to select an installed Language Pack to use with GAX.

## Modifying plug-in settings

#### [+] Click here to show procedure

## Modifying plug-in settings

#### **Steps**

- 1. Select an application in the **Administrator Applications** list. A new panel opens to the right.
- Click Plug-ins to view which plug-ins are associated with the application. A new panel opens to the right.
- 3. Select a plug-in in the **Plug-in Info** list. A new panel opens to the right.
- 4. Click **Plug-in Options**. A new panel opens to the right. The panel displays the options that are associated with the plug-in.
- 5. Click an option to view more information about the option in a separate panel that opens to the right.
- 6. When you have finished modifying the option(s), perform one of the following actions:
  - Click Save to save your changes.
  - Click Cancel to discard your changes.

## Enabling or disabling a plug-in in GAX

## Important

- It is not possible to disable the gax-core plug-in.
- The option to enable or disable a plug-in is available only for the application or node to which the user is currently connected. Other GAX applications or nodes will provide a link to manually log in to that instance.

## [+] Click to show procedure

## Enabling or disabling a plug-in in GAX

#### **Steps**

- 1. Select an item in the **Administrator Applications** list. More information about the item displays in a new panel to the right.
- 2. Click **Plug-ins**. More information about the plug-ins for the item display in a panel to the right.
- 3. Select a plug-in from the list.
- 4. Do one of the following:
  - If the plug-in is currently enabled, the **Disable** button is displayed. Click
     **Disable** to disable the plug-in.
  - If the plug-in is currently disabled, the **Enable** button is displayed. Click **Enable** to enable the plug-in.

#### Important

To see the changes to the plug-in, refresh the display in your browser.

## Removing a plug-in from GAX

[+] Click to show procedure

## Removing a plug-in from GAX

#### **Steps**

- 1. Stop GAX.
- 2. Go to **GAX\_HOME**>/webapp/WEB-INF/lib on the file system (where **GAX\_HOME**> is your home folder for the GAX application).
- 3. Delete the .jar files for the plug-ins that you want to remove.
- 4. Go to **<GAX\_HOME>/webapp/plugins** on the file system (where **<GAX\_HOME>** is your home folder for the GAX application).
- 5. Delete the folder for the plug-ins that you want to remove.
- 6. Start GAX.

## **Upgrading GAX**

This page describes how to upgrade GAX from previous versions to the current version. Before you begin, it is recommended that you review the Setting Up Genesys Administrator Extension page to learn more about prerequisites, supported browsers, and other useful upgrade information.

To begin, click the tab below that applies to your system.

### **Important**

Genesys Administrator Extension uses an embedded instance of Jetty for web-server functions, whereas previous releases have used Tomcat. The upgrade procedures below explain how to upgrade GAX to use Jetty. To continue using Tomcat, you must remove the old <Tomcat Home>/webapps/gax folder and copy the new gax.war file from the GAX installation folder to the <Tomcat Home>/webapps folder.

**Upgrading GAX (Management Framework 8.1.1 or higher)** 

Upgrading GAX (Management Framework 8.1.1 or Higher)

#### Steps

- 1. Stop the instance of GAX that you want to upgrade.
- Ensure that Management Framework, Configuration Server, and Genesys
  Administrator are all upgraded to versions that are compatible with the latest version
  of GAX before proceeding (refer to Prerequisites for Genesys Administrator
  Extension Modules).
- 3. Click the option below that describes your GAX environment. You can skip this step if your GAX Application object type is **Genesys Administrator Server** and you do not intend to use the Pulse 8.5 plug-in.

## "[+] Click here if your GAX Application object is of type "Genesys Generic Server"

Create and configure the configuration objects that are required for the latest version of GAX by using Genesys Administrator to perform the following steps:

- a. Open your existing GAX Application object of type Genesys Generic Server in edit mode.
- b. Click the **Options** tab.
- Click Export to save your configured GAX options to a file on your local file system of type CONF/CFG.
- d. Create and configure a new Server Application object for Genesys Administrator Extension of type **Genesys Administrator Server** by following Step 4 of Creating the necessary configuration objects for Genesys Administrator Extension.
  - Ensure that you follow the steps that pertain to the use of Management Framework Configuration Server 8.1.1, or higher.
  - ii. Replicate any configuration that you wish to add to your newly created Application object by referring to the GAX Application object of your previous version.
  - iii. Click the Options tab.
  - iv. Click **Import** and specify the **CONF/CFG** file that you previously created. Select **No** to not overwrite any existing options.
  - v. (Optional) Create a DAP that points to the Log Database (refer to Step 3 of Creating the necessary configuration objects for Genesys Administrator Extension. Set the role of the DAP to auditing. Enable auditing by setting the value of the **general/auditing** option to **true**. Add the DAP to your GAX connections. On the **Options** tab of the DAP, in the **GAX** section, configure the **role** option with the value auditing.

#### "[+] Click here if you intend to use the Pulse 8.5 plug-in"

You must reuse the existing GAX Application object if you intend to migrate to Pulse 8.5. To do so, use Genesys Administrator to perform the steps below:

- a. Upload the GAX 8.5 Application Template. Refer to the Genesys Administrator 8.1 Help for additional instructions on how to upload Application Templates.
- b. Open the GAX 8.5 Application Template object.
- c. Click the **Options** tab.

- d. Click **Export** to save your configured GAX options to a file on your local file system of type **CONF/CFG**.
- e. Close the GAX 8.5 Application Template.
- f. Open your existing GAX Application object.
- g. Click the **Options** tab.
- h. Click Import and specify the CONF/CFG file that you previously created from the GAX 8.5 Application Template. Select No to not overwrite any existing options.
- i. Click Save & Close.
- (Optional) If you want to retain the installed plug-ins that you used with GAX 8.1.4, go to the GAX folder and back up the webapp folder by renaming it to webapp\_backup.
- 5. On the target machine, run the GAX installer for the release to which you want to upgrade. The installer copies the binary file and all of the required files to the target directory. See Install the GAX server on a host for more information.
- 6. Execute all applicable database upgrade scripts, if necessary. To determine if you have to apply any database scripts:
  - i. Execute the following SQL statement upon your existing GAX database: select \* from db schema version.
  - ii. Compare the result with the update scripts in the **resources/sql\_scripts** folder in the target directory of the installation.

## **Important**

The latest database schema versions are:

- asd—8.5.000.01
- opm-arm—8.1.301.01
- core—8.1.301.01

The following examples list the upgrade scripts for Solution Deployment:

- (Oracle only) gax\_asd\_upgrade\_db\_8.1.320.01\_to\_8.5.000.01\_ora.sql
- (Microsoft SQL only)

```
gax_asd_upgrade_db_8.1.320.01_to_8.5.000.01_mssql.sql
```

(PostgreSQL only)

```
gax_asd_upgrade_db_8.1.320.01_to_8.5.000.01_postgres.sql
```

- 4. As a local user on the host machine, whether in person or via a remote desktop connection, launch GAX and run Setup Mode. Follow the instructions in the procedure Deploy GAX Using Setup Mode (Existing Deployment).
- 5. (Optional) You can delete the previous GAX Application object after you have verified that the new release is working correctly.

- To use the System Dashboard feature, you must set up a connection to Solution Control Server (SCS). Refer to the procedure Adding a Connection to SCS from GAX for more information.
- 7. If you backed up the **webapp** folder in Step 4 to **webapp\_backup**, you must perform the following actions:
  - a. Stop GAX.
  - b. Copy the plug-in .jar files from **webapp\_backup** to the new **webapp** folder in the GAX 8.5.0 installation folder.
  - c. Delete the webapp backup folder.
  - d. Start GAX.

### **Important**

- Some plug-ins might require additional configuration. Refer to the plug-in documentation for more information about installing and configuring the plug-in.
- You must upload the plug-in installation package into GAX if the plug-in contains new privileges.
- If you are migrating from Tomcat to Jetty, you might need to update the paths used in the asd configuration options if they refer to the {CATALINA\_HOME} variable that was previously used by Tomcat.

**Upgrading GAX (Management Framework 8.1.0 or Lower)** 

Upgrading GAX (Management Framework 8.1.0 or Lower)

OLOPO
-------

Important

Refer to Known Issues for information about using Management Framework versions prior to the 8.1.0 release.

- 1. Stop the instance of GAX that you intend to upgrade.
- 2. (Optional) Complete this step if you intend to migrate an earlier version of Pulse to Pulse 8.5.

You must reuse the existing GAX Application object if you intend to migrate to Pulse 8.5. To do so, use Genesys Administrator to perform the steps below:

- Upload the GAX 8.5 Application Template. Refer to the Genesys Administrator 8.1 Help for additional instructions on how to upload Application Templates.
- b. Open the GAX 8.5 Application Template object.
- c. Click the **Options** tab.
- d. Click **Export** to save your configured GAX options to a file on your local file system of type **CONF/CFG**.
- e. Close the GAX 8.5 Application Template.
- f. Open your existing GAX Application object.
- g. Click the **Options** tab.
- h. Click **Import** and specify the **CONF/CFG** file that you previously created from the GAX 8.5 Application Template. Select **No** to not overwrite any existing options.
- i. Click Save & Close.
- (Optional) If you want to retain the installed plug-ins that you used with GAX 8.1.4, go to the GAX folder and back up the webapp folder by renaming it to webapp\_backup.
- 11. On the target machine, run the GAX installer for the release to which you want to upgrade. The installer copies the binary file to the target directory that was defined during installation, and also copies all of the required files to the target directory. See Install the GAX server on a host for more information.
- 12. Execute all of the applicable database upgrade scripts, if necessary. To determine if you have to apply any database scripts:
  - i. Execute the following SQL statement upon your existing GAX database: select \* from db\_schema\_version.
  - ii. Compare the result with the update scripts in the **resources/sql\_scripts** folder in the target directory of the installation.

Im	po	rta	nt
	_		

The latest database schema versions are:

- asd—8.5.000.01
- opm-arm—8.1.301.01
- core—8.1.301.01

The following examples list the upgrade scripts for Solution Deployment:

- (Oracle only) gax asd upgrade db 8.1.320.01 to 8.5.000.01 ora.sql
- (Microsoft SQL only)

gax\_asd\_upgrade\_db\_8.1.320.01\_to\_8.5.000.01\_mssql.sql

(PostgreSQL only)

gax\_asd\_upgrade\_db\_8.1.320.01\_to\_8.5.000.01\_postgres.sql

- 4. As a local user on the host machine, whether in person or via a remote desktop connection, launch GAX and run Setup Mode. Follow the instructions in the procedure Deploy GAX Using Setup Mode (Existing Deployment).
- 5. (Optional) You can delete the previous GAX Application object after you have verified that the new release is working correctly; however, you can choose to maintain both versions simultaneously.
- To use the System Dashboard feature, you must set up a connection to Solution Control Server (SCS). Refer to the procedure Adding a Connection to SCS from GAX for more information.
- 7. If you backed up the **webapp** folder in Step 4 to **webapp\_backup**, you must perform the following actions:
  - a. Stop GAX.
  - b. Copy the plug-in .jar files from **webapp\_backup** to the new **webapp** folder in the GAX 8.5.0 installation folder.
  - c. Delete the **webapp\_backup** folder.
  - d. Start GAX.

## **Important**

- Some plug-ins might require additional configuration. Refer to the plug-in documentation for more information about installing and configuring the plug-in.
- You must upload the plug-in installation package into GAX if the plug-in contains new privileges.
- If you are migrating from Tomcat to Jetty, you might need to update the paths used in the asd

configuration options if they refer to the **{CATALINA\_HOME}** variable that was previously used by Tomcat.

### **Important**

- Role privileges must be renewed if the application type is changed. Genesys stores role privileges that are associated with the application type to which they apply, but since GAX is associated with Genesys Administrator Server in 8.1.1 releases of Management Framework (for GAX 8.1.2 and higher), not Genesys Generic Server, the role privileges must be set using the correct type.
- Database upgrade scripts that have version numbers prior to the ones from which you upgraded do not have to be executed. You must log in to the database schema as a GAX user and run the commands inside the SQL scripts as commands for the database.
- If you are installing GAX for the first time or upgrading from release 8.1.4 to 8.5.0, when you execute the SQL upgrade scripts, make sure that the scripts are properly committed. If your client application has auto-commit switched off, you might have to add the following line(s) to the scripts:

For Oracle: commit;For MS SQL: BEGIN

TRANSACTION; COMMIT TRANSACTION;

For PostgreSQL: commit;

## **Customizing the GAX Homepage**

When Genesys Administrator Extension is launched, it opens to the default homepage view. The default view is a placeholder that you can customize to suit your business needs.

The homepage is an HTML document (home.html) and a style sheet (home.css) that are stored in the following location after you install GAX: <gax-installation-dir>\webapp\ plugins\gax-core\home\

The file **home.html** is a document fragment. It does not contain all of the standard HTML tags. The default, temporary content is the following:

```
<div class="home-container">
        <h1>Welcome to ${GENESYS_ADMINISTRATOR_EXTENSION}</h1>
        This is a placholder page for the Home module. You can customize it by editing home.html and home.css.
</div>
```

You can change the contents of this page to suit your requirements.

The style sheet file can also be modified to suit your requirements. The default contents are as follows:

```
.home-container {
    padding: 16px;
    height: 400px;
    background-image: url(i/background.jpg);
    background-repeat: no-repeat;
}Genesys recommends that you use a class prefix like "'''home-'''"
to prevent clashes with class names that are used elsewhere within GAX.
```

The images that are referenced by the CSS file are in the folder that is named "i" in the same folder as **home.css**. You can store as many image files as you require in this folder. Reference your images in the CSS file.

After you edit the **home.html** file, click **Refresh** in the GAX interface to display your updates.

# Cleaning the GAX Database After a Tenant is Deleted

If a tenant has been deleted from your environment, some data from that tenant might not be removed from the GAX database.

For more information on how to clean the GAX database after a tenant is deleted, please contact Genesys Customer Care.

## Accessing Genesys Administrator Extension

This chapter describes how to log in to, and out of, Genesys Administrator Extension.

This chapter contains the following sections:

- Logging In
- Logging In Remotely
- Logging In to Genesys Administrator from GAX
- Logging Out
- Starting and Stopping GAX

## **Logging In**

The Genesys Administrator Extension web-based interface runs on a web application server. It is loaded into your browser each time that you open the website where you installed Genesys Administrator Extension. You then log in.

### **Important**

Genesys Administrator Extension supports the use of blank passwords only if Configuration Server is configured to allow blank passwords. Refer to the *Genesys Security Deployment Guide* for information about using blank passwords.

## Logging in to Genesys Administrator Extension

#### **Prerequisites**

- Configuration DB Server and Configuration Server are installed and running.
- An instance of a Genesys Administrator Extension Application object is connected to Configuration Server and running.
- Your browser and its windows are set to a resolution of 1024x768 or greater. If you are working in 1024x768, maximize the browser.
- The user logging in must have Read permission to their own User object and Read and Execute permissions on the Genesys Administrator Extension client object.

Refer to the *Genesys Security Deployment Guide* for information about permissions. Genesys Administrator Extension respects read-write permissions that are set for Environments and Tenants. You can only access those objects that you have permission to see.

#### **Steps**

- 1. Start GAX.
- Open a web browser.
- 3. Enter the following URL in the address bar of the browser:

```
http://<Host name>:8080/gax/
```

where <Host name> is the name of the computer on which you installed Genesys Administrator Extension. The port number is the port that was defined when setting up GAX in Deploying Genesys Administrator Extension.

4. Log in to Genesys Administrator Extension with your assigned user name and password, and click **Log in**.

### **Important**

Each instance of Genesys Administrator Extension is associated with a single instance of Management Framework; Configuration Server and Port selection is not required during login, nor is it possible to select it.

If you get a permissions error, refer to Required Permissions for instructions.

Your login name is displayed in the Header Bar of the Genesys Administrator Extension window. Select **About** in the Profile menu to see when you last logged in.

## **Important**

The date and time of the local machine and the Management Framework machine must be synchronized for the last login time to be accurate.

- 5. Your account might be configured to set a new password the first time that you log in, or after a system administrator has reset your password. The **Change Password** dialog box is displayed:
  - a. Enter a new password in the **New Password** field.
  - b. Enter the same password in the **Confirm Password** field.
  - c. Click OK.

### **Important**

Please see the *Genesys Security Deployment Guide* for more information about resetting passwords.

## **Logging In Remotely**

Genesys Administrator Extension supports remote logins for users who might access GAX through a customized login page that is located on another website (for example, a corporate portal page).

In this scenario, the company network can pass the user's credentials to GAX, and GAX automatically logs in the user via a background process so that the user bypasses the login screen.

In addition, a logout URL can be set so the user returns to the company portal page after logging out of GAX.

To use this feature, the customized login page must submit a form to the GAX login page. The following is an example:

```
<form name="logon" action="" method="post" onsubmit = "logonGax()">
UserID:<input type="text" name="username">
Password:<input type="password" name="password">
<input type="hidden" name="newPassword" value=""><
input type="hidden" name="newPasswordConfirm" value="">
<input type="hidden" name="login_success_url" value=""><
input type="hidden" name="logout_url" value=""><
input type="hidden" name="logout_url" value=""><
<p><input type="submit" value="Login">
</form>
```

The following values can be set:

- The login\_success\_url value can be set to the URL for the GAX login page. If
  this value is not set, the page is redirected to itself and the URL is appended with
  #success.
- The <code>login\_failure\_url</code> value can be set to a URL to which the user will be directed if the supplied credentials are invalid. If this value is not set, the page is redirected to itself and the URL is appended with <code>#failure</code>.
- The logout\_url value can be set to a URL to which the user will be directed after logging out of GAX. If this value is not set, the user is redirected to the initial credential screen and the URL is appended with #logout.

You can also define a list of trusted URLs, called whitelisted hosts, to which these three variables can be set. Use the **host\_whitelist** and **host\_whitelist\_enabled** options, as described in the security section.

## **Logging In to Genesys Administrator from GAX**

You can access Genesys Administrator from GAX by using the **gax-ga** plug-in that is part of the core plug-ins that are installed when you install GAX. Your role, and the credentials that you use to log in to GAX, must enable you to access Genesys Administrator.

Login to Genesys Administrator occurs during your login to GAX (refer to Logging in to Genesys Administrator Extension).

When you enter your GAX login credentials and click **Log in**, the following process is started:

- 1. The Log In button becomes disabled.
- A progress indicator is displayed.
- 3. The credentials and role that enable you to log in to GAX and Genesys Administrator are verified by GAX.
- 4. The GAX interface is displayed.
- 5. If you are permitted to use Genesys Administrator, a menu that enables you to link to Genesys Administrator is displayed.
- 6. If you click the **Genesys Administrator** menu, you can select one of the following views in Genesys Administrator:
  - MONITORING > Environment > Dashboard
  - PROVISIONING > Environment > Applications > New Application
  - DEPLOYMENT > Repository > Installation Packages
  - OPERATIONS > Outbound Contact > Dialing Sessions

Genesys Administrator is launched in a new browser tab or window. The content that is displayed depends on your privileges and access.

7. If you log out of Genesys Administrator, you can continue to use GAX. If you log out of GAX, you are also logged out of Genesys Administrator.

## **Logging Out**

To log out of Genesys Administrator Extension, click on your user name in the Header Bar and select **Log Out**.

## **Starting and Stopping GAX**

There are several ways to start and stop GAX, depending on your operating system.

### Linux

Linux users can start and stop GAX by using one of the following methods:

- The System Dashboard in GAX.
- Genesys Administrator
- Solution Control Interface (SCI)

Please refer to the product documentation for details on how to start and stop an Application.

### **Windows**

Windows users can start and stop GAX by using one of the following methods:

- The System Dashboard in GAX.
- Genesys Administrator
- Solution Control Interface (SCI)
- Restarting the GAX Windows Service

Please refer to the product documentation for details on how to start and stop an Application.

## Important

You cannot use the GAX System Dashboard to stop the GAX instance you are currently using.

Troubleshooting Plug-in Issues

## Troubleshooting

Follow the suggestions in this chapter if your Genesys Administrator Extension installation does not seem to work correctly.

This chapter contains the following sections:

- Plug-in Issues
- Required Permissions
- Deployment Issues
- Running Out of Memory
- Tomcat Issues
- Browser Issues

## Plug-in Issues

Genesys Administrator Extension is built upon the Spring Framework and is deployed as a set of plug-ins. If one of these plug-ins fails to load, the entire GAX instance fails to start.

If you install a plug-in and then GAX fails to start, you can try to fix the problem by removing the plug-in and restarting GAX. If GAX starts correctly after the plug-in is removed, the problem is with the plug-in and not within the rest of the GAX instance.

## **Required Permissions**

Access to Genesys Administrator Extension and its functionality is protected by user permissions and Role-Based Access Control. If you get a permissions error when you try to log in to Genesys Administrator Extension or use any of its functionality, you probably do not have the appropriate permissions or role privileges.

An example of a required permission is this: a Tenant user must have write (Create) permission on his or her own User object to save his or her User Preferences in Genesys Administrator Extension.

Refer to the *Genesys Security Deployment Guide* for more information about permissions and Role-Based Access Control, including how to set up appropriate permissions and role privileges.

Troubleshooting Deployment Issues

## **Deployment Issues**

## **Using Setup Mode**

If you are unable to use GAX after you have used Setup Mode to deploy it, you probably encountered some interruption during the deployment. Any interruption in the Setup Mode process might result in only partial and incomplete configuration of your environment.

To resolve this, reset Configuration Server and the Configuration Database to their initial values. Stop any running Configuration Server processes. Then restart the deployment, using Setup Mode, from scratch.

**Recommendation:** When deploying GAX to an existing Management Framework deployment, make sure that the host property of the Configuration Server application is set.

## **Running Out of Memory**

If you are working with a large amount of data, such as deploying large or multiple Solutions with Solution Deployment, the installation process might fail with one or both of the following indicators:

• In the **gax.log**, the following entry:

lang.OutOfMemoryError: Java heap space

• In the Genesys Administrator Extension interface, on the Solutions Packages screen, there might be an error message similar to:

Error while fetching lists of dns. There has been a server error.

This error is caused when the Java heap space is not large enough to support the current process. The default size of the heap is 64 MB. In the default installation, the heap size is set to 1024 MB (the Tomcat default is only 64 MB). If you still need to increase the memory assigned to Tomcat, do so by editing the **\$CATALINA\_HOME/bin/setenv.sh** (Linux) file or **\$CATALINA\_HOME/bin/setenv.bat** (Windows) file and adjusting the memory value.

However, if you still see these errors, increase the size of the heap as necessary.

Troubleshooting Tomcat Issues

## **Tomcat Issues**

If you encounter problems with your Tomcat host, you can try the following to determine and resolve the problem:

- From the Tomcat host, ping Configuration Server and Solution Control Server by name and by IP address.
- From Solution Control Server, ping the Tomcat Host by name and by IP address.
- From Solution Control Server, telnet to the Tomcat host on all ports, disabling SELinux or any firewalls if necessary.
- A dedicated Tomcat startup script for Genesys Administrator Extension sets the environment variable GAX\_CMD\_LINE\_ARGS. To check if this variable has been created correctly, use gax\_startup.sh and pass parameters using the command line, or use Solution Control Interface or Genesys Administrator.
- Check that Database Access Points are configured and connected.
- Check that the ojdbc6.jar file (for Oracle) or jtda-<version>.jar file (Microsoft SQL Server) has been copied into the Tomcat lib directory.
- Check that gzip compression is enabled in Tomcat for responses.

#### **Ports in Use**

The table below shows the typical ports used in a Genesys environment.

#### **Typical Ports Used**

Port	Description
22	Remote shell (ssh) connections
80	Webserver; can only be used by Tomcat if it is started from the root.
8080	Web server; any user starting Tomcat may use this
1521	Oracle database connections
1433	Microsoft SQL Server
4999	Local Control Agent
5000	Genesys Deployment Agent (GDA)

Troubleshooting Browser Issues

## **Browser Issues**

This section describes possible browser-related issues that you may encounter when deploying and using GAX.

## **Blocked Downloads in Internet Explorer 9**

If you are using Microsoft Internet Explorer (IE) 9, an attempt to download Audio Resource Files, encoded files, and other GAX downloads might be blocked by the IE information bar. After you confirm the download, you are redirected to the main page and then have to repeat the download request. You can adjust your browser settings to prevent this scenario.

This issue is not GAX-specific; it is related to your IE settings. To prevent IE 9 from blocking your GAX downloads, you must disable the download information bar for GAX downloads.

There are two approaches that you can take to solve this issue:

- Configuring IE 9 to allow all downloads without warnings
- Configuring IE 9 to allow GAX downloads without warnings

If you are using IE 10 or 11, the Windows Download Manager handles all download requests, and this problem does not occur.

## Configuring IE 9 to allow all downloads without warnings

This procedure disables the Information bar for all downloads. You will be able to download GAX files without being blocked; however, other content will also now be downloaded without warnings.

## [+] Click to show procedure

# Configuring IE 9 to allow all downloads without warnings

Purpose: To prevent the information bar from blocking GAX file and software downloads.

#### **Steps**

1. Launch Internet Explorer version 9.

Troubleshooting Browser Issues

- Click Tools.
- 3. Select Internet Options.
- 4. Select the **Security** tab.
- 5. Click Custom level.
- Scroll to the **Downloads** section of the list.
- 7. Click **Enable** under **File download** and under **Font download**.
- 8. Click OK.
- 9. Click **Yes** to confirm that you want to make the change.
- 10. Click **OK**.

The Information bar for file downloads is now turned off. You can download GAX files without being blocked by Internet Explorer.

#### Configuring IE 9 to allow GAX downloads without warnings

This procedure enables you to maintain your security settings when you download files from the internet, while making GAX a trusted site from which all your GAX files are downloaded without warnings in the Internet Explorer information bar. You can choose to run with the security level set to High.

#### [+] Click to show procedure

# Configuring IE 9 to allow GAX downloads without warnings

**Purpose:** Adjust the settings of Internet Explorer to make it less restrictive when you want to download GAX files.

#### Steps

- 1. Launch Internet Explorer 9.
- Open the GAX site URL.
- 3. Click Tools.
- 4. Select Internet Options.
- 5. Click the **Security** tab.
- 6. Click Trusted sites.
- 7. Click Sites.
- 8. In the **Add this website to the zone** field, verify that the GAX URL is displayed. If not, enter the website in the field. It is not necessary to include the port number.

Troubleshooting Browser Issues

- 9. Click Add.
- 10. De-select Require server verification (https:) for all sites in this zone.
- 11. Click Close.
- 12. Click Custom level.
- 13. Scroll to the **Downloads** section of the **Settings** list.
- 14. Click Enable under File download and under Font download.
- 15. Scroll to the **Scripting** section of the **Settings** list.
- 16. Under Active Scripting, click Enable.
- 17. Click **OK**.
- 18. Click Yes to confirm that you want to make the change.
- 19. In the Internet Options window, click OK.

The Information bar warnings for file downloads is now turned off for trusted sites only, and GAX is set as a trusted site.

# Audio Resource File Playback Issues in Internet Explorer and Firefox

Internet Explorer does not support playing an audio file directly. You must download the file and playback the file locally. Firefox cannot play  $\mu$ -law and A-law audio codecs. Only PCM Audio codecs can be played in Firefox.

#### Audio Resource File Playback Issue in Safari

Users of Safari cannot play Audio Resource files in Genesys Administrator Extension. This is because Safari does not support playing .wav files.

Role Privileges General

## Role Privileges

This section describes the role privileges that are available and enforced by Genesys Administrator Extension. The privileges are in a hierarchy based on the modules in Genesys Administrator Extension, as follows:

- General
- GA Direct Login Integration
- · Operational Parameter Management
- Solution Deployment
- · Configuration Object Management
- Agent Management
- Bulk Operations
- Audio Resources Management-Tenant
- Audio Resources Management-System
- Centralized Logs

For more information about role privileges specifically, and Role-Based Access Control in general, refer to the *Genesys Security Deployment Guide*.

#### **General**

The following privileges apply to Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

View Audit History Data	Enables users to read privilege auditing history information.
Read Plug-ins	Enables users to read nodes and plug-ins.
Write Plug-ins	Enables users to enable or disable plug-ins, and also enables users to modify plug-in options.
Read System Preferences	Enables users to read system preferences.
Access Dashboard	Enables users to access the System Dashboard.

Stay On Dashboard Indefinitely	Enables users to stay on a dashboard screen indefinitely, without being sent back to the login page due to inactivity.
Edit Default Dashboards	Enables users to edit the default dashboard.
Add Widget	Enables users to add a widget to any dashboard.
Move Widget	Enables users to move a widget around in any dashboard.
Edit Widget	Enables users to edit the configuration in any dashboard.
Clone Widget	Enables users to clone a widget in any dashboard.
Remove Widget	Enables users to remove a widget from any dashboard.
Edit Tab	Enables users to edit the configuration in any dashboard.
Clone Tab	Enables users to clone a tab in any dashboard.
Delete Tab	Enables users to remove a tab from any dashboard.
Reset Tab	Enables users to reset a tab from any dashboard.
Add Tab	Enables users to add a tab to any dashboard.

# **GA Direct Login Integration**

The following privileges apply to Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

# **Operational Parameter Management**

Operational Parameter Management role privileges control what tasks a user can do in the Operational Parameter Management module of Genesys Administrator Extension.

Role Privileges Solution Deployment

#### **Required Privileges**

None

#### **Role Privileges**

Read Parameters	Allows a user to view Operational Parameters for OPM. Prerequisites: None.
Write Parameters	Allows a user to create, update, and delete Operational Parameters for OPM. Prerequisites: <b>Read Parameters</b> .
Read Group Templates	Allows a user to view Parameter Group Templates.  Prerequisites: Read Parameters.
Write Group Templates	Allows a user to create, update, and delete Parameter Group Templates. Prerequisites: <b>Read Group Templates</b> .
Read Parameter Groups	Allows a user to view Parameter Groups. Prerequisites: None.
Update and Delete Parameter Groups	Allows a user to update or delete Parameter Groups.  Prerequisites: Read Parameter Groups.
Deploy and Re- associate Parameter Groups	Allows a user to deploy or re-associate Parameter Groups.  Prerequisites: Read Group Templates and Read Parameter Groups.

# **Solution Deployment**

Solution Deployment role privileges control what tasks a user can perform in the Solution Deployment module of Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

Delete IPs and SPDs	Delete privilege for IPs and SPDs of ASDs. This privilege is required to delete deployments. Prerequisite: <b>Read Deployable IPs and SPDs</b> .
Deploy IPs	Deploy privilege for IPs of ASDs. This privilege is required to delete deployments. Prerequisite: <b>Read Deployable IPs and SPDs</b> .

Deploy SPDs	Deploy privilege for SPDs of ASDs. This privilege is required to delete deployments. Prerequisite: <b>Read Deployable IPs and SPDs</b> .
Read Deployable and Undeployable IPs and SPDs	Read privilege to read all IPs and SPDs, including those that are marked as undeployable. Prerequisite: <b>Read Deployable IPs and SPDs</b>
Read Deployable IPs and SPDs	Read privilege for marked IPs and SPDs of ASDs.
Read Deployed IPs and SPDs	Read privilege for deployed IPs, SPDs, and audit logs of ASDs. Prerequisites: None.
Replace IPs and SPDs	Enables a user to upload another version of an IP or SPD and replace the version that is already in the database.
Upload IPs and SPDs	Create privilege for IPs and SPDs of ASDs. Prerequisites: Read Deployable IPs and SPDs and Write IPs and SPDs.
Write IPs and SPDs	Write privilege for IPs and SPDs of ASDs. Enables the copy and move operations. Prerequisite: <b>Read Deployable IPs and SPDs</b> .

# **Configuration Object Management**

Configuration Object Management role privileges control what tasks a user can perform in the Configuration Object Management module of Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

#### **Configuration Manager**

[+] Click here to reveal section

Important

Unless otherwise specified, the following roles apply when using both Configuration Manager and Bulk Change Sets.

#### Access Configmanager

Allows a user to access Configuration Manager. Applies only when using Configuration Manager.

# Access to the Application Log Configuration Wizard

Allows a user to access the **Configuration of Logging** window for configuration objects such as Applications, Hosts, and Solutions. Prerequisite: **Modify General Options and State of Applications**, **Modify General Options and State of Hosts**, or **Modify General Options and State of Solutions**.

Allows a user to read and update the Force Password Reset on Next Login option in the User Accounts section. It also allows access to the User Options, Access Control, and Accessible Objects panels. Prerequisite: **Write Users**. Applies only when using Bulk Change Sets.

#### Administer Users

#### **Important**

- The Force Password Reset on Next Login option appears only if Genesys Administrator Extension connects to Management Framework version 8.1.1 and above.
- See the Genesys Security
   Deployment Guide for more information about resetting passwords.

Allows a user to access the **Change Password** task in the **Accounts** > **User Accounts** panel. Prerequisite: **Read Users**. Applies only when using Bulk Change Sets.

# Administer Users Password

#### **Important**

This role privilege is available only in release 8.1.400.45 or later.

	Allows a user to access the <b>Change Password</b> option in the Profile menu. Prerequisite: None.
Modify User Password	Important This role privilege is only available in the 8.1.400.51 release or later.
Read Agent Information	Allows a user to access the <b>Agent Information</b> function and to view agent information in the User Accounts section. Prerequisites: None. Applies only when using Bulk Change Sets.
Read Users	Allows a user to access the User Accounts details pane, except for Force Password Reset on Next Login, User Options, Access Control, Accessible Objects, and Agent Information. Prerequisites: None. Applies only when using Bulk Change Sets.
Write Agent Information	Allows a user to create and update all values on the User Accounts details pane for agents. Prerequisite: <b>Read Agent Information</b> . Applies only when using Bulk Change Sets.
Write Users	Allows a user to create and update all values on the User Accounts details pane except for Force Password Reset on Next Login, User Options, Access Control, Accessible Objects, and Agent Information. Prerequisite: Read Users.
Administer Roles	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. Prerequisite: <b>Write Roles</b> . Applies only when using Bulk Change Sets.
Read Roles	Allows a user to only read Roles. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None.
Write Roles	Allows a user to create, update, and delete Roles. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: <b>Read Roles</b> .
Administer Skills	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. Prerequisite: <b>Write Skills</b> . Applies only when using Bulk Change Sets.
Read Skills	Allows a user to only read Skills. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None.
Write Skills	Allows a user to create, update, and delete Skills. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: <b>Read Skills</b> . Applies only when using Bulk Change Sets.

Administer Agent Groups	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. Prerequisite: <b>Write Agent Groups</b> . Applies only when using Bulk Change Sets.
Read Agent Groups	Allows a user to only read Agent Groups. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None.
Write Agent Groups	Allows a user to create, update, and delete Agent Groups. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: <b>Read Agent Groups</b> . Applies only to Bulk Change Sets views.
Administer Access Groups	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. Prerequisite: <b>Write Access Groups</b> . Applies only when using Bulk Change Sets.
Read Access Groups	Allows a user to only read Access Groups. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None.
Write Access Groups	Allows a user to create, update, and delete Access Groups. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: <b>Read Access Groups</b> . Applies only when using Bulk Change Sets.
Administer Capacity Rules	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. Prerequisite: <b>Write Capacity Rules</b> . Applies only when using Bulk Change Sets.
Read Capacity Rules	Allows a user to only read Capacity Rules. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None. Applies only when using Configuration Manager.
Write Capacity Rules	Allows a user to create, update, and delete Capacity Rules. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: <b>Read Capacity Rules</b> . Applies only when using Bulk Change Sets.
Administer Bulk Change Sets	Allows a user to access the <b>User Options</b> and <b>Access Control</b> buttons. In addition, it allows the user to execute Bulk Change Sets. Prerequisite: <b>Read Bulk Change Sets</b> . Applies only when using Bulk Change Sets.
Read Bulk Change Sets	Allows a user to only read Bulk Change Sets. The <b>User Options</b> and <b>Access Control</b> buttons are not displayed. Prerequisite: None. Applies only when using Bulk Change Sets.
Write Bulk Change Sets	Allows a user to create, update, and delete Bulk Change Sets. The User Options and Access Control buttons are not displayed. Prerequisite: Read Bulk Change Sets. Applies only when using Bulk Change Sets.

#### **Access Groups**

#### [+] Click here to reveal section

Create/Full Control of Access Groups	Full control for Access Group objects (in Configuration Manager). It allows a user to create, copy, or move an Access Group. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Access Groups</b> .
Delete Access Groups	Allows a user to delete Access Groups (in Configuration Manager).  Prerequisite: Read Access Groups.
Modify General Options and State of Access Groups	Allows a user to modify the general options and state of Access Groups (in Configuration Manager). Prerequisite: <b>Read Access Groups</b> .
Modify Options/ Annex of Access Groups	Allows a user to modify settings in the Options tab of Access Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Access Groups</b> .
Read Access Groups	Allows a user to view Access Groups (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.

#### **Action Codes**

Create/Full Control of Action Codes	Full control for Action Code objects. It allows a user to create, copy, or move an Action Code. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Action Codes</b> .
Delete Action Codes	Allows a user to delete Action Codes. Prerequisite: <b>Read Action Codes</b> .
Modify General Options and State of Action Codes	Allows a user to modify the general options and state of Action Codes.  Prerequisite: <b>Read Action Codes</b> .

Modify Options/Annex of Action Codes	Allows a user to modify settings in the Options tab of Action Codes and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Action Codes</b> .
Read Action Codes	Allows a user to view Action Codes in a list and access the object to view its details. Prerequisite: None.

#### **Agent Groups**

#### [+] Click here to reveal section

Create/Full Control of Agent Group objects (in Configuration Manager). It allows a user to create, copy, or move an Agent Group. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: Read Agent Groups.  Delete Agent Groups  Allows a user to delete Agent Groups (in Configuration Manager). Prerequisite: Read Agent Groups.  Modify General Options and State of Agent Groups  Modify Options/ Annex of Agent Groups  Allows a user to modify the general options and state of Agent Groups (in Configuration Manager). Prerequisite: Read Agent Groups.  Allows a user to modify settings in the Options tab of Agent Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Agent Groups.  Allows a user to view Agent Groups (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.		
Modify General Options and State of Agent Groups  Modify Options/ Annex of Agent Groups  Read Agent  Allows a user to modify the general options and state of Agent Groups (in Configuration Manager). Prerequisite: Read Agent Groups.  Allows a user to modify settings in the Options tab of Agent Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Agent Groups.  Allows a user to view Agent Groups (in Configuration Manager) in a list	Control of	allows a user to create, copy, or move an Agent Group. It also allows a user to modify settings in the Permissions tab and view dependencies.
General Options and State of Agent Groups  Modify Options/ Annex of Agent Groups  Read Agent  Allows a user to modify the general options and state of Agent Groups.  Prerequisite: Read Agent Groups.  Allows a user to modify settings in the Options tab of Agent Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Agent Groups.  Allows a user to view Agent Groups (in Configuration Manager) in a list	•	1 \ 0 /
Options/ Annex of Agent Groups  Allows a user to modify settings in the Options tab of Agent Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Agent Groups.  Allows a user to modify settings in the Options tab of Agent Groups (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Agent Groups.	General Options and State of	, , , , , , , , , , , , , , , , , , ,
	Options/ Annex of	Configuration Manager) and view the Permissions and Dependencies
		• • • • • • • • • • • • • • • • • • • •

#### **Agent Logins**

Create/Full Control of Agent Logins	Full control for Agent Login objects. It allows a user to create, copy, or move an Agent Login. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Agent Logins</b> .
Delete Agent Logins	Allows a user to delete Agent Logins. Prerequisite: <b>Read Agent Logins</b> .

Modify General Options and State of Agent Logins	Allows a user to modify the general options and state of Agent Logins.  Prerequisite: <b>Read Agent Logins</b> .
Modify Options/Annex of Agent Logins	Allows a user to modify settings in the Options tab of Agent Logins and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Agent Logins</b> .
Read Agent Logins	Allows a user to view Agent Logins in a list and access the object to view its details. Prerequisite: None.

#### **Alarm Conditions**

#### [+] Click here to reveal section

Create/Full Control of Alarm Conditions	Full control for Alarm Condition objects. It allows a user to create, copy, or move an Alarm Condition. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Alarm Conditions</b> .
Delete Alarm Conditions	Allows a user to delete Alarm Conditions. Prerequisite: <b>Read Alarm Conditions</b> .
Modify General Options and State of Alarm Conditions	Allows a user to modify the general options and state of Alarm Conditions. Prerequisite: <b>Read Alarm Conditions</b> .
Modify Options/ Annex of Alarm Conditions	Allows a user to modify settings in the Options tab of Alarm Conditions and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Alarm Conditions</b> .
Read Alarm Conditions	Allows a user to view Alarm Conditions in a list and access the object to view its details. Prerequisite: None.

#### **Alarm Scripts**

Delete Alarm Scripts	Allows a user to delete Alarm Scripts. Prerequisite: <b>Read Alarm Scripts</b> .
Modify General Options and State of Alarm Scripts	Allows a user to modify the general options and state of Alarm Scripts.  Prerequisite: <b>Read Alarm Scripts</b> .
Modify Options/Annex of Alarm Scripts	Allows a user to modify settings in the Options tab of Alarm Scripts and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Alarm Scripts</b> .
Read Alarm Scripts	Allows a user to view Alarm Scripts in a list and access the object to view its details. Prerequisite: None.

#### **Applications**

#### [+] Click here to reveal section

Create/Full Control of Applications	Full control for Application objects. It allows a user to create, copy, or move an Application. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Applications</b> .
Delete Applications	Allows a user to delete Applications. Prerequisite: Read Applications.
Modify General Options and State of Applications	Allows a user to modify the general options and state of Applications.  Prerequisite: <b>Read Applications</b> .
Modify Options/Annex of Applications	Allows a user to modify settings in the Options tab of Applications and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Applications</b> .
Read Applications	Allows a user to view Applications in a list and access the object to view its details. Prerequisite: None.

#### **Application Templates**

Create/Full	Full control for Application Template objects. It allows a user to
Control of	create, copy, or move an Application Template. It also allows a user

Application Templates	to modify settings in the Permissions tab and view dependencies.  Prerequisite: Read Application Templates.
Delete Application Templates	Allows a user to delete Application Templates. Prerequisite: <b>Read Application Templates</b> .
Modify General Options and State of Application Templates	Allows a user to modify the general options and state of Application Templates. Prerequisite: <b>Read Application Templates</b> .
Modify Options/ Annex of Application Templates	Allows a user to modify settings in the Options tab of Application Templates and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Application Templates</b> .
Read Application Templates	Allows a user to view Application Templates in a list and access the object to view its details. Prerequisite: None.

#### **Business Attributes**

Create/Full Control of Business Attributes	Full control for Business Attribute objects. It allows a user to create, copy, or move a Business Attribute. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Business Attributes</b> .
Delete Business Attributes	Allows a user to delete Business Attributes. Prerequisite: <b>Read Business Attributes</b> .
Modify General Options and State of Business Attributes	Allows a user to modify the general options and state of Business Attributes. Prerequisite: <b>Read Business Attributes</b> .
Modify Options/ Annex of Business Attributes	Allows a user to modify settings in the Options tab of Business Attributes and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Business Attributes</b> .

Read Business	Allows a user to view Business Attributes in a list and access the
Attributes	object to view its details. Prerequisite: None.

#### **Business Attribute Values**

#### [+] Click here to reveal section

Create/Full Control of Business Attribute Values	Full control for Business Attribute Value objects. It allows a user to create, copy, or move a Business Attribute Value. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Business Attribute Values</b> .
Delete Business Attribute Values	Allows a user to delete Business Attribute Values. Prerequisite: <b>Read Business Attribute Values</b> .
Modify General Options and State of Business Attribute Values	Allows a user to modify the general options and state of Business Attribute Values. Prerequisite: <b>Read Business Attribute Values</b> .
Modify Options/ Annex of Business Attribute Values	Allows a user to modify settings in the Options tab of Business Attribute Values and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Business Attribute Values</b> .
Read Business Attribute Values	Allows a user to view Business Attribute Values in a list and access the object to view its details. Prerequisite: None.

#### **Calling Lists**

Create/Full Control of Calling Lists	Full control for Calling List objects. It allows a user to create, copy, or move a Calling List. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Calling Lists</b> .
Delete Calling Lists	Allows a user to delete Calling Lists. Prerequisite: Read Calling Lists.
Modify General Options and State of Calling Lists	Allows a user to modify the general options and state of Calling Lists.  Prerequisite: Read Calling Lists.

Modify Options/Annex of Calling Lists	Allows a user to modify settings in the Options tab of Calling Lists and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Calling Lists</b> .
Read Calling Lists	Allows a user to view Calling Lists in a list and access the object to view its details. Prerequisite: None.

#### **Campaign Groups**

#### [+] Click here to reveal section

Create/Full Control of Campaign Groups	Full control for Campaign Group objects. It allows a user to create, copy, or move a Campaign Group. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Campaign Groups</b> .
Delete Campaign Groups	Allows a user to delete Campaign Groups. Prerequisite: <b>Read Campaign Groups</b> .
Modify General Options and State of Campaign Groups	Allows a user to modify the general options and state of Campaign Groups. Prerequisite: <b>Read Campaign Groups</b> .
Modify Options/ Annex of Campaign Groups	Allows a user to modify settings in the Options tab of Campaign Groups and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Campaign Groups</b> .
Read Campaign Groups	Allows a user to view Campaign Groups in a list and access the object to view its details. Prerequisite: None.

#### **Campaigns**

Create/Full Control of Campaigns	Full control for Campaign objects. It allows a user to create, copy, or move a Campaign. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Campaigns</b> .
Delete Campaigns	Allows a user to delete Campaigns. Prerequisite: Read Campaigns.

Modify General Options and State of Campaigns	Allows a user to modify the general options and state of Campaigns.  Prerequisite: <b>Read Campaigns</b> .
Modify Options/Annex of Campaigns	Allows a user to modify settings in the Options tab of Campaigns and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Campaigns</b> .
Read Campaigns	Allows a user to view Campaigns in a list and access the object to view its details. Prerequisite: None.

#### **Capacity Rules**

#### [+] Click here to reveal section

Create/Full Control of Capacity Rules	Full control for Capacity Rule objects (in Configuration Manager). It allows a user to create, copy, or move a Capacity Rule. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Capacity Rules</b> .
Delete Capacity Rules	Allows a user to delete Capacity Rules (in Configuration Manager). Prerequisite: <b>Read Capacity Rules</b> .
Modify General Options and State of Capacity Rules	Allows a user to modify the general options and state of Capacity Rules (in Configuration Manager). Prerequisite: <b>Read Capacity Rules</b> .
Modify Options/ Annex of Capacity Rules	Allows a user to modify settings in the Options tab of Capacity Rules (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Capacity Rules</b> .
Read Capacity Rules	Allows a user to view Capacity Rules (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.

#### **Configuration Units**

Create/Full Control of Configuration Units	Full control for Configuration Units. It allows a user to create, copy, or move a Configuration Unit. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Configuration Units</b> .
Modify General Options and State of Configuration Units	Allows a user to modify the general options and state of Configuration Units. Prerequisite: <b>Read Configuration Units</b> .
Read Configuration Units	Allows a user to view Configuration Units. Prerequisite: None.

#### **DN Groups**

#### [+] Click here to reveal section

Create/Full Control of DN Groups	Full control for DN Group objects. It allows a user to create, copy, or move a DN Group. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read DN Groups</b> .
Delete DN Groups	Allows a user to delete DN Groups. Prerequisite: Read DN Groups.
Modify General Options and State of DN Groups	Allows a user to modify the general options and state of DN Groups.  Prerequisite: <b>Read DN Groups</b> .
Modify Options/Annex of DN Groups	Allows a user to modify settings in the Options tab of DN Groups and view the Permissions and Dependencies tabs. Prerequisite: <b>Read DN Groups</b> .
Read DN Groups	Allows a user to view DN Groups in a list and access the object to view its details. Prerequisite: None.

#### DNs

Create/Full Control of DNs	Full control for DN objects. It allows a user to create, copy, or move a DN. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read DNs</b> .
<b>Delete DNs</b>	Allows a user to delete DNs. Prerequisite: Read DNs.
Modify General Options and State of DNs	Allows a user to modify the general options and state of DNs.  Prerequisite: <b>Read DNs</b> .
Modify Options/Annex of DNs	Allows a user to modify settings in the Options tab of DNs and view the Permissions and Dependencies tabs. Prerequisite: <b>Read DNs</b> .
Read DNs	Allows a user to view DNs in a list and access the object to view its details. Prerequisite: None.

#### **Fields**

#### [+] Click here to reveal section

Create/Full Control of Fields	Full control for Field objects. It allows a user to create, copy, or move a Field. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Fields</b> .
<b>Delete Fields</b>	Allows a user to delete Fields. Prerequisite: Read Fields.
Modify General Options and State of Fields	Allows a user to modify the general options and state of Fields.  Prerequisite: <b>Read Fields</b> .
Modify Options/Annex of Fields	Allows a user to modify settings in the Options tab of Fields and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Fields</b> .
Read Fields	Allows a user to view Fields in a list and access the object to view its details. Prerequisite: None.

#### **Filters**

Create/Full Control of Filters	Full control for Filter objects. It allows a user to create, copy, or move a Filter. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Filters</b> .
<b>Delete Filters</b>	Allows a user to delete Filters. Prerequisite: Read Filters.
Modify General Options and State of Filters	Allows a user to modify the general options and state of Filters.  Prerequisite: <b>Read Filters</b> .
Modify Options/Annex of Filters	Allows a user to modify settings in the Options tab of Filters and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Filters</b> .
Read Filters	Allows a user to view Filters in a list and access the object to view its details. Prerequisite: None.

#### **Folders**

#### [+] Click here to reveal section

Create/Full Control of Folders	Full control for Folders. It allows a user to create, copy, or move a Folder. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Folders</b> .
Modify General Options and State of Folders	Allows a user to modify the general options and state of Folders.  Prerequisite: <b>Read Folders</b> .
Read Folders	Allows a user to view Folders. Prerequisite: None.

#### **Formats**

Create/Full Control of Formats	Full control for Format objects. It allows a user to create, copy, or move a Format. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Formats</b> .
<b>Delete Formats</b>	Allows a user to delete Formats. Prerequisite: Read Formats.
Modify General Options and State of Formats	Allows a user to modify the general options and state of Formats.  Prerequisite: <b>Read Formats</b> .

Modify Options/Annex of Formats	Allows a user to modify settings in the Options tab of Formats and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Formats</b> .
Read Formats	Allows a user to view Formats in a list and access the object to view its details. Prerequisite: None.

#### Hosts

#### [+] Click here to reveal section

Access Hosts Checkports	Allows a user to use the <b>Check Ports</b> feature for Host objects in Configuration Manager. Prerequisite: <b>Read Hosts</b> .
Create/Full Control of Hosts	Full control for Host objects. It allows a user to create, copy, or move a Host. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Hosts</b> .
<b>Delete Hosts</b>	Allows a user to delete Hosts. Prerequisite: Read Hosts.
Modify General Options and State of Hosts	Allows a user to modify the general options and state of Hosts.  Prerequisite: <b>Read Hosts</b> .
Modify Options/Annex of Hosts	Allows a user to modify settings in the Options tab of Hosts and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Hosts</b> .
Read Hosts	Allows a user to view Hosts in a list and access the object to view its details. Prerequisite: None.

#### **IVR Ports**

Create/Full Control of IVR Ports	Full control for IVR Port objects. It allows a user to create, copy, or move an IVR Port. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read IVR Ports</b> .
Delete IVR Ports	Allows a user to delete IVR Ports. Prerequisite: Read IVR Ports.
Modify General Options and	Allows a user to modify the general options and state of IVR Ports.  Prerequisite: <b>Read IVR Ports</b> .

State of IVR Ports	
Modify Options/Annex of IVR Ports	Allows a user to modify settings in the Options tab of IVR Ports and view the Permissions and Dependencies tabs. Prerequisite: <b>Read IVR Ports</b> .
Read IVR Ports	Allows a user to view IVR Ports in a list and access the object to view its details. Prerequisite: None.

#### **IVRs**

#### [+] Click here to reveal section

Create/Full Control of IVRs	Full control for IVR objects. It allows a user to create, copy, or move an IVR. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read IVRs</b> .
Delete IVRs	Allows a user to delete IVRs. Prerequisite: Read IVRs.
Modify General Options and State of IVRs	Allows a user to modify the general options and state of IVRs. Prerequisite: <b>Read IVRs</b> .
Modify Options/ Annex of IVRs	Allows a user to modify settings in the Options tab of IVRs and view the Permissions and Dependencies tabs. Prerequisite: <b>Read IVRs</b> .
Read IVRs	Allows a user to view IVRs in a list and access the object to view its details. Prerequisite: None.

#### **Objective Tables**

Create/Full Control of Objective Tables	Full control for Objective Table objects. It allows a user to create, copy, or move an Objective Table. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite:  Read Objective Tables.
Delete Objective Tables	Allows a user to delete Objective Tables. Prerequisite: Read Objective Tables.

Modify General Options and State of Objective Tables	Allows a user to modify the general options and state of Objective Tables. Prerequisite: <b>Read Objective Tables</b> .
Modify Options/Annex of Objective Tables	Allows a user to modify settings in the Options tab of Objective Tables and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Objective Tables</b> .
Read Objective Tables	Allows a user to view Objective Tables in a list and access the object to view its details. Prerequisite: None.

#### **Persons**

#### [+] Click here to reveal section

Create/Full Control of Persons  Full control for Person objects (in Configuration Manager). It allows a user to create, copy, or move a Person. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: Read Persons.  Allows a user to delete Persons (in Configuration Manager). Prerequisite: Read Persons.  Allows a user to modify the general options and state of Persons (in Configuration Manager). Prerequisite: Read Persons.  Allows a user to modify the general options and state of Persons (in Configuration Manager). Prerequisite: Read Persons.  Allows a user to modify settings in the Options tab of Persons (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Persons.  Allows a user to view Persons (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.		
Persons  Modify General Options and State of Persons  Modify Options/ Annex of Persons  Read  Prerequisite: Read Persons.  Prerequisite: Read Persons (in Configuration Manager). Prerequisite: Read Persons (in Configuration Manager) in a list and	Control of	user to create, copy, or move a Person. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite:
General Options and State of Persons  Modify Options/ Annex of Persons  Allows a user to modify the general options and state of Persons (in Configuration Manager). Prerequisite: Read Persons.  Allows a user to modify settings in the Options tab of Persons (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Persons.  Read  Allows a user to view Persons (in Configuration Manager) in a list and		` ,
Options/ Annex of Persons  Allows a user to modify settings in the Options tab of Persons (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: Read Persons.  Allows a user to modify settings in the Options tab of Persons (in Configuration Manager) and View the Permissions and Dependencies tabs. Prerequisite: Read Persons.	General Options and State of	,
`	Options/ Annex of	Configuration Manager) and view the Permissions and Dependencies
		` ,

#### **Place Groups**

Create/Full Control of Place Groups	Full control for Place Group objects. It allows a user to create, copy, or move a Place Group. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Place Groups</b> .
Delete Place Groups	Allows a user to delete Place Groups. Prerequisite: <b>Read Place Groups</b> .
Modify General Options and State of Place Groups	Allows a user to modify the general options and state of Place Groups. Prerequisite: <b>Read Place Groups</b> .
Modify Options/Annex of Place Groups	Allows a user to modify settings in the Options tab of Place Groups and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Place Groups</b> .
Read Place Groups	Allows a user to view Place Groups in a list and access the object to view its details. Prerequisite: None.

#### **Places**

#### [+] Click here to reveal section

Create/Full Control of Places	Full control for Place objects. It allows a user to create, copy, or move a Place. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Places</b> .
<b>Delete Places</b>	Allows a user to delete Places. Prerequisite: Read Places.
Modify General Options and State of Places	Allows a user to modify the general options and state of Places.  Prerequisite: <b>Read Places</b> .
Modify Options/Annex of Places	Allows a user to modify settings in the Options tab of Places and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Places</b> .
Read Places	Allows a user to view Places in a list and access the object to view its details. Prerequisite: None.

#### Roles

Create/Full Control of Roles	Full control for Role objects (in Configuration Manager). It allows a user to create, copy, or move a Role. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Roles</b> .
Delete Roles	Allows a user to delete Roles (in Configuration Manager). Prerequisite: <b>Read Roles</b> .
Modify General Options and State of Roles	Allows a user to modify the general options and state of Roles (in Configuration Manager). Prerequisite: <b>Read Roles</b> .
Modify Options/ Annex of Roles	Allows a user to modify settings in the Options tab of Roles (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Roles</b> .
Read Roles	Allows a user to view Roles (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.

#### **Scripts**

Create/Full Control of Scripts	Full control for Script objects. It allows a user to create, copy, or move a Script. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Scripts</b> .
<b>Delete Scripts</b>	Allows a user to delete Scripts. Prerequisite: Read Scripts.
Modify General Options and State of Scripts	Allows a user to modify the general options and state of Scripts.  Prerequisite: <b>Read Scripts</b> .
Modify Options/Annex of Scripts	Allows a user to modify settings in the Options tab of Scripts and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Scripts</b> .
Read Scripts	Allows a user to view Scripts in a list and access the object to view its details. Prerequisite: None.

#### **Sites**

#### [+] Click here to reveal section

Create/Full Control of Sites	Full control for Sites. It allows a user to create, copy, or move a Site. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Sites</b> .
Modify General Options and State of Sites	Allows a user to modify the general options and state of Sites.  Prerequisite: <b>Read Sites</b> .
Read Sites	Allows a user to view Sites. Prerequisite: None.

#### Skills

#### [+] Click here to reveal section

Create/Full Control of Skills	Full control for Skill objects (in Configuration Manager). It allows a user to create, copy, or move a Skill. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Skills</b> .
Delete Skills	Allows a user to delete Skills (in Configuration Manager). Prerequisite: <b>Read Skills</b> .
Modify General Options and State of Skills	Allows a user to modify the general options and state of Skills (in Configuration Manager). Prerequisite: <b>Read Skills</b> .
Modify Options/ Annex of Skills	Allows a user to modify settings in the Options tab of Skills (in Configuration Manager) and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Skills</b> .
Read Skills	Allows a user to view Skills (in Configuration Manager) in a list and access the object to view its details. Prerequisite: None.

#### **Solutions**

Create/Full Control of Solutions	Full control for Solution objects. It allows a user to create, copy, or move a Solution. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Solutions</b> .
Delete Solutions	Allows a user to delete Solutions. Prerequisite: Read Solutions.
Modify General Options and State of Solutions	Allows a user to modify the general options and state of Solutions.  Prerequisite: <b>Read Solutions</b> .
Modify Options/Annex of Solutions	Allows a user to modify settings in the Options tab of Solutions and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Solutions</b> .
Read Solutions	Allows a user to view Solutions in a list and access the object to view its details. Prerequisite: None.

#### **Statistical Days**

Create/Full Control of Statistical Days	Full control for Statistical Day objects. It allows a user to create, copy, or move a Statistical Day. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Statistical Days</b> .
Delete Statistical Days	Allows a user to delete Statistical Days. Prerequisite: <b>Read Statistical Days</b> .
Modify General Options and State of Statistical Days	Allows a user to modify the general options and state of Statistical Days. Prerequisite: <b>Read Statistical Days</b> .
Modify Options/Annex of Statistical Days	Allows a user to modify settings in the Options tab of Statistical Days and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Statistical Days</b> .
Read Statistical Days	Allows a user to view Statistical Days in a list and access the object to view its details. Prerequisite: None.

#### **Statistical Tables**

#### [+] Click here to reveal section

Create/Full Control of Statistical Tables	Full control for Statistical Table objects. It allows a user to create, copy, or move a Statistical Table. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Statistical Tables</b> .
Delete Statistical Tables	Allows a user to delete Statistical Tables. Prerequisite: <b>Read Statistical Tables</b> .
Modify General Options and State of Statistical Tables	Allows a user to modify the general options and state of Statistical Tables. Prerequisite: <b>Read Statistical Tables</b> .
Modify Options/ Annex of Statistical Tables	Allows a user to modify settings in the Options tab of Statistical Tables and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Statistical Tables</b> .
Read Statistical Tables	Allows a user to view Statistical Tables in a list and access the object to view its details. Prerequisite: None.

#### **Switches**

Create/Full Control of Switches	Full control for Switch objects. It allows a user to create, copy, or move a Switch. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Switches</b> .
Delete Switches	Allows a user to delete Switches. Prerequisite: Read Switches.
Modify General Options and State of Switches	Allows a user to modify the general options and state of Switches.  Prerequisite: <b>Read Switches</b> .

Modify Options/Annex of Switches	Allows a user to modify settings in the Options tab of Switches and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Switches</b> .
Read Switches	Allows a user to view Switches in a list and access the object to view its details. Prerequisite: None.

#### **Switching Offices**

#### [+] Click here to reveal section

Create/Full Control of Switching Offices	Full control for Switching Office objects. It allows a user to create, copy, or move a Switching Office. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Switching Offices</b> .
Delete Switching Offices	Allows a user to delete Switching Offices. Prerequisite: <b>Read Switching Offices</b> .
Modify General Options and State of Switching Offices	Allows a user to modify the general options and state of Switching Offices. Prerequisite: <b>Read Switching Offices</b> .
Modify Options/ Annex of Switching Offices	Allows a user to modify settings in the Options tab of Switching Offices and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Switching Offices</b> .
Read Switching Offices	Allows a user to view Switching Offices in a list and access the object to view its details. Prerequisite: None.

#### **Table Accesses**

Create/Full Control of Table Accesses	Full control for Table Access objects. It allows a user to create, copy, or move a Table Access. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Table Accesses</b> .
Delete Table Accesses	Allows a user to delete Table Accesses. Prerequisite: <b>Read Table Accesses</b> .

Modify General Options and State of Table Accesses	Allows a user to modify the general options and state of Table Accesses. Prerequisite: <b>Read Table Accesses</b> .
Modify Options/ Annex of Table Accesses	Allows a user to modify settings in the Options tab of Table Accesses and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Table Accesses</b> .
Read Table Accesses	Allows a user to view Table Accesses in a list and access the object to view its details. Prerequisite: None.

#### **Tenants**

#### [+] Click here to reveal section

Create/Full Control of Tenants	Full control for Tenant objects. It allows a user to create, copy, or move a Tenant. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Tenants</b> .
<b>Delete Tenants</b>	Allows a user to delete Tenants. Prerequisite: Read Tenants.
Modify General Options and State of Tenants	Allows a user to modify the general options and state of Tenants.  Prerequisite: <b>Read Tenants</b> .
Modify Options/Annex of Tenants	Allows a user to modify settings in the Options tab of Tenants and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Tenants</b> .
Read Tenants	Allows a user to view Tenants in a list and access the object to view its details. Prerequisite: None.

#### Time Zones

Create/Full Control of Time Zones	Full control for Time Zone objects. It allows a user to create, copy, or move a Time Zone. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Time Zones</b> .
Delete Time Zones	Allows a user to delete Time Zones. Prerequisite: Read Time Zones.

Modify General Options and State of Time Zones	Allows a user to modify the general options and state of Time Zones.  Prerequisite: <b>Read Time Zones</b> .
Modify Options/Annex of Time Zones	Allows a user to modify settings in the Options tab of Time Zones and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Time Zones</b> .
Read Time Zones	Allows a user to view Time Zones in a list and access the object to view its details. Prerequisite: None.

#### **Transactions**

#### [+] Click here to reveal section

Create/Full Control of Transactions	Full control for Transaction objects. It allows a user to create, copy, or move a Transaction. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Transactions</b> .
Delete Transactions	Allows a user to delete Transactions. Prerequisite: <b>Read Transactions</b> .
Modify General Options and State of Transactions	Allows a user to modify the general options and state of Transactions.  Prerequisite: <b>Read Transactions</b> .
Modify Options/Annex of Transactions	Allows a user to modify settings in the Options tab of Transactions and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Transactions</b> .
Read Transactions	Allows a user to view Transactions in a list and access the object to view its details. Prerequisite: None.

#### **Treatments**

Delete Treatments	Allows a user to delete Treatments. Prerequisite: Read Treatments.
Modify General Options and State of Treatments	Allows a user to modify the general options and state of Treatments.  Prerequisite: <b>Read Treatments</b> .
Modify Options/Annex of Treatments	Allows a user to modify settings in the Options tab of Treatments and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Treatments</b> .
Read Treatments	Allows a user to view Treatments in a list and access the object to view its details. Prerequisite: None.

#### **Voice Platform Profiles**

Create/Full Control of Voice Platform Profiles	Full control for Voice Platform Profile objects. It allows a user to create, copy, or move a Voice Platform Profile. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Voice Platform Profiles</b> .
Delete Voice Platform Profiles	Allows a user to delete Voice Platform Profiles. Prerequisite: <b>Read Voice Platform Profiles</b> .
Modify General Options and State of Voice Platform Profiles	Allows a user to modify the general options and state of Voice Platform Profiles. Prerequisite: <b>Read Voice Platform Profiles</b> .
Modify Options/ Annex of Voice Platform Profiles	Allows a user to modify settings in the Options tab of Voice Platform Profiles and view the Permissions and Dependencies tabs.  Prerequisite: <b>Read Voice Platform Profiles</b> .
Read Voice Platform Profiles	Allows a user to view Voice Platform Profiles in a list and access the object to view its details. Prerequisite: None.

#### **Voice Prompts**

#### [+] Click here to reveal section

Create/Full Control of Voice Prompts	Full control for Voice Prompt objects. It allows a user to create, copy, or move a Voice Prompt. It also allows a user to modify settings in the Permissions tab and view dependencies. Prerequisite: <b>Read Voice Prompts</b> .
Delete Voice Prompts	Allows a user to delete Voice Prompts. Prerequisite: <b>Read Voice Prompts</b> .
Modify General Options and State of Voice Prompts	Allows a user to modify the general options and state of Voice Prompts. Prerequisite: <b>Read Voice Prompts</b> .
Modify Options/Annex of Voice Prompts	Allows a user to modify settings in the Options tab of Voice Prompts and view the Permissions and Dependencies tabs. Prerequisite: <b>Read Voice Prompts</b> .
Read Voice Prompts	Allows a user to view Voice Prompts in a list and access the object to view its details. Prerequisite: None.

#### **System Dashboard**

Clear Active Alarms	Allows a user to clear active alarms in the <b>Alarms</b> tab of the System Dashboard.
Access Alarm Conditions Test	Allows a user to access the <b>Activate Alarm</b> function in the <b>Alarm Conditions</b> window. Prerequisite: <b>Read Alarm Conditions</b>
Start Applications	Allows a user to start applications by using the System Dashboard.
Stop Applications	Allows a user to stop applications by using the System Dashboard.
Switch Applications Mode	Allows a user to access the <b>Switch Mode</b> function when using the System Dashboard.
Start Solutions	Allows a user to start solutions by using the System Dashboard.
Stop Solutions	Allows a user to stop solutions by using the System Dashboard.

Role Privileges Agent Management

# **Agent Management**

Agent Management role privileges control what tasks a user can perform in the **Agents** window of Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

_
Access to
View Agents
of other
Tenants

Allows a user to view the **Tenant Directory** in the **Agents** window. By default, in a multi-tenant environment, users can only see Agents that belong to their Tenant. However, if users have this privilege and Read access to Agents of other Tenants, they can use the **Tenant Directory** to switch Tenants and view these Agents to which they have access. Prerequisite: **Read Agents in Agent Management**.

Create
Agents in
Agent
Management

Allows a user to create Agents and copy Agents in the **Agents** window.

Prerequisite: Read Agents in Agent Management.

Allows a user to create Skills when creating Agents in the **Agents** window. Prerequisite: **Modify Agents in Agent Management**.

Allow Skill Creation under Agent Management

#### **Important**

When you create a Skill in the **Add Agent** window, you also create a Virtual Agent Group with the same name as the Skill and all Agents that have this Skill are automatically assigned to this Virtual Agent Group.

Delete Agents in Agent

Allows a user to delete Agents in the **Agents** window. Prerequisite: **Read** 

Agents in Agent Management.

Management Modify Agents in

Management

Agent

Allows a user to modify Agents and copy Agents in the **Agents** window.

Prerequisite: Read Agents in Agent Management.

Role Privileges Bulk Operations

Read Agents in Agent Management	Allows a user to view Agents in the <b>Agents</b> window.
Access Contextual Skill	Allows a user to access Contextual Skills. Prerequisite: Read Agents in Agent Management.
Create Skills under Contextual Skill	Allow a User to use the Contextual Skill Interface to create new Skills.  Prerequisite: Read Agents in Agent Management.

# **Bulk Operations**

Bulk Operations role privileges control what tasks a user can perform relating to Bulk Operations on Agents in Genesys Administrator Extension.

#### **Required Privileges**

Category	Privilege
Agent Management	Read Agents in Agent Management

#### **Role Privileges**

Administer User Bulk Operations	Allows a user to access History of Bulk Operations, and to delete completed or abandoned operations in the History.
Create User Bulk Operations	Allows a user to upload a spreadsheet, start or stop Bulk Operations, and access the History of Bulk Operations.
Export and Create Spreadsheet for User Bulk Operations	Allows a user to create or export a spreadsheet in .csv format for use when performing bulk creations and updates of Agents.

# Audio Resources Management—Tenant

Audio Resource Management—Tenant role privileges control what tasks a user can perform at the Tenant level in the Audio Resource Management module of Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

Write Audio Resources	Allows a user to create, update, and delete Audio Resources and the Audio Resource Files that they contain. Prerequisites: <b>Read Audio Resources</b> and <b>Read Personalities</b> .
Write Personalities	Allows a user to create, update, and delete Personalities for Audio Resources and their files. Prerequisite: <b>Read Personalities</b> .
Process Audio Resources	Allows a user to initiate re-encoding of Audio Resources and re- transferring them to target storage. Prerequisites: <b>Read Audio</b> <b>Resources</b> and <b>Read Personalities</b> .
Read Audio Resources	Allows a user to view Audio Resources and the Audio Resource Files that they contain. Prerequisite: None.
Read Personalities	Allows a user to view Personalities for Audio Resources and their files. Prerequisite: None.

## **Audio Resources Management—System**

Audio Resource Management—System role privileges control what tasks a user can perform at the Solution Provider level in the Audio Resource Management module of Genesys Administrator Extension.

#### **Required Privileges**

None

#### **Role Privileges**

Deploy
Audio
Resources

Allows a user to deploy Audio Resources and the Audio Resource Files that they contain from the System Provider to Tenants. Prerequisites: **Read Audio Resources** and **Read Personalities**. This privilege is effective only if it is granted to a user in the Environment Tenant. Users in other Tenants are unable to deploy Audio Resources even if they are granted this privilege.

Role Privileges Centralized Log

# **Centralized Log**

Centralized Log privileges control what level of logs a user can view in the **Centralized Logs** window of Genesys Administrator Extension.

# **Required Privileges**

None

# **Role Privileges**

•	
Access Centralized Log messages	Allows a user to access (see) the Centralized Logs option in the GAX header.
Read Alarm Centralized Log messages	Allows a user to view all Alarm-level logs in the Centralized Log Database.  Prerequisite: Access Centralized Log messages.
Read Centralized Standard Log messages	Allows a user to view all Standard-level logs in the Centralized Log Database.  Prerequisite: Access Centralized Log messages.
Read Centralized Interaction Log messages	Allows a user to view all Interaction-level logs in the Centralized Log Database.  Prerequisite: Access Centralized Log messages.
Read Centralized Trace Log messages	Allows a user to view all Trace-level logs in the Centralized Log Database.  Prerequisite: Access Centralized Log messages.
Read Audit Centralized Log messages	Allows a user to view all Audit-type logs in the Centralized Log Database.  Prerequisite: Access Centralized Log messages.
Delete Centralized Log messages	Allows a user to delete logs in the Centralized Log Database.

Role Privileges Centralized Log

Prerequisite: Access Centralized Log messages.

Configuration Options Centralized Log

# **Configuration Options**

This appendix describes the configuration options for Genesys Administrator Extension, and contains the following sections:

- Mandatory Options
- general Section
- security Section
- · asd Section
- arm Section
- ga Section
- log Section
- clog Section
- · opm Section

### **Important**

There are no configuration options required for the Operational Parameters Management module.

# **Setting Configuration Options**

The configuration options specified in this chapter are used by GAX after it has connected to Configuration Server. GAX also reads the **gax.properties** file for configuration options that are set before it connects to Configuration Server. See Configuring GAX Properties for more information about the **gax.properties** file.

Unless specified otherwise, set Genesys Administrator Extension configuration options in the **Application Options** tab of the Genesys Administrator Extension Application object.

### Warning

Configuration section names, configuration option names, and predefined option values are case-sensitive. Type them in Genesys Administrator Extension exactly as they are documented in this appendix.

Configuration Options Mandatory Options

# **Mandatory Options**

You do not have to configure any options to start Genesys Administrator Extension.

# general Section

This section must be called general, and is configured in the Genesys Administrator Extension Server Application object of type **Generic Genesys Server**.

The options in this section are required for the general behavior of Genesys Administrator Extension.

#### auditing

Default Value: true

Valid Values: true, false

Changes Take Effect: After Genesys Administrator Extension is restarted.

By default GAX is set to audit all actions that are performed by users. Set to false if auditing is not required.

#### client\_app\_name

Default Value: default

Valid Values: The valid name of an application object of type Configuration Manager.

Changes Take Effect: After Genesys Administrator Extension is restarted.

Specifies the name of the client application. GAX requires a client application object to enable access control of the browser-based interface.

#### confserv\_timeout

• Default Value: 30

- Valid Values: The value of the timeout protocol.
- Changes Take Effect: Immediately.

Protocol timeout value for connections to Configuration Server.

Configuration Options general Section

#### default\_account\_dbid

- Default Value: 100
- Valid Values: The database ID of the default account. A valid DBID that represents the person object that should be used as the default account (refer to Default Account Support).
- Changes Take Effect: After Genesys Administrator Extension is restarted.
- The DBID that is assigned to default account. This DBID can be set to any DBID of any valid user. The user with the specified DBID will have all role privileges.
- If this option is not set, GAX uses the value 100 for the DBID. The default account is identified by DBID. The default value for the DBID is 100. If the default account is deleted and recreated, it will be assigned a new DBID. Use the default\_account\_dbid option to specify the DBID of the default account if the value is not 100.

#### help\_external\_url

- **Default Value**: docs.genesys.com
- Valid Values: Any reachable website domain or IP address (do not include http://prefix). You must include a port number after the address. For example: docs.mycompany.com: 4001
- Changes Take Effect: Upon page refresh.
- Specifies the location of Genesys Administrator Extension Help content—either the Genesys Documentation website (docs.genesys.com) or an internal company server for those that have installed the offline documentation package.

#### inactivity\_timeout

- Default Value: 600
- · Valid Values: Any integer value.
- Changes Take Effect: Immediately.
- Specifies the value of the inactivity timeout in seconds. A negative value deactivates this timer.

#### msgsrv\_attempts

- Default Value: 1
- Valid Values: Any positive integer value greater than 0.
- Changes Take Effect: After Genesys Administrator Extension is restarted.

Configuration Options general Section

Specifies the number of connection attempts that will be made until GAX tries to

#### msgsrv\_max\_switchovers

- Default Value: -1
- Valid Values: Any integer value.

connect to the backup Message Server.

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the number of switch-overs between Message Servers before GAX gives up trying to reconnect. 0 specifies no reconnection attempts. A negative values specifies unlimited reconnection attempts.

#### msgsrv\_timeout

- Default Value: 10
- Valid Values: Any positive integer value.
- Changes Take Effect: After Genesys Administrator Extension is restarted.
- · Specifies the protocol timeout value for connections to Message Server.

#### msgsrv\_warmstandby\_timeout

- Default Value: 60
- · Valid Values: Any integer value.
- Changes Take Effect: Immediately.
- The time in seconds between reconnection attempts to Message Server.

#### scs\_attempts

- Default Value: 1
- Valid Values: Any positive integer value greater than 0.
- · Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the number of connection attempts that will be made until GAX tries to connect to the backup Solution Control Server.

#### scs\_max\_switchovers

- Default Value: -1
- Valid Values: Any integer value.

Configuration Options security Section

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the number of switch-overs between Solution Control Servers before GAX gives up trying to reconnect. 0 specifies no reconnection attempts. A negative values specifies unlimited reconnection attempts.

#### scs\_timeout

- Default Value: 10
- Valid Values: Any positive integer value.
- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the protocol timeout value for connections to Solution Control Server.

#### scs\_warmstandby\_timeout

- Default Value: 60
- Valid Values: Any integer value.
- Changes Take Effect: After Genesys Administrator Extension is restarted.
- The time in seconds between reconnection attempts to Solution Control Server.

#### session timeout

- Default Value: 900
- Valid Values: Any positive integer value.
- Changes Take Effect: Immediately.
- The time in seconds after the session timeout that the GAX user session on the server will be destroyed.

# security Section

This section must be called security, and is configured in the Genesys Administrator Extension Server Application object of type Generic Genesys Server.

The options in this section relate to security features in Genesys Administrator Extension.

#### host\_whitelist

Default Value: Empty

Valid Values: URLs of hosts trusted by this GAX instance, separated by semi-colons (;); for

example 132.56.54.34; host1; 34.32.12.8

Changes Take Effect: After restart

Specifies the host URLs that can be whitelisted. This option only takes effect when **host\_whitelist\_enabled** is set to true.

#### host\_whitelist\_enabled

Default Value: false Valid Values: true, false

Changes Take Effect: After restart

Specifies if host whitelisting is enabled in GAX. If this option is not set or set to false (the default), then host whitelisting is disabled and all hosts are allowed by GAX.

If set to true, only those hosts specified in the option **host\_whitelist** can appear as:

- values of the parameters logout\_success\_url, logout\_failure\_url, and logout\_url
  when logging in remotely
- list of hosts from which to select UNC Path to Mounted CD or Directory, UNC Path to an Existing Administrator Repository, and UNC Path to Zipped IPs when uploading IPs.

### asd Section

This section must be called asd, and is configured in the Genesys Administrator Extension Server Application object of type **Genesys Administrator Server**.

The options in this section are required for the Solution Deployment module in Genesys Administrator Extension.

#### local ip cache dir

- Default Value: ./plugin.data/asd/gaxLocalCache
- · Valid Values: Any valid folder

• Changes Take Effect: After Genesys Administrator Extension is restarted.

Specifies the folder where the IP used for the deployment is cached. Caching the IP reduces deployment time if the IP is reused. This option must be set to a UNC path or a local path that points to a directory that can be accessed (with read\write permissions) from the machine that is running the Genesys Administrator Extension server.

#### silent\_ini\_path

- Default Value: ./plugin.data/asd/installation/genesys silent ini.xml
- Valid Values: Any valid path and XML file name
- · Changes Take Effect: Immediately.

Specifies the name of the silent installation folder used by ASD. May start with . to resolve the GAX base path automatically based on the local system settings. The default value is sufficient unless the path or file has been changed after installing Genesys Administrator Extension.

## arm Section

This section must be called arm, and is configured in the Genesys Administrator Extension Server Application object of type Genesys Administrator Server.

The options in this section are required for the Audio Resource Management module in Genesys Administrator Extension.

#### delete from db after processing

- Default Value: false
- Valid Values: false, true
- Changes Take Effect: Immediately.
- Specifies if the original audio file is to be deleted from the database after all required processing (including any format conversion and transfer to target storage) is complete. If set to true, the original file located in the target storage is used for any subsequent reprocessing, and if required, is downloaded from the target storage rather than from the database (from which it was removed).

This option enables the user to decide if he or she wants the system to delete the binary audio information in the original audio file from the database after processing is done. The

advantage of deleting the information is that less database space is used. The disadvantage is that reprocessing is possible on the files located in target storage. These files could be subject to corruption, loss, or a problem with the target storage itself, thereby losing the original information. In this case, the database just offers redundancy and robustness of the data.

#### local\_announcement\_folder

- Default Value: announcement
- · Valid Values: Any valid folder
- Changes Take Effect: Immediately.
- Specifies the name of the folder where the audio data for audio resources of type Announcement is stored while the audio resource is stored in the database, encoded, and moved to target storage. This folder is specified relative to the path specified by the option local path.

#### local\_music\_folder

- Default Value: music
- · Valid Values: Any valid folder
- Changes Take Effect: Immediately.
- Specifies the name of the folder where the audio data for audio resources of type
  Music is stored while the audio resource is stored in the database, encoded, and
  moved to target storage. This folder is specified relative to the path specified by the
  option local path.

#### local\_path

- **Default Value**: /opt/gax/arm
- · Valid Values: Any valid path
- Changes Take Effect: Immediately.
- Specifies the absolute path to the location of local audio storage, that is, to the folders specified by the options target\_announcement\_folder and local\_music\_folder.

#### local\_sox\_path

- Default Value: /usr/bin/sox
- · Valid Values: Any valid path
- Changes Take Effect: Immediately.

Specifies the absolute path to the SoX binary (executable) file.

#### max upload audio file size

- Default Value: 20
- Valid Values: Any positive integer
- · Changes Take Effect: Immediately.
- Specifies the maximum file size, in megabytes, for audio files that are uploaded to GAX.

#### target\_announcement\_folder

- Default Value: announcement
- · Valid Values: Any valid folder name
- Changes Take Effect: Immediately.
- Specifies the folder where all audio files of type Announcement, both original and encoded, are stored. Media Server retrieves the files from this folder and uses them. This folder is specified relative to the path specified by the option target path.
- If the delete\_from\_db\_after\_processing option is set to true, the original audio files stored in this folder are used for reprocessing, and are downloaded from this folder instead of from the database. However, the encoded files are always downloaded from this folder, not from the database.

#### target music folder

- Default Value: music
- Valid Values: Any valid folder name
- Changes Take Effect: Immediately.
- Specifies the folder where all audio files of type Music, both original and encoded, are stored. Media Server retrieves the files from this folder and uses them. This folder is specified relative to the path specified by the option target path.

If the delete\_from\_db\_after\_processing option is set to true, the original audio files stored in this folder are used for reprocessing, and are downloaded from this folder instead of from the database. However, the encoded files are always downloaded from this folder, not from the database.

#### target\_path

- Default Value: /mnt/arm/target
- · Valid Values: Any valid path
- Changes Take Effect: Immediately.
- Specifies the absolute path to the location of the folders specified by the options target\_announcement\_folder and target\_music\_folder. This path must appear local to the Genesys Administrator Extension server, even though target storage is located on a different host. The path specified here must be served by the ARM Web Proxy server (this is typically the root directory from the perspective of the web server).

# ga Section

#### ga\_appName

- Default Value: default
- Valid Values: The valid name of the Genesys Administrator application object.
- Changes Take Effect: Immediately.
- Specifies the Application name for Genesys Administrator that is to be used to directly log in to Genesys Administrator from GAX.

#### ga\_host

- Default Value: ""
- Valid Values: The name of a host or an IP address.
- Changes Take Effect: Immediately.
- Specifies the Genesys Administrator host parameter that enables direct login to Genesys Administrator.

#### ga\_port

- Default Value: 80
- Valid Values: A valid port ID.
- Changes Take Effect: Immediately.
- Specifies the Application port number for Genesys Administrator that is to be used to directly log in to Genesys Administrator from GAX. This option is mandatory if the Genesys Administrator port number is not 80.

#### ga\_protocol

- Default Value: http
- Valid Values: http, https
- Changes Take Effect: Immediately.
- Specifies the Genesys Administrator protocol that is required to directly log in to Genesys Administrator from GAX.

#### ga\_timeout

- Default Value: 2
- · Valid Values: Any positive integer.
- Changes Take Effect: Immediately.

Specifies in seconds how long Genesys Administrator Extension waits to allow Genesys Administrator to successfully authenticate login parameters before Genesys Administrator Extension authenticates its login session and allows user to access GAX. Provide a value that is sufficient to accommodate Genesys Administrator.

# log Section

#### all

- **Default Value**: stdout, ./logs/gax.log
- · Valid Values:

Value	Description	
stdout	Log events are sent to the Standard output.	

#### network

Log events are sent to Message Server, which can reside anywhere on the network. Message Server stores the log events in the Log Database.

Value Description

Setting the all log level option to the network output enables an application to send log events of the Standard, Interaction, and Trace levels to Message Server. Debug-level log events are neither sent to Message Server nor stored in the Log Database.

[filename]

Log events are stored in a file with the specified name. If a path and filename are not specified, the file is created in the application's working directory.

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the outputs to which an application sends all log events. The log output types must be separated by a comma when more than one output is configured. For example: stdout, logfile

#### expire

- Default Value: 20
- Valid Values: Any integer value.
- Changes Take Effect: After Genesys Administrator Extension is restarted.

Specifies the maximum number of log files to be kept.

#### log-cache-size

• Default Value: 16000

- Valid Values: Any integer value.
- Changes Take Effect: After Genesys Administrator Extension is restarted.

Specifies the maximum number of logs in the log message queue.

#### segment

• Default Value: 10000

- · Valid Values: Any valid file size.
- Changes Take Effect: After Genesys Administrator Extension is restarted.

Specifies the maximum log file size in kilobytes.

#### standard

Default Value: ""

Valid Values:

Value	Description
stdout	Log events are sent to the Standard output.
network	Log events are sent to Message Server, which can reside anywhere on the network. Message Server stores the log events in the Log Database.
[filename]	Log events are stored in a file with the specified name. If a path and filename are not specified, the file is created in the application's working directory.

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the outputs to which an application sends the log events of the Standard level. The log output types must be separated by a comma when more than one output is configured. For example: stderr, network

#### trace

- · Default Value: ""
- Valid Values:

Value	Description	
stdout	Log events are sent to the Standard output.	

Value	Description
network	Log events are sent to Message Server, which can reside anywhere on the network. Message Server stores the log events in the Log Database.
[filename]	Log events are stored in a file with the specified name. If a path and filename are not specified, the file is created in the application's working directory.

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Specifies the outputs to which an application sends the log events of the Trace level and higher (that is, log events of the Standard, Interaction, and Trace levels). The log outputs must be separated by a comma when more than one output is configured.
   For example: stderr, network

#### verbose

- Default Value: standard
- Valid Values:

Value	Description
all	All log events (that is, log events of the Standard, Trace, Interaction, and Debug levels) are generated.
debug	The same as all.

Value	Description
trace	Log events of the Trace level and higher (that is, log events of the Standard, Interaction, and Trace levels) are generated, but log events of the Debug level are not generated.
interaction	Log events of the Interaction level and higher (that is, log events of the Standard and Interaction levels) are generated, but log events of the Trace and Debug levels are not generated.
standard	The same as interaction.
none	

• Changes Take Effect: After Genesys Administrator Extension is restarted.

Determines whether a log output is created. If it is, specifies the minimum level of log events generated. The log events levels, starting with the highest priority level, are Standard, Interaction, Trace, and Debug.

# clog Section

This section contains configuration options for configuring the display of log records from the Centralized log.

### maxlogs

Default Value: 5000

Valid Values: Any positive integer starting at 5000

Changes Take Effect: After the browser page is refreshed

No output is produced.

Specifies the maximum number of log records that can be displayed in GAX. When the user scrolls down or pages through to the end of the list, GAX displays a message suggesting that the user refine the search criteria to get better results. If this option is not set or set to a value less than 5000 (the default), the default is used. When used with the minlogs option, the rules in the following table might apply:

<b>Configured Values</b>	Value used for maxlogs	Value used for minlogs
minlogs < 5000 maxlogs < 5000 minlogs > maxlogs	5000 or the configured value of <b>maxlogs</b> , whichever is greater	100 or the configured value of <b>minlogs</b> , whichever is greater
minlogs >= 5000 maxlogs >= 5000 minlogs > maxlogs	Configured value of <b>minlogs</b>	Configured value of minlogs

### minlogs

Default Value: 100

Valid Values: Any positive integer starting at 100

Changes Take Effect: After the browser page is refreshed

Specifies the number of log records that are to be retrieved from the Centralized Log Database when the user scrolls down or pages through the list of logs. If not set or set to a value less than 100 (the default), the default is used. When used with the maxlogs option, the rules in the table above might apply.

# opm Section

#### write\_json

Default Value: false

• Valid Values: true, false

- Changes Take Effect: After Genesys Administrator Extension is restarted.
- Defines whether OPM writes JSON data directly to transaction objects in binary form (data is written as value for the key " json").

Product Alert opm Section

# **Product Alert**

The following information applies to Genesys 8.5.x software and is important for you to note.

Customers using VP Reporting Plugin for GAX version 8.5.120.30 (or lower) should not upgrade to GAX 8.5.220.20, as this combination has not been qualified and there is at least one known issue. (GVP-22684)

Genesys Administrator Extension can be used with Management Framework 7.6, but only the Automatic Solution Deployment (ASD) and License Reporting Manager (LRM) plug-ins can be used. All other default plug-ins, including Configuration Object Management (COM), Operational Parameter Management (OPM), Audio Resource Management (ARM), and the Genesys Administrator pass-through, cannot be used with Management Framework 7.6.

You can import the Application Template for Genesys Administrator Extension into Genesys Administrator, but you cannot import the associated metadata. The metadata includes prerequisite information for role privileges, which is not supported by Genesys Administrator.

Genesys Administrator Extension does not currently support all functions of the latest versions of Genesys Administrator, Genesys Configuration Manager, and Solution Control Interface. This includes the following features:

- Outbound-related operations
- Configuration of Resource Groups and DID Groups
- · Bulk updates using wizards
- CSV export and import options for some objects, such as Switches or Agent Logins.

You must use GAX 8.500.65 or later to use Setup Mode to deploy Management Framework 8.5.x. If you are using GAX 8.500.58 or earlier, Setup Mode can only deploy Management Framework 8.1.x.

Setup Mode cannot deploy Configuration Server and Database Server on operating systems other than Windows Server 2003/2008/2012 and Red Hat Enterprise Linux 5.5/6.x.

Product Alert opm Section

When launching Genesys Administrator from GAX using Internet Explorer, the **About Internet Explorer** window appears. Click **OK** to close the window and work in Genesys Administrator.

GAX 8.5.x only supports the Pulse 8.5.x plug-in. If you are using the Pulse 8.1.4 plug-in, you must upgrade to Pulse 8.5.x or continue to use GAX 8.1.4.

If you are planning to use Internet Explorer 9.0 with Genesys Administrator Extension, do not install Pulse. If you want to use Pulse, install GAX on Internet Explorer 10 or later, or on another supported browser.

Users of the SIP Feature Server plug-in must use version 8.1.200.23 or later. Earlier versions of this plug-in might exhibit display issues when used with GAX 8.5.0 or later.

Link to 8.1 Product Release Advisory

Change History opm Section

# **Change History**

This topic lists all the changes in this document between the specified versions.

### Changes in 8.5.2

### New pages

- Coordinating Simultaneous Changes to Data: How changes made to one object by multiple Users working simultaneously are handled.
- **Deployment Issues:** Troubleshooting deployment issue when GAX does not start when deployed using Setup Mode.
- Bulk Operations: Role privileges for bulk operations
- Centralized Log: Role privileges for Centralized Logs
- Security Section: Configuration options for whitelisting IPs
- clog Section: Configuration options for Centralized Logs

### **Updated pages**

- Solution Deployment: New section "Protection Against External XML Entity Injection Protection"; added description of whitelisting IPs
- Deploying Genesys Administrator Extension: Added limitation about connections to Configuration Server Proxy; clarified use of user account in Setup mode; added warning to reset configuration environment and Configuration Server if deployment using Setup Mode is interrupted.
- Configuring GAX Properties: Added new option enable\_web\_notification
- Prerequisites for Genesys Administrator Extension Modules: Added procedure for setting up ARM on Windows; reorganized page
- Configuring System Security: Clarified how to set up trust store and set required options; added procedure to set up secure use of the auto-detect port; updated use of the JSONSESSIONID session cookie; added information about setting up Mutual TLS for GDA
- Logging In Remotely: Added description of whitelisting IPs
- **Browser Issues:** Removed mention of IE 8; clarified that blocked downloads issue applies only if using IE 9; added issue about playing ARM files in IE and Firefox.
- Configuration Option Management: Added information about to which views the Configuration Manager privileges apply.
- Known Issues and Limitations replaced by Product Alert: A duplicate of the Product Alert found in the Readme; includes information in what was formerly the Known Issues and Limitations page.

Change History opm Section

### **Deleted pages**

• Preferences: This page was a duplicate of information found in GAX Help.

Changes in 8.5.0

### **Updated Pages**

• **Deploying GAX:** Added support for Java JRE version 8 when configuring the host in step 2.

- Prerequisites for Genesys Administrator Extension Modules: Added additional browser requirements and constraints if playing audio files.
- **System Preferences:** In Throttling section, clarified definition and use of configuration options.
- Configuration Object Management: In Configuration Manager section, updated Administer Bulk Change Sets privilege.