FORMANT TABLE 9/13/12 10:14 PM

## <u>QUICK-REF</u> - <u>CsoundManual</u> - <u>Previous section</u> - <u>Contents</u> - <u>Index</u>

## **TABLE III:** Formant values

	f1	f2	f3	f4	f5			
soprano "a"								
freq (Hz)	800	1150	2900	3900	4950			
amp (dB)	0	-6	-32	-20	-50			
bw (Hz)	80	90	120	130	140			
	S	soprano	"e"					
freq (Hz)	350	2000	2800	3600	4950			
amp (dB)	0	-20	-15	-40	-56			
bw (Hz)	60	100	120	150	200			
soprano "i"								
freq (Hz)	270	2140	2950	3900	4950			
amp (dB)	0	-12	-26	-26	-44			
bw (Hz)	60	90	100	120	120			
	soprano "o"							
freq (Hz)	450	800	2830	3800	4950			
amp (dB)	0	-11	-22	-22	-50			
bw (Hz)	70	80	100	130	135			
soprano "u"								
freq (Hz)	325	700	2700	3800	4950			
amp (dB)	0	-16	-35	-40	-60			
bw (Hz)	50	60	170	180	200			
alto "a"								
freq (Hz)	800	1150	2800	3500	4950			
amp (dB)	0	-4	-20	-36	-60			
bw (Hz)	80	90	120	130	140			

values							
	f1	f2	f3	f4	f5		
tenor "a"							
freq (Hz)	650	1080	2650	2900	3250		
amp (dB)	0	-6	-7	-8	-22		
bw (Hz)	80	90	120	130	140		
tenor "e"							
freq (Hz)	400	1700	2600	3200	3580		
amp (dB)	0	-14	-12	-14	-20		
bw (Hz)	70	80	100	120	120		
tenor "i"							
freq (Hz)	290	1870	2800	3250	3540		
amp (dB)	0	-15	-18	-20	-30		
bw (Hz)	40	90	100	120	120		
tenor "o"							
freq (Hz)	400	800	2600	2800	3000		
amp (dB)	0	-10	-12	-12	-26		
bw (Hz)	40	80	100	120	120		
		tenor '					
freq (Hz)	350	600	2700	2900	3300		
amp (dB)	0	-20	-17	-14	-26		
bw (Hz)	40	60	100	120	120		
bass "a"							
freq (Hz)	600	1040	2250	2450	2750		
amp (dB)	0	-7	-9	-9	-20		
bw (Hz)	60	70	110	120	130		

FORMANT TABLE 9/13/12 10:14 PM

alto "e"						
freq (Hz)	400	1600	2700	3300	4950	
amp (dB)	0	-24	-30	-35	-60	
bw (Hz)	60	80	120	150	200	
		alto "	i"			
freq (Hz)	350	1700	2700	3700	4950	
amp (dB)	0	-20	-30	-36	-60	
bw (Hz)	50	100	120	150	200	
		alto "	o"			
freq (Hz)	450	800	2830	3500	4950	
amp (dB)	0	-9	-16	-28	-55	
bw (Hz)	70	80	100	130	135	
alto "u"						
freq (Hz)	325	700	2530	3500	4950	
amp (dB)	0	-12	-30	-40	-64	
bw (Hz)	50	60	170	180	200	
countertenor "a"						
freq (Hz)	660	1120	2750	3000	3350	
amp (dB)	0	-6	-23	-24	-38	
bw (Hz)	80	90	120	130	140	
countertenor "e"						
freq (Hz)	440	1800	2700	3000	3300	
amp (dB)	0	-14	-18	-20	-20	
bw (Hz)	70	80	100	120	120	
countertenor "i"						
freq (Hz)	270	1850	2900	3350	3590	
amp (dB)	0	-24	-24	-36	-36	
bw (Hz)	40	90	100	120	120	
countertenor "o"						

bass "e"						
freq (Hz)	400	1620	2400	2800	3100	
amp (dB)	0	-12	-9	-12	-18	
bw (Hz)	40	80	100	120	120	
bass "i"						
freq (Hz)	250	1750	2600	3050	3340	
amp (dB)	0	-30	-16	-22	-28	
bw (Hz)	60	90	100	120	120	
bass "o"						
freq (Hz)	400	750	2400	2600	2900	
amp (dB)	0	-11	-21	-20	-40	
bw (Hz)	40	80	100	120	120	
bass "u"						
freq (Hz)	350	600	2400	2675	2950	
amp (dB)	0	-20	-32	-28	-36	
bw (Hz)	40	80	100	120	120	

FORMANT TABLE 9/13/12 10:14 PM

freq (Hz)	430	820	2700	3000	3300	
amp (dB)	0	-10	-26	-22	-34	
bw (Hz)	40	80	100	120	120	
countertenor "u"						
freq (Hz)	370	630	2750	3000	3400	
amp (dB)	0	-20	-23	-30	-34	
bw (Hz)	40	60	100	120	120	

HTML Csound Manual - © Jean Piché & Peter J. Nix, 1994-97