

```
## R1_VLAN (SW1_3560)
```

```
```
```

```
hostname R1_VLAN
```

```
vlan 8
```

```
name VerHa
```

```
exit
```

```
vlan 16
```

```
name WLAN
```

```
exit
```

```
vlan 24
```

```
name Myy
```

```
exit
```

```
vlan 48
```

```
name Osto
```

```
exit
```

```
ip routing
```

```
interface vlan 1
```

```
ip address 172.21.1.1 255.255.255.0
```

```
exit
```

```
interface vlan 8
```

```
ip address 172.21.8.1 255.255.254.0
```

```
exit
```

```
interface vlan 16
ip address 172.21.16.1 255.255.252.0
exit
```

```
interface vlan 24
ip address 172.21.24.1 255.255.248.0
exit
```

```
interface vlan 48
ip address 172.21.48.1 255.255.240.0
exit
```

```
interface range f0/21-22
channel-group 1 mode active
exit
interface port-channel 1
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 1,8,16,24,48
switchport trunk native vlan 8
exit
```

```
interface f0/24
no switchport
ip address 192.168.12.1 255.255.255.240
no shutdown
exit
```

```
interface f0/23
switchport mode access
switchport access vlan 1
```

```
switchport nonegotiate
```

```
exit
```

```
interface f0/1
```

```
switchport mode access
```

```
switchport access vlan 1
```

```
switchport nonegotiate
```

```
exit
```

```
interface range f0/2-3
```

```
switchport mode access
```

```
switchport access vlan 8
```

```
switchport nonegotiate
```

```
exit
```

```
interface range f0/4-8
```

```
switchport mode access
```

```
switchport access vlan 16
```

```
switchport nonegotiate
```

```
exit
```

```
interface range f0/9-14
```

```
switchport mode access
```

```
switchport access vlan 24
```

```
switchport nonegotiate
```

```
exit
```

```
interface range f0/15-20
```

```
switchport mode access
```

```
switchport access vlan 48
```

```
switchport nonegotiate
```

exit

interface loopback 0

ip address 10.1.1.1 255.255.255.255

exit

router ospf 3

router-id 11.1.1.1

exit

router ospf 3

interface f0/24

ip ospf 3 area 0

exit

router ospf 3

interface loopback 0

ip ospf 3 area 0

exit

router ospf 3

interface vlan 1

ip ospf 3 area 0

exit

router ospf 3

interface vlan 8

ip ospf 3 area 0

exit

router ospf 3

```
interface vlan 16
```

```
ip ospf 3 area 0
```

```
exit
```

```
router ospf 3
```

```
interface vlan 24
```

```
ip ospf 3 area 0
```

```
exit
```

```
router ospf 3
```

```
interface vlan 48
```

```
ip ospf 3 area 0
```

```
exit
```

```
router ospf 3
```

```
passive-interface default
```

```
no passive-interface f0/24
```

```
redistribute connected subnets
```

```
```
```

```
## R2_Reuna
```

```
```
```

```
hostname R2_Reuna
```

```
interface loopback 0
```

```
ip address 10.2.2.2 255.255.255.255
```

```
exit
```

```
interface loopback 21
ip address 172.22.0.1 255.255.252.0
exit
```

```
interface loopback 22
ip address 172.22.4.1 255.255.252.0
exit
```

```
interface loopback 23
ip address 172.22.8.1 255.255.252.0
exit
```

```
interface loopback 24
ip address 172.22.12.1 255.255.252.0
exit
```

```
interface g0/0
ip address 192.168.12.2 255.255.255.240
no shutdown
exit
```

```
interface g0/1
ip address 192.168.23.2 255.255.255.240
no shutdown
exit
```

```
interface g0/2
ip address 192.168.1.2 255.255.255.252
no shutdown
exit
```

```
ip route 0.0.0.0 0.0.0.0 192.168.1.1
```

```
router ospf 3
```

```
 router-id 22.1.1.1
```

```
 exit
```

```
router ospf 3
```

```
 interface g0/0
```

```
 ip ospf 3 area 0
```

```
 exit
```

```
router ospf 3
```

```
 interface g0/1
```

```
 ip ospf 3 area 0
```

```
 exit
```

```
interface loopback 0
```

```
 ip ospf 3 area 0
```

```
 exit
```

```
interface loopback 21
```

```
 ip ospf 3 area 0
```

```
 exit
```

```
interface loopback 22
```

```
 ip ospf 3 area 0
```

```
 exit
```

```
interface loopback 23
```

```
 ip ospf 3 area 0
```

```
exit
```

```
interface loopback 24
```

```
ip ospf 3 area 0
```

```
exit
```

```
router ospf 3
```

```
passive-interface default
```

```
no passive-interface g0/0
```

```
no passive-interface g0/1
```

```
Default-information originate
```

```
redistribute connected subnets
```

```
```
```

```
## R3_ETA
```

```
```
```

```
hostname R3_Eta
```

```
interface f0/1
```

```
ip address 192.168.23.3 255.255.255.240
```

```
no shutdown
```

```
exit
```

```
interface loopback 0
```

```
ip address 10.3.3.3 255.255.255.255
```

```
exit
```

```
interface loopback 1
ip address 172.23.0.1 255.255.248.0
exit
```

```
interface loopback 8
ip address 172.23.8.1 255.255.248.0
exit
```

```
interface loopback 16
ip address 172.23.16.1 255.255.248.0
exit
```

```
interface loopback 24
ip address 172.23.24.1 255.255.248.0
exit
```

```
interface loopback 64
ip address 172.23.64.1 255.255.240.0
exit
```

```
interface loopback 80
ip address 172.23.80.1 255.255.240.0
exit
```

```
interface loopback 96
ip address 172.23.96.1 255.255.240.0
exit
```

```
interface loopback 112
ip address 172.23.112.1 255.255.240.0
```

exit

router ospf 3

interface f0/1

ip ospf 3 area 0

exit

router ospf 3

interface loopback 0

ip ospf 3 area 0

exit

router ospf 3

interface loopback 1

ip ospf 3 area 0

exit

router ospf 3

interface loopback 8

ip ospf 3 area 0

exit

router ospf 3

interface loopback 16

ip ospf 3 area 0

exit

router ospf 3

interface loopback 24

ip ospf 3 area 0

exit

```
router ospf 3
interface loopback 64
ip ospf 3 area 0
exit
```

```
router ospf 3
interface loopback 80
ip ospf 3 area 0
exit
```

```
router ospf 3
interface loopback 96
ip ospf 3 area 0
exit
```

```
router ospf 3
interface loopback 112
ip ospf 3 area 0
exit
```

```
router ospf 3
router-id 13.1.1.1
exit
```

```
router ospf 3
passive-interface default
no passive-interface f0/1
```

```
redistribute connected subnets
```

```

ISP

```

hostname ISP

interface loopback 0

ip address 111.112.113.1 255.255.255.255

exit

interface f0/0

ip address 192.168.1.1 255.255.255.252

no shutdown

exit

ip route 0.0.0.0 0.0.0.0 192.168.1.2

```

SW2_3560

```

hostname SW2\_3560

vlan 8

name VerHa

exit

```
vlan 16
name WLAN
exit
```

```
vlan 24
name Myy
exit
```

```
vlan 48
name Osto
exit
```

```
interface range f0/21-22
channel-group 1 mode active
exit
interface port-channel 1
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 1,8,16,24,48
switchport trunk native vlan 8
exit
```

```
interface range f0/23-24
channel-group 2 mode active
exit
interface port-channel 2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 1,8,16,24,48
switchport trunk native vlan 8
```

exit

interface f0/1

switchport mode access

switchport access vlan 1

switchport nonegotiate

exit

interface range f0/2-3

switchport mode access

switchport access vlan 8

switchport nonegotiate

exit

interface range f0/4-8

switchport mode access

switchport access vlan 16

switchport nonegotiate

exit

interface range f0/9-14

switchport mode access

switchport access vlan 24

switchport nonegotiate

exit

interface range f0/15-20

switchport mode access

switchport access vlan 48

switchport nonegotiate

exit

```
interface vlan 8
ip address 172.21.8.21 255.255.254.0
exit
```

```
ip default-gateway 172.21.8.1
```

```
```
```

```
## SW3_2960
```

```
```
```

```
hostname SW3_2960
```

```
vlan 8
name VerHa
exit
```

```
vlan 16
name WLAN
exit
```

```
vlan 24
name Myy
exit
```

```
vlan 48
name Osto
exit
```

```
interface range f0/23-24
channel-group 2 mode active
exit
interface port-channel 2
switchport mode trunk
switchport trunk allowed vlan 1,8,16,24,48
switchport trunk native vlan 8
exit
```

```
interface range f0/21-22
switchport mode access
switchport access vlan 1
switchport nonegotiate
exit
```

```
interface f0/1
switchport mode access
switchport access vlan 1
switchport nonegotiate
exit
```

```
interface range f0/2-3
switchport mode access
switchport access vlan 8
switchport nonegotiate
exit
```

```
interface range f0/4-8
switchport mode access
switchport access vlan 16
switchport nonegotiate
```

exit

interface range f0/9-14

switchport mode access

switchport access vlan 24

switchport nonegotiate

exit

interface range f0/15-20

switchport mode access

switchport access vlan 48

switchport nonegotiate

exit

interface vlan 8

ip address 172.21.8.22 255.255.254.0

exit

ip default-gateway 172.21.8.1

```

PC

```

PC1

default gateway: 172.21.8.1

172.21.8.51 255.255.254.0

PC2

default gateway: 172.21.8.1

172.21.8.52 255.255.254.0

PC3

default gateway: 172.21.8.1

172.21.8.53 255.255.254.0

...