
Chapter 9: Virtual Memory





Chapter 9: Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples





Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model






Background


- Virtual memory separation of user logical memory from physical memory.
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation






Virtual Memory That is Larger Than Physical Memory






Virtual-address Space







Shared Library Using Virtual Memory





Silberschatz, Galvin and Gagne ©2009

9.7




Demand Paging

- Bring a page into memory only when it is needed
 - Less I/O needed
 - Less memory needed
 - Faster response
 - More users
- Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager






Transfer of a Paged Memory to Contiguous Disk Space







Valid-Invalid Bit


- With each page table entry a valid–invalid bit is associated (v ⇒ in-memory, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:


Frame #	valid-invalid bit	
	V	
	V	
	V	
	V	
	i	
	i	
	i	
page table		


■ During address translation, if valid–invalid bit in page table entry is I ⇒ page fault



Page Table When Some Pages Are Not in Main Memory











Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:

page fault


- 1. Operating system looks at another table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory
- 2. Get empty frame
- 3. Swap page into frame
- 4. Reset tables
- 5. Set validation bit = v
- 6. Restart the instruction that caused the page fault





Page Fault (Cont.)

- Restart instruction
 - block move




auto increment/decrement location





Steps in Handling a Page Fault







Performance of Demand Paging

- Page Fault Rate $0 \le p \le 1.0$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in
+ restart overhead
```





Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds

■ EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$

If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!





Process Creation

- Virtual memory allows other benefits during process creation:
 - Copy-on-Write
 - Memory-Mapped Files (later)






Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- Free pages are allocated from a pool of zeroed-out pages






Before Process 1 Modifies Page C







After Process 1 Modifies Page C








- Page replacement find some page in memory, but not really in use, swap it out
 - algorithm
 - performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times






Page Replacement


- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory







Need For Page Replacement















Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
- Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Restart the process





Page Replacement



memory




Page Replacement Algorithms

- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is





Graph of Page Faults Versus The Number of Frames







First-In-First-Out (FIFO) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)


4 frames


■ Belady's Anomaly: more frames ⇒ more page faults






FIFO Page Replacement








FIFO Illustrating Belady's Anomaly





Optimal Algorithm

- Replace page that will not be used for longest period of time
- 4 frames example


1	4	
2		6 page faults
3		
4	5	

- How do you know this?
- Used for measuring how well your algorithm performs





Optimal Page Replacement







Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

1	1	1	1	5
2	2	2	2	2
3	5	5	4	4
4	4	3	3	3


- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to determine which are to change





LRU Page Replacement





page frames





LRU Algorithm (Cont.)


- Stack implementation keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - No search for replacement






Use Of A Stack to Record The Most Recent Page References

reference string








LRU Approximation Algorithms

- Reference bit
 - With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
 - Replace the one which is 0 (if one exists)
 - We do not know the order, however
- Second chance
 - Need reference bit
 - Clock replacement
 - If page to be replaced (in clock order) has reference bit = 1 then:
 - set reference bit 0
 - leave page in memory
 - replace next page (in clock order), subject to same rules



Second-Chance (clock) Page-Replacement Algorithm





Counting Algorithms

- Keep a counter of the number of references that have been made to each page
- LFU Algorithm: replaces page with smallest count
- MFU Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used





Allocation of Frames

- Each process needs minimum number of pages
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Two major allocation schemes
 - fixed allocation
 - priority allocation





Fixed Allocation

- Equal allocation For example, if there are 100 frames and 5 processes, give each process 20 frames.
- Proportional allocation Allocate according to the size of process

$$-s_i = \text{size of process } p_i$$

$$-S = \sum S_i$$

-m = total number of frames

$$-a_i =$$
allocation for $p_i = \frac{s_i}{S} \times m$

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 5$$

$$a_2 = \frac{127}{137} \times 64 \approx 59$$





Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number





Global vs. Local Allocation


- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
- Local replacement each process selects from only its own set of allocated frames






Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
 - low CPU utilization
 - operating system thinks that it needs to increase the degree of multiprogramming
 - another process added to the system
- Thrashing = a process is busy swapping pages in and out





Thrashing (Cont.)








Demand Paging and Thrashing

- Why does demand paging work? Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Why does thrashing occur?
 Σ size of locality > total memory size





Locality In A Memory-Reference Pattern







Working-Set Model

- Δ = working-set window = a fixed number of page references Example: 10,000 instruction
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \Sigma WSS_i \equiv \text{total demand frames}$
- if $D > m \Rightarrow$ Thrashing
- Policy if D > m, then suspend one of the processes






Working-set model

page reference table

23444343434413234443444...



$$WS(t_1) = \{1,2,5,6,7\}$$



$$WS(t_2) = \{3,4\}$$





Keeping Track of the Working Set


- Approximate with interval timer + a reference bit
- Example: $\Delta = 10,000$
 - Timer interrupts after every 5000 time units
 - Keep in memory 2 bits for each page
 - Whenever a timer interrupts copy and sets the values of all reference bits to 0
 - If one of the bits in memory = $1 \Rightarrow$ page in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units





Page-Fault Frequency Scheme


- Establish "acceptable" page-fault rate
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame



number of frames



Working Sets and Page Fault Rates








Memory-Mapped Files


- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory
- A file is initially read using demand paging. A page-sized portion of the file is read from the file system into a physical page. Subsequent reads/writes to/from the file are treated as ordinary memory accesses.
- Simplifies file access by treating file I/O through memory rather than read() write() system calls
- Also allows several processes to map the same file allowing the pages in memory to be shared






Memory Mapped Files





Memory-Mapped Shared Memory in Windows







Allocating Kernel Memory


- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous





Buddy System


- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available





Buddy System Allocator

physically contiguous pages





Silberschatz, Galvin and Gagne ©2009

9.58




Slab Allocator

- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction



Slab Allocation






Other Issues -- Prepaging

Prepaging

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- Assume s pages are prepaged and α of the pages is used
 - Is cost of s * α save pages faults > or < than the cost of prepaging
 - s * (1- α) unnecessary pages?
 - α near zero \Rightarrow prepaging loses





Other Issues – Page Size

- Page size selection must take into consideration:
 - fragmentation
 - table size
 - I/O overhead
 - locality





Other Issues - TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
 - Otherwise there is a high degree of page faults
- Increase the Page Size
 - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
 - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation





Other Issues – Program Structure

- Program structure
 - Int[128,128] data;
 - Each row is stored in one page
 - Program 1

```
for (j = 0; j <128; j++)
for (i = 0; i < 128; i++)
data[i,j] = 0;
```

 $128 \times 128 = 16,384$ page faults

Program 2

```
for (i = 0; i < 128; i++)
for (j = 0; j < 128; j++)
data[i,j] = 0;
```

128 page faults






Other Issues – I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm





Reason Why Frames Used For I/O Must Be In Memory







Operating System Examples


- Windows XP
- Solaris





Windows XP

- Uses demand paging with clustering. Clustering brings in pages surrounding the faulting page
- Processes are assigned working set minimum and working set maximum
- Working set minimum is the minimum number of pages the process is guaranteed to have in memory
- A process may be assigned as many pages up to its working set maximum
- When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory
- Working set trimming removes pages from processes that have pages in excess of their working set minimum




Solaris

- Maintains a list of free pages to assign faulting processes
- Lotsfree threshold parameter (amount of free memory) to begin paging
- Desfree threshold parameter to increasing paging
- Minfree threshold parameter to being swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Pageout is called more frequently depending upon the amount of free memory available



Solaris 2 Page Scanner



End of Chapter 9

