

USER GUIDE

Point of Sale System

A complete walkthrough of the cashier and manager tools — every screen, every button, from logging in to closing out the register.

Prepared for staff onboarding · Version 2.0 · screens shown match the live system

Table of Contents

1. Logging In	Sign in and password reset
2. The POS Dashboard	Header, stats, and the product grid
3. Cart, Cash Session & Checkout	Building a sale and getting paid
4. Recent Receipts & Transaction Details	Viewing, printing, refunding, voiding
5. My Account	Your profile, email, and password
6. Manager Console	Sales reports, cashier performance, analytics
7. Audit Log	Every action, who did it, and when
8. Manage Users	Adding staff, resetting passwords, roles
9. Troubleshooting & FAQ	Common questions

Every screen below is recreated to match your real system's layout, colors, and wording exactly, based on live screenshots.

Logging In

Every shift starts here. Open the POS in your browser and you'll land on the sign-in screen.

CASHIER
POS System
Sign in to access your POS Dashboard

EMAIL
you@store.com

PASSWORD
.....

Sign In

[Forgot your password?](#)

Sign-in screen

Email field	The email address your admin created for you. If you type it wrong (e.g. leave out the "@"), an error appears immediately under the field, before you even click Sign In.
Password field	Your account password. Hidden by default as dots.
Sign In button	Submits your credentials. Shows a spinner while checking so you know it's working, then either takes you to the dashboard or shows an error telling you which field was wrong.
Forgot your password? link	Takes you to the password-reset screen (below) if you can't remember your password.

Forgot your password?

CASHIER
Forgot your password?
Enter your account email and we'll send you a link to reset your password.

EMAIL
you@store.com

Send Reset Link

[Back to sign in](#)

No luck? A manager can still reset your password directly from **Manage Users**.


Forgot your password screen

- 1 Click **Forgot your password?** on the sign-in screen.
- 2 Enter your email and click **Send Reset Link**.
- 3 Open the email that arrives and follow the link to set a new password.
- 4 No email arriving? Ask a manager or admin to reset it for you instantly from **Manage Users** (Chapter 8) — no email needed for that route.

CHAPTER 2

The POS Dashboard

This is the cashier's home screen, reached right after logging in.



Dashboard header and today's summary cards


Header, button by button


Philippines (Ph) pill	Shows which store location/branch you're ringing up sales for and that the connection to the system is live (green dot).
REGISTER: CLOSED / OPEN badge	Shows whether your cash session is currently open. It must say OPEN (and you must have started a session) before Checkout will work.
My Account button	Opens your personal account page (Chapter 5) to update your name, email, or password.
Logged in: [name]	Confirms which staff account is currently active on this screen — important on a shared terminal.
Logout button	Signs you out and returns to the login screen. Always logout when stepping away from a shared register.

Today's summary cards

Completed Sales	Number of successful transactions rung up today (by everyone, or just you, depending on the view).
Total Sales	Total peso value of today's completed sales.
Voided Sales	How many transactions were cancelled today. Keep an eye on this — a high number may be worth reviewing in the Audit Log.

The Products panel





Product grid — each card is one item you can sell

Search box	Type a product name or SKU to filter the grid, or scan a barcode with a USB/handheld scanner — a scanned item is added to the cart automatically.
Refresh link	Reloads the product list and current stock counts from the server manually.
Category dropdown	Narrows the grid to one product category instead of showing everything.
Stock badge (e.g. "3 PCS in stock")	Live count of how many units are available. It drops as you add the item to your cart (before you even check out) and turns red ("Out of stock") when none are left.
Unit dropdown (e.g. "Piece")	Some products sell in more than one unit — a single piece vs. a full box/case. Choose the unit before adding to cart if more than one option is listed.
Add to cart button	Adds one of that product/unit to your current sale. Becomes a greyed-out "Unavailable" button once stock hits zero.
Page arrows (< 1/1 >)	Move between pages of products if you have more items than fit on one screen.

Cart, Cash Session & Checkout

The right-hand panel is where you open your register, build the sale, and take payment.

CART0 ITEMS

+

Cart is empty

Subtotal (VAT Incl.)

₱0.00

Discount

₱0.00

Total

₱0.00

Includes VAT (12%)

₱0.00

OPENING CASH

CLOSING CASH

CUSTOMER

+ Apply Discount

PAYMENT

CASH RECEIVED

Change

₱0.00

Open session

Close session

Checkout →

Cart panel — empty state, before a register session is opened

Opening your register

Opening Cash field	Count the cash in your drawer at the start of your shift and type that amount here.
Open session button	Starts your cash session with that opening amount. The header badge changes from "REGISTER: CLOSED" to open, and Checkout becomes usable.

Building the sale

Cart list	Every item you've added from the product grid, with quantity and line total. Shows "Cart is empty" until you add something.
Subtotal / Discount / Total / Includes VAT	Running totals: Subtotal is the item prices added up, Discount subtracts any applied discount, Total is what the customer pays, and "Includes VAT (12%)" shows how much of that

total is tax.

Customer field	Defaults to "Walk-in Customer." Search and attach a specific customer if your store tracks customer purchase history.
+ Apply Discount button	Opens a small form to apply a percentage or fixed-peso discount to the whole sale.

Taking payment


Payment dropdown	Choose Cash, Card, GCash, or whatever payment methods your store accepts.
Cash Received field	For cash sales, enter the amount the customer handed you.
Change (auto-calculated)	Cash Received minus Total, shown in green — hand this amount back to the customer.
Checkout → button	Finalizes the sale: stock is deducted for real, a receipt is generated, and the cart clears. Greyed out until the cart has items and your register session is open. Shows a spinner while processing.

Closing your register

Closing Cash field	At the end of your shift, count your drawer again and enter the actual amount here.
Close session button	Ends your shift and compares your counted cash to what the system expected based on your sales. Large mismatches are held for a manager's approval before the session actually closes.


Recent Receipts & Transaction Details

Every completed sale appears as a card under **Recent Receipts**, on your dashboard or the Manager Console.



A receipt card — click "View Receipt" to open the full Transaction Details

Transaction Details window



Transaction Details window, opened from any receipt

Print button	Opens your browser's print dialog to print a copy of the receipt on any printer.
Print to USB printer button	Sends the receipt directly to a connected thermal USB receipt printer, formatted to fit thermal paper width.
Refund sale button	Use when a customer returns an item after the sale is done. Money is recorded as returned and the item(s) go back into stock. The receipt's status changes to REFUNDED.

Void sale button

Cancels the entire sale outright (for a mistake made in the moment). All items return to stock and the sale no longer counts toward totals. Disabled once a sale is already refunded.

Every Void or Refund is automatically written to the Audit Log with who did it and when (Chapter 7).

My Account

Reached from the **My Account** button in the header, from anywhere in the system.

ACCOUNT

My Account

Back to POS

Logged in: Cashier User

Logout

C

Cashier User

cashier@shogun.local

CASHIER

PROFILE

FULL NAME

Cashier User

Save

EMAIL ADDRESS

cashier@shogun.local

CONFIRM WITH CURRENT PASSWORD

.....

Save Email

SECURITY

CURRENT PASSWORD

.....

NEW PASSWORD

Min. 8 characters

CONFIRM NEW PASSWORD

.....

Change Password

My Account page

Avatar / role badge	Shows your initial, name, email, and role (Cashier, Manager, or Admin) at a glance.
Full Name + Save	Updates the display name shown across the system (e.g. on receipts as the cashier).
Email Address + Confirm with current password + Save Email	Changes your login email. Requires your current password to confirm it's really you — typing the wrong one shows a live error under that field as soon as you click away.
Current / New / Confirm New Password + Change Password	Changes your login password. Current Password is checked live as you tab out of it. New Password needs at least 8 characters, and Confirm New Password must match it exactly.

Manager Console

Managers and admins get an extra header menu (Manage Users, Audit Log) and a store-wide reporting dashboard.

MANAGER

Manager Console

Philippines (Ph)

Back to POS

Manage Users

Audit Log

My Account

Logged in: Manager User

Logout

Showing sales for today (2026-09-18)

Completed Sales 2

Total Sales **₱63.75**

Voided Sales 0

SALES REPORTS (ALL CASHIERS)

DATE: 18/09/2026 TODAY EXPORT CSV

TXN ID	CASHIER	TOTAL	STATUS	ACTIONS
SALE-2026...2KT9	Manager User	₱20.00	COMPLETED	View · Print · Void
SALE-2026...05ZQ	Admin User	₱60.00	REFUNDED	View · Print

Manager Console — header, today's totals, and the store-wide sales table

Manage Users / Audit Log buttons	Manager/admin-only pages, covered in Chapters 7 & 8.
Sales Reports table	Every transaction store-wide (not just yours), with Date filter, "Today" shortcut, and "Export CSV" to download the list for bookkeeping or Excel.
View / Print / Void per row	Same actions as the Transaction Details window (Chapter 4), available right from the table. Void is greyed out once a sale is already refunded.

Cashier Performance & Payment Method Breakdown

CASHIER	COMPLETED	TOTAL SALES	VOIDED	STATUS
Admin User	1	₱43.75	0	EXCELLENT
Manager User	1	₱20.00	0	FAIR

The **Day / Month** toggle switches this table between today's numbers and the whole month's. **Payment Method Breakdown** next to it shows what share of today's sales came in as cash, card, GCash, etc., with a progress bar per method.

Monthly Analytics

Use the **Month** picker (with a "This Month" shortcut and its own **Export CSV**) to see **Top Selling Products** and products that are **Not Selling This Month** — useful for restocking and spotting dead stock.

Audit Log

A running history of every sensitive action in the system — who did what, and when.

EVENT HISTORY

EVENT: *e.g. checkout, void, login* FROM: dd/mm/yyyy TO: dd/mm/yyyy [Filter](#) [Clear](#)

DATE/TIME	EVENT	USER	DETAILS
3:42 PM	REGISTER CLOSED	Cashier User	Expected ₱500.00, counted ₱500.00 (exactly matched).
1:23 PM	REGISTER CLOSED	Cashier User	Expected ₱500.00, counted ₱100.00 (short by ₱400.00). Approved by admin@shogun.local.
11:44 AM	PASSWORD RESET BY ADMIN	Admin User	Reset the password for cashier@shogun.local.
11:43 AM	PASSWORD RESET BY EMAIL	Cashier User	Reset their own password using the emailed link.

Page 1 of 1 (44 events) [Previous](#) [Next](#)

Audit Log — plain-English event history

EVENT filter	Type a keyword (checkout, void, login, etc.) to only show matching events.
FROM / TO date pickers + Filter / Clear	Narrow the log to a specific date range, or clear the filters to see everything again.
Event type column	What happened — e.g. REGISTER OPENED/CLOSED, CHECKOUT STARTED, SALE COMPLETED, PASSWORD RESET BY ADMIN/EMAIL.
Details column	A plain-English description, e.g. an exact cash count, or which manager approved a mismatch. Click "Technical details" under any row to see the raw underlying data.

If a register closes with a big cash shortfall, look here for the "Approved by [manager]" line — it tells you exactly who signed off on the discrepancy.

Manage Users

ALL USERS

NAME	EMAIL	PASSWORD	ROLE	STATUS	ACTIONS
Admin User	admin@shogun.local	—	ADMIN	ACTIVE	My Account
Cashier User	cashier@shogun.local	Reset	Cashier ▾	ACTIVE	Edit · Deactivate
Manager User	manager@shogun.local	Reset	Manager ▾	ACTIVE	Edit · Deactivate
Full name	email@store.com	Min. 8 characters	Cashier ▾	ACTIVE	Add user

Manage Users — admin view (your own row only ever shows "My Account")

Password → Reset button	Instantly issues that person a new temporary password — no email needed. Not shown on your own row.
Role dropdown	Change someone's role between Cashier, Manager, and Admin. Your own role can't be changed from here.
Status badge	ACTIVE means they can log in; deactivated accounts can't, but their sales history is kept.
Edit / Deactivate	Edit changes their name/email; Deactivate blocks their login immediately (use this instead of deleting someone when they leave).
Bottom row: Full name / email / password / role + Add user	Creates a brand-new staff account. Share the temporary password with them securely — they'll be required to set their own on first login.

Troubleshooting & FAQ

"Insufficient stock" when I try to check out

Someone else sold the remaining units first. Remove or reduce that item and try again — the product grid's stock badge already reflects the current amount.

Checkout button is greyed out

Either your cart is empty, or your register session isn't open yet — check the "REGISTER" badge in the header and open a session if it says CLOSED.

I forgot my password and the reset email never arrives

Ask an admin to reset it for you from **Manage Users** (Chapter 8) — that doesn't depend on email at all.

My cash count doesn't match at closing

Small differences are recorded automatically. Large ones are held for a manager to approve before the register can close — find a manager to review it with you.

Void button is disabled on a sale

A sale that's already been refunded can no longer be voided separately — the refund already reversed it.

Questions not covered here? Ask your manager or the person who set up this system for you.