

BATCH - using FRED in batch.

FRED programs may be executed from GCOS8 batch using the following JCL:

```
$      program    fred
$      limits     10,40k
$      prmf1      **,r/c,r,cmdlib/etc/qstar
command line or FRED commands
```

If the first line of input after the \$PRMFL card begins with the command name `fred`, it is assumed to be a command line for a FRED program. Otherwise, the input is assumed to be a sequence of FRED commands. Note that this input will be converted to BCD, and therefore single case. The `O+IL` option may be useful to distinguish cases.

Batch FRED has several differences from TSS FRED:

- The `!` command does not work.
- `O+P` has no effect on output; however, `F0` will give the current pagesize setting.
- After a file I/O operation, the number register is not set to the number of blocks read. File I/O will not tell you whether a file is temporary or permanent.
- The special commands `w3` and `w7` write Media-3 (BCD print image) and Media-7 (ASCII print image) files, respectively. Each time you issue one of these commands, FRED attaches a different report code to the output, starting at zero and increasing by one; this wraps around at octal 70.

If there is no `I*` data present, FRED will instead use the system console (TY2) for interactive input/output.

Copyright © 1998, Thinkage Ltd.