实验2 跨交换机实现VLAN

【实验名称】

跨交换机实现VLAN。

【实验目的】

理解跨交换机之间VLAN的特点。使在同一VLAN里的计算机系统能跨交换机进行相互通信,而在不同VLAN里的计算机系统不能进行相互通信。


【技术原理】

Tag Vlan是基于交换机端口的另外一种类型,主要用于实现跨交换机的相同VLAN内主机之间可以直接访问,同时对于不同VLAN的主机进行隔离。Tag Vlan遵循了IEEE802.1q协议的标准。在利用配置了Tag vlan的接口进行数据传输时,需要在数据帧内添加4个字节的802.1q标签信息,用于标识该数据帧属于哪个VLAN,以便于对端交换机接收到数据帧后进行准确的过滤。

【实验设备】

S3760 (两台)、主机(3台)、直连线(4条)

【实验拓扑】



实验时,按照拓扑图进行网络的连接,注意主机和交换机连接的端口。

【实验步骤】

在未划分VLAN前两台PC1、PC2、PC3互相ping是可以通的。

验证: PC1, 192.168.10.10、255.255.255.0

PC2, 192. 168. 10. 20, 255. 255. 255. 0

PC3, 192. 168. 10. 30, 255. 255. 255. 0

在PC1端, C:>ping 192.168.10.20

步骤1.在交换机SwitchA上创建Vlan 10,并将0/5端口划分到Vlan 10中。

SwitchA#configure terminal

SwitchA(config)# vlan 10

SwitchA(config-vlan)# name sales

SwitchA(config-vlan)#exit

SwitchA(config)#interface fastethernet0/5

SwitchA(config-if)#switchport access vlan 10

验证测试:验证已创建了Vlan 10,并将0/5端口已划分到Vlan 10中。

SwitchA#show vlan id 10!查看某一个VLAN的信息

VLAN Name Status Ports

10 sales STATIC Fa0/5

步骤2.在交换机switchA上创建Vlan 20,并将0/15端口划分到Vlan 20中。

SwitchA(config)# vlan 20

SwitchA(config-vlan)# name technical

SwitchA(config-vlan)#exit

SwitchA(config)#interface fastethernet0/15

SwitchA(config-if)#switchport access vlan 20

验证测试:验证已创建了Vlan 20,并将0/15端口已划分到Vlan 20中。

SwitchA#show vlan id 20

VLAN Name Status Ports

20 technical STATIC Fa0/15

步骤3.把交换机SwitchA与交换机SwitchB相连的端口(假设为0/24端口)定义为tag vlan模式。

SwitchA(config)#interface fastethernet0/24

SwitchA(config-if)#switchport mode trunk !将fastethernet 0/24端口设为tag vlan模式

验证测试:验证fastethernet 0/24端口已被设置为tag vlan模式。

SwitchA#show interfaces fastEthernet0/24 switchport

Interface Switchport Mode Access Native Protected VLAN lists

Fa0/24 Enabled Trunk 1 1 Disabled All

注:交换机的Trunk接口默认情况下支持所有VLAN。

步骤4.在交换机SwitchB上创建Vlan 10,并将0/5端口划分到Vlan 10中。

SwitchB # configure terminal

SwitchB(config)# vlan 10

SwitchB(config-vlan)# name sales

SwitchB(config-vlan)#exit

SwitchB(config)#interface fastthernet0/5

SwitchB(config-if)#switchport access vlan 10

验证测试:验证已在SwitchB上创建了Vlan 10,并将0/5端口已划分到Vlan 10中。

SwitchB#show vlan id 10

VLAN Name Status Ports

10 sales STATIC Fa0/5

步骤**5.** 把交换机**SwitchB**与交换机**SwitchA**相连的端口(假设为**0/24**端口)定义为**tag vlan**模式。

SwitchB(config)#interface fastethernet0/24

SwitchB(config-if)#switchport mode trunk

验证测试:验证fastethernet 0/24端口已被设置为tag vlan模式。

SwitchB#show interfaces fastEthernet 0/24 switchport

Interface Switchport Mode Access Native Protected VLAN lists

Fa0/24 Enabled Trunk 1 1 Disabled All

步骤6.PC1与PC3能互相通信,但PC2与PC3不能互相通信。

C:\>ping 192.168.10.30!在PC1的命令行方式下验证能Ping通PC3

Pinging 192.168.10.30 with 32 bytes of data:

Reply from 192.168.10.30: bytes=32 time<10ms TTL=128

Reply from 192.168.10.30: bytes=32 time<10ms TTL=128

Reply from 192.168.10.30: bytes=32 time<10ms TTL=128

Ping statistics for 192.168.10.30:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = Oms, Maximum = Oms, Average = Oms

C:\>ping 192.168.10.30! 在PC2的命令行方式下验证不能Ping通PC3

Pinging 192.168.10.30 with 32 bytes of data:

Request timed out.

Request timed out.

Request timed out.

Ping statistics for 192.168.10.30:

Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

Approximate round trip times in milli-seconds:

Minimum = Oms, Maximum = Oms, Average = Oms

【注意事项】

- 1、两台交换机之间相连的端口应该设置为tag vlan模式。
- 2、Trunk接口在默认情况下支持所有VLAN的传输。

【命令参考】

SwitchA#show running-config ! 显示交换机SwitchA的全部配置

Current configuration: 284 bytes

Building configuration...

version 1.0

hostname SwitchA

vlan 1

vlan 10!创建VLAN10

name sales

vlan 20!创建VLAN20

name technical

interface fastEthernet 0/5

switchport access vlan 10 !将FO/5加入VLAN10

interface fastEthernet 0/15

switchport access vlan 20 !将F0/15加入VLAN20

interface fastEthernet 0/24

switchport mode trunk !将FO/24设为TRUNK, 支持TAG VLAN

end

SwitchB#show running-config! 显示交换机SwitchB的全部配置

Building configuration...

Current configuration: 284 bytes

version 1.0

hostname SwitchB

vlan 1

vlan 10!创建VLAN10

name sales

interface fastEthernet 0/5

switchport access vlan 10 !将FO/5加入VLAN10

interface fastEthernet 0/24

switchport mode trunk !将FO/24设为TRUNK, 技术TAG VLAN

end

【思考】

- 1. 说明vlan技术中的trunk模式端口的意义。
- 2. 如何查看trunk接口允许哪些VLAN通过?
- 3. 实验开始前请先确定三台PC机处于一个网段里面。为什么做这样的限定?