Concurrent Systems Operating Systems

Andrew Butterfield ORI.G39, Andrew.Butterfield@scss.tcd.ie




Going "virtual"

- An operating system is running a (large) number of processes
 - running their code, interrupting them, running some other process' code...
- Nowadays we expect to be able to run more processes than will fit in physical memory
 - memory of currently running process needs to be in RAM
 - what about a waiting/ready process?

Process memory management

- Solution: use another memory device (e.g. a hard disk) to increase memory capacity
 - A "swap device" or "page file"
 - Treat the memory used by a process as a set of fixed size memory chunks, called pages
 - Simplifies moving memory contents to/from the swap device
 - Leads to fragmentation: process's memory is no longer contiguous in physical memory
 - Not only does the programmer not know where his/her program will be located, but now it can also move over time


Relocation and non-contiguity






- Better solution: Give each process its own virtual address space
 - Divide the space into fixed-size pages (e.g. 4KB or 212B)
- Programs refer to addresses in their own virtual memory space virtual addresses

• "On-the-fly" conversion of virtual addresses into physical addresses, which are applied to



- A Memory Management Unit (MMU) is usually integrated into modern CPUs
- If we use 32-bit addresses (physical and virtual) and if the address space is divided into 4KB pages
 - The total addressable memory is $2^{32} = 4GB$
 - Each page contains 2¹² bytes (4KB) requiring a 12-bit offset
 - There are 2²⁰ (1,048,576) 4KB pages, each with a 20-bit page number

- Per-process virtual address space
 - Each process has its own virtual address space
- The size of the virtual address space is typically much larger than the physical address space
 - Every virtual page won't be mapped to a physical page
 - Some virtual pages may not be used
 - Some pages may be mapped to a swap device or page file



- Helps solve issues with
 - Location
 - Protection
 - Sharing
 - Logical Organisation
 - Physical Organisation

Location

- In a multiprogramming environment, processes (and the operating system) need to share physical memory
- Programs must be paged in and out of memory
- Programmers have no way of knowing where in physical memory their processes will be located, and processes won't be continuous
- Virtual memory gives each process it's own contiguous virtual memory space, within which the program works.

Protection

- In a multiprogramming environment, a user process must be prevented from interfering with memory belonging to other processes and the operating system itself
- This protection must be implemented at run-time
- Each process only has access to its own virtual memory space, which should never map to the physical memory of another process (except under specific circumstances!)

Sharing

- Protection must be flexible enough to allow portions of memory to be shared between processes
- We can map the virtual pages of different processes to the same physical memory page frame (or same frame on disk)


Logical Organisation

- Programs are organised as modules with different properties
 - Executable code, data, shared data
- Assign properties to virtual memory pages, e.g. read-only, executable, non-executable, etc.

Physical Organisation

- The program should be isolated from implementation of the memory hierarchy (e.g. swapping)
- The program shouldn't be affected with the amount of physical memory available
- The virtual memory hides such details from the program
- Program can enquire about properties of interest, can ask for pages to be "wired" or locked into physical memory for performance or response reasons

Virtual memory implementation



- Each process has its own page table
 - Used to map virtual pages to physical page frames
 - Page tables are also stored in memory
- To translate a virtual page number to a physical page frame number
 - Use the virtual page number as an index to the page table
 - Read the physical page frame number from the table




Virtual memory implementation

- Each process has its own page table
 - Used to map virtual pages to physical page frames
 - Page tables are also stored in memory
- To translate a virtual page number to a physical page frame number
 - Use the virtual page number as an index to the page table
 - Read the physical page frame number from the table

E.g. Virtual memory implementation

Page table format (32-bit addresses and 4KB pages)



page table entry (PTE)


<u>Status</u>: e.g. valid, protection level, modified, referenced




Multi-level page tables

- Assuming 32-bit addresses and 4KB page size
 - 1,048,576 page table entries x 20+ bits bytes each \approx 3 MB
 - i.e. every process requires a 3 MB page table!!
 - wasteful, when you consider that most processes will use only a small portion of the virtual address space
 - most of the page table will be unused
- Solution
 - A multi-level page table scheme:

Multi-level page tables



Multi-level page tables



Two-level page tables

- One primary page table
- As many secondary page tables as needed
- Secondary page tables are created (and removed) as needed
 - Depending on how much of the virtual memory space is required by the process


Two-level page tables


■What is the total size of all page tables in the preceding example, if two primary PTEs are used?

Two-level page tables

- In the preceding example, each page table was 4 kB in size so each page table fitted in exactly one page frame
- Different schemes will use different size bit-fields for 1st and 2nd indices
- Different schemes will use three (or more?) levels of page tables
- More efficient than a single-level scheme
- The page offset still remains un-translated.

Typical process memory layout





Page Faults

- When the MMU accesses a PTE, it checks the Valid bit of the status field to determine if the entry is valid:
 - if V==0 and a primary PTE is being accessed then a secondary page table has not been allocated physical memory
 - if V==0 and a secondary PTE is being accessed
 then no physical memory has been allocated to the referenced page
 - in either case, a page fault occurs

Page Faults

- The OS is responsible for handling page faults by ...
 - ... allocating a page of physical memory for a secondary page frame
 - ... allocating a page of physical memory for the referenced page
 - ... updating page table entries
 - ... writing a replaced page to disk if it is dirty
 - ... reading code or data from disk (another thread will be scheduled pending the I/O operation)
 - ... signalling an access violation
 - ... retrying to execute the faulting instruction

Translation look aside buffer

- Each virtual-to-physical memory address translation requires one memory access for each level of page tables
 - 2 memory accesses in a 2-level scheme
- To reduce the number of memory access required for virtual-to-physical address translation, the MMU uses a Translation Look-Aside Buffer (TLB)
 - An on-chip cache
 - Stores the results of the *m* most recent address translations

0	virtual page number		secondary page table entry
		•	
m-I			

Translation Look-Aside Buffer

- Before walking the page tables to translate a virtual address to a physical address...
 - ... the MMU checks each entry in the TLB
- If the virtual page number is found, the cached secondary PTE is used by the MMU to translate the address ...
 - ... and there is no need to walk the page tables in memory
- If a TLB match is not found ...
 - ... The MMU walks the page tables and locates the required PTE
- The least recently used (LRU) TLB entry is now replaced with the current virtual page number and the PTE from the secondary page table
- What are the TLB implications of a context switch?



Page fault handling

