ПЛШ Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition Stability Cancellation

#### 1. Motivation and Introduction

Numerical Algorithms in Computer Science - Basics and **Applications** 

#### What is Numerics?

#### Numerical Mathematics:

- Field of (applied) mathematics.
- Designing computational methods for continuous problems mainly in the fields of linear algebra (solving systems of linear equations, finding eigenvalues etc.) and calculus (finding roots or extrema etc.).
- Often related to approximations (solving differential equations, computing integrals) unlike other fields of mathematics.
- Analysis of numerical algorithms: memory requirements, computing time, accuracy of approximation (if using an approximate algorithm).

# • Numerical Programming:

- Field of computer science.
- Efficient implementation of numerical algorithms (memory efficiency, speed, hardware considerations (e.g. cache), parallelizability).

Motivation and Introduction: Numerical Algorithms in Computer Science     Numerisches Programmieren, ST23, Thomas Huckle	page 1 of 48	Motivation and Introduction: Numerical Algorithms in Computer Science     Numerisches Programmieren, ST23, Thomas Huckle	page 2 of 48		
Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition	Stability Cancellation	Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition Sta	bility Cancellation		


#### Numerical Simulation:


- Main field in the application of numerical methods.
- Present in nearly every discipline of science and engineering.
- Provides the third possibility of knowledge acquisition, the other two "classics" being theoretical analysis and physical experimentation.
- Is, and always has been, the main use of HPC (supercomputers and cluster computers).

# 1.1. Applications of Numerical Methods in Computer Science

# **Geometric Modeling**

- Geometric modeling or CAGD (Computer-Aided Geometric Design) deals with the modeling of geometric objects on a computer (car bodies, dinosaurs for
- · For the generation and modification of nonlinear curves and surfaces, there are a number of efficient numerical methods:
  - Bézier curves and surfaces
  - B-spline curves and surfaces
  - NURBS (Non-Uniform Rational B-Splines)
- Such methods are based on the methods of interpolation from Chapter 2.





ТИП

1. Motivation and Introduction: Numerical Algorithms in Computer Science 1. Motivation and Introduction: Numerical Algorithms in Computer Scien page 3 of 48 page 4 of 48 sches Programmieren, ST23, Thomas Huckle n. ST23. Thomas Huckle ТИП ТИП Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Float & Rounding Floating Point Arithmetic

#### **Computer Graphics**

- Computer graphics is a very computationally intensive branch of computer science:
  - In ray tracing, to compute highlight and reflection effects, a huge number of intersection points of rays with objects of the scenery have to be computed which leads to the problem of solving a system of linear or nonlinear equations (see Chapters 4 and 6).
  - In the radiosity method, used for computing diffuse illumination, a large linear system of equations is constructed which typically has to be solved iteratively - this is covered in Chapter 6.
  - Computer games or flight simulations require very powerful numerical algorithms such that they can be run in real time





# **Image Processing**

- Image processing without numerical methods is also unthinkable. Almost all filters and transformations are numerical algorithms, that are typically related to the fast Fourier transformation (FFT).
- In addition, most methods for image compression (such as JPEG) rely on numerical transformations (discrete cosine transformation, wavelet transformation)
- We will have a quick look at those transformations in Chapter 2.






1. Motivation and Introduction: Numerical Algorithms in Computer Science 1. Motivation and Introduction: Numerical Algorithms in Computer Science page 6 of 48 ge 5 of 48 en, ST23, Thomas ПШ ТИП Float & Rounding Floating Point Arithmetic Rounding Error Analysis Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition

## **Numerical Simulation & High Performance Computing**


- The links to numerics are nowhere as strong as in High-Performance Scientific Computing, i.e. numerical simulation on high-performance computers.
- As supercomputers spend most of their time on numerical calculations, they're highly optimized for floating point performance.
- As well as this. efficient methods to solve differential equations numerically are needed - a first foretaste of this will be given in Chapter 8.






### **Games Engineering**

- A Physics Engine is needed for realistic simulations (collisions, water flows, flying bullets).
- Many physical phenomena can be described by ordinary differential equations whose numerical solution will be discussed in Chapter 5.






ПЛШ

#### Games Engineering

- Special effects: Curtains in the wind, flames, fog and smoke, biomechanics, etc.
- Handling those effects often results in linear systems of equations. How to solve those systems is discussed in Chapters 4 and 6.



from Ronald Fedkiw et al.





from NVidia

# **Machine Learning**

ML requires a lot of computations typically associated with

- Iterative methods: e.g. in the context of numerical optimization to compute optimal parameters for Neural Networks or hyperparameters in general Iterative methods are tackled in Chapter 6.
- Solving (large) linear systems of equations: Gaussian processes or numerical
  optimization of hyperparameters of ML methods require the efficient solution of
  linear systems of equations How to solve those systems is discussed in Chapters 4 and 6.





1. Motivation and Introduction: Numerical Algorithms in Computer Science risches Programmieren, ST23, Thomas Huckle

page 9 of 48 ТИП

sches Programmieren, ST23, Thomas Huckle

1. Motivation and Introduction: Numerical Algorithms in Computer Science

page 10 of 48

Float & Rounding

only approximations of these geometries.


ПΠ


ТИП

The Principle of Discretization

- In numerics, we have to deal with *continuous* problems, but computers can in principle only handle discrete items:
  - Computers typically cannot store real numbers, such as  $\sqrt{2},\,\pi,$  and 1/3, but only discrete approximations of these numbers. - Computers cannot compute functions such as sine, but can only compute
  - approximations consisting of simple components (e.g. polynomials). Computers cannot perfectly process complex geometry such as a tree, but
  - Computers typically cannot perform operations such as differentiation but only approximations, e.g. by the difference quotient.

- The transformation from continuous spaces to discrete spaces is called discretization. We discretize
  - real numbers by using **floating point numbers**, see section 1.2;
  - regions (e.g. time intervals when solving ordinary differential equations numerically (see Chapter 6) or spatial regions when solving partial differential equations numerically) by introducing a grid of discrete grid points;
  - operators such as  $d/d\boldsymbol{x}$  by forming difference quotients from function values in adjacent grid points.





Discrete terrain model (right) including contour lines (left)

1. Motivation and Introduction: Numerical Algorithms in Computer Science isches Programmieren, ST23, Thomas Huckle

page 11 of 48

. Motivation and Introduction: Numerical Algorithms in Computer Science n. ST23. Thomas Huckle

page 12 of 48

Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition Stability Cancellation

Floating Point Arithmetic Rounding Error Analysis Condition Stability

ТИП

## 1.2. Floating Point Numbers and Rounding

#### **Discrete and Finite Sets of Numbers**

- The set  $\mathbb R$  of real numbers is *unbounded* and *continuous* (between two distinct real numbers always lies another real number), there are infinitely, even uncountably many, real numbers.
- $\bullet$  The set  $\mathbb Z$  of integers is discrete with constant distance 1 between two neighboring numbers, but it is also unbounded.
- The set of numbers that can be exactly represented by a computer is inevitably finite, and hence discrete and bounded.
- The probably easiest realization of such a set of numbers and of the arithmetic using it, is integer arithmetic:
  - only using integers, typically in a range [-N, N] or [-N+1, N]
  - apparent disadvantage: big problems with all continuous concepts (derivatives, convergence, ...)
- The so called fixed point arithmetic also allows non-integers:
  - working with decimal numbers with a constant number of digits left and right of the decimal point, typically in a range such as [-999.9999, 999.9999] with (as in  $\ensuremath{\mathbb{Z}})$  a fixed distance between neighboring numbers
  - obvious disadvantage: fixed range of numbers, frequent overflow
  - observation: between 0 and 0.001 additional digits are often wished for, whereas between 998 and 999 a rougher partition would be sufficient
- A floating point arithmetic also works with decimal numbers, but allows a
  varying position of the decimal point and therefore can represent ranges of numbers with variable precisions

1. Motivation and Introduction: Numerical Algorithms in Computer Science

nmieren, ST23, Thomas Huckle

Float & Rounding Floating Point Arithmetic Rounding Error Analysis



. Motivation and Introduction: Numerical Algorithms in Computer Science n. ST23. Thomas Huckle

Rounding Error Analysis Condition

page 14 of 48 ПШ

page 16 of 48

Float & Rounding Floating Point Arithmetic

 $-54110 \cdot 4^{0}$ :

1. Motivation and Introduction: Numerical Algorithms in Computer Science

 Example (note 54410<sub>10</sub> = 31102022<sub>4</sub>):  $126880 \cdot 10^{-34}$ :  $B = 10, t = 6, M = 126880 \in [10^5, 10^6), E = -34,$  $B=2, t=16, M=40001 \in [2^{15}, 2^{16}), E=3,$  $40001 \cdot 2^3$ :

 $B = 4, t = 8, |M| = 54110 \in [4^7, 4^8), E = 0.$ 

10000

# Floating Point Numbers - Definition

• Definition of normalized t-digit floating point numbers to basis B $(B \in \mathbb{N} \setminus \{1\}, t \in \mathbb{N})$ :

$$\mathbb{F}_{B,t} \; := \; \left\{ M \cdot B^E : M = 0 \text{ or } B^{t-1} \leq \mid M \mid < B^t, \;\; M, E \in \mathbb{Z} \right\}$$

- M is called the mantissa, E is called the exponent.

- discrete set of numbers, infinite range of numbers

- The normalization (i.e. removing leading zeros) assures uniqueness of the representation:  $1.0\cdot 10^2=0.1\cdot 10^3$  .
- We assume a varying distance between neighboring numbers (constant number of subdivisions, independent of the exponent). The adoption of a feasible range for the exponent leads to the machine numbers:

$$\mathbb{F}_{B,t,\alpha,\beta} := \{ f \in \mathbb{F}_{B,t} : \alpha \le E \le \beta \} .$$

- The quadruple  $(B,t,\alpha,\beta)$  completely characterizes the system of those machine numbers, in computers such a system is used most times
- Hence, to represent a concrete number, the respective values of M and E have to be stored.
- Often the terms floating point number and machine number are used interchangeably; normally  $\boldsymbol{B}$  and  $\boldsymbol{t}$  are clear in context, which is why we will only write  $\mathbb{F}$  in the following.

1. Motivation and Introduction: Numerical Algorithms in Computer Science ieren, ST23, Tho

Floating Point Arithmetic Rounding Error Analysis

# Floating Point Numbers - Range of Representable Numbers

- The absolute distance between two neighbouring floating point numbers is not constant:
  - Consider for instance the pairs of neighbours  $9998\cdot 10^0$  and  $9999\cdot 10^0$  (distance 1) as well as  $1000\cdot 10^{-7}$  and  $1001\cdot 10^{-7}$  (distance  $10^{-7}$ ) in case
  - If the absolute values of the numbers become bigger, the "mesh width" of the discrete grid of floating point numbers also increases - we get a logarithmic
  - That's reasonable: a million doesn't make a big difference to national debt but considering one's own wage a 100 euros difference is quite important for most people.
  - Overall, the usage of floating point numbers increases the range of representable numbers compared to fixed point numbers.

The maximal possible relative distance between two neighboring floating point numbers is called **resolution**  $\varrho$ . It holds:

$$\frac{(|M|+1) \cdot B^E - |M| \cdot B^E}{|M| \cdot B^E} \ = \ \frac{1 \cdot B^E}{|M| \cdot B^E} \ = \ \frac{1}{|M|} \ \le \ B^{1-t} \ =: \ \varrho \, .$$

ТИП

- For the boundaries of the representable region, we get:
  - smallest positive machine number:  $\sigma := B^{t-1} \cdot B^{\alpha}$
  - biggest machine number:  $\lambda := (B^t 1) \cdot B^{\beta}$

1. Motivation and Introduction: Numerical Algorithms in Computer Science							1. Motivation and Introduction: Numerical Algorithms in Computer Science								
Numerisches Programmieren, ST23, Thomas Huckle page				page 17 of 48	ALL.Y	Numerisches Programmieren, ST23, Thomas Huckle					page 18 of 48				
Applications	Float & Rounding	Floating Point Arithmetic	Rounding Error Analysis	Condition	Stability	Cancellation	тип	Applications	Float & Rounding	Floating Point Arithmetic	Rounding Error Analysis	Condition	Stability	Cancellation	тип

#### Floating Point Numbers - Examples

 Famous and most important example is the floating point number format set by the IEEE (Institute of Electrical and Electronics Engineers), which is defined in the US norm ANSI/IEEE-Std-754-1985 and traces back to a patent of Konrad Zuse from the year 1936 (!):

level	B	t	$\alpha$	β	ρ	σ	λ
single precision							
double precision							
extended precision	2	64	-16445	16320	$2^{-63}$	$2^{-16382}$	$\doteq 2^{16384}$

- Single precision hence corresponds to approx. 6 to 7 decimal digits, at double precision approx. 15 decimal digits are stored.
- Exactly those definitions are behind the nomenclature used in standard programming languages (e.g float or double in C++).

# Floating Point Numbers - Exceptions

The Principle of Rounding

Exceptions in which one has to rely on correct troubleshooting by the system's

- NaN (Not-a-Number): undefined value, implemented as quiet (inherits quietly) or signalizing (activates alert)
- Exponent overflow: absolute value of the number is bigger than  $\lambda$
- **Exponent underflow**: absolute value of the number is smaller than  $\sigma$  (threatens to happen e.g. if comparing a < b is realized by comparing their difference with 0).

Motivation and Introduction: Numerical Algorithms in Computer Science     Numerisches Programmieren, ST23, Thomas Huckle page 19					page 19 of 48	ALTA.		Motivation and Introduction: Numerical Algorithms in Computer Science     Numerisches Programmieren, ST23, Thomas Huckle					page 20 of 48		
Applications	Float & Rounding	Floating Point Arithmetic	Rounding Error Analysis	Condition	Stability	Cancellation	тип	Applications	Float & Rounding	Floating Point Arithmetic	Rounding Error Analysis	Condition	Stability	Cancellation	ТИП

#### IEEE 754 standard: binary32

The IEEE 754 standard specifies a binary32 as having:

- Sign of Mantissa: 1 bit. 0 represents a positive number while 1 represents a negative number.
- Biased exponent: 8 bits. The exponent field needs to represent both positive and negative exponents. A bias, in this case is 127, is added to the actual exponent in order to get the stored exponent.
- Normalised Mantissa: 23 bits. A normalised mantissa is one mantissa with only one 1 to the left of the decimal. And the numbers after the decimal point is explicitly stored.



Consider a fraction number  $-\frac{9}{8}$ . It can be converted into a binary as follows,

$$-\frac{9}{8} = -1001_2 : 1000_2 = -1.001_2,$$

with exponent 0. Therefore in IEEE 754 standard it is stored as:



Float & Rounding Floating Point Arithmetic Rounding Error Analysis

I. Motivation and Introduction: Numerical Algorithms in Computer Science page 22 of 48 rammieren, ST23, Thomas Huckle ПШ Floating Point Arithmetic Rounding Error Analysis Condition

• There are different ways to round sensibly (i.e. following the above postulations)

As floating point numbers are also discrete, certain real numbers cannot be

number - we round off, the according transformation is called rounding.

In the special case  $x \in \mathbb{F}$ , of course  $f_l(x) = f_r(x) = x$  holds.

• Reasonable postulations for a rounding method  $\, \mbox{rd} : \mathbb{R} \to \mathbb{F} \,$  are:

- monotony:  $x \leq y \Rightarrow \operatorname{rd}(x) \leq \operatorname{rd}(y) \quad \forall x, y \in \mathbb{R}$ 

- surjectivity:  $\forall f \in \mathbb{F} \ \exists x \in \mathbb{R} \ \text{with } \mathrm{rd}(x) = f$ 

- idempotence:  $\operatorname{rd}(\operatorname{rd}(x)) = \operatorname{rd}(x) \forall x \in \mathbb{R}$ 

represented. Each of those has to be sensibly assigned to a suitable floating point

• For every arbitrary  $x \in \mathbb{R}$ , there exists exactly one left and one right neighbor in  $\mathbb{F}$ :

An explicit formula for the floating point numbers of x > 0, x = (M + δ) · B<sup>E</sup>,

 $f_l(x) \ = \ M \cdot B^E \ , \qquad \qquad f_r(x) \ = \ \left\{ \begin{array}{ll} f_l(x) & \mbox{if} \ \delta = 0 \ , \\ (M+1) \cdot B^E & \mbox{otherwise} \end{array} \right.$ 

 $f_l(x) := \max\{f \in \mathbb{F} : f \le x\}, \quad f_r(x) := \min\{f \in \mathbb{F} : f \ge x\}.$ 

#### Types of Rounding

- We distinguish between three important types of directed rounding:
  - At rounding down the number is mapped onto the left neighbor:

$$\operatorname{rd}_-(x) \;:=\; f_l(x)\,.$$

- At rounding up it is accordingly mapped to the right neighbor:

$$\mathsf{rd}_+(x) \ := \ f_r(x) \,.$$

- Chopping off maps the number onto the neighbor closer to zero:

$$\operatorname{rd}_0(x) \; := \; \left\{ \begin{array}{ll} f_l(x) & \text{ if } \; x \geq 0 \,, \\ f_r(x) & \text{ if } \; x \leq 0 \,. \end{array} \right.$$

The idea that underlies this notation is to neglect (chop off) every digit from a certain decimal place onward.

In practice, the most important form of rounding is correct rounding, which

$$\operatorname{rd}_*(x) \; := \; \left\{ \begin{array}{ll} f_l(x) & \text{ if } \; x \leq \frac{f_l(x) + f_r(x)}{2} \, , \\ \\ f_r(x) & \text{ if } \; x \geq \frac{f_l(x) + f_r(x)}{2} \, , \end{array} \right.$$

plus a rule for the procedure in the case of  $x=\ldots$ , i.e. if x lies exactly in the middle of its two neighbors (e.g. rounding such that the resulting mantissa is even).

You can easily check that all four ways of rounding introduced here are surjective,

ATT.

ПЛШ

ТИП ТИП Float & Rounding Floating Point Arithmetic

#### The Relative Rounding Error

- Due to rounding, errors are inevitable in numerical computations. We distinguish:
  - absolute rounding error: rd(x) x
  - relative rounding error:  $\frac{\operatorname{rd}(x)-x}{x}$ , if  $x\neq 0$
- As the whole construct of floating point numbers is aiming at a high relative precision, the relative rounding error will play the decisive role for every analysis This error has to be estimated to judge the possible effect of rounding errors in a numerical algorithm.
- Let the relative rounding error be denoted with  $\varepsilon$  . Then:

$$\operatorname{rd}(x) \ = \ x \cdot (1+\varepsilon) \qquad \forall x \in \mathbb{R} \, .$$

- For the relative rounding error the following bounds apply:
  - directed rounding:

 $|\varepsilon| < \varrho$ 

- correct rounding:

 $|\varepsilon| \le \frac{1}{2}\varrho$ 

The relative rounding error is directly linked to the resolution.

# Rounding Errors - a Dramatic Example

- In the second gulf war an American patriot missile missed an approaching Iraqi Scud missile on February 25, 1991 in Saudi Arabia. The Scud missile hit barracks killing 28 US soldiers.
- The cause was a rounding error:
  - The interior clock of the patriot missile saved the time elapsed since booting up the system in tenths of seconds (24-Bit-register).
  - As the tenth of a second is not exactly representable in a binary system, only the first 24 digits were used for calculations, and a resulting rounding error

$$0.1\,s \; = \; (0.000\overline{1100})_2\,s \; \approx \; 0.00011001100110011001100\,s \, ,$$

error 
$$\approx 9.5 \cdot 10^{-8} s$$
.

The Ideal Floating Point Number Arithmetic

introduced types of rounding.

· What is ideal in the sense of floating point numbers?

a \* b = rd(a \* b)

- Since booting up the last time, the system hadn't been shut down.
- After 100 hours of operation, the rounding error had accumulated to

Ideally, the computed result should match the rounded exact result:

- Reason: This error is inevitable - even when the exact result is known, the

Such an ideal arithmetic is not a utopia but possible. The IEEE standard requests it for the basic operations in binary floating point arithmetic and even for square roots; and for all three introduced accuracy levels and for all four

exact result also has to be forced into F, like a corset, i.e. it has to be

• With this, we get bounds for the rounding error of our arithmetic operations in the

 $a \,\dot{*}\, b \; = \; \operatorname{rd}(a * b) \; = \; (a * b)(1 + \varepsilon(a,b)) \qquad \forall a,b \in \mathbb{F}$ 

 $\mid \varepsilon(a,b)\mid \ \leq \ \, \bar{\varepsilon} \ \, = \ \, \frac{1}{2}\varrho \ \, \text{or.} \ \, \varrho \qquad \text{(depending on the type of rounding)}\,.$ 

 $\forall a,b \in \mathbb{F}, \quad \forall * \in \{+,-,\cdot,/\}$ 

$$100\cdot 60\cdot\ 60\cdot 10\cdot 9.5\cdot 10^{-8}$$
 tenths of a second  $\ \approx\ 0.34\, \text{seconds}$  .

During this time the Scud missile covered a distance of about 570 metres and couldn't be detected by the Patriot missile's sensors anymore.

#### 1. Motivation and Introduction: Numerical Algorithms in Computer Science I. Motivation and Introduction: Numerical Algorithms in Computer Science page 25 of 48 page 26 of 48 isches Programmieren, ST23, Thomas Huckle en, ST23, Thomas Huckle ПП ТИП Float & Rounding Floating Point Arithmetic Float & Rounding Floating Point Arithmetic

#### 1.3. Floating Point Arithmetic

## **Calculating with Floating Point Numbers**

- Upon rounding a single number, you still know the exact value.
- That changes already with the simplest calculations:
- Even after a single arithmetic approximation, it is often the case that the exact number cannot be represented.
  - The exact execution of basic arithmetic operations  $*\in\{+,-,\cdot,/\}$  in the system  $\mathbb F$  of floating point numbers is usually impossible even when using arguments from  $\mathbb F$ : How can the sum of 1234 and 0.1234 be exactly represented with four digits?
- Therefore, we need a "clean" floating point arithmetic that avoids building up accumulated errors.
- Notation:
  - $-a*b \in \mathbb{R}$  is the exact result of the arithmetic operation \* (usually a \* b not in F)
  - $a * b \in \mathbb{F}$  is the *actually computed* result of the arithmetic operation \*
- Again, the relative error is the interesting quantity:  $\varepsilon(a,b) \,:=\, \frac{a*b-a*b}{a*b}\,, \quad \text{fo}$

$$\varepsilon(a,b) := \frac{a \cdot b - a \cdot b}{a \cdot b}, \quad \text{for } a \cdot b \neq 0.$$

- The different postulations for a "clean" floating point arithmetic now differ in the postulations for a \* b.
  - depends only on the parameters B and t of the floating point arithmetic.
    - en, ST23, Thomas Huckle

ideal arithmetic:

with

The variable  $\bar{\varepsilon}$  is called machine accuracy or computational accuracy and

#### 1. Motivation and Introduction: Numerical Algorithms in Computer Science page 27 of 48 page 28 of 48 sches Programmieren, ST23, Thomas Huckle ТИП Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis ations Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition

# Relaxations

- · Although an ideal arithmetic technically is feasible, in some computers only a weaker version is realized.
- strong hypothesis:
  - There exists an  $\tilde{\varepsilon}=O(\varrho)$  that bounds the relative error in every case:

$$a \mathbin{\dot{*}} b \ = \ (a * b)(1 + \varepsilon(a,b))$$

with

$$|\varepsilon(a,b)| \leq \tilde{\varepsilon}$$
.

- The strong hypothesis applies for most computers.
- weak hypothesis:
  - With  $\tilde{\varepsilon}$  from above only holds

$$a \,\dot{*}\, b \;=\; (a(1+\varepsilon_1)) * (b(1+\varepsilon_2))$$

with

$$\mid \varepsilon_1 \mid, \mid \varepsilon_2 \mid \leq \tilde{\varepsilon}$$
.

- That means, there is no direct functional dependency of the calculated result on the exact result any more.
- At least this weak postulation applies for nearly every computer.

Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condit

# **Surprising Properties of Floating Point Arithmetic**

- ullet The floating point operators  $\dot{*}$  do not have the same properties as their "authentic"
- We will study this at the example of floating point addition +:
  - The floating point addition is not associative.
  - Depending on the order of execution of calculation, different final results can
- For demonstration, the numbers  $2^{20}$ ,  $2^4$ ,  $2^7$ ,  $-2^3$  as well as  $-2^{20}$  shall be added. The exact result is 136. Depending on the bracketing of the summands we get different results when calculating with 8 binary digits:

$$\begin{array}{rcl} (((2^{20}\dotplus-2^{20})\dotplus2^4)\dotplus-2^3)\dotplus2^7 & \doteq & 136 \\ 2^{20}\dotplus(-2^{20}\dotplus(2^4\dotplus(-2^3\dotplus2^7))) & \doteq & 0 \\ (2^{20}\dotplus(-2^{20}\dotplus2^4))\dotplus(-2^3\dotplus2^7) & \doteq & 120 \\ (2^{20}\dotplus((-2^{20}\dotplus2^4)+-2^3))\dotplus2^7 & \doteq & 128 \\ \end{array}$$

## 1.4. Rounding Error Analysis

#### **A-priori Rounding Error Analysis**

1. Motivation and Introduction: Numerical Algorithms in Computer Science

mieren, ST23, Thomas Huckle

- A numerical algorithm is a finite sequence of basic arithmetic operations with a clearly defined order.
- The floating point arithmetic presents an essential source of error in numerical
- Therefore, the most important goals in this regard for a numerical algorithm are:
  - small discretization error; as little influence of discretization as possible
  - efficiency: minimal runtime
  - small rounding error: as little influence of (accumulated) rounding errors as
- The latter goal requires an a priori rounding error analysis:
  - Which bounds can be determined for the total error assuming a certain quality of the basic operations?

### **Forward and Backward Error Analysis**

I. Motivation and Introduction: Numerical Algorithms in Computer Science

en, ST23, Thomas Huckle

Float & Rounding Floating Point Arithmetic

- · For the a priori rounding error analysis there are two obvious strategies:
  - Forward analysis: Interpret the computed result as a perturbed exact result (Practical, as corresponds directly to the relative error. But is very hard to do with floating point arithmetic).

Rounding Error Analysis Condition

- Backward analysis: Interpret the computed result as the exact result of perturbed input data (the easier and more popular method)
- Interpretation of the backward analysis: If the input perturbations due to rounding error analysis are of the same order as their blurring (quite frequently anyway due to measurement errors, previous calculations), then everything is fine.
- Note: The weak hypothesis only allows for a backward analysis, the strong hypothesis and the ideal arithmetic allow for a backward and a forward interpretation, whereby the relative error of the computed result is bounded by  $\varepsilon$  in

$$\begin{array}{lll} a\dot{+}b &=& (a+b)(1+\varepsilon) &=& a(1+\varepsilon)+b(1+\varepsilon) \\ a\dot{\cdot}b &=& ab(1+\varepsilon) &=& a\sqrt{1+\varepsilon}\cdot b\sqrt{1+\varepsilon} \\ & & \text{forward} & \text{backward} \end{array}$$

1. Motivation and Introduction: Numerical Algorithms in Computer Science

page 31 of 48

page 29 of 48

ТИП

1. Motivation and Introduction: Numerical Algorithms in Computer Science

page 30 of 48

ПШ

#### An Example: The Horner Scheme

- Task: Find the value y:=p(x) of the polynomial  $p(x):=\sum_{i=0}^n a_i x^i$  for a aiven x.
- Algorithm: Horner scheme

 $y := (\dots(((a_nx + a_{n-1})x + a_{n-2})x + a_{n-3})\dots + a_1)x + a_0$ 

y := a[n];

for i:=n-1 downto 0 do y:=y\*x+a[i] od; For every step according to the strong hypothesis, we have

 $\tilde{y} := (\tilde{y} \cdot x \cdot (1 + \mu_i) + a_i) \cdot (1 + \alpha_i)$ 

Transformations provide

$$\tilde{a}_i := a_i \cdot (1 + \alpha_i) \cdot (1 + \mu_{i-1}) \cdot \ldots \cdot (1 + \alpha_0), \qquad \alpha_n := 0.$$

• This means: The  $\emph{computed}$  value  $\tilde{y}$  can be interpreted as  $\emph{exact}$  value of a polynomial with slightly differed coefficients.

# Float & Rounding Floating Point Arithmetic Well- and III-Conditioned Problems

- Perturbations  $\delta x$  in the input data have to be studied because the input is often imprecise (obtained by measuring or from former calculations) and, thus, such perturbations occur frequently, even for exact computing.
- well-conditioned problems:
  - Rule of thumb: Small  $\delta x$  lead to little perturbations  $\delta y$  of the results.
  - Perturbations of the input, thus, are relatively uncritical.
  - Here, it pays off to invest in a good algorithm.
- ill-conditioned problems:

1. Motivation and Introduction: Numerical Algorithms in Computer Science

1. Motivation and Introduction: Numerical Algorithms in Computer Science

isches Programmieren, ST23, Thomas Huckle

isches Programmieren, ST23, Thomas Huckle

nealected):

- Rule of thumb: Even smallest  $\delta x$  can lead to big  $\delta y$ .
- The solution reacts in an extremely sensitive way to perturbations of the input.
- Here, even excellent algorithms generally have difficulties.
- From the perspective of a numerical programmer:
  - Ill-conditioned problems are very difficult (in extreme cases even impossible) to deal with numerically.
  - Every error in the input data, every inaccuracy in the run-up by rounding can distort the computed result completely when the problem is ill-conditioned.

## 1.5. The Concept of Condition

# **Definition and Examples**

· Condition is a very crucial, but most times only qualitatively defined concept of

ТИП

page 34 of 48

page 36 of 48

ТИП

ТИП

- How sensitive is the result of a problem concerning changes in the input?
  - For high sensitivity: Bad condition or an ill-conditioned problem
  - For low sensitivity: good condition or a well-conditioned problem
- Very important: The condition number is a property of the examined *problem*, not of the used algorithm.
- Examples:

Numerisches Programmieren, ST23, Thomas Huckle

- Solving a linear system of equations Ax=b: Input data is  $A\in\mathbb{R}^{n,n}$  and  $b\in\mathbb{R}^n$ , result is  $x\in\mathbb{R}^n$ .
- Compute the roots of a polynomial of order n with real coefficients: Input data are the polynomial coefficients  $a_0,...,a_n$ , results are the n(complex) roots of p.
- Compute the eigenvalues of a matrix A: Input data is the matrix  $A \in \mathbb{R}^{n,n}$ , results are all complex  $\lambda$  with  $Ax = \lambda x$  for an eigenvector x different from zero.

Float & Rounding Floating Point Arithmetic Relative error of the Basic Arithmetic Operations

1. Motivation and Introduction: Numerical Algorithms in Computer Science

- We examine the arithmetic basic operations. Those obviously represent a numerical problem and, thus, have a condition number.
- For this purpose, we investigate the relative output error and introduce the absolute output error as the difference between exact result with exact input data and exact result with perturbed input data,

$$f(x+\delta x)-f(x)$$

and as the relative output error the quotient

$$\frac{f(x+\delta x)-f(x)}{f(x)}$$

The absolute and relative condition number is the quotient of the respective output error and the input error:

$$\begin{array}{ll} \frac{f(x+\delta x)-f(x)}{\delta x} & (absolute) \\ \frac{f(x+\delta x)-f(x)}{f(x)} & \\ \hline \frac{f(x)}{\delta x} & (relative) \end{array}$$

Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition The following shows the resulting condition numbers or the leading order term in each case (for example, higher square terms in the perturbations  $\delta a$  and  $\delta b$  are

operation	absolute output error	relative output error	condition
addition/subtraction	$\delta a \pm \delta b$	$(\delta a \pm \delta b)/(a \pm b)$	?
multiplication	$\approx b \cdot \delta a + a \cdot \delta b$	$\delta a/a + \delta b/b$	$\approx 1$
division	$\approx \delta a/b - a \cdot \delta b/b^2$	$\delta a/a - \delta b/b$	$\approx 1$

- For multiplication, division, and square root; the relative condition number stavs within the relative input perturbation range  $\frac{\delta a}{a}$  and  $\frac{\delta b}{b}$
- Unlike for the real subtraction (a,b>0): If the exact result is close to zero, the relative condition can become arbitrarily large

# en, ST23, Thomas Huckle Applications Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition Stability The Condition of Compound Problems

1. Motivation and Introduction: Numerical Algorithms in Computer Science

• Usually, the condition of a problem p(x) for the input x is not defined as above by a simple difference (thus by the relative error) but by the derivative of the result w.r.t. the input:

$$\mathsf{cond}(p(x)) \; := \; \frac{\partial p(x)}{\partial x}$$

ullet When decomposing the problem p into two or more subproblems, the result is

$$\operatorname{cond}(p(x)) \ = \ \operatorname{cond}(r(q(x))) \ = \ \frac{\partial r(z)}{\partial z} \mid_{z=q(x)} \cdot \frac{\partial q(x)}{\partial x}$$

- Of course, the total condition of p(x) is independent of the decomposition, but the partial conditions do depend on it. This might lead to problems:
  - Let p be well-conditioned with an excellently conditioned first part q and lousily conditioned second part r.
  - If now errors occur in the first part, those could lead to a catastrophe in the
  - Consider:  $\frac{\partial p}{\partial x} = O(10^{-10})$ ,  $\frac{\partial r}{\partial z} = O(10^{10})$ ,  $\frac{\partial q}{\partial x} = O(10^{-20})$ .

Rounding errors in the first step of order  $O(10^{-14})$  will be inflated to the dimension of  $O(10^{-4})$  by r during the second step – and, hey presto, there are only 4 significant digits left, although p was that well-conditioned!

en, ST23, Thomas Huckle

ge 38 of 48 ТИП

ATT.

ТИП

# Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition **Example 1: The Symmetric Problem of Eigenvalues**

- As an example, we examine the problem of finding the n real eigenvalues of a symmetric matrix  $A=A^T\in\mathbb{R}^{n,n}$ .
- The complete problem is very well-conditioned: Small perturbations of the input (the elements of the matrix) only lead to small perturbations of the eigenvalues.
- A solution strategy well-known from linear algebra provides a decomposition into the two subproblems "setting up the characteristic polynomial" and "finding its
  - The first supproblem is perfectly conditioned, the second one lousily: Even errors in the last significant digit of the polynomial's coefficients lead to a completely different graph, therefore, to a different position of the roots.
  - Therefore, the total result is completely useless (cf. Chapter Interpolation) -finding roots of polynomials should always be avoided as a subproblem. The consequence: The eigenvalues of  $\boldsymbol{A}$  certainly must not be determined in
  - For comfort: There are other ways, i.e. without ill-conditioned subproblems

#### **Example 2: The Intersection Point of Two Non-Parallel** Straight Lines

- In the plane, the point of intersection of two straight non-parallel lines ax+by=cand dx + ey = f shall be determined:
  - Input data: the coefficients a,b,c,d,e,f of the linear equations
  - Result: the coordinates  $\bar{x}$  and  $\bar{y}$  of the intersection point
- Geometrically, it is clear:
- If the lines run almost orthogonally, the problem of determining the intersection point is very well-conditioned.
- On the contrary, if the lines run almost parallel, the problem of determining the intersection point is very ill-conditioned.



with  $\alpha_i$  and  $\mu_i$  bounded by  $\tilde{\varepsilon}$ .

 $\tilde{y} = \sum_{i=0}^{n} \tilde{a}_{i}x^{i}$ 

with

1. Motivation and Introduction: Numerical Algorithms in Computer Science risches Programmieren, ST23, Thomas Huckle

page 33 of 48

page 35 of 48

ТИП

page 39 of 48

ST23, Th

1. Motivation and Introduction: Numerical Algorithms in Computer Science

page 40 of 48

#### 1.6. The Concept of Stability

### **Numerically Acceptable Results**

- With the concept of condition we are now able to characterize problems. Now we will have a look at the characterization of numerical algorithms.
- As we have already seen, input data can be perturbed. From the mathematical point of view, that means that they are only fixed within a certain tolerance, meaning they lie e.g. in a neighborhood

$$U_\varepsilon(x) \;:=\; \{\tilde{x}:\; |\tilde{x}-x|<\varepsilon\}$$

of the exact input x. Hence, any such  $\tilde{x}$  has to be considered as virtually equal to x. With this, the following definition suggests itself:

• An approximation  $\tilde{y}$  for y=p(x) is called **acceptable**, if  $\tilde{y}$  is the exact solution to one of the above  $\tilde{x}$ , thus

$$\tilde{y} = p(\tilde{x})$$
.

- In literature varying weaker definitions can be found.
  - The proof of acceptability can be similar to backward calculation at rounding error analysis - carried out by a validation computation.
- The occurring error  $\tilde{y}-y$  has different sources:
  - rounding errors
  - method or discretization errors: Series and integrals are approximated by sums, derivatives by difference quotients, iterations will stop after a few iteration steps, ...

#### 1. Motivation and Introduction: Numerical Algorithms in Computer Science risches Programmieren, ST23, Thomas Huckle

page 41 of 48

1. Motivation and Introduction: Numerical Algorithms in Computer Science en, ST23, Thomas Huckle

page 42 of 48

ТИП

Float & Rounding Floating Point Arithmetic

ТИП

Float & Rounding

тип

### **Numerically Stable Algorithms**

- Stability is another vital concept in numerics. A numerical algorithm is called (numerically) stable, if for all permitted input data perturbed in the size of computational accuracy  $O(\tilde{\varepsilon})$  acceptable results are produced under the influence of rounding and method errors.
- A stable algorithm can definitely produce large errors for example when the problem to solve is ill-conditioned. In this case, acceptable results can be positioned far away from the exact results.
- What is stable, what is unstable?
  - The basic arithmetic operations are numerically stable under the precondition of the weak hypothesis.
  - Compositions of stable methods are not necessarily stable otherwise the statement above would indicate everything being numerically stable.
  - For methods to numerically solve ordinary and partial differential equations, stability is a very vital topic. For the former, see Chapter Ordinary Differential Equations.

# **Example of an Unstable Algorithm**

 A simple example shall clarify the phenomenon of stability. The bigger of the two roots of the quadratic equation

$$x^2 + 2px - q = 0$$

is to be found, namely for the concrete input data

$$p = 500, q = 1.$$

The formula

$$x \: := \: \sqrt{p^2 + q} - p$$

well-known from school delivers

$$\sqrt{250001} - 500 = 0.00099999900...$$

- When computing with 5 digits, the computed result however is zero. Zero can only be root for the input q=0 which however is no modification within the computing accuracy  $O(10^{-5})$ .
- Therefore, the computed result is not acceptable and the algorithm is unstable.

#### 1. Motivation and Introduction: Numerical Algorithms in Computer Science risches Programmieren, ST23, Thomas Huckle

digits



risches Programmieren, ST23, Thomas Huckle

page 44 of 48 ТИП

- Float & Rounding Floating Point Arithmetic Rounding Error Analysis Condition Stability Cancellation
  - Note that for p = q = 1 no problems occur not even when computing with 5

This formula represents a stable instruction for calculation.

- What does unstable behavior look like?
  - For example it takes the form of oscillations: The computed approximate solution for an ordinary differential equation oscillates around the exact solution and, therefore, shows a totally different behavior compared with the exact solution – so it can't be an acceptable result.

# 1.7. Cancellation

#### The Phenomenon of Cancellation

1. Motivation and Introduction: Numerical Algorithms in Computer Science

- Cancellation describes the effect occurring at the subtraction of two numbers with same signs that leading identical digits cancel each other, that means leading non-zeros disappear. The number of relevant digits can be reduced dramatically.
- Loss of significance impends particularly when both numbers are of the same order of magnitude and sign.
- Examples:
  - Subtract 4444.4444 from 4444.5555. Both numbers have eight significant digits, the result only has four!
  - Subtract 999999 from a million. We assume a perturbation of  $\pm 1$  for both numbers and, beside the exact result 1, get the exactly calculated result of the perturbed numbers:

$$(1000000 + 1) - (999999 - 1) = 3.$$

Hence, the relative output error is

$$\frac{\delta(a-b)}{a-b} \; = \; \frac{3-1}{1} \; = \; 2 \, ,$$

Rounding Error Analysis

although the relative perturbation of the input data was only of the order  ${\cal O}(10^{-6}).$  The condition number is therefore in  ${\cal O}(10^6)$ 

Motivation	and	Introduction:	Numerical	Algorithms i	n Computer	Science



1. Motivation and Introduction: Numerical Algorithms in Computer Science en. ST23. Thomas Huckle

page 46 of 48

ТИП

page 48 of 48

ПШ

 This gets even more alarming for complete cancellation, i.e. when the exact result would be zero - in this case the relative error becomes infinitely large.

ullet A nice example: Compute  $e^{-20}$  via the known expansion of the exponential function. Keep adding up until the value does not change any more. Observation: Instead of the correct value of approximately  $2.061\cdot 10^{-9}$  a completely incorrect result may be delivered due to cancellation! When computing with 7 digits, the Maple program

delivers the result 7.014115, for 14 digits (Digits := 14)  $9.253\cdot10^{-7},$  for 21 digits indeed the correct  $2.061\cdot10^{-9}.$ 

 $^{-20} \approx S(n)$ S(n)-19.0 -186231.6448688.6 30  $1.599699 \cdot 10^{6}$  $1.011906 \cdot 10^{6}$  620347 $\frac{31}{32}$ 41 42 -2124.511 1005.75143 -450.1857.014426 7.01401058 59 60 61 62 63 64  $\begin{array}{c} 7.014149 \\ 7.014104 \end{array}$ 7.014119 7.014119 7.014114 7.014115 7.014115



ST23, Th

1. Motivation and Introduction: Numerical Algorithms in Computer Science