Manual for RADMC-3D Version 0.41


C.P. Dullemond

with substantial contributions from: M. Min, A. Juhasz, A. Pohl, R. Shetty, F. Sereshti, T. Peters, B. Commercon

and testing and feedback by:

D. Harsono, R. Rolffs, L. Szucs, S. Andrews, S. Offner, C. Beaumont K. Rosenfeld, Søren Frimann, Jon Ramsey, Seokho Lee, Blake Hord and others

This code benefitted from financial support by the german science foundation (DFG) under the Schwerpunkt Programm (SPP) "Interstellar Medium"





Contents

1	Intr	oduction, copyright and disclaimer	10	
	1.1	Introduction	10	
	1.2	Version tracker	12	
	1.3	Copyright and disclaimer	12	
2 Quick-Start			13	
3	Overview of the RADMC-3D package			
	3.1	Introduction	15	
	3.2	Requirements	15	
	3.3	The archive, how to unzip it, and what it contains	16	
	3.4	Units: RADMC3D uses CGS	16	
4	Con	npilation and installation of radmc3d	17	
	4.1	Compiling the code with 'make'	17	
		4.1.1 Compiling the OpenMP version	17	
	4.2	The install.perl script	18	
	4.3	What to do if this all does not work?	19	
	4.4	Installing the Python analysis tools	20	
	4.5	Installing the IDL analysis tools	20	
	4.6	Installing the stand-alone (non-IDL) version of viewimage	21	
	4.7	Making special-purpose modified versions of RADMC-3D (optional)	21	
5	Basi	ic structure and functionality	23	
	5.1	Basic dataflow	23	
	5.2	Radiative processes	25	
	5.3	Coordinate systems	26	
	5.4	The spatial grid	26	
	5.5	Computations that RADMC-3D can perform	27	
	5.6	How a model is set up and computed: a rough overview	28	
	5.7	Organization of model directories	29	
	5.8	Running the example models	29	

6	Dust	contin	uum radiative transfer	31
	6.1	The the	ermal Monte Carlo simulation: computing the dust temperature	31
		6.1.1	Modified Random Walk method for high optical depths	32
	6.2	Makin	g SEDs, spectra, images for dust continuum	33
	6.3	OpenM	MP parallelized Monte Carlo	34
	6.4	Overvi	ew of input data for dust radiative transfer	34
	6.5	Specia	l-purpose feature: Computing the local radiation field	35
	6.6	More a	about scattering of photons off dust grains	36
		6.6.1	Five modes of treating scattering	36
		6.6.2	Scattering phase functions	37
		6.6.3	Scattering of photons in the Thermal Monte Carlo run	38
		6.6.4	Scattering of photons in the Monochromatic Monte Carlo run	38
		6.6.5	Scattered light in images and spectra: The "Scattering Monte Carlo" computation	39
		6.6.6	Single-scattering vs. multiple-scattering	41
		6.6.7	Warning when using an-isotropic scattering	41
		6.6.8	For experts: Some more background on scattering	42
	6.7	Polariz	cation, Stokes vectors and full phase-functions	42
		6.7.1	Definitions and conventions for Stokes vectors	44
		6.7.2	Our conventions compared to other literature	45
		6.7.3	Defining orientation for non-observed radiation	46
		6.7.4	Polarized scattering off dust particles: general formalism	47
		6.7.5	Polarized scattering off dust particles: randomly oriented particles	48
		6.7.6	Scattering and axially symmetric models	49
	6.8	More a	about photon packages in the Monte Carlo simulations	49
	6.9	Polariz	red emission and absorption by aligned grains	50
		6.9.1	Basics	50
		6.9.2	Implementation in RADMC-3D	52
			Polarized emission in the images and spectra	52
			Polarized emission as source term in the Monte Carlo simulation	54
		6.9.3	Consistency with other radiative processes	54
		6.9.4	Input files for RADMC-3D for aligned grains	54
		6.9.5	Effect of aligned grains on the scattering	56
	6.10	Quantu	ım-heated grains: PAHs and VSGs	56
		6.10.1	Approximations to quantum-heating in RADMC-3D	58
		6.10.2	Dust opacities for PAHs and VSGs	59
		6.10.3	Quantum-heated grains in RADMC-3D: How to do it	59
7	Line	radiati	ive transfer	61
	7.1	Quick	start for adding line transfer to images and spectra	61
	7.2	Some of	definitions for line transfer	61

	7.3	Line transfer modes and how to activate the line transfer	62
		7.3.1 Two different atomic/molecular data file types	62
		7.3.2 The different line modes (the lines_mode parameter)	63
	7.4	The various input files for line transfer	63
		7.4.1 INPUT: The line transfer entries in the radmc3d.inp file	63
		7.4.2 INPUT: The line.inp file	64
		7.4.3 INPUT: Molecular/atomic data: The molecule_XXX.inp file(s)	65
		7.4.4 INPUT: Molecular/atomic data: The linelist_XXX.inp file(s)	68
		7.4.5 INPUT: The number density of each molecular species	69
		7.4.6 INPUT: The gas temperature	69
		7.4.7 INPUT: The velocity field	69
		7.4.8 INPUT: The local microturbulent broadening (optional)	69
		7.4.9 INPUT for LTE line transfer: The partition function (optional)	70
		7.4.10 INPUT: The number density of collision partners (for non-LTE transfer)	70
	7.5	Making images and spectra with line transfer	71
		7.5.1 Speed versus realism of rendering of line images/spectra	72
		7.5.2 Line emission scattered off dust grains	72
	7.6	Non-LTE Transfer: The Large Velocity Gradient (LVG) + Escape Probability (EscProb) method	72
	7.7	Non-LTE Transfer: The optically thin line assumption method	74
	7.8	Non-LTE Transfer: Full non-local modes (FUTURE)	75
	7.9	Non-LTE Transfer: Inspecting the level populations	75
		Non-LTE Transfer: Reading the level populations from file	
	7.11	What can go wrong with line transfer?	76
	7.12	Preventing doppler jumps: The "doppler catching method"	77
	7.13	Background information: Calculation and storage of level populations	79
		In case it is necessary: On-the-fly calculation of populations	
	7.15	For experts: Selecting a subset of lines and levels "manually"	80
8	Gas	continuum opacities and emissivities	82
	8.1	Gas continuum opacities and emissivities	82
		8.1.1 Thermal free-free emission/absorption	82
	8.2	Self-consistent gas temperature iteration	83
9	Mak	ing images and spectra	84
	9.1	Basics of image making with RADMC-3D	84
	9.2	Making multi-wavelength images	86
	9.3	Making spectra	87
		9.3.1 What is "in the beam" when the spectrum is made?	87
		9.3.2 Can one specify more realistic "beams"?	88
	9.4	Specifying custom-made sets of wavelength points for the camera	89
		9.4.1 Using lambdarange and (optionally) nlam	89

		9.4.2	Using allwl	89
		9.4.3	Using loadcolor	89
		9.4.4	Using loadlambda	90
		9.4.5	Using iline, imolspec etc (for when lines are included)	90
	9.5	Heads-	up: In reality wavelength are actually wavelength bands	90
		9.5.1	Using channel-integrated intensities to improve line channel map quality	90
	9.6	The iss	ue of flux conservation: recursive sub-pixeling	91
		9.6.1	The problem of flux conservation in images	91
		9.6.2	The solution: recursive sub-pixeling	91
		9.6.3	A danger with recursive sub-pixeling	92
		9.6.4	Recursive sub-pixeling in spherical coordinates	92
		9.6.5	How can I find out which pixels RADMC-3D is recursively refining?	93
		9.6.6	Alternative to recursive sub-pixeling	93
	9.7	Stars in	the images and spectra	93
	9.8	Second	order ray-tracing (Important information!)	94
		9.8.1	Second order integration in spherical coordinates: a subtle issue	95
	9.9	Visuali	zing the $ au=1$ surface	96
	9.10	Using o	circularly arranged pixels for spectra (special topic)	97
	9.11	For pul	olic outreach work: local observers inside the model	97
	9.12	Multip	e vantage points: the "Movie" mode	98
10	More	e inforn	nation about the gridding 1	01
	10.1	Regula	r grids	01
	10.2	C 1	1	00
		Separa	ble grid refinement in spherical coordinates (important!)	02
		_	e Adaptive Mesh Refinement	
	10.3	Oct-tre		04
	10.3	Oct-tre Layere	e Adaptive Mesh Refinement	04 05
	10.310.410.5	Oct-tre Layere 10.4.1 Unstruc	e Adaptive Mesh Refinement	04 05 05 07
	10.310.410.5	Oct-tre Layere 10.4.1 Unstructure 1-D Pla	e Adaptive Mesh Refinement	04 05 05 07
	10.310.410.5	Oct-tre Layere 10.4.1 Unstructure 1-D Plate 10.6.1	e Adaptive Mesh Refinement	04 05 05 07 07
	10.310.410.5	Oct-tre Layere 10.4.1 Unstruc 1-D Pla 10.6.1 10.6.2	e Adaptive Mesh Refinement	04 05 05 07 07 08
	10.3 10.4 10.5 10.6	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3	e Adaptive Mesh Refinement	04 05 05 07 07 08 08
	10.3 10.4 10.5 10.6	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe	e Adaptive Mesh Refinement	04 05 07 07 08 08 09
	10.3 10.4 10.5 10.6	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe	e Adaptive Mesh Refinement	04 05 07 07 08 08 09
11	10.3 10.4 10.5 10.6	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe	e Adaptive Mesh Refinement	04 05 07 07 08 08 09
11	10.3 10.4 10.5 10.6	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe Therma	e Adaptive Mesh Refinement	04 05 07 07 08 08 09 09
11	10.3 10.4 10.5 10.6 10.7 10.8 More 11.1	Oct-tre Layere 10.4.1 Unstruc 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe Therma e inform	e Adaptive Mesh Refinement	04 05 07 07 08 08 09 09
11	10.3 10.4 10.5 10.6 10.7 10.8 More 11.1 11.2	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe Therma Stars tr Stars tr	the Adaptive Mesh Refinement	04 05 05 07 08 08 09 09 10 11
11	10.3 10.4 10.5 10.6 10.7 10.8 More 11.1 11.2 11.3	Oct-tre Layere 10.4.1 Unstruct 1-D Pla 10.6.1 10.6.2 10.6.3 2-D Pe Therma e inform Stars tr Stars tr Distrib	e Adaptive Mesh Refinement	04 05 05 07 08 08 09 09 10 11

	11.4.2 Role of the external radiation field in images and spectra	112
	11.5 Internal heat source	112
	11.5.1 Slow performance of RADMC-3D with heat source	113
12	Using RADMC-3D in child mode (optional)	114
13	Using the userdef_module.f90 file for internal model setup and user-defined emission/absorption produced to the control of the	cesses (optional)116
	13.1 Setting up a model <i>inside</i> of RADMC-3D	116
	13.2 The pre-defined subroutines of the userdef_module.f90 \dots	117
	13.3 Some caveats and advantages of internal model setup	119
	13.4 Using the userdef module to compute integrals of J_{ν}	119
	13.5 Some tips and tricks for programming user-defined subroutines	120
	13.6 Creating your own emission and absorption processes	120
	13.7 Using RADMC-3D as a fancy volume-rendering tool	121
14	Model analysis (I): The IDL model analysis tool set	122
	14.1 The readradmc.pro tools	122
	14.1.1 Function readimage	122
	14.1.2 Subroutine plotimage	123
	14.1.3 Subroutine makeimage	124
	14.1.4 Subroutine read_data()	125
	14.2 Support for FITS	126
	14.3 The image viewing GUI: viewimage	127
	14.4 Making and reading spectra with IDL	130
	14.5 A general-purpose 3-D datacube analysis GUI	130
15	Model analysis (II): Tools inside of radmc3d	132
	15.1 Making a regularly-spaced datacube ('subbox') of AMR-based models	132
	15.1.1 Creating and reading a subbox from within IDL	132
	15.1.2 Creating and reading a subbox by directly communicating with radmc3d	133
	15.1.3 Format of the subbox output files	133
	15.2 Alternative to subbox: arbitrary sampling of AMR-based models	134
16	Model analysis (III): Visualization with VTK tools (e.g. Paraview or VisIt)	136
17	Creating Protoplanetary Disk Models using a GUI	139
	17.1 How to run the GUI	139
	17.2 Create your own setup and/or open your own tab	140
18	How to convert old-style RADMC models to RADMC-3D	142
19	Tips, tricks and problem hunting	143
	19.1 Tips and tricks	143

	19.2 Bug hunting	13
	19.3 Some tips for avoiding troubles and for making good models	14
	19.4 Careful: Things that might go wrong	14
	19.5 Common technical problems and how to fix them	15
A	A Main input and output files of RADMC-3D	18
	A.1 INPUT: radmc3d.inp	19
	A.2 INPUT (required): amr_grid.inp	52
	A.2.1 Regular grid	52
	A.2.2 Oct-tree-style AMR grid	53
	A.2.3 Layer-style AMR grid	54
	A.3 INPUT (required for dust transfer): dust_density.inp	56
	A.3.1 Example: dust_density.inp for a regular grid	56
	A.3.2 Example: dust_density.inp for an oct-tree refined grid	57
	A.3.3 Example: dust_density.inp for a layer-style refined grid	58
	A.4 INPUT/OUTPUT: dust_temperature.dat	59
	A.5 INPUT/OUTPUT (only if required): electron_numdens.inp	50
	A.6 INPUT/OUTPUT (only if required): ion_numdens.inp	50
	A.7 INPUT (mostly required): stars.inp	50
	A.8 INPUT (optional): stellarsrc_templates.inp	51
	A.9 INPUT (optional): stellarsrc_density.inp	52
	A.10 INPUT (optional): external_source.inp	52
	A.11 INPUT (optional): heatsource.inp	53
	A.12 INPUT (required): wavelength_micron.inp	53
	A.13 INPUT (optional): camera_wavelength_micron.inp	53
	A.14 INPUT (required for dust transfer): dustopac.inp and dustkappa_*.inp or dustkapscatmat_*.inp or dust_c	
	A.14.1 The dustopac.inp file	54
	A.14.2 The dustkappa_ <name>.inp files</name>	55
	A.14.3 The dustkapscatmat_ <name>.inp files</name>	55
	A.14.4 The dustopac_ <name>.inp files: Backward compatibility with RADMC-2D 16</name>	57
	A.15 OUTPUT: spectrum.out	58
	A.16 OUTPUT: image.out or image_****.out	58
	A.17 INPUT: (minor input files)	70
	A.17.1 The color_inus.inp file (required with comm-line option 'loadcolor') 17	70
	A.17.2 INPUT: aperture_info.inp	70
	A.18 For developers: some details on the internal workings	71
В	B Binary I/O files	72
	B.1 Overview	72
	B.2 How to switch to binary (or back to ascii)	73
	B.3 Binary I/O file format of RADMC-3D	

F	Vers	sion tracker: Development history	186
E	Acq	uiring opacities from the WWW	185
	D.3	Local observer mode	183
	D.2	Scattering off dust grains	183
	D.1	Coordinate systems	183
D	Whi	ch options are mutually incompatible?	183
	C.4	Commands for child mode	182
		Switching on/off of radiation processes	
	C.2	Additional arguments: general	179
	C .1	Main commands	178
C	Con	nmand-line options	178
	B.4	F77-unformatted file structure used by RADMC-3D	176

Introduction, copyright and disclaimer

1.1 Introduction

RADMC-3D is a software package for astrophysical radiative transfer calculations in arbitrary 1-D, 2-D or 3-D geometries. It is mainly written for continuum radiative transfer in dusty media, but also includes modules for gas line transfer and gas continuum transfer.

RADMC-3D is a new incarnation of an older software package called RADMC. The original RADMC package was written in Fortran 77 and was only for axially symmetric problems in spherical coordinates. Because it was written in Fortran 77, the arrays had a fixed maximum size, so whenever a new grid was necessary, the code had to be recompiled. RADMC was also ageing in many other ways, in the sense that it used input formats that stemmed from the very early developing phase, and were not particularly practical. Also, RADMC's limitation to axisymmetric configurations and rigid gridding made it not capable of dealing with more complex 3-D models that are now becoming ever more mainstream. For these reasons I decided to make a huge make-over of the code, or more precise: to build a new incarnation of RADMC, called RADMC-3D, almost completely from scratch.

At the moment RADMC-3D is still in the development phase, but is is already reasonably mature. Here is a list of current and planned features. Those features that are now already working are marked with [+], while those which are not yet (!!) built in are marked with [-]. Those that are currently being developed are marked with [.] and those that are ready, but are still in the testing phase are marked with [t].

- Coordinate systems:
 - [+] Cartesian coordinates (3-D)
 - [+] Spherical coordinates (1-D, 2-D and 3-D)
- Gridding systems (regular and adaptive mesh refinement grids are available for cartesian and spherical coordinates):
 - [+] Regular
 - [+] Adaptive Mesh Refinement: oct-tree style
 - [+] Adaptive Mesh Refinement: layered ('patch') style
 - [-] Voronoi gridding [To be implemented on request]
- Radiation mechanisms:
 - [+] Dust continuum, thermal emission
 - [t] Dust continuum scattering:
 - [+] ...in isotropic approximation
 - [+] ...with full anisotropy
 - [+] ...with full Stokes and Polarization

- [-] Dust quantum heated grains [To be implemented on request]
- [t] Polarized dust emission by aligned grains [first test version]
- [+] Gas line transfer (LTE)
- [+] Gas line transfer (non-LTE: LVG)
- [+] Gas line transfer (non-LTE: LVG + Escape Probability)
- [-] Gas line transfer (non-LTE: full transfer)
- [+] Gas line transfer with user-defined populations
- [+] Gas continuum opacity and emissivity sources
- Radiation netto sources for continuum:
 - [+] Discrete stars positioned at will
 - [t] Continuous 'starlike' source
 - [t] Continuous 'dissipation' source
 - [t] External 'interstellar radiation field'
- Imaging options:
 - [+] Easy-to-use IDL front-end widget interface for imaging
 - [+] Observer from 'infinite' distance
 - [+] Zoom-in at will
 - [+] Flux-conserving imaging, i.e. pixels are recursively refined
 - [+] A movie-making tool
 - [+] Multiple wavelengths in a single image
 - [+] Local observer with perspective view (for PR movies!)
- Spectrum options:
 - [+] SED spectrum (spectrum on 'standard' wavelength grid)
 - [+] Spectrum on any user-specified wavelength grid
 - [+] Spectrum of user-specified sub-region (pointing)
 - [t] Specification of size and shape of a primary 'beam' for spectra
- User flexibility:
 - [+] Free model specification via tabulated input files
 - [+] Easy special-purpose compilations of the code (optional)
- Front-end IDL packages:
 - [+] Example model setups
 - [+] Image viewing GUI (graphical user interface). NOTE: As of now also a non-IDL stand-alone image viewing GUI (in Qt) is available.
- Front-end Python packages:
 - [+] Python RADMC-3D library (author: A. Juhasz)
- Miscellaneous:
 - [+] Stars can be treated as point-sources or as spheres
 - [+] Option to calculate the mean intensity $J_{\nu}(\vec{x})$ in the model
 - [+] OpenMP parallellization of the thermal Monte Carlo

1.2 Version tracker

The RADMC-3D software package in under continuous development. A very detailed development log-book can be found in the src/Radmc_3D_LOG.txt text file, but this may be too detailed for most users. A more user-friendly overview of the development history can be found in this manual, in appendix F.

1.3 Copyright and disclaimer

RADMC-3D was developed from 2007 to 2010/2011 at the Max Planck Institute for Astronomy in Heidelberg, funded by a Max Planck Research Group grant from the Max Planck Society. As of 2011 the development continues at the Institute for Theoretical Astrophysics (ITA) of the Zentrum für Astronomy (ZAH) at the University of Heidelberg.

The use of this software is free of charge. However, it is not allowed to distribute this package without prior consent of the lead author (C.P. Dullemond). Please refer any interested user to the web site of this software where the package is available, which is currently:

http://www.ita.uni-heidelberg.de/dullemond/software/radmc-3d/

IMPORTANT NOTICE 1: I/We reject all responsibility for the use of this package. The package is provided as-is, and we are not responsible for any damage to hardware or software, nor for incorrect results that may result from the software. The user is fully responsible for any results from this code, and we strongly recommend thorough testing of the code before using its results in any scientific papers.

IMPORTANT NOTICE 2: Any publications which involve the use of this software must mention the name of this software package and cite the accompanying paper once it is published (Dullemond et al. in prep), or before that the above mentioned web site.

IMPORTANT NOTICE 3: If you use this software, you may want to notify the lead author (C.P. Dullemond) so that you are put on an email list. This ensures that you are always up to date with major bug reports and major updates. This mail list is only used for important enough news, so you will not be flooded with emails and you can always unsubscribe.

Quick-Start

In general I recommend reading the manual fully, but it is often useful to get a quick impression of the package with a quick-start. To make your first example model, this is what you do:

- 1. When you read this you have probably already unzipped this package. You should find, among others, a src/directory and a examples/directory. Go into the src/directory.
- 2. Edit the src/Makefile file, and make sure to set the FF variable to the Fortran-90 compiler you have installed on your system.
- 3. Type make. If all goes well, this should compile the entire code and create an executable called radmc3d.
- 4. Type make install. If all goes well this should try to create a link to radmc3d in your ~/bin/ directory. If this directory does not exist, it will ask to make one.
- 5. Make sure to have the ~/bin/ directory in your path. If you use, for instance, the tcsh shell, you do this by setting the path variable: set path = (~/bin \$path) in your ~/.tcshrc file. If you change these things you may have to open a new shell to make sure that the shell now recognizes the new path.
- 6. Check if the executable is OK by typing radmc3d in the shell. You should get a small welcoming message by the code.
- 7. Now enter the directory examples/run_simple_1/.
- 8. Copy all standard IDL (see Section 3.2 about IDL) routines from the ../../idl/ directory into the current directory by typing in the tesh or bash shell cp ../../idl/*.pro ./. NOTE: This is a quick-and-dirty way of using the IDL routines, only meant to get the stuff running quickly without going through the somewhat more involved IDL routines installation procedure described in Section 4.5. For the the proper use of the RADMC-3D package, it is recommended to follow the procedures described in Section 4.5.
- 9. Enter IDL.
- 10. Type (in IDL) .r problem_setup.pro, and after that exit to exit IDL again.
- 11. Type radmc3d mctherm. This should let the code do a Monte Carlo run. You should see Photon nr 1000, followed by Photon nr 2000, etc until you reach Photon nr 1000000. The Monte Carlo modeling for the dust temperatures has now been done.
- 12. Go into IDL again and type .r viewimage.pro followed by viewimage. This should bring an image viewer on the screen and show what the simple model looks like when rendered at some angle¹. The model is very simple: a spherical blob, so do not expect to see much in this simple example.

¹Note: on some systems there is an apparent problem with the communication pipe between radmc3d and IDL which causes things to freeze. Try typing viewimage, /nochild in that case, which should fix the problem, although the viewer may then be substantially slower. I am working on figuring out how the problem can be fixed, but have so far been not successful.

If you experience troubles with the above steps, and you cannot fix it, please read the next chapters for more details.

Tip: If the code unexpectedly quits or freezes while using viewimage, please have a look at the file radmc3d.out which contains the messages that RADMC-3D outputs. This may give hints what went wrong. Note that this file is only written if RADMC-3D is used in child mode, which is the case when it is spawned from viewimage. Otherwise this output will be written to screen. Also, when viewimage is called with the option , /nochild the output will also be written to screen instead of the file radmc3d.out.

Overview of the RADMC-3D package

3.1 Introduction

The RADMC-3D code is written in fortran-90 and should compile with most f90 compilers without problems. It needs to be compiled only once for each platform. Note that the code is developed for Unix-based systems such as linux machines or Mac OS X machines. It may also work on Windows machines, but this is not guaranteed, and throughout this manual a Unix-based machine is assumed, with a csh, tcsh or bash shell. User-level knowledge of Unix-like operating systems is required.

The executable is called radmc3d and it performs all the model calculations of the RADMC-3D package, for instance the Monte Carlo simulations, ray-tracing runs (images, spectra), etc. There is also a set of useful subroutines written in the IDL¹ language to use the radmc3d code, but radmc3d can also run without IDL. In that case the user will have to write his/her own pre- and post-processing subroutines in e.g. python or other data processing languages.

3.2 Requirements

This package runs under linux/unix/MacOSX, but has not been tested under Windows. The following pre-installed software is required:

- make or gmake
 This is the standard tool for compiling packages on all Unix/Linux-based systems.
- This is a standard scripting language available on most or all Unix/Linux-based systems. If you are in doubt: type which perl to find the location of the perl executable. See http://www.perl.org/ for details on perl, should you have any problems. But on current-day UNIX-type operating systems perl is nearly always installed in the /usr/bin/ directory.
- A fortran-90 compiler

 Preferably the gfortran compiler (which the current installation assumes is present on the system). Website: http://gcc.gnu.org/fortran/. Other compilers may work, but have not been tested yet.
- An OpenMP-fortran-90 compiler
 Only needed if you want to use the parallelized OpenMP version for the thermal Monte Carlo (from version 0.38 onward). Preferably the GNU OpenMP/GOMP compiler which is an implementation of OpenMP for the Fortran compiler in the GNU Compiler Collection. Websites: http://openmp.org/wp and http://gcc.gnu.org.
 Other compilers may work, but have not been tested yet.

¹IDL is a commercial data processing package used frequently among astrophysicists. See http://www.ittvis.com/idl/for more information.

• The IDL package (Interactive Data Language)

IDL is a software package similar to MatLab, and it is not free. While RADMC-3D can be used without IDL, all examples and all post-processing scripts are written in IDL, so it would require the user to rewrite them into other languages (fortran, c, c++, perl, python or whatever). The website for IDL is: http://www.ittvis.com/. If IDL is not present on your system, and your system administrators cannot install this package due to lack of funding, you can also use an open source clone called GDL (Gnu Data Language) which can be readily downloaded from the web (http://gnudatalanguage.sourceforge.net/). This GDL package misses some libraries and features, but the RADMC-3D code can be used with GDL with the exception that the Graphical User Interfaces of RADMC-3D (such as viewimage.pro) cannot be used.

Note that the Monte Carlo code RADMC-3D itself is in Fortran-90. Only the creation of the input files (and hence the problem definition) and the analysis of the output files is done in IDL. The user is of course invited to use other ways to create the input files for RADMC-3D if he/she is not able to use IDL. Therefore IDL are not strictly required for the use of this code.

3.3 The archive, how to unzip it, and what it contains

The package of RADMC-3D is packed in a zip archive called radmc-3d_v*.**_##.##.##.zip where the *.** is the version number and ##.##.## is the date of this version in dd.mm.yy format. To unpack on a linux, unix or Mac OS X machine you type:

```
unzip <this archive file>
i.e. for example for radmc-3d_v0.07_27.07.09.zip you type
unzip radmc-3d_v0.07_29.07.09.zip
```

A directory radmc-3d is created which has the following subdirectory structure:

The first directory, src/, contains the fortran-90 source code for RADMC-3D. The second directory, idl/, contains a set of IDL routines that are useful for model preparation and post-processing. The third directory contains a series of example models. The fourth directory contains this manual.

NOTE: As of version 0.38 there is also Python support. This was developed by Attila Juhasz. As of version 0.40 Python (version 2.7) is now the standard front-end, but we still keep the IDL routines as secondary analysis toolset.

3.4 Units: RADMC3D uses CGS

The RADMC-3D package is written such that all units are in CGS (length in cm, time in sec, frequency in Hz, energy in erg, angle in steradian). There are exceptions:

- Wavelength is usually written in micron
- Sometimes angles are in degrees (internally in radian, but input as degrees)

Compilation and installation of radmc3d

Although the RADMC-3D package contains a lot of different software, the main code is located in the src/directory, and is written in Fortran-90. The executable is radmc3d. Here we explain how to compile the fortran-90 source codes and create the executable radmc3d.

4.1 Compiling the code with 'make'

To compile the code, enter the src/ directory in your shell (we assume a tcsh shell here, but bash or other Unixshells are also fine). You now may need to edit the Makefile in this directory using your favorite text editor and replace the line

```
FF = gfortran
```

with a line specifying your own compiler. If, of course, you use gfortran, you can keep this line. But if you use, e.g., ifort, then replace the above line by

```
FF = ifort
```

If you save this file, and you are back in the shell, you can compile the radmc3d code by typing

make

in the shell. If all goes well, you have now created a file called radmc3d in the src/directory.

4.1.1 Compiling the OpenMP version

To compile the code of version 0.38 or higher, including the parallelized OpenMP part, enter the src/ directory in your shell and edit the Makefile in this directory by adding -fopenmp (assumption that you use GNU OpenMP, cf. Sect. 3.2) to either

```
OPTIM = -02 -fopenmp
or to

FF = gfortran -fopenmp
```

After saving the file, you can compile the radmc3d code by typing make in the shell, as described above. If you prefer to use another compiler, please have a look at http://openmp.org/wp/openmp-compilers/.

4.2 The install.perl script

If instead of typing just 'make' you type

```
make install
```

(or you first type 'make' and then 'make install', it's the same), then in addition to creating the executable, it also automatically executes a perl script called install.perl (located also in the src/directory) that installs the code in such a way that it can be conveniently used in any directory. What it does is:

- 1. It checks if a bin/ directory is present in your home directory (i.e. a ~/bin/ directory). If not, it asks if you want it to automatically make one.
- 2. It checks if the ~/bin/ directory is in the 'path' of the currently used shell. This is important to allow the computer to look for the program 'radmc3d' in the ~/bin/ directory. If you use a csh or tcsh shell, then you can add the following line to your ~/.tcshrc file:

```
set path=($HOME/bin $path)
```

- 3. It creates a file radmc3d in this ~/bin/ directory with the correct executable permissions. This file is merely a dummy executable, that simply redirects everything to the true radmc3d executable located in your current src/ directory. When you now open a new shell, the path contains the ~/bin/ directory, and the command radmc3d is recognized. You can also type source ~/.tcshrc followed by rehash. This also makes sure that your shell recognizes the radmc3d command.
- 4. It checks if a python/ subdirectory exists in the above mentioned bin directory, i.e. a ~/bin/python/ directory. If not, it asks if you want it to automatically create one.
- 5. If yes, then it will copy all the files ending with .py in the python/radmc3dPy/ directory of the distribution to that ~/bin/python/radmc3dPy/ directory. This is useful to allow you to make an PYTHONPATH entry to allow python to find these python scripts automatically (see Section 4.4).
- 6. It checks if a idl/ subdirectory exists in the above mentioned bin directory, i.e. a ~/bin/idl/ directory. If not, it asks if you want it to automatically create one.
- 7. If yes, then it will copy all the files ending with .pro in the idl/ directory of the distribution to that ~/bin/idl/ directory. This is useful to allow you to make an IDL_PATH entry to allow idl to find these idl scripts automatically (see Section 4.5).

Note that this perl script installs the code only for the user that installs it. A system-wide installation is, in my view, not useful, because the code package is not very big and it should remain in the control of the user which version of the code he/she uses for each particular problem.

If all is 'normal', then the perl.install script described here is called automatically once you type make install following the procedure in Section 4.1.

Before the installation is recognized by your shell, you must now either type rehash in the shell or simply open a new shell.

How do you know that all went OK? If you type radmc3d in the shell the RADMC-3D code should now be executed and give some comments. It should write:

```
WELCOME TO RADMC-3D: A 3-D CONTINUUM RT SOLVER

This is the 3-D version of the 2-D RADMC code
(c) 2008 Cornelis Dullemond

Nothing to do... Use command line options to generate action:
mctherm
Do Monte Carlo simul of thermal radiation
mcscat
Do Monte Carlo simul only for scattering
spectrum
Make continuum spectrum
image
Make continuum image
```

on the screen (or for newer versions of RADMC-3D perhaps some more or different text). This should also work from any other directory.

4.3 What to do if this all does not work?

In case the above compilation and installation does not work, here is a proposed procedure to do problem hunting:

- First, answer the following questions:
 - Did you type make install in the src/directory? I mean, did you not forget the install part?
 - Did you put \sim /bin/ in your path (see above)?
 - If you just added ~/bin/ to your path, did you follow the rest of the procedure (either closing the current shell and opening a new shell or typing the source and rehash commands as described above)?

If this does not help, then continue:

- Close the shell, open a new shell.
- Go to the RADMC-3D src/ directory.
- Type ./radmc3d. This should give the above message. If not, then make sure that the compilation went right in the first place:
 - Type rm -f radmc3d, to make sure that any old executable is not still present.
 - Type make clean. This should return the sentence OBJECT and MODULE files removed.
 - Then type make. This should produce a set of lines, each representing a compilation of a module, e.g. gfortran -c -02 ./amr_module.f90 -o amr_module.o, etc. The final line should be something like gfortran -02 main.o rtglobal_module.o montecarlo_module.o dust_module.o quantum_module.o mathroutines_module.o ioput_module.o stars_module.o amr_module.o amrray_module.o constants_module.o camera_module.o lines_module.o namelist_module.o userdef_module.o gascontinuum_module.o -o radmc3d. If instead there is an error message, then do the following:
 - * Check if the compiler used (by default gfortran) is available on your computer system.
 - * If you use an other compiler, check if the compiler options used are recognized by your compiler.
 - Check if the executable radmc3d is now indeed present. If it is not present, then something must
 have gone wrong with the compilation. So then please check the compilation and linking stage again
 carefully.

If you followed all these procedures, but you still cannot get even the executable in the src/directory to run by typing (in the src/directory)./radmc3d (don't forget the dot slash!), then please contact the author.

- At this point I assume that the previous point worked. Now go to another directory (any one), and type radmc3d. This should also give the above message. If not, but the radmc3d executable was present, then apparently the shell path settings are wrong. Do this:
 - Check if, in the current directory (which is now not src/) there is by some accident another copy of the executable radmc3d. If yes, please remove it.
 - Type which radmc3d to find out if it is recognized at all, and if yes, to which location it points.
 - Did you make sure that the shell path includes the ~/bin/ directory, as it should? Otherwise the shell
 does not know where to find the ~/bin/radmc3d executable (which is a perl link to the src/radmc3d
 executable).
 - Does the file \sim /bin/radmc3d perl file exist in the first place? If no, check why not.
 - Type less ~/bin/radmc3d and you should see a text with first line being #!/usr/bin/perl and the second line being someting like system("/Users/user1/radmc-3d/version_0.12/src/radmc3d@ARGV"); where the /Users/user1 should of course be the path to your home directory, in fact to the directory in which you installed RADMC-3D.

If this all brings you no further, please first ask your system administrators if they can help. If not, then please contact the author.

4.4 Installing the Python analysis tools

In the package there is a directory containing a whole series of analysis tools written in Python for analyzing the results of RADMC-3D. They are highly recommended, but not essential for using RADMC-3D. These Python routines were developed and programmed by A. Juhasz.

The tools are written in Python 2.7 and you can find them in the python/ directory. The documentation can be found in that directory. To use them in a convenient way one must let Python know where to find these routines. Since the install.perl script described above copies all these files to the ~/bin/python/ directory, it is advisable to put that directory as the PYTHONPATH instead of the local python directory. The reason is that if you have multiple versions of RADMC-3D on your system, you always are assured that Python finds the python routines belonging to the latest installation of RADMC-3D (note: only assured if that latest compilation was done with make install).

In PYTHON here are two ways how you can make sure that PYTHON automatically finds the RADMC-3D scripts:

1. Under Unix/Linux/MacOSX you can set the PYTHONPATH directly in your .cshrc or .tcshrc or .bashrc file. For example: in .tcshrc (if you use the tcsh shell) you can write:

```
setenv PYTHONPATH "/myhomedirectory/bin/python"

(where myhomedirectory should be replaced by your home directory name).
```

2. You can set the PYTHONPATH in a more elegant way directly from within Python with the python command:

```
import os
import sys
home = os.environ["HOME"]
sys.path.append(home+'/bin/python')
```

If all goes well, if you now start Python you should be able to have access to the Python routines of RADMC-3D directly. To test this, try typing from image import * in Python. If this gives an error message that image.py cannot be found, then please ask your system administrators how to solve this.

4.5 Installing the IDL analysis tools

Instead of the Python analysis tools you can also use the IDL analysis tools. These tools are described in detail in Chapter 14.

The tools are written in IDL and you can find them in the idl/ directory. To use them in a convenient way one must let IDL know where to find these routines. Since the install perl script described above copies all these files to the ~/bin/idl/ directory, it is advisable to put that directory as the IDL_PATH instead of the local idl directory. The reason is that if you have multiple versions of RADMC-3D on your system, you always are assured that IDL finds the idl routines belonging to the latest installation of RADMC-3D (note: only assured if that latest compilation was done with make install).

In IDL here are two ways how you can make sure that IDL automatically finds the RADMC-3D scripts:

1. Under Unix/Linux/MacOSX you can set the IDL_PATH directly in your .cshrc or .tcshrc or .bashrc file. For example: in .tcshrc (if you use the tcsh shell) you can write:

```
setenv IDL_PATH "/myhomedirectory/bin/idl:/Applications/itt/idl70/lib:\
/Applications/itt/idl70/lib/iTools:\
/Applications/itt/idl70/lib/iTools/framework:\
/Applications/itt/idl70/lib/iTools/components:\
/Applications/itt/idl70/lib/iTools/ui_widgets"
```

(where myhomedirectory should be replaced by your home directory name). Note that the entire IDL default path also has to be added, as it is done here, otherwise most of IDL libraries are not working anymore. The disadvantage of this method is that if IDL adds further directories to its default path in the future, you would have to add them by hand here.

2. You can set the IDL_PATH in a more elegant way directly from within IDL with the command:

```
PREF_SET, 'IDL_PATH', '/myhomedirectory/bin/idl:<IDL_DEFAULT>',/COMMIT
```

(where myhomedirectory should be replaced by your home directory name). Of course, you do not want to have to type this line every time you start up IDL. So you can make a startup script that IDL executes every time it is started or reset. The way to do this is:

- (a) Make a script file, e.g. called .idl_startup in your home directory (Note: by starting the name with a "." it will remain invisible under Unix/Linux unless you type ls -a), containing the above line (i.e. containing PREF_SET, 'IDL_PATH', '/myhomedirectory/bin/idl:<IDL_DEFAULT>', /COMMIT).
- (b) In your .tcshrc or .bashrc file in your home directory set the IDL_STARTUP environment variable to /myhomedirectory/.idl_startup. For .tcshrc this works by adding a line setenv IDL_STARTUP /myhomedirectory/.idl_startup.

If all goes well, if you now start IDL you should be able to have access to the IDL routines of RADMC-3D directly. To test this, try typing .r viewimage in IDL. If this gives an error message that viewimage.pro cannot be found, then please ask your system administrators how to solve this.

NOTE: You can also ignore all of this, and not copy any of the IDL routines to this central location, and instead simply copy all the *.pro files of the idl/ directory that you use to the local model directory (see Section 5.7 for what we mean with 'model directory'). Or you could, in IDL, give the full path to each of the files. But these solutions are a lot messier.

4.6 Installing the stand-alone (non-IDL) version of viewimage

Farzin Sereshti developed the stand-alone version of viewimage (which is a useful interactive tool for making images of models). It can be found in the directory viewimage_QT_GUI/. The documentation is in that directory. For all questions of this package please contact Farzin Sereshti.

4.7 Making special-purpose modified versions of RADMC-3D (optional)

For most purposes it should be fine to simply compile the latest version of RADMC-3D once-and-for-all, and simply use the resulting radmc3d executable for all models you make. Normally there is no reason to have to modify the code, because models can be defined quite flexibly by preparing the various input files for RADMC-3D to your needs. So if you are an average user, you can skip to the next subsection without problem.

But sometimes there *is* a good reason to want to modify the code. For instance to allow special behavior for a particular model. Or for a model setup that is simply easier made internally in the code rather than by preparing large input files. One can imagine some analytic model setup that might be easier to create internally, so that one can make use of the full AMR machinery to automatically refine the grid where needed. Having to do so externally from the code would require you to set up your own AMR machinery, which would be a waste of time.

The problem is that if the user would modify the central code for each special purpose, one would quickly lose track of which modification of the code is installed right now.

Here is how this problem is solved in RADMC-3D:

• For most purposes you can achieve your goals by only editing the file userdef_module.f90. This is a set of standard subroutines that the main code calls at special points in the code, and the user can put anything he/she wants into those subroutines. See Chapter 13 for more information about these standard subroutines. This method is the safest way to create special-purpose codes. It means (a) that you know that your modification cannot do much harm unless you make really big blunders, because these subroutines are meant to be modified, and (b) you have all your modifications *only* in one single file, leaving the rest of the code untouched.

- You can create a *local* version of the code, without touching the main code. Suppose you have a model directory run_mymodel and for this model you want to make a special-purpose version of the code. This is what you do:
 - 1. Copy the Makefile from the src/directory into run_mymodel.
 - 2. Copy the .f90 file(s) you want to modify from the src/ directory into run_mymodel. Usually you only want to modify the userdef_module.f90 file, but you can also copy any other file if you want.
 - 3. In the run_mymodel/Makefile replace the SRC = . line with SRC = XXXXXX, where XXXXXX should be the *full* path to the src/directory. An example line is given in the Makefile, but is commented out.
 - 4. In the run_mymodel/Makefile make sure that all the .f90 files that should remain as they are have a \$(SRC)/ in front of the name, and all the .f90 files that you want to modify (and which now have a copy in the run_mymodel directory) have a ./ in front of the name. By default all .f90 files have \$(SRC)/ in front of the name, except the userdef_module.f90 file, which has a ./ in front of the name because that is the file that is usually the one that is going to be edited by you.
 - Now edit the local .f90 files in the run_mymodel directory in the way you want. See Chapter 13 for more details.
 - 6. Now *inside* the run_mymodel directory you can now type make and you will create your own local radmc3d executable. NOTE: Do not type make install in this case, because it should remain a local executable, only inside the run_mymodel directory.
 - 7. If you want (though this is not required) you can clean up all the local .o and .mod files by typing make clean, so that your run_mymodel directory is not filled with junk.
 - 8. You can now use this special purpose version of radmc3d by simply calling on the command line: ./radmc3d, with any command-line options you like. Just beware that, depending on the order in which you have your paths set (in tcsh or bash) typing just radmc3d may instead use the global version (that you may have created in the src/directory with make install). So to be sure to use the local version, just put the ./ in front of the radmc3d.

Note: In chapter 13 there is more information on how to set up models internally in the code using the method described here.

Note: You can use make clean to remove all the .o and .mod files from your model directory, because they can be annoying to have hanging around. By typing make cleanmodel you remove, in addition to the .o and .mod files, also all model input and output files, with the exception of dust opacity or molecular data files (because these latter files are usually not created locally by the problem_setup.pro script). By typing make cleanall you remove everything *except* the basic files such as the Makefile, any .f90 files, any .pro files, the dust opacity or molecular data files and README files.

Basic structure and functionality

RADMC-3D is a very versatile radiative transfer package with many possibilities. As a consequence it is a rather complex package. However, we have tried to keep it still as easy as possible to use as a first-time user. We tried to do so by keeping many of the sophisticated options "hidden" and having many default settings already well-chosen. The idea is that one can already use the code at an entry level, and then gradually work oneself into the more fancy options.

RADMC-3D is a general-purpose package, so there are no 'built-in' models inside the radmc3d executable (Except if you insert one yourself using the userdef module, see Chapter 13). For instance, if you want to model a protoplanetary disk, then you would have to design the grid and density structure of the disk on this grid yourself. To make it easier for the user, we have provided several IDL-scripts as examples. Among these examples is indeed a protoplanetary disk model. So this is as close as we go to 'built-in' models: we provide, for some cases, already well-developed example models that you, the user, can use out-of-the-box, or that you can adapt to your needs.

In this chapter we give an overview of the rough functionality of the code in its simplest form: ignoring all the hidden fancy options and possibilities. For the details we then refer to the chapters ahead.

5.1 Basic dataflow

Let us first clarify the basic philosophy of the code package (details will be done later). When we talk about "RADMC-3D" we talk about the fortran-90 program. The source codes are in the directory <code>src/</code> and the executable is called <code>radmc3d</code>. This is the code that does all the main calculations. You can call the code from the tcsh or bash shell (in Unix/Linux/MacOSX systems) and you can specify command-line options to tell RADMC-3D what you want it to do.

The code RADMC-3D is in a way an "empty shell". It is totally dependent on input files of various kinds. These input files have filenames that end in .inp, .uinp or .binp, dependent on whether the data in ASCII¹, f77-unformatted or binary form. You, the user, will have to create these input files. RADMC-3D will simply look if an .inp, a .uinp or a .binp file is present, and will switch to ASCII, f77-unformatted or binary input, dependent on which file-extension it finds.

After you run RADMC-3D (by calling radmc3d with the appropriate command-line options) you will see that the code will have produced one or more output files, with filenames ending in .out, .uout or .bout. Whether RADMC-3D produces ASCII, f77-unformatted or binary files, depends on a flag called rto_style that you can set (see Chapter B).

IMPORTANT NOTE: In this manual we will mostly refer to the ASCII form of input and output files for convenience. But each time we refer to an **.inp, **.dat or **.out file, we implicitly assume that this could also be a **.uinp, **.udat or **.uout or **.binp, **.bdat or **.bout file.

This basic dataflow is shown in Fig. 5.1.

Not always can RADMC-3D produce its output files in one go. Sometimes it has to use a two-stage proce-

¹ASCII files are human-readable text files.




Figure 5.1. Pictographic representation of the basic dataflow of RADMC-3D. The user produces the input files; RADMC-3D reads them, performs the calculation, and produces output files. The user can then analyze the output files.



Figure 5.2. Pictographic representation of the dataflow of RADMC-3D for the case of a 2-stage procedure, such as for dust continuum transfer. An intermediate file is produced that will be used by stage 2, but of course the user can also analyze the intermediate file itself.

dure: For dust continuum radiative transfer the dust temperatures are computed first (stage 1), and the images and/or spectra are rendered after that (stage 2). Between stage 1 and stage 2 an intermediate file is then produced (with filename ending in .dat, .udat or .bdat), which in the case of dust continuum radiative transfer is dust_temperature.dat (or **.udat or **.bdat).

This basic dataflow is shown in Fig. 5.2.

Several of these input files contain large tables, for instance of the density at each grid point, or the stellar flux at each wavelength bin. It is, of course, impossible to create these datafiles by hand. The idea is that you design a program (in any language you like) that creates these datafiles. In that program you essentially "program the model". We have provided a number of example model setups in the examples/directory. For these examples models the setup programs were written in IDL (their filenames all start with problem and end with .pro). For you as the user it is therefore the easiest to start from one of these examples and modify the IDL code to your needs. However, if you have no IDL license, and/or if you prefer to use another language, you can use the examples to see how the input files were generated and then program this in another programming language.

Note: The IDL files called problem_***.pro are meant to be edited and changed by you! They are templates from which you can create your own models.

For the analysis of the output files created by RADMC-3D you can use your own favorite plotting or data-analysis software. But also here we provide some basic tools in IDL. These IDL routines are in the idl/ directory. Typically you will create your own program, e.g. plot_model.pro or so, that will use these subroutines, e.g. by putting in the first line: @readradmc.pro. In this way IDL is used also as a post-processing tool. But again: this can also be done in another language.

This procedure is shown in Fig. 5.3 for the single-stage dataflow and in Fig. 5.4 for the two-stage dataflow.




Figure 5.3. Pictographic representation of how the IDL programs in the example directories are used to create the input files of RADMC-3D.




Figure 5.4. Pictographic representation of the dataflow of RADMC-3D for the case of a 2-stage procedure, such as for dust continuum transfer. An intermediate file is produced that will be used by stage 2, but of course the user can also analyze the intermediate file itself.

5.2 Radiative processes

Currently RADMC-3D handles the following radiative processes:

• Dust thermal emission and absorption

RADMC-3D can compute spectra and images in dust continuum. The dust temperature must be known in addition to the dust density. In typical applications you will know the dust density distribution, but not the dust temperature, because the latter is the results of a balance between radiative absorption and re-emission. So in order to make spectra and images of a dusty object we must first calculate the dust temperature consistently. This can be done with RADMC-3D by making it perform a "thermal Monte Carlo" simulation (see Chapter 6). This can be a time-consuming computation. But once this is done, RADMC-3D writes the resulting dust temperatures out to the file dust_temperature.dat, which it can then later use for images and spectra. We can then call RADMC-3D again with the command to make an image or a spectrum (see Chapter 6). To summarize: a typical dust continuum radiative transfer calculation goes in two stages:

- 1. A thermal Monte Carlo simulation with RADMC-3D to compute the dust temperatures.
- 2. A spectrum or image computation using ray-tracing with RADMC-3D.

• Dust scattering

Dust scattering is automatically included in the thermal Monte Carlo simulations described above, as well as in the production of images and spectra. For more details, consult Chapter 6.

• Gas atomic/molecular lines

RADMC-3D can compute spectra and images in gas lines (see Chapter 7). The images are also known as "channel maps". To compute these, RADMC-3D must know the population densities of the various atomic/molecular levels. For now there are two options how to let RADMC-3D know these values:

- Tell RADMC-3D to assume that the molecules or atoms are in "Local Thermodynamic Equilibrium" (LTE), and specify the gas temperature at each location to allow RADMC-3D to compute these LTE level populations. Note that in principle one is now faced with the same problem as with the dust continuum: we need to know the gas temperature, which we typically do not know in advance. However, computing the gas temperature self-consistently is very difficult, because it involves many heating and cooling processes, some of which are very complex. That's why most line radiative transfer codes assume that the user gives the gas temperature as input. We do so as well. If you like, you can tell RADMC-3D to use the (previously calculated) dust temperature as the gas temperature, for convenience.
- Deliver RADMC-3D an input file with all the level populations that you have calculated youself using some method.
- Tell RADMC-3D to compute the level populations according to some simple local non-LTE prescription such as the Sobolev approximation ("Large Velocity Gradient method") or the Escape Probability Method. (This is still under development!)

Currently RADMC-3D does not have a full non-local non-LTE computation method implemented. The reason is that it is very costly, and for many applications presumably not worth the computational effort. But we are working on a full non-LTE mode. Stay tuned!

• Gas continuum opacities

We are currently working on implementing gas continuum opacities as well. Again we are faced with the question how to compute the gas temperature. For now we simply require you to specify the gas temperature yourself.

Remark: We are thinking of methods to compute gas temperatures self-consistently in some special situations. Stay tuned...

5.3 Coordinate systems

With RADMC-3D you can specify your density distribution in two coordinate systems:

- Cartesian coordinates: 3-D
 - The simplest coordinate system is the Cartesian coordinate system (x, y, z). For now each model must be 3-D (i.e. you must specify the densities and other quantities as a function of x, y and z).
- Cartesian coordinates: 1-D plane-parallel

 This is like the normal cartesian coordinates, but now the x- and y- directions are "infinitely extended".

 Only the z-direction has finite-size cells, and hence the grid is only in z-direction. This mode is the usual plane-parallel mode of radiative transfer. See Section 10.6 for more details on this mode.
- Cartesian coordinates: 2-D pencil-parallel

 This is the intermediate between full 3-D cartesian and 1-D plane-parallel. In this mode only the x-direction is infinitely extended and a finite grid is in both y and z directions. This mode is only useful in very special cases, and is much less familiar to most so use only when you are confident.
- Spherical coordinates

You can also specify your model in spherical coordinates (r, θ, ϕ) . These coordinates are related to the cartesian ones by:

$$x = r\sin\theta\cos\phi \tag{5.1}$$

$$y = r\sin\theta\sin\phi \tag{5.2}$$

$$z = r\cos\theta \tag{5.3}$$

This means that the spatial variables (density, temperature etc) are all specified as a function of (r,θ,ϕ) . However, the location of the stars, the motion and direction of photon packages etc. are still given in cartesian coordinates (x,y,z). In other words: any function of space $f(\vec{x})$ will be in spherical coordinates $f(r,\theta,\phi)$, but any point-like specification of position \vec{x} will be given as Cartesian coordinates $\vec{x}=(x,y,z)$. This hybrid method allows us to do all physics in cartesian coordinates: photon packages or rays are treated always in cartesian coordinates, and so is the physics of scattering, line emission etc. Only if RADMC-3D needs to know what the local conditions are (dust temperature, gas microturbulence, etc) RADMC-3D looks up which coordinates (r,θ,ϕ) belong to the current (x,y,z) and looks up the value of the density, microturbulence etc. at that location in the (r,θ,ϕ) grid. And the same is true if RADMC-3D updates or calculates for instance the dust temperature: it will compute the (r,θ,ϕ) belong to the current (x,y,z) and update the temperature in the cell belonging to (r,θ,ϕ) . For the rest, all the physics is done in the Cartesian coordinate system. This has the major advantage that we do not need different physics modules for cartesian and spherical coordinates. Most parts of the code don't care which coordinate system is used: they will do their own work in Cartesian coordinates. When using spherical coordinates, please read Section 10.2.

5.4 The spatial grid

To specify the density or temperature structure (or any other spatial variable) as a function of spatial location we must have a grid. There are two basic types of grids:

- Structured grids (AMR grids)
 - The standard gridding is a simple rectangular grid.
 - Cartesian coordinates: When cartesian coordinates are used, this simply means that each cell is defined as $x_l < x < x_r$, $y_l < y < y_r$ and $z_l < z < z_r$, where l and r stand for the left and right cell walls respectively.
 - Spherical coordinates: When spherical coordinates are used, this simply means that each cell is defined as $r_l < r < r_r$, $\theta_l < \theta < \theta_r$ and $\phi_l < \phi < \phi_r$. Note therefore that the shape of the cells in spherical coordinates is (in real space) curved. For spherical coordinates the following four modes are available:
 - * 1-D Spherical symmetry: All spatial functions depend only on r.
 - * 2-D Axial symmetry: All spatial functions depend only on r and θ .
 - * 2-D Axial symmetry with mirror symmetry: All spatial functions depend only on r and θ , where the θ grid only covers the part above the z=0 plane. Internally it is in this mode assumed that all quantities below the z=0 plane are equal to those above the plane by mirror symmetry in the z=0 plane. This saves a factor of two in computational effort for Monte Carlo calculations, as well as in memory useage. Note that also the resulting output files such as dust_temperature.dat will only be specified for z>0.
 - * 3-D: All spatial functions depend on all three variables r, θ and ϕ .
 - * 3-D with mirror symmetry: All spatial functions depend on all three variables r, θ and ϕ , but like in the 2-D case only the upper part of the model needs to be specified: the lower part is assumed to be a mirror copy.

When using spherical coordinates, please read Section 10.2.

In all cases these structured grids allow for oct-tree-style grid refinement, or its simplified version: the layer-style grid refinement. See Section A.2 and Chapter 10 for more information about the gridding and the (adaptive) mesh refinement (AMR).

• Unstructured grids (for now: cartesian coordinates only)

For some applications it may be more convenient to specify spatial variables not on a structured grid, but on a semi-random set of points in 3-D space. RADMC-3D will (hopefully) soon feature a mode in which it can handle such a situation, and use a Delaunay triangulation to produce a triangulation on the basis of this set of points, thus creating an unstructured grid. Unfortunately, for now this mode is not yet ready. Stay tuned...

5.5 Computations that RADMC-3D can perform

The code RADMC-3D (i.e. the executable radmc3d) is *one* code for *many* actions. Depending on which command-line arguments you give, RADMC-3D can do various actions. Here is a list:

- *Compute the dust temperature:*
 - With radmc3d mctherm you call RADMC-3D with the command of performing a thermal Monte Carlo simulation to compute the dust temperature under the assumption that the dust is in radiative equilibrium with its radiation field. This is normally a prerequisite for computing SEDs and images from dusty objects (see "computing spectra and images" below). The output file of this computation is dust_temperature.dat which contains the dust temperature everywhere in the model.
- Compute a spectrum or SED:

With radmc3d sed you call RADMC-3D with the command of performing a ray-tracing computation to compute the spectral energy distribution (SED) for the model at hand. Typically you first need to have called radmc3d mctherm (see above) beforehand to compute dust temperatures (unless you have created the file dust_temperature.dat yourself because you have a special way of computing the dust temperature). With radmc3d sed the spectrum is computed for the wavelengths points given in the file wavelength_micron.inp, which is the same wavelength grid that is used for radmc3d mctherm. If you want to compute the spectrum at wavelength other than those used for the thermal Monte Carlo simulation, you should instead call radmc3d spectrum, and you have the full freedom to choose the spectral wavelengths points at will, and you can specify these in various ways described in Section 9.4. Most easily you can create a file called

camera_wavelength_micron.inp (see Section A.13) and call RADMC-3D using radmc3d spectrum loadlambda. In all these cases the vantage point (where is the observer) can of course be set as well, see Section 6.2 and Chapter 9.

• Compute an image:

With radmc3d image you call RADMC-3D with the command of performing a ray-tracing computation to compute an image. You must specify the wavelength(s) at which you want the image by, for instance, calling RADMC-3D as radmc3d image lambda 10, which makes the image at $\lambda = 10 \mu m$. But there are other ways by which the wavelength(s) can be set, see Section 9.4. In all these cases the vantage point (where is the observer) can of course be set as well, see Section 6.2 and Chapter 9.

• Compute the local radiation field inside the model: With radmc3d mcmono you call RADMC-3D with the command of performing a wavelength-by-wavlength monochromatic Monte Carlo simulation (at the wavelengths that you specify in the file mcmono_wavelength_micron.inp). The output file of this computation is mean_intensity.out which contains the mean intensity J_{ν} as a function of the (x,y,z) (cartesian) or (r,θ,ϕ) (spherical) coordinates at the frequencies $\nu_i \equiv 10^4 c/\lambda_i$ where λ_i are the wavelengths (in μ m) specified in the file mcmono_wavelength_micron.inp. The results of this

In addition to the above main methods, you can ask RADMC-3D to do various minor things as well, which will be described throughout this manual.

computation can be interesting for, for instance, models of photochemistry. But if you use RADMC-3D only

5.6 How a model is set up and computed: a rough overview

for computing spectra and images, then you will not use this.

A radiative transfer code such as RADMC-3D has the task of computing synthetic images and spectra of a model that you specify. You tell the code what the dust and/or gas density distribution in 3-D space is and where the star(s) are, and the code will then tell you what your cloud looks like in images and/or spectra. That's basically it. That's the main task of RADMC-3D².

First you have to tell RADMC-3D what 3-D distribution of dust and/or gas you want it to model. For that you must specify a coordinate system (cartesian or spherical) and a spatial grid. For cartesian coordinates this grid should be 3-D (although there are exceptions to this), while for spherical coordinates it can be 1-D (spherical symmetry), 2-D (axial symmetry) or 3-D (no symmetry). RADMC-3D is (for most part) a cell-based code, i.e. your grid devides space in cells and you have to tell RADMC-3D what the average densities of dust and/or gas are in these cells.

The structure of the grid is specified in a file amr_grid.inp (see Section A.2). All the other data, such as dust density and/or gas density are specified in other files, but all assume that the grid is given by amr_grid.inp.

We can also specify the locations and properties of one or more stars in the model. This is done in the stars.inp (see Section A.7) file.

Now suppose we want to compute the appearance of our model in dust continuum. We will describe this in detail in Chapter 6, but let us give a very rough idea here. We write, in addition to the amr_grid.inp and stars.inp files, a file dust_density.inp which specifies the density of dust in each cell (see Section A.3). We also must write the main input file radmc3d.inp (see Section A.1), but we can leave it empty for now. We must give RADMC-3D a dust opacity table in the files dustopac.inp and for instance dustkappa_silicate.inp (see Section A.14). And finally, we have to give RADMC-3D a table of discrete wavelengths in the file wavelength_micron.inp that it will use to perform its calculations on. We then call the radmc3d code with the keyword mctherm (see Chapter 6) to tell it to perform a Monte Carlo simulation to compute dust temperatures everywhere. RADMC-3D will write this to the file dust_temperature.dat. If we now want to make a spectral energy distribution, for instance, we call radmc3d sed (see Section 9.3) and it will write a file called spectrum.out which is a list of fluxes at the discrete wavelengths we specified in wavelength_micron.inp. Then we are done: we have computed the spectral energy distribution of our model. We could also make an image at wavelength 10 \mu m for instance with radmc3d image lambda 10 (see Section 9.1). This will write out a file image.out containing the image data (see Section A.16).

²It can/will, of course, do much more, but that is described later in this manual.

As you see, RADMC-3D reads all its information from tables in various files. Since you don't want to make large tables by hand, you will have to write a little computer program that generates these tables automatically. You can do this in any programming language you want. But in the example models (see Section 5.8) we use the programming language IDL (see Section 3.2) for this. This is a very simple (BASIC-like) programming language that makes it easy to create the above input files. It is easiest to indeed have a look at the example models to see how this is (or better: can be) done.

We will explain all these things in much more detail below, and we will discuss also many other radiative transfer problem types. The above example is really just meant to give an impression of how RADMC-3D works.

5.7 Organization of model directories

The general philosophy of the RADMC-3D code package is the following. The core of everything is the fortran code radmc3d. This is the main code which does the hard work for you: it makes the radiative transfer calculations, makes images, makes spectra etc. Normally you compile this code just once-and-for-all (see Chapter 4), and then simply use the executable radmc3d for all models. There is an exception to this 'once-and-for-all' rule described in Section 4.7, but in the present chapter we will not use this (see Chapter 13 for this instead). So we will stick here to the philosophy of compiling this code once and using it for all models.

So how to set up a model? The trick is to present radmc3d with a set of input files in which the model is described in all its details. The procedure to follow is this:

- 1. The best thing to do (to avoid a mess) is to make a directory for *each model*: one model, one directory. Since radmc3d reads multiple input files, and also outputs a number of files, this is a good way to keep organized and we recommend it strongly. So if we wish to make a new model, we make a new directory, or copy an old directory to a new name (if we merely want to make small changes to a prior model).
- 2. In this directory we generate the input files according to their required format (see Chapter A). You can create these input files in any way you want. But since many of these input files will/must contain huge lists of numbers (for instane, giving the density at each location in your model), you will typically want to write some script or program in some language (be it either C, C++, Fortran, IDL, GDL, perl, python, you name it) that automatically creates these input files. We recommend using IDL, because we provide examples and standard subroutines in the programming language IDL; see below for more details. But IDL is not a strict requirement for using RADMC-3D. Section 5.8 describes how to use the example IDL scripts to make these input files with IDL.
- 3. When all the input files are created, and we make sure that we are inside the model directory, we call radmc3d with the desired command-line options (see Chapter C). This will do the work for us.
- 4. Once this is done, we can analyze the results by reading the output files (see Chapter A). To help you reading and analyzing these output files you can use a set of IDL routines that we created for the user (see Chapter 14 and Section 4.5). But here again, you are free to use any other plotting software and/or data postprocessing packages (many people favor python, for instance).

5.8 Running the example models

Often the fastest and easiest way to learn a code is simply to analyze and run a set of example models. They are listed in the examples directory. Each model occupies a separate directory. This is also the style we normally recommend: each model should have its own directory. Of course there are also exceptions to this rule, and the user is free to organize her/his data in any way he/she pleases. But in all the examples and throughout this manual each model has its own directory.

To run an example model, go into the directory of this model, and follow the directions that are written in the README file in each of these directories. This is under the assumption that you have IDL installed on your system, and that you have a license for it.

Let us do for instance run_simple_1/:

```
cd examples/run_simple_1
```

Now we must create all the input files for this model. These input files are all described in chapter A, but let us here just 'blindly' follow the example. In this example most (all except one) of the input files are created using an IDL script called problem_setup.pro. To execute this script, this is what you do:

```
idl
IDL> .r problem_setup.pro
IDL> exit
```

or in words: you go into IDL and within the IDL prompt you type .r problem_setup.pro, and if this is ready, you can leave IDL again (the latter is not required of course)³. This IDL script has now created a whole series of input files, all ending with the extension .inp. To see which files are created, type the following in the shell:

```
ls -l *.inp
```

There is one file that this example does not create, and that is the file dustkappa_silicate.inp. This is a file that contains the dust opacity in tabulated form. This is a file that you as the user should provide to the RADMC-3D code package. The file dustkappa_silicate.inp is merely an example, which is an amorphous spherical silicate grain with radius 0.1 micron. But see Section A.14 for more information about the opacities.

Now that the input files are created we must run radmc3d:

```
radmc3d mctherm
```

This tells RADMC-3D to do the thermal Monte Carlo simulation. This may take some time. When the model is ready, the prompt of the shell returns. To see what files have been created by this run of the code, type:

```
ls -l *.dat
```

You will find the dust_temperature.dat containing the dust temperature everywhere in the model. See again chapter A for details of these files. To create a spectrum:

```
radmc3d sed incl 45.
```

This will create a file spectrum.dat. To analyze these data you can use the IDL routines delivered with the code (see Chapter 14 and Section 4.5).

There is a file Makefile in the directory. This is here only meant to make it easy to clean the directory. Type make cleanmodel to clean all the output from the radmc3d code. Type make cleanall to clean the directory back to basics

Let us now do for instance model run_simple_1_userdef/:

```
cd examples/run_simple_1_userdef
```

This is the same model as above, but now the grid and the dust density are set up <code>inside</code> <code>radmc3d</code>, using the file <code>userdef_module.f90</code> which is present in this directory. See Chapter 13 for details and follow the directions in the <code>README</code> file. In short: first edit the variable <code>SRC</code> in the <code>Makefile</code> to point to the <code>src/</code> directory. Then type <code>make</code>. Then go into IDL and run the <code>problem_setup.pro</code> script (which now only sets up the frequency grid, the star and the <code>radmc3d.inp</code> file and some small stuff). Now you can run the model.

Please read the README file in each of the example model directories. Everything is explained there, including how to make the relevant plots.

³Note that this does not work in IDL demo mode, which is what you get if you use IDL without a license, because files will be written, which is not possible in demo mode.

Dust continuum radiative transfer

Many of the things related to dust continuum radiative transfer have already been said in the previous chapters. But here we combine these things, and expand with more in-depth information.

Most users simply want RADMC-3D to compute images and spectra from a model. This is done in a two-stage procedure:

- 1. First compute the dust temperature everywhere using the thermal Monte Carlo computation (Section 6.1).
- 2. Then making the images and/or spectra (Section 6.2).

You can then view the output spectra and images with the IDL tools or use your own plotting software.

Some expert users may wish to use RADMC-3D for something entirely different: to compute the local radiation field *inside* a model, and use this for e.g. computing photochemistry rates of a chemical model or so. This is described in Section 6.5.

You may also use the thermal Monte Carlo computation of the dust temperature to help estimating the *gas* temperature for the line radiative transfer. See Chapter 7 for more on line transfer.

6.1 The thermal Monte Carlo simulation: computing the dust temperature

RADMC-3D can compute the dust temperature using the Monte Carlo method of Bjorkman & Wood (2001, ApJ 554, 615) with various improvements such as the continuous absorption method of Lucy (1999, A&A 344, 282). Once a model is entirely set up, you can ask radmc3d to do the Monte Carlo run for you by typing in a shell:

radmc3d mctherm

if you use the standard radmc3d code, or

./radmc3d mctherm

if you have created a local version of radmc3d (see Section 4.7).

What the method does is the following: First all the netto sources of energy (or more accurately: sources of luminosity) are identified. The following net sources of energy can be included:

• Stars: You can specify any number of individual stars: their position, and their spectrum and luminosity (See Section A.7). This is the most commonly used source of luminosity, and as a beginning user we recommend to use only this for now.

- Continuum stellar source: For simulations of galaxies it would require by far too many individual stars to properly include the input of stellar light from the billions of stars in the galaxy. To overcome this problem you can specify a continuously spatially distributed source of stars. NOTE: Still in testing phase.
- Viscous heating / internal heating: Sometimes the dust grains acquire energy directly from the gas, for instance through viscous heating of the gas or adiabatic compression of the gas. This can be included as a spatially distributed source of energy. NOTE: Still in progress... Not yet working.

To compute the dust temperature we must have at least one source of luminosity, otherwise the equilibrium dust temperature would be everywhere 0.

The next step is that this total luminosity is divided into nphot packages, where nphot is 100000 by default, but can be set to any value by the user (see the file radmc3d.inp described in Section A.1). Then these photon packages are emitted by these sources one-by-one. As they move through the grid they may scatter off dust grains and thus change their direction. They may also get absorbed by the dust. If that happens, the photon package is immediately re-emitted in another direction and with another wavelength. The wavelength is chosen according to the recipe by Bjorkman & Wood (2001, ApJ 554, 615). The luminosity fraction that each photon package represents remains, however, the same. Each time a photon package enters a cell it increases the "energy" of this cell and thus increases the temperature of the dust of this cell. The recipe for this is again described by Bjorkman & Wood (2001, ApJ 554, 615), but contrary to that paper we increase the temperature of the dust always when a photon package enters a cell, while Bjorkman & Wood only increase the dust temperature if a discrete absorption event has taken place. Each photon package will ping-pong through the model and never gets lost until it escapes the model through the outer edge of the grid (which, for cartesianl coordinates, is any of the grid edges in x, y or z, and for spherical coordinates is the outer edge of r). Once it escapes, a new photon package is launched, until also it escapes. After all photon packages have been launched and escaped, the dust temperature that remains is the final answer of the dust temperature.

One must keep in mind that the temperature thus computed is an *equilibrium* dust temperature. It assumes that each dust grain acquires as much energy as it radiates away. This is for most cases presumably a very good approximation, because the heating/cooling time scales for dust grains are typically very short compared to any time-dependent dynamics of the system. But there might be situations where this may not be true: in case of rapid compression of gas, near shock waves or in extremely optically thick regions.

NOTE: Monte Carlo simulations are based on pseudo-random numbers. The seed for the random number generator is by default set to -17933201. If you want to perform multiple identical simulations with a different random sequence you will need to set the seed by hand. This can be done by adding a line

iseed = -5415

(where -5415 is to be replaced by the value you want) to the radmc3d.inp file.

6.1.1 Modified Random Walk method for high optical depths

As you will soon find out: very optically thick models make the RADMC-3D thermal Monte Carlo simulations to be slow. This is because in the thermal Monte Carlo method a photon package is never destroyed unless it leaves the system. A photon package can thus "get lost" deep inside an optically thick region, making millions (or even billions) of absorption+reemission or scattering events. Furthermore, you will notice that in order to get the temperatures in these very optically thick regions to be reliable (i.e. not too noisy) you may need a very large number of photon packages for your simulation, which slows down the simulation even more. It is hard to prevent such problems. Min, Dullemond, Dominik, de Koter & Hovenier (2009) A&A 497, 155 discuss two methods of dealing with this problem. One is a diffusion method, which we will not discuss here. The other is the "Modified Random Walk" (MRW) method, based on the method by Fleck & Canfield (1984) J.Comput.Phys. 54, 508. Note that Robitaille (2010) A&A 520, 70 presented a simplification of this method. Min et al. first implemented this method into the MCMax code. Now, as of v.0.35, it is also implemented in RADMC-3D, in Robitaille's simplified form.

The crucial idea of the method is that if a photon package "gets lost" deep inside a single ultra-optically-thick cell, we can use the analytical solutions of the diffusion equation in a constant-density medium to predict where the

photon package will go next. This thus allows RADMC-3D to make a single large step of the photon package which actually corresponds to hundreds or thousands of absorption+reemission or scattering events.

The method works best if the optically thick cells are as large as possible. This is because the analytical solutions are only valid within a single cell, and thus the "large step" can not be larger than a single cell size. Moreover, cell crossings will reduce the step length again to the physical mean free path, so the more cell crossings are made, the less effective the MRW becomes.

NOTE: The MRW is by default switched off. The reason is that it is, after all, an approximation. However, if RADMC-3D thinks that the MRW may help speed up the thermal Monte Carlo, it will make the suggestion to the user to switch on the MRW method.

You can switch on the MRW by adding the following line to the radmc3d.inp file:

```
modified_random_walk = 1
```

NOTE: This mode has only been added in version 0.34, so for now stay vigilant when using it.

6.2 Making SEDs, spectra, images for dust continuum

You can use RADMC-3D for computing spectra and images in dust continuum emission. This is described in detail in Chapter 9. RADMC-3D needs to know not only the dust spatial distribution, given in the file dust_density.inp, but also the dust temperature, given in the file dust_temperature.dat (see Chapter B for the binary version of these files, which are more compact, and which you can use instead of the ascii versions). The dust_temperature.dat is normally computed by RADMC-3D itself through the thermal Monte Carlo computation (see Section 6.1). But if you, the user, wants to specify the dust temperature at each location in the model youself, then you can simply create your own file dust_temperature.dat and skip the thermal Monte Carlo simulation and go straight to the creation of images or spectra.

The basic command to make a spectrum at the global grid of wavelength (specified in the file wavelength_micron.inp, see Section A.12) is:

```
radmc3d sed
```

You can specify the direction of the observer with incl and phi:

```
radmc3d sed incl 20 phi 80
```

which means: put the observer at inclination 20 degrees and ϕ -angle 80 degrees.

You can also make a spectrum for a given grid of wavelength (independent of the global wavelength grid). You first create a file camera_wavelength_micron.inp, which has the same format as wavelength_micron.inp. You can put any set of wavelengths in this file without modifying the global wavelength grid (which is used by the thermal Monte Carlo computation). Then you type

```
radmc3d spectrum loadlambda
```

and it will create the spectrum on this wavelength grid. More information about making spectra is given in Chapter

For creating an image you can type

```
radmc3d image lambda 10
```

which creates an image at wavelength $\lambda=10\mu m$. More information about making images is given in Chapter 9.

Important note: To handle scattering of light off dust grains, the ray-tracing is preceded by a quick Monte Carlo run that is specially designed to compute the "scattering source function". This Monte Carlo run is usually *much* faster than the thermal Monte Carlo run, but must be done at each wavelength. It can lead, however, to slight spectral noise, because the random photon paths are different for each wavelength. See Section 6.6 for details.

6.3 OpenMP parallelized Monte Carlo

Depending on the model properties and the number of photon packages used in the simulation the Monte Carlo calculation (in particular the thermal Monte Carlo, but under some conditions also the scattering Monte Carlo) can be a time-consuming computation when executed only in a serial mode. To improve this, these Monte Carlo calculations can be done in OpenMP parallel mode. The loop over photon packages is then distributed amongst the different threads, where each thread adopts a specific number of loop iterations following the order of the thread identification number. To this end the random number generator was modified. The important point for the parallel version is that different threads must not share the same random seed initially. To be certain that each thread is assigned a different seed at the beginning, the thread identity number is added to the initial seed.

The default value for the number of threads in the parallel version is set to one, so that the program is identical with the serial version, except for the random generator's initial seed. The user can change the value by either typing 'setthreads and a number of threads (integer value) in the command line or by adding a corresponding line to the radmc3d.inp file. If the chosen number of threads is larger than the available number of processor cores, the user is asked to reduce it.

For example, you can ask radmc3d to do the parallelized Monte Carlo run for you by typing in a shell:

```
radmc3d mctherm setthreads 4
```

or by adding the following keyword to the radmc3d.inp file:

```
setthreads = 4
```

which means that four threads are used for the thermal Monte Carlo computation.

For the image or spectrum you can do the same: just add setthreads 4 or so on the command line or put setthreads = 4 into the radmc3d.inp file.

Make sure that you have included the -fopenmp keyword in the Makefile and have compiled the whole radmc3d source code with this additional command before using the OpenMP parallelized thermal Monte Carlo version (cf. Sect. 4.1).

6.4 Overview of input data for dust radiative transfer

In order to perform any of the actions described in Sections 6.1, 6.5 or 6.2, you must give RADMC-3D the following data:

- amr_grid.inp: The grid file (see Section A.2).
- wavelength_micron.inp: The global wavelength file (see Section A.12).
- stars.inp: The locations and properties of stars (see Section A.7).
- dust_density.inp: The spatial distribution of dust on the grid (see Section A.3).
- dustopac.inp: A file with overall information about the various species of dust in the model (see Section A.14). One of the main pieces of information here is (a) how many dust species are included in the model and (b) the tag names of these dust species (see dustkappa_XXX.inp below). The file dust_density.inp must contain exactly this number of density distributions: one density distribution for each dust species.
- dustkappa_XXX.inp: One or more dust opacity files (where XXX should in fact be a tag name you define, for instance dustkappa_silicate.inp). The labels are listed in the dustopac.inp file. ee Section A.14 for more information.
- camera_wavelength_micron.inp (optional): This file is only needed if you want to create a spectrum at a special set of wavelengths (otherwise use radmc3d sed).

• mcmono_wavelength_micron.inp (optional): This file is only needed if you want to compute the radiation field inside the model by calling radmc3d mcmono (e.g. for photochemistry).

Other input files could be required in certain cases, but you will then be asked about it by RADMC-3D.

6.5 Special-purpose feature: Computing the local radiation field

If you wish to use RADMC-3D for computing the radiation field *inside* the model, for instance for computing photochemical rates in a chemical model, then RADMC-3D can do so by calling RADMC-3D in the following way:

radmc3d mcmono

This computes the mean intensity

$$J_{\nu} = \frac{1}{4\pi} \oint I_{\nu}(\Omega) d\Omega \tag{6.1}$$

(in units of erg s⁻¹ cm⁻² Hz⁻¹ ster⁻¹) as a function of the (x,y,z) (cartesian) or (r,θ,ϕ) (spherical) coordinates at frequencies $\nu_i \equiv 10^4 c/\lambda_i$ where λ_i are the wavelengths (in μ m) specified in the file mcmono_wavelength_micron.inp (same format as the file wavelength_micron.inp which is described in Section A.12). The results of this computation can be interesting for, for instance, models of photochemistry.

The file that is produced by radmc3d mcmono is called mean_intensity.out and has the following form:

```
<=== Typically 2 at present
iformat
nrcells
                                         <=== Nr of frequencies
nfreq
freq_1 freq_2 ... freq_nfreq
                                         <=== List of frequencies in Hz
meanint[1,icell=1]
meanint[1,icell=2]
meanint[1,icell=nrcells]
meanint[2,icell=1]
meanint[2,icell=2]
meanint[2,icell=nrcells]
meanint[nfreq,icell=1]
meanint[nfreq,icell=2]
meanint[nfreq,icell=nrcells]
```

The list of frequencies will, in fact, be the same as those listed in the file mcmono_wavelength_micron.inp.

Note that if your model is very large, the computation of the radiation field on a large set of wavelength could easily overload the memory of the computer. However, often you are in the end not interested in the entire spectrum at each location, but just in integrals of this spectrum over some cross section. For instance, if you want to compute the degree to which dust shields molecular photodissociation lines in the UV, then you only need to compute the total photodissociation rate, which is an integral of the photodissociation cross section times the radiation field. In Section 13.4 it will be explained how you can create a userdef subroutine (see Chapter 13) that will do this for you in a memory-saving way.

There is an important parameter for this Monochromatic Monte Carlo that you may wish to play with:

• nphot_mono

The parameter nphot_mono sets the number of photon packages that are used for the Monochromatic Monte Carlo simulation. It has as default 100000, but that may be too little for 3-D models. You can set this value in two ways:

- In the radmc3d.inp file as a line nphot_mono = 1000000 for instance.
- On the command-line by adding nphot_mono 1000000.

6.6 More about scattering of photons off dust grains

Photons can not only be absorbed and re-emitted by dust grains: They can also be scattered. Scattering does nothing else than change the direction of propagation of a photon, and in case polarization is included, its Stokes parameters. Strictly speaking it may also slightly change its wavelength, if the dust grains move with considerable speed they may Doppler-shift the wavelength of the outgoing photon (which may be relevant, if at all, when dust radiative transfer is combined with line radiative transfer, see chapter 7), but this subtle effect is not treated in RADMC-3D. For RADMC-3D scattering is just the changing of direction of a photon.

6.6.1 Five modes of treating scattering

RADMC-3D has five levels of realism of treatment of scattering, starting with scattering_mode=1 (simplest) to scattering_mode=5 (most realistic):

- 1. No scattering (scattering_mode=0):

 If either the dustkappa_XXX.inp files do not contain a scattering opacity or scattering is switched off by setting scattering_mode_max to 0 in the radmc3d.inp file, then scattering is ignored. It is then assumed that the dust grains have zero albedo.
- 2. Isotropic scattering (scattering_mode=1):

 If either the dustkappa_XXX.inp files do not contain information about the anisotropy of the scattering or anisotropic scattering is switched off by setting scattering_mode_max to 1 in the radmc3d.inp file, then scattering is treated as isotropic scattering. Note that this can be a bad approximation.
- 3. Anisotropic scattering using Henyey-Greenstein (scattering_mode=2): If the dustkappa_XXX.inp files contain the scattering opacity and the g parameter of anisotropy (the Henyey-Greenstein g parameter which is equal, by definition, to $g = \langle \cos \theta \rangle$, where θ is the scattering deflection angle), and scattering_mode_max is set to 2 or higher in the radmc3d.inp file then anisotropic scattering is treated using the Henyey-Greenstein approximate formula.
- 4. Anisotropic scattering using tabulated phase function (scattering_mode=3):

 To treat scattering using a tabulated phase function, you must specify the dust opacities using dustkapscatmat_XXX.inp files instead of the simpler dustkappa_XXX.inp files (see Section A.14.3). You must also set scattering_mode_max is set to 3 or higher.
- 5. Anisotropic scattering with polarization for last scattering (scattering mode=4):

 To treat scattering off randomly oriented particles with the full polarization you need to set scattering mode_max is set to 4 or higher, and you must specify the full dust opacity and scattering matrix using the dustkapscatmat_XXX.inp files instead of the simpler dustkappa_XXX.inp files (see Section A.14.3). If scattering_mode=4 the full polarization is only done upon the last scattering before light reaches the observer (i.e. it is only treated in the computation of the scattering source function that is used for the images, but it is not used for the movement of the photons in the Monte Carlo simulation). See Section 6.7 for more information about polarized scattering.
- 6. Anisotropic scattering with polarization, full treatment (scattering_mode=5):

 For the full treatment of polarized scattering off randomly oriented particles, you need to set scattering_mode_max is set to 5, and you must specify the full dust opacity and scattering matrix using the dustkapscatmat_XXX.inp files instead of the simpler dustkappa_XXX.inp files (see Section A.14.3). See Section 6.7 for more information about polarized scattering.

Please refer to Sections 6.6.2 and 6.7 for more information about these different scattering modes.

So in summary: the dust opacity files themselves tell how detailed the scattering is going to be included. If no scattering information is present in these files, RADMC-3D has no choice but to ignore scattering. If they only contain scattering opacities but no phase information (no *g*-factor), then RADMC-3D will treat scattering in the isotropic approximation. If the *g*-factor is also included, then RADMC-3D will use the Henyey-Greenstein formula for anisotropic scattering. If you specify the full scattering matrix (using the dustkapscatmat_xxx.inp files instead of the dustkappa_xxx.inp files) then you can use tabulated scattering phase functions, and even polarized scattering.

If scattering_mode_max is not set in the radmc3d.inp file, it is by default 9999, meaning: RADMC-3D will always use the maximally realistic scattering mode that the dust opacities allow.

BUT you can always limit the realism of scattering by setting the scattering mode max to 4, 3, 3, 1 or 0 in the file radmc3d.inp. This can be useful to speed up the calculations or be sure to avoid certain complexities of the full phase-function treatment of scattering.

At the moment there are some limitations to the full anisotropic scattering treatment:

- *Anisotropic scattering in 1-D and 2-D Spherical coordinates:* For 1-D and 2-D Spherical coordinates there is currently no possibility of treating anisotropic scattering in the image- and spectrum-making. The reason is that the scattering source function (see Section 6.6.5) must be stored in an angle-dependent way. However, in 2-D spherical coordinates, each cell is in fact a ring around the symmetry axis, and the angular dependence of the scattering source function would depend on which position along the ring the scattering takes place (with respect to the location of the observer). This will be fixed hopefully later by storing the scattering source function for different angles in each cell; stay tuned!
- Full phase functions and polarization only for randomly-oriented particles: Currently RADMC-3D cannot handle scattering off fixed-oriented non-spherical particles, because it requires a much more detailed handling of the angles. It would require at least 3 scattering angles (for axiallysymmetric particles) or more (for completely asymmetric particles), which is currently beyond the scope of RADMC-3D.

Scattering phase functions

As mentioned above, for the different scattering mode settings you have different levels of realism of treating scattering.

The transfer equation along each ray, ignoring polarization for now, is:

$$\frac{dI_{\nu}}{ds} = j_{\nu}^{\text{therm}} + j_{\nu}^{\text{scat}} - (\alpha_{\nu}^{\text{abs}} + \alpha_{\nu}^{\text{scat}})I_{\nu}$$
(6.2)

where $\alpha_{\nu}^{\rm abs}$ and $\alpha_{\nu}^{\rm scat}$ are the extinction coefficients for absorption and scattering. Let us assume, for convenience of notation, that we have just one dust species with density distribution ρ , absorption opacity $\kappa_{\nu}^{\rm abs}$ and scattering opacity $\kappa_{\nu}^{\rm scat}$. We then have

$$\alpha_{\nu}^{\text{abs}} \equiv \rho \kappa_{\nu}^{\text{abs}}$$

$$\alpha_{\nu}^{\text{scat}} \equiv \rho \kappa_{\nu}^{\text{scat}}$$

$$j_{\nu}^{\text{therm}} = \alpha_{\nu}^{\text{abs}} B_{\nu}(T)$$
(6.3)
(6.4)

$$\alpha_{\nu}^{\text{scat}} \equiv \rho \kappa_{\nu}^{\text{scat}}$$
 (6.4)

$$j_{\nu}^{\text{therm}} = \alpha_{\nu}^{\text{abs}} B_{\nu}(T) \tag{6.5}$$

where $B_{\nu}(T)$ is the Planck function. The last equation is an expression of Kirchhoff's law.

For *isotropic* scattering (scattering_mode=1) the scattering source function $j_{\nu}^{\rm scat}$ is given by

$$j_{\nu}^{\text{scat}} = \alpha_{\nu}^{\text{scat}} \frac{1}{4\pi} \oint I_{\nu} d\Omega \tag{6.6}$$

where the integral is the integral over solid angle. In this case $j_{\nu}^{\rm scat}$ does not depend on solid angle.

For anisotropic scattering (scattering_mode \geq 2) we must introduce the scattering phase function $\Phi(\mathbf{n}_{in}, \mathbf{n}_{out})$, where \mathbf{n}_{in} is the unit direction vector for incoming radiation and $\mathbf{n}_{\mathrm{out}}$ is the unit direction vector for the scattered radiation. The scattering phase function is normalized to unity:

$$\frac{1}{4\pi} \oint \Phi(\mathbf{n}_{\rm in}, \mathbf{n}_{\rm out}) d\Omega_{\rm out} = \frac{1}{4\pi} \oint \Phi(\mathbf{n}_{\rm in}, \mathbf{n}_{\rm out}) d\Omega_{\rm in} = 1$$
 (6.7)

where we integrated over all possible n_{out} or n_{in} . Then the scattering source function becomes:

$$j_{\nu}^{\text{scat}}(\mathbf{n}_{\text{out}}) = \alpha_{\nu}^{\text{scat}} \frac{1}{4\pi} \oint I_{\nu}(\mathbf{n}_{\text{in}}) \Phi(\mathbf{n}_{\text{in}}, \mathbf{n}_{\text{out}}) d\Omega_{\text{in}}$$
(6.8)

which is angle-dependent. The angular dependence means: a photon package has not completely forgotten from which direction it came before hitting the dust grain.

If we do not include the polarization of radiation and we have randomly oriented particles, then the scattering phase function will only depend on the scattering (deflection) angle θ defined by

$$\cos \theta \equiv \mu = \mathbf{n}_{\text{out}} \cdot \mathbf{n}_{\text{in}} \tag{6.9}$$

We will thus be able to write

$$\Phi(\mathbf{n}_{\rm in}, \mathbf{n}_{\rm out}) \equiv \Phi(\mu) \tag{6.10}$$

where $\Phi(\mu)$ is normalized as

$$\frac{1}{2} \int_{-1}^{+1} \Phi(\mu) d\mu = 1 \tag{6.11}$$

If we have scattering_mode=2 then the phase function is the Henyey-Greenstein phase function defined as

$$\Phi(\mu) = \frac{1 - g^2}{(1 + g^2 - 2g\mu)^{3/2}} \tag{6.12}$$

where the value of the anisotropy parameter g is taken from the dust opacity file. Note that for g=0 you get $\Phi(\mu)=1$ which is the phase function for isotropic scattering.

If we have scattering_mode=3 then the phase function is tabulated by you. You have to provide the tabulated phase function as the $Z_{11}(\theta)$ scattering matrix element for a tabulated set of θ_i values, and this is done in a file dustkapscatmat_xxx.inp (see Section A.14.3 and note that for scattering_mode=3 the other Z_{ij} elements can be kept 0 as they are of no consequence). The relation between $Z_{11}(\theta)$ and $\Phi(\mu)$ is:

$$\Phi(\mu) \equiv \Phi(\cos(\theta)) = \frac{4\pi}{\kappa_{\text{scat}}} Z_{11}(\theta)$$
(6.13)

(which holds at each wavelength individually).

If we have scattering_mode=4 then the scattering in the Monte Carlo code is done according to the tabulated $\Phi(\mu)$ mode mentioned above, but for computing the scattering source function the full polarized scattering matrix is used. See Section 6.7.

If we have scattering_mode=5 then the scattering phase function is not only dependent on μ but also on the other angle. And it depends on the polarization state of the input radiation. See Section 6.7.

6.6.3 Scattering of photons in the Thermal Monte Carlo run

So how is scattering treated in practice? In the thermal Monte Carlo model (Section 6.1) the scattering has only one effect: it changes the direction of propagation of the photon packages whenever such a photon package experiences a scattering event. This may change the results for the dust temperatures subtly. In special cases it may even change the dust temperatures more strongly, for instance if scattering allows "hot" photons to reach regions that would have otherwise been in the shadow. It may also increase the optical depth of an object and thus change the temperatures accordingly. But this is all there is to it.

If you include the full treatment of polarized scattering (scattering_mode=5), then a photon package also gets polarized when it undergoes a scattering event. This can affect the phase function for the next scattering event. This means that the inclusion of the full polarized scattering processes (as opposed to using non-polarized photon packages) can, at least in principle, have an effect on the dust temperatures that result from the thermal Monte Carlo computation. This effect is, however, rather small in practice.

6.6.4 Scattering of photons in the Monochromatic Monte Carlo run

For the monochromatic Monte Carlo calculation for computing the mean intensity radiation field (Section 6.5) the scattering has the same effect as for the thermal Monte Carlo model: it changes the direction of photon packages. In this way "hot" radiation may enter regions which would otherwise have been in a shadow. And by increasing the

optical depth of regions, it may increase the local radiation field by the greenhouse effect or decrease it by preventing photons from entering it. As in the thermal Monte Carlo model the effect of scattering in the monochromatic Monte Carlo model is simply to change the direction of motion of the radiation field, but for the rest nothing differs to the case without scattering. Also here the small effects caused by polarized scattering apply, like in the thermal Monte Carlo case.

6.6.5 Scattered light in images and spectra: The "Scattering Monte Carlo" computation

For making images and spectra with the ray-tracing capabilities of RADMC-3D (see Section 6.2 and Chapter 9) the role of scattering is a much more complex one than in the thermal and monochromatic Monte Carlo runs. The reason is that the scattered radiation will eventually end up on your images and spectra.

If we want to make an image or a spectrum, then for each pixel we must integrate Eq. (6.2) along the 1-D ray belonging to that pixel. If we performed the thermal Monte Carlo simulation beforehand (or if we specified the dust temperatures by hand) we know the thermal source function through Eq. (6.5). But we have, at that point, no information yet about the scattering source function. The thermal Monte Carlo calculation *could* have also stored this function at each spatial point and each wavelength and each observer direction, but that would require gigantic amounts of memory (for a typical 3-D model it might be many Gbytes, going into the Tbyte regime). So in RADMC-3D the scattering source function is *not* computed during the thermal Monte Carlo run.

In RADMC-3D the scattering source function $j_{\nu}^{\rm scat}(\Omega')$ is computed *just prior to* the ray-tracing through a brief "Scattering Monte Carlo" run. This is done *automatically* by RADMC-3D, so you don't have to worry about this. Whenever you ask RADMC-3D to make an image (and if the scattering is in fact included in the model, see Section 6.6.1), RADMC-3D will automatically realize that it requires knowledge of $j_{\nu}^{\rm scat}(\Omega')$, and it will start a brief single-wavelength Monte Carlo simulation for computing $j_{\nu}^{\rm scat}(\Omega')$. This single-wavelength "Scattering Monte Carlo" simulation is relatively fast compared to the thermal Monte Carlo simulation, because photon packages can be destroyed by absorption. So photon packages do not bounce around for long, as they do in the thermal Monte Carlo simulation. This Scattering Monte Carlo simulation is in fact very similar to the monochromatic Monte Carlo model described in Section 6.5. While the monochromatic Monte Carlo model is called specifically by the user (by calling RADMC-3D with radmc3d mcmono), the Scattering Monte Carlo simulation is not something the user must specify him/her-self: it is automatically done by RADMC-3D if it is needed (which is typically before making an image or during the making of a spectrum). And while the monochromatic Monte Carlo model returns the mean intensity inside the model, the Scattering Monte Carlo simulation provides the raytracing routines with the scattering source function but does *not* store this function in a file.

You can see this happen if you have a model with scattering opacity included, and you make an image with RADMC-3D, you see that it prints 1000, 2000, 3000, ... etc., in other words, it performs a little Monte Carlo simulation before making the image.

There is an important parameter for this Scattering Monte Carlo that you may wish to play with:

• nphot_scat

The parameter nphot_scat sets the number of photon packages that are used for the Scattering Monte Carlo simulation. It has as default 100000, but that may be too little for 3-D models and/or cases where you wish to reduce the "streaky" features sometimes visible in scattered-light images when too few photon packages are used. You can set this value in two ways:

- In the radmc3d.inp file as a line nphot_scat = 1000000 for instance.
- On the command-line by adding nphot_scat 1000000.

In Figure 6.1 you can see how the quality of an image in scattered light improves when increasing nphot_scat.

• nphot_spec

The parameter nphot_spec is actually exactly the same as nphot_scat, but is used (and used only!) for the creation of spectra. The default is 10000, i.e. substantially smaller than nphot_scat. The reason for this separate parameter is that if you make spectra, you integrate over the image to obtain the flux (i.e. the value of the spectrum at that wavelength). Even if the scattered light image may look streaky, the integral may still be accurate. We can thus afford much fewer photon packages when we make spectra than when we make images, and can thus speed up the calculation of the spectrum. You can set this value in two ways:




Figure 6.1. The effect of nphot_scat on the image quality when the image is dominated by scattered light. The images show the result of model examples/run_simple_2_scatmat at $\lambda=0.84\mu\mathrm{m}$ in which polarized scattering with the full scattering phase function and scattering matrix is used. The images were made with the viewimage.pro GUI interface, in which (as of version 0.35 of RADMC-3D) you can set the value of nphot_scat. See Section 6.7 about the scattering matrices for polarized scattering. See Section 6.6.6 for a discussion about the "scratches" seen in the top two panels.

- In the radmc3d.inp file as a line nphot_spec = 100000 for instance.
- On the command-line by adding nphot_spec 100000.

NOTE: It may be possible to get still very good results with even smaller values of nphot_spec than the default value of 10000. That might speed up the calculation of the spectrum even more in some cases. On the other hand, if you notice "noise" on your spectrum, you may want to increase nphot_spec. If you are interested in an optimal balance between accuracy (high value of nphot_spec) and speed of calculation (low value of nphot_spec) then it is recommended to experiment with this value. If you want to be on the safe side, then set nphot_spec to a high value (i.e. set it to 100000, as nphot_spec).

WARNING: At wavelengths where the dominant source of photons is thermal dust emission but scattering is still important (high albedo), it cannot be excluded that the "scattering monte carlo" method used by RADMC-3D produces very large noise. Example: a very optically thick dust disk consisting of large grains (10 μ m size), producing thermal dust emission in the near infrared in its inner disk regions. This thermal radiation can scatter off the large dust grains at large radii (where the disk is cold and where the only "emission" in the near-infrared is thus the scattered light) and thus reveal the outer disk in scattered light emerging from the inner disk. However, unless nphot_scat is huge, most thermally emitted photons from the inner disk will be emitted so deeply in the disk interior (i.e. below the surface) that they will be immediately reabsorbed and lost. This means that that radiation that does escape is extremely noisy. The corresponding scattered light source function at large radii is therefore very noisy as well, unless nphot_scat is taken to be huge. Currently no elegant solution is found, but maybe there will in the near future. Stay tuned...

NOTE: Monte Carlo simulations are based on pseudo-random numbers. The seed for the random number generator is by default set to -17933201. If you want to perform multiple identical simulations with a different random sequence you will need to set the seed by hand. This can be done by adding a line

iseed = -5415

(where -5415 is to be replaced by the value you want) to the radmc3d.inp file.

6.6.6 Single-scattering vs. multiple-scattering

If scattering is included in the images and spectra, the Monte Carlo run computes the full multiple-scattering problem. Photon packages are followed as they scatter and change their direction (possibly many times) until they escape to infinity or until they are extincted by many orders of magnitude (the exact extinction limit can be set by mc_scat_maxtauabs, which by default is set to 30, meaning a photon package is considered extincted when it has travelled an absorption optical depth of 30).

Important note: In many (most?) cases this default value of mc_scat_maxtauabs=30 is overly conservative. Especially when the scattering Monte Carlo is very time-consuming, you may want to experiment with a lower value. Try adding a line to the radmc3d.inp with:

```
mc_scat_maxtauabs = 5
```

This may speed up the scattering Monte Carlo by up to a factor of 6, while still yielding reasonable results.

It can be useful to figure out how important the effect of multiple scattering in an image is compared to single scattering. For instance: a protoplanetary disk with a "self-shadowed" geometry will show some scattering even in the shadowed region because some photon packages scatter *into* the shadowed region and then scatter into the line of sight. To figure out if this is indeed what happens, you can make two images: one normal image with

```
radmc3d image lambda 1.0
cp image.out image_fullscat.out
```

and then another image which only treats single scattering:

```
radmc3d image lambda 1.0 maxnrscat 1
cp image.out image_singlescat.out
```

The command-line option maxnrscat 1 tells RADMC-3D to stop following photon packages once they hit their first discrete scattering event. You can also check out the effect of single- and double-scattering (but excluding triple and higher order scattering) with: maxnrscat 2, etc.

Note that multiple scattering may require a very high number of photon packages (i.e. setting nphot_scat to a very high number). For single scattering with too low nphot_scat you typically see radial "rays" in the image emanating from each stellar source of photons. For multiple scattering, when taking too low nphot_scat small you would see strange non-radial "scratches" in the image (see Fig. 6.1, top two images). It looks as if someone has used a pen and randomly added some streaks. These streaks are the double-scattering events which, in that case, apparently are rare enough that they show up as individual streaks. To test whether these streaks are indeed such double scattering events, you can use maxnrscat 1, and they should disappear. If the streaks are indeed very few, it may turn out that the single-scattering image (maxnrscat 1) is almost already the correct image. The double scattering is then only a minor addition to the image, but due to the finite Monte Carlo noise it would yield annoying streaks which ruin a nice image. If you are very sure that the second scattering and higher-order scattering are only a very minor effect, then you might use the maxnrscat 1 image as the final image. By comparing the flux in the images with full scattering and single scattering you can estimate how important the multiple-scattering contribution is compared to single scattering. But of course, it is always safer to simply increase nphot_scat and patiently wait until the Monte Carlo run is finished.

6.6.7 Warning when using an-isotropic scattering

An important issue with anisotropic scattering is that if the phase function is very forward-peaked, then you may get problems with the *spatial* resolution of your model: it could then happen that one grid cell may be too much to the left to "beam" the scattered light into your line of sight, while the next grid point will be too much to the right. A proper treatment of strongly anisotropic scattering therefore requires also a good check of the spatial resolution of your model. There are, however, also two possible tricks (approximations) to prevent problems. They both involve slight modifications of the dust opacity files:

1. You can simply assure in the opacity files that the forward peaking of the phase function has some upper limit.

2. Or you can simply treat extremely forward-peaked scattering as no scattering at all (simply setting the scattering opacity to zero at those wavelengths).

Both "tricks" are presumably reasonable and will not affect your results, unless you concentrate in your modeling very much on the angular dependence of the scattering.

6.6.8 For experts: Some more background on scattering

The inclusion of the scattering source function in the images and spectra is a non-trivial task for RADMC-3D because of memory constraints. If we would have infinite random access memory, then the inclusion of scattering in the images and spectra would be relatively easy, as we could then store the entire scattering source function $j^{\rm scat}(x,y,z,\nu,\Omega)$ and use what we need at any time. But as you see, this function is a 6-dimensional function: three spatial dimensions, one frequency and one angular direction (which consists of two angles). For any respectable model this function is far too large to be stored. So nearly all the "numerical logistic" complexity of the treatment of scattering comes from various ways to deal with this problem. In principle RADMC-3D makes the choices of which method to use itself, so the user is not bothered with it. But depending on which kind of model the user sets up, the performance of RADMC-3D may change as a result of this issue.

So here are a few hints as to the internal workings of RADMC-3D in this regard. You do not have to read this, but it may help understanding the performance of RADMC-3D in various cases.

- Scattering in spectra and multi-wavelength images

 If no scattering is present in the model (see Section 6.6.1), then RADMC-3D can save time when making spectra and/or multi-wavelength images. I will then do each integration of Eq. (6.2) directly for all wavelengths at once before going to the next pixel. This saves some time because RADMC-3D then has to calculate the geometric stuff (how the ray moves through the model) just once for each ray. If, however, scattering is included, the scattering source function must be computed using the Scattering Monte Carlo computation. Since for large models it would be too memory consuming (in particular for 3-D models) to store this function for all positions and all wavelengths, it must do this calculation one-by-one for each wavelength, and calculate the image for that wavelength, and then go off to the next wavelength. This means that for each ray (pixel) the geometric computations (where the ray moves through the model) has to be redone for each new wavelength. This may slow down the code a bit.
- Anisotropic scattering and multi-viewpoint images
 Suppose we wish to look at an object at one single wavelength, but from a number of different vantage points. If we have isotropic scattering, then we need to do the Scattering Monte Carlo calculation just once, and we can make multiple images at different vantage points with the same scattering source function. This saves time, if you use the "movie" mode of RADMC-3D (Section 9.12). However, if the scattering is anisotropic, then the source function would differ for each vantage point. In that case the scattering source function must be recalculated for each vantage point. There is, deeply hidden in RADMC-3D, a way to compute scattering source functions for multiple vantage points within a single Scattering Monte Carlo run, but for the moment this is not yet activated.

6.7 Polarization, Stokes vectors and full phase-functions

As of version 0.35 RADMC-3D can deal with polarization of continuum radiation. The module in RADMC-3D that deals with polarization (polarization_module.f90) is based on code developed by Michiel Min for his MCMAX code, and has been used and modified for use in RADMC-3D with his permission.

Radiative transfer of polarized radiation is a relatively complex issue. A good and extensive review on the details of polarization is given in the book by Mishchenko, Travis & Lacis, "Scattering, Absorption and Emission of Light by Small Particles", 2002, Cambridge University Press (also electronically available on-line). Another good book (and a classic!) is the book by Bohren & Huffman "Absorption and scattering of light by small particles", Wiley-VCH. Finally, the ultimate classic is the book by van de Hulst "Light scattering by small particles", 1981. For some discussions on how polarization can be built in into radiative transfer codes, see e.g. Wolf, Voshchinnikov & Henning (2002, A&A 385, 365).

When we wish to include polarization in our model we must follow not just the intensity I of light (or equivalently, the energy E of a photon package), but the full Stokes vector (I,Q,U,V) (see review above for definitions, or any textbook on radiation processes). If a photon scatters off a dust grain, then the scattering angular probability density function depends not only on the scattering angle μ , but also on the input state of polarization, i.e. the values of (I,Q,U,V). And the output polarization state will be modified. Moreover, even if we would not be interested in polarization at all, but we do want to have a correct scattering phase function, we need to treat polarization, because a first scattering will polarize the photon, which will then have different angular scattering probability in the next scattering event. Normally these effects are very small, so if we are not particularly interested in polarization, one can usually ignore this effect without too high a penalty in reliability. But if one wants to be accurate, there is no way around a full treatment of the (I,Q,U,V).

Interaction between polarized radiation with matter happens through so-called Müller matrices, which are 4×4 matrices that can be multiplied by the (I,Q,U,V) vector. More on this later.

It is important to distinguish between two situations:

- 1. The simplest case (and fortunately applicable in many cases) is if all dust particles are **randomly oriented**, and there is **no preferential helicity** of the dust grains (i.e. for each particle shape there are equal numbers of particles with that shape and with its mirror copy shape). This is also automatically true if all grains are spherically symmetric. In this case the problem of polarized radiative transfer simplifies in several ways:
 - The scattering Müller matrix simplifies, and contains only 6 independent matrix elements (see later). Moreover, these matrix elements depend only on a single angle: the scattering angle θ , and of course on the wavelength. This means that the amount of information is small enough that these Müller matrix elements can be stored in computer memory in tabulated form, so that they do not have to be calculated real-time.
 - The total scattering cross section is independent of the input polarization state. Only the output radiation (i.e. in which direction the photon will scatter) depends on the input polarization state.
 - The absorption cross section is the same for all components of the (I,Q,U,V)-vector. In other words: the absorption Müller matrix is the usual scalar absorption coefficient times the unit matrix.

The last two points assure that most of the structure of the RADMC-3D code for non-polarized radiation can remain untouched. Only for computing the new direction and polarization state of a photon after a scattering event in the Monte Carlo module, as well as for computing the scattering source function in the Monte Carlo module (for use in the camera module) we must do extra work. Thermal emission and thermal absorption remain the same, and computing optical depths remains also the same.

- 2. A (much!) more complex situation arises if dust grains are **non-spherical** and are somehow **aligned due to external forces**. For instance, particles tend to align themselves in the interstellar medium if strong enough magnetic fields are present. Or particles tend to align themselves due to the combination of gravity and friction if they are in a planetary/stellar atmosphere. Here are the ways in which things become more complex:
 - All the scattering Müller matrix components will become non-zero and independent. We will thus get 16 independent variables.
 - The matrix elements will depend on four angles, of which one can, in some cases, be removed due to symmetry (e.g. if we have gravity, there is still a remaining rotational symmetry; same is true of particles are aligned by a \vec{B} -field; but if both gravity and a \vec{B} -field are present, this symmetry may get lost). It will in most practical circumstances not be possible to precalculate the scattering Müller matrix beforehand and tabulate it, because there are too many variables. The matrix must be computed on-the-fly.
 - The total scattering cross section now *does* depend on the polarization state of the input photon, and on the incidence angle. This means that scattering extinction becomes anisotropic.
 - Thermal emission and absorption extinction will also no longer be isotropic. Moreover, they are no longer scalar: they are described by a non-trivial Müller matrix.

The complexity of this case is rather large. As of version 0.41 we have included polarized thermal emission by aligned grains (see Section 6.9), and we will implement more of the above mentioned aspects of aligned grains step by step.




Figure 6.2. The definition of the Stokes parameters used in RADMC-3D, which is consistent with the IAU 1974 definitions (see Hamaker & Bregman (1996) A&AS 117, pp.161). First panel shows that positive angle means counter-clockwise. In the second to fourth panels the fat lines show how the tip of the real electric field vector goes as a function of time for an observer at a fixed location in space watching the radiation. The radiation moves toward the reader. We call the second panel (Q = +I) "horizontally polarized", the third panel (U = +I) "diagonally polarized by +45 degrees" and the fourth panel (V = +I) "right-handed circularly polarized". In the images produced by RADMC-3D (image.out, see Section A.16 and Fig. 9.1) the x' direction is the horizontal direction and the y' direction is the vertical direction.

6.7.1 Definitions and conventions for Stokes vectors

There are different conventions for how to set up the coordinate system and define the Stokes vectors. Our definition follows the IAU 1974 definition as described in Hamaker & Bregman (1996) A&AS 117, pp.161.

In this convention the x' axis points to the north on the sky, while the y' axis points to the east on the sky (but see the "important note" below). The z' axis points to the observer. This coordinate system is positively right-handed. The radiation moves toward positive z'. Angles in the (x', y') plane are measured counter-clockwise (angle=0 means positive x' direction, angle= $\pi/2$ means positive y' direction).

In the following we will (still completely consistent with the IAU definitions above, see the "important note" below) define "up" to be positive y' and "right" to be positive x'. So, the (x', y') coordinates are in a plane perpendicular to the photon propagation, and oriented as seen by the observer of that photon. So the direction of propagation is toward you, while y' points up and x' points to the right, just as one would normally orient it.

Important Note: This is fully equivalent to adjusting the IAU 1974 definition to have x' pointing west and y' pointing north, which is perhaps more intuitive, since most images in the literature have this orientation. So for convenience of communication, let us simply adjust the IAU 1974 definition to have positive x' ("right") pointing west and positive y' ("up") pointing north. It will have no further consequences for the definitions and internal workings of RADMC-3D because RADMC-3D does not know what "north" and "east" are.

The (Q, U) definition (linear polarization) is such that a linearly polarized ray with Q = +I, U = V = 0 has the electric field in the (x', y') = (1, 0) direction, while Q = -I, U = V = 0 has the electric field in the (x', y') = (0, 1) direction. If we have Q = 0, U = +I, V = 0 then the E-field points in the x' = y' direction, while Q = 0, U = -I, V = 0 the E-field points in the x' = -y' direction (see Figure 1 of Hamaker & Bregman 1996).

The (V) definition (circular polarization) is such that (quoting directly from the Hamaker & Bregman paper): "For right -handed circularly polarized radiation, the position angle of the electric vector at any point increases with time; this implies that the y' component of the field lags the x' component. Also the electric vectors along the line of sight form a left -handed screw. The Stokes V is positive for right-handed circular polarization."

We can put these definitions into the standard formulae:

$$Q = I\cos(2\beta)\cos(2\chi) \tag{6.14}$$

$$U = I\cos(2\beta)\sin(2\chi) \tag{6.15}$$

$$V = I\sin(2\beta) \tag{6.16}$$

The angle χ is the angle of the E-field in the (x',y') coordinates, measured counter-clockwise from x' (consistent with our definition of angles). Example: $\chi=45$ deg = $\pi/4$, then $\cos(2\chi)=0$ and $\sin(2\chi)=1$, meaning that Q=0 and U/I=+1. Indeed this is consistent with the above definition that U/I=+1 is $E_x'=E_y'$.

The angle 2β is the phase difference between the y'-component of the E-field and the x'-component of the E-field such that for $0 < \beta < \pi/2$ the E-field rotates in a counter-clockwise sense. In other words: the y'-wave lags 2β

behind the x' wave. Example: if we have $\beta = \pi/4$, i.e. $2\beta = \pi/2$, then $\cos(2\beta) = 0$ and $\sin(2\beta) = 1$, so we have Q = U = 0 and V/I = +1. This corresponds to the y' wave being lagged $\pi/2$ behind the x' wave, meaning that we have a counter-clockwise rotation. If we use the right-hand-rule and point the thumb into the direction of propagation (toward us) then the fingers indeed point in counter-rotating direction, meaning that V/I=+1 is righthanded polarized radiation.

In terms of the *real* electric fields of a plane monochromatic wave:

$$E_x'(t) = E_h \cos(\omega t - \Delta_h) \tag{6.17}$$

$$E_v'(t) = E_v \cos(\omega t - \Delta_v) \tag{6.18}$$

(with $E_h > 0$ and $E_v > 0$ and $\Delta_{h,v}$ are the phase lags of the components with respect to some arbitrary phase) we can write the Stokes components as:

$$I = E_h^2 + E_v^2 (6.19)$$

$$Q = E_h^2 - E_v^2 (6.20)$$

$$U = 2E_h E_v \cos(\Delta) \tag{6.21}$$

$$V = 2E_h E_v \sin(\Delta) \tag{6.22}$$

with $\Delta = \Delta_v - \Delta_h = 2\beta$.

In terms of the *complex* electric fields of a plane monochromatic wave (the sign before the $i\omega t$ is important):

$$E_x'(t) = E_h e^{i(\Delta_h - \omega t)} \tag{6.23}$$

$$E'_{x}(t) = E_{h}e^{i(\Delta_{h}-\omega t)}$$

$$E'_{y}(t) = E_{v}e^{i(\Delta_{v}-\omega t)}$$
(6.23)

(with $E_h > 0$ and $E_v > 0$ real numbers and $\Delta_{h,v}$ are the phase lags of the components with respect to some arbitrary phase) we can write the Stokes components as:

$$I = \langle E_{x'} E_{x'}^* + E_{y'} E_{y'}^* \rangle \tag{6.25}$$

$$Q = \langle E_{x'} E_{x'}^* - E_{y'} E_{y'}^* \rangle \tag{6.26}$$

$$U = \langle E_{x'} E_{y'}^* + E_{y'} E_{x'}^* \rangle \tag{6.27}$$

$$V = i \langle E_{x'} E_{y'}^* - E_{y'} E_{x'}^* \rangle \tag{6.28}$$

Our conventions compared to other literature

The IAU 1974 definition is different from the definitions used in the Planck mission, for instance. So be careful. There is something said about this on the website of the healpix software¹.

Our definition is also different from the Mishchenko book and papers (see below). Compared to the books of Mishchenko and Bohren & Huffman, our definitions are:

$$I_{\text{ours}} = I_{\text{mishch}} = I_{\text{bohrenhuffman}}$$
 (6.29)

$$Q_{\text{ours}} = Q_{\text{mishch}} = Q_{\text{bohrenhuffman}}$$
 (6.30)

$$U_{\text{ours}} = -U_{\text{mishch}} = -U_{\text{bohrenhuffman}}$$
 (6.31)

$$V_{\text{ours}} = -V_{\text{mishch}} = -V_{\text{bohrenhuffman}}$$
 (6.32)

As you see: only the U and V change sign. For a 4×4 Müller matrix M this means that the M_{II} , M_{IQ} , M_{QI} , M_{QQ} , as well as the M_{UU} , M_{UV} , M_{VU} , M_{VV} stay the same, while M_{IU} , M_{IV} , M_{QU} , M_{QV} , as well as M_{UI} , M_{UQ} , M_{VI} , M_{VQ} components would flip sign.

Compared to Mishchenko, Travis & Lacis book, what we call x' they call θ and what we call y' they call ϕ . In their Figure 1.3 (which describes the definition of the Stokes parameters) they have the θ direction pointing downward, rather than toward the right, i.e. rotated by 90 degrees clockwise compared to RADMC-3D. However, since RADMC-3D does not know what "right" or "down" are (only what x' and y' are) this rotation is merely a

http://healpix.jpl.nasa.gov/html/intronode12.htm

difference in how we plot things in a figure, and has no consequences for the results, as long as we define how x' and y' are oriented compared to our model (see Fig. 9.1 where x_{image} is our x' here and likewise for y').

Bohren & Huffman have the two unit vectors plotted in the following way: \mathbf{e}_{\parallel} is plotted horizontally to the left and \mathbf{e}_{\perp} is plotted vertically upward. Compared to us, our x' points toward *minus* their \mathbf{e}_{\parallel} , while our y' points toward their \mathbf{e}_{\perp} , but since they plot their \mathbf{e}_{\parallel} to the left, the orientation of our plot and their plots are consistent (i.e. if they say "pointing to the right", they mean the same direction as we). But their definition of "right-handed circular polarization" (clockwise when seen toward the source of the radiation) is our "left handed".

The book by Wendisch & Yang "Theory of Atmospheric Radiative Transfer" uses the same conventions as Bohren & Huffman, but their basis vector \mathbf{e}_{\parallel} is plotted vertically and \mathbf{e}_{\perp} is plotted horizontally to the right. This only affects what they call "horizontal" and "vertical" but the math stays the same.

Our definition is identical to the one on the *English* Wikipedia page on Stokes parameters² (on 2 January 2013), with the only exception that what they call "righthanded" circularly polarized, we call "lefthanded". This is just a matter of nomenclature of what is right/left-handed, and since RADMC-3D does not know what "right/lefthanded" is, this difference has no further consequences. *Note*, however, that the same Wikipedia page in different languages use different conventions! For instance, the German version of the page (on 2 January 2013) has the same Q and U definitions, but has the sign of V flipped.

Note that in RADMC-3D we have no global definition of the orientation of x' and y' (see e.g. Section 6.7.3). If we make an image with RADMC-3D, then the horizontal (x-) direction in the image corresponds to x' and the vertical (y-) direction corresponds to y', just as one would expect. So if you obtain an image from RADMC-3D and all the pixels in the image have Q = I and U = V = 0, then the electric field points horizontally in the image.

6.7.3 Defining orientation for non-observed radiation

To complete our description of the Stokes parameters we still need to define in which direction we let x' and y' point if we do *not* have an obvious observer, i.e. for radiation moving through our object of interest which may never reach us. In the Monte Carlo modules of RADMC-3D, when polarization is switched on, any photon package does not only have a wavelength λ and a direction of propagation \mathbf{n} associated with it, but also a second unit vector \mathbf{S} , which is always assured to obey:

$$|\mathbf{S}| = 1 \quad \text{and} \quad \mathbf{S} \cdot \mathbf{n} = 0 \tag{6.33}$$

This leaves, for a given n, one degree of freedom (any direction as long as it is perpendicular to n). It is irrelevant which direction is chosen for this, but whatever choice is made, it sets the definitions of the x' and y' directions. The definitions are:

$$x'$$
 points in the direction $\mathbf{S} \times \mathbf{n}$
 y' points in the direction \mathbf{S} (6.34)
 z' points in the direction \mathbf{n}

So for Q = -I, U = V = 0 the electric field points in the direction of S, while for Q = +I, U = V = 0 it is perpendicular to both n and S.

However, if you are forced to change the direction of S for whatever reason, the Stokes components will also change. This coordinate transformation works as follows. We can transform from a '-basis to a "-basis by rotating the S-vector counter-clockwise (as seen by the observer watching the radiation) by an angle α . Any vector (x', y') in the '-basis will become a vector (x'', y'') in a "-basis, given by the transformation:

$$\begin{pmatrix} x'' \\ y'' \end{pmatrix} = \begin{pmatrix} \cos(\alpha) & \sin(\alpha) \\ -\sin(\alpha) & \cos(\alpha) \end{pmatrix} \begin{pmatrix} x' \\ y' \end{pmatrix}$$
(6.35)

NOTE: We choose (x', y') to be the usual counter-clockwise basis for the observer seeing the radiation. Rotating the basis in counter-clockwise direction means rotating the vector in that basis in clockwise direction, hence the sign convention in the matrix.

²http://en.wikipedia.org/wiki/Stokes_parameters

If we have (I, Q, U, V) in the '-basis (which we might have written as (I', Q', U', V') but by convention we drop the '), the (I'', Q'', U'', V'') in the "-basis becomes

$$\begin{pmatrix} I'' \\ Q'' \\ U'' \\ V'' \end{pmatrix} = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \cos(2\alpha) & \sin(2\alpha) & 0 \\ 0 & -\sin(2\alpha) & \cos(2\alpha) & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix}$$
(6.36)

6.7.4 Polarized scattering off dust particles: general formalism

Suppose we have *one* dust particle of mass m_{grain} and we place it at location x. Suppose this particle is exposed to a plane wave of electromagnetic radiation pointing in direction \mathbf{n}_{in} with a flux $\mathbf{F}_{\text{in}} = F_{\text{in}} \mathbf{n}_{\text{in}}$. This radiation can be polarized, so that F_{in} actually is a Stokes vector:

$$F_{\rm in} = \begin{pmatrix} F_{I,\rm in} \\ F_{Q,\rm in} \\ F_{U,\rm in} \\ F_{V,\rm in} \end{pmatrix}$$

$$(6.37)$$

This particle will scatter some of this radiation into all directions. What will the flux of scattered radiation be, as observed at location $y \neq x$? Let us define the vector

$$\mathbf{r} = \mathbf{y} - \mathbf{x} \tag{6.38}$$

its length

$$r = |\mathbf{r}|\tag{6.39}$$

and the unit vector

$$\mathbf{e}_r = \frac{\mathbf{r}}{r} \tag{6.40}$$

We will assume that $r \gg a$ where a is the particle size. We define the scattering matrix elements Z_{ij} (with i, j = 1, 2, 3, 4) such that the measured outgoing flux from the particle at y is

$$\mathbf{F}_{\text{out}} = F_{\text{out}} \mathbf{e}_r \tag{6.41}$$

with

$$F_{\text{out}} = \begin{pmatrix} F_{I,\text{out}} \\ F_{Q,\text{out}} \\ F_{U,\text{out}} \\ F_{V,\text{out}} \end{pmatrix} = \frac{m_{\text{grain}}}{r^2} \begin{pmatrix} Z_{11} & Z_{12} & Z_{13} & Z_{14} \\ Z_{21} & Z_{22} & Z_{23} & Z_{24} \\ Z_{31} & Z_{32} & Z_{33} & Z_{34} \\ Z_{41} & Z_{42} & Z_{43} & Z_{44} \end{pmatrix} \begin{pmatrix} F_{I,\text{in}} \\ F_{Q,\text{in}} \\ F_{U,\text{in}} \\ F_{V,\text{in}} \end{pmatrix}$$
(6.42)

The values Z_{ij} depend on the direction into which the radiation is scattered (i.e. \mathbf{e}_r) and on the direction of the incoming flux (i.e. \mathbf{n}), but not on r: the radial dependence of the outgoing flux is taken care of through the $1/r^2$ factor in the above formula.

Some notes about our conventions are useful at this place. In many books the "scattering matrix" is written as F_{ij} instead of Z_{ij} , and is defined as the Z_{ij} for the case when radiation comes from one particular direction: $\mathbf{n} = (0,0,1)$. In this manual and in the RADMC-3D code, however, we will always write Z_{ij} , because the symbol F can be confused with flux. The normalization of these matrix elements is also different in different books. In our case it has the dimension cm²/gram/steradian. The conversion from the conventions of other books is (where $k = 2\pi/\lambda$ is the wave number in units of 1/cm):

$$Z_{ij,\text{RADMC-3D}} = \frac{Z_{ij,\text{Mishchenko}}}{m_{\text{grain}}} = \frac{S_{ij,\text{BohrenH}}}{k^2 m_{\text{grain}}}$$
(6.43)

except that for the Z_{13} , Z_{14} , Z_{23} , Z_{24} , Z_{31} , Z_{41} , Z_{32} , Z_{42} elements (if non-zero) there must be a minus sign before the $Z_{ij,RADMC-3D}$ because of the opposite U and V sign conventions (see Section 6.7.2).

Note that the $S_{ij,BohrenH}$ are the matrix elements obtained from the famous BHMIE.F code from the Bohren & Huffman book (see Chapter E).

6.7.5 Polarized scattering off dust particles: randomly oriented particles

In the special case in which we either have spherical particles or we average over a large number of randomly oriented particles, the Z_{ij} elements are no longer dependent on both \mathbf{e}_r and \mathbf{n} but only on the angle between them:

$$\cos \theta = \mathbf{n} \cdot \mathbf{e}_r \tag{6.44}$$

So we go from $Z_{ij}(\mathbf{n}, \mathbf{e}_r)$, i.e. a four-angle dependence, to $Z_{ij}(\theta)$, i.e. a one-angle dependence.

Now let us also assume that there is no netto helicity of the particles (they are either axisymmetric or there exist equal amounts of particles as their mirror symmetric counterparts). In that case (see e.g. Mishchenko book) of the 16 matrix elements only 6 are non-zero and independent:

$$F_{\text{out}} = \begin{pmatrix} F_{I,\text{out}} \\ F_{Q,\text{out}} \\ F_{U,\text{out}} \\ F_{V,\text{out}} \end{pmatrix} = \frac{m_{\text{grain}}}{r^2} \begin{pmatrix} Z_{11} & Z_{12} & 0 & 0 \\ Z_{12} & Z_{22} & 0 & 0 \\ 0 & 0 & Z_{33} & Z_{34} \\ 0 & 0 & -Z_{34} & Z_{44} \end{pmatrix} \begin{pmatrix} F_{I,\text{in}} \\ F_{Q,\text{in}} \\ F_{U,\text{in}} \\ F_{V,\text{in}} \end{pmatrix}$$
(6.45)

This is the case for scattering in RADMC-3D. Note that in Mie scattering the number of independent matrix elements reduces to just 4 because then $Z_{22}=Z_{11}$ and $Z_{44}=Z_{33}$. But RADMC-3D also allows for cases where $Z_{22}\neq Z_{11}$ and $Z_{44}\neq Z_{33}$, i.e. for opacities resulting from more detailed calculations such as DDA or T-matrix calculations.

Now, as described above, the Stokes vectors only have meaning if the directions of x' and y' are well-defined. For Eq. (6.45) to be valid (and for the correct meaning of the Z_{ij} elements) the following definition is used: Before the scattering, the S-vector of the photon package is rotated (and the Stokes vectors accordingly transformed) such that the new S-vector is perpendicular to both \mathbf{n} and \mathbf{e}_r . In other words, the scattering angle θ is a rotation of the photon propagation around the (new) S-vector. The sign convention is such that

$$(\mathbf{n} \times \mathbf{e}_r) \cdot \mathbf{S} = \sin(\theta) \tag{6.46}$$

In other words, if we look into the incoming light (with z' pointing toward us), then for $\sin(\theta) > 0$ the photon is scattered into the x' > 0, y' = 0 direction (i.e. for us it is scattered to the right). The **S** vector for the outgoing photon remains unchanged, since the new **n** is also perpendicular to it.

So what does this all mean for the opacity? The scattering opacity tells us how much of the incident radiation is removed and converted into outgoing scattered radiation. The absorption opacity tells us how much of the incident radiation is removed and converted into heat. For randomly oriented particles without netto helicity both opacities are independent of the polarization state of the radiation. Moreover, the thermal emission is unpolarized in this case. This means that in the radiative transfer equation the extinction remains simple:

$$\frac{d}{ds} \begin{pmatrix} I_I \\ I_Q \\ I_U \\ I_V \end{pmatrix} = \begin{pmatrix} j_{\text{emis},I} \\ 0 \\ 0 \\ 0 \end{pmatrix} + \begin{pmatrix} j_{\text{scat},I} \\ j_{\text{scat},Q} \\ j_{\text{scat},U} \\ j_{\text{scat},V} \end{pmatrix} - \rho(\kappa_{\text{abs}} + \kappa_{\text{scat}}) \begin{pmatrix} I_I \\ I_Q \\ I_U \\ I_V \end{pmatrix}$$
(6.47)

where I_I , I_Q , I_U , I_V are the intensities (erg/s/cm²/Hz/ster) for the four Stokes parameters, and likewise for $j_{\rm emis}$ and $j_{\rm scat}$, and finally, s the path length along the ray under consideration. Note that if we would allow for fixed-orientation dust particles (which we don't), Eq. (6.47) would become considerably more complex, with extinction being matrix-valued and thermal emission being polarized.

Since $\kappa_{\rm scat}$ converts incoming radiation into outgoing scattered radiation, it should be possible to calculate $\kappa_{\rm scat}$ from angular integrals of the scattering matrix elements. For randomly oriented non-helical particles we indeed have:

$$\kappa_{\text{scat}} = \oint Z_{11} d\Omega = 2\pi \int_{-1}^{+1} Z_{11}(\mu) d\mu$$
(6.48)

where $\mu = \cos \theta$. In a similar exercise we can calculate the anisotropy factor g from the scattering matrix elements:

$$g = \frac{2\pi}{\kappa_{\text{scat}}} \int_{-1}^{+1} Z_{11}(\mu) \mu d\mu \tag{6.49}$$

This essentially completes the description of scattering as it is implemented in RADMC-3D.

We can precalculate the $Z_{ij}(\theta)$ for every wavelength and for a discrete set of values of θ , and store these in a table. This is indeed the philosophy of RADMC-3D: You have to precompute them using, for instance, the Mie code of Bohren and Huffman (see Chapter E for RADMC-3D compliant wrappers around that code), and then provide them to RADMC-3D through a file called dustkapscatmat_xxx.inp (where xxx is the name of the dust species) which is described in Section A.14.3. This file provides not only the matrix elements, but also the $\kappa_{\rm abs}$, $\kappa_{\rm scat}$ and g (the anisotropy factor). RADMC-3D will then internally check that Eqs.(6.48, 6.49) are indeed fulfilled. If not, an error message will result.

One more note: As mentioned in Section 6.7.1, the sign conventions of the Stokes vector components we use (the IAU 1974 definition) are different from the Bohren & Huffman and Mishchenko books. For randomly oriented particles, however, the sign conventions of the Z-matrix elements are not affected, because those matrix elements that would be affected are those that are in the upper-right and lower-left quadrants of the matrix, and these elements are anyway zero. So we can use, for randomly oriented particles, the matrix elements from those books and their computer codes without having to adjust the signs.

6.7.6 Scattering and axially symmetric models

In spherical coordinates it is possible in RADMC-3D to set up axially symmetric models. The trick is simply to set the number of ϕ coordinate points nphi to 1 and to switch off the ϕ -dimension in the grid (see Section A.2). For isotropic scattering this mode has always been implemented. But for anisotropic scattering things become more complex. For such a model the scattering remains a fully 3-D problem: the scattering source function has to be stored not only as a function of r and θ , but also as a function of ϕ (for a given observer vantage point). The reason is that anisotropic scattering *does* care about viewing angle (in contrast to isotropic scattering). So even though for an axisymmetric model the density and temperature functions only depend on r and θ (and are therefore mathematically 2-D), the scattering source function depends on r, θ and ϕ .

For this reason anisotropic scattering was, until version 0.40, not allowed for 2-D axisymmetric models. As of version 0.41 it is now possible to use the full polarized scattering mode (scattering_mode=5) also for 2-D axisymmetric models. The intermediate scattering modes (scattering_mode=2, 3, 4) remain incompatible with 2-D axisymmetry. Isotropic scattering remains, as before, fully compatible with 2-D axisymmetry.

One note of explanation: the way the full scattering is now implemented into the case of 2-D axisymmetry is the following: internally we compute not just the scattering source function for one angle, but for a whole set of ϕ angles (even though the grid has no ϕ -points). Each time a photon in the scattering Monte Carlo simulation enters a cell (which in 2-D axisymmetry is an annulus), a loop over 360 ϕ angles is performed, and the scattering source function is computed for all of these angles. *This makes the code rather slow for each photon package!* But one needs fewer photon packages to get sufficiently high signal-to-noise ratio. You can experiment with fewer ϕ angles by adding, in radmc3d.inp, the following line (as an example):

```
dust_2daniso_nphi = 60
```

in which case instead of 360 the model will only use 60 ϕ points. That will speed up the code significantly, but of course will treat the ϕ -dependence of the scattering source function with lower precision.

For now the 2-D axisymmetric version of full scattering is only possible with first-order integration.

6.8 More about photon packages in the Monte Carlo simulations

In the "standard" Monte Carlo approach, the input energy (e.g. starlight or, for the scattering Monte Carlo, the thermal emission of dust) is divided into N equal energy packages of photons, which then travel through the model and eventually either escape or get destroyed. This equal division scheme is, however, problematic for some model setups. For instance, if you have stars with vastly different luminosity in the model, then the brightest of these stars will dominate, by far, the number of output photon packages. This means that the material around low-brightness stars (which, by their proximity to these low-brightness stars, are still dominated by heating by these low-brightness stars) will experience very bad photon statistics.

To avoid this problem, RADMC-3D has, by default, its "weighted photon package mode" switched on. This will make sure that each source of energy (i.e. each star, but also each other type of source) emits the same amount of

photons. Only: bright stars will emit more energetic photon packages than dim stars.

The "weighted photon package mode" will also solve another problem. Suppose a star lies far outside of the grid. It will emit most of its photons in directions that completely miss the grid. This means that RADMC-3D would waste a lot of time drawing random numbers for photons that will anyway not affect the model. Also here the "weighted photon package mode" solves the problem: It will focus the photon packages toward the model grid, and lower their energy to compensate for their favorable focusing toward the grid.

NOTE: Since RADMC-3D is still in beta-phase, and both aspects of the "weighted photon package mode" meddle with the standard equal-weighting procedure, it might be useful to sometimes check the results against a run without this mode but with a huge number of photon packages to compensate - just to check if there are no bugs or other subtleties. You can switch the mode off by setting mc_weighted_photons=0 in the radmc3d.inp file.

6.9 Polarized emission and absorption by aligned grains

NOTE: This mode is still in the testing phase (February 2017)!

Grain alignment and its effects on radiative transfer is a complex topic. A review is e.g. Andersson, B.G., Lazarian, A., & Vaillancourt, J.E. (2015) "Interstellar Dust Grain Alignment", Annual Review of Astronomy and Astrophysics, 53(1), 501539. In RADMC-3D grain alignment is included only in a limited form. First and foremost: RADMC-3D does not know about the physics causing the grain alignment. You, the user, will have to tell how the grain are aligned by giving the code a directional vector field and for each wavelength the degree to which the grain is aligned to that directional vector (more on this later). This is according to the RADMC-3D philosophy of doing only the radiative transfer and leaving the physics of the material to the user.

6.9.1 **Basics**

Suppose we have flattened (oblate) ellipsoidal grains with one axis of symmetry and no helicity³. Let us assume that they are aligned with that symmetry axis along the y-axis. We view radiation from the point where the z-axis points toward us. Horizontally polarized light (which has E-field in horizontal direction, i.e. in x-direction) has Q/I=+1, vertically polarized light (with the \vec{E} vector aligned with the symmetry axis of the grain) has Q/I = -1. We can then assume that the dust has different extinction coefficients for the horizontal and vertical axis. Let us call these:

$$\alpha_{\text{abs},\nu,h} \equiv \rho_d \kappa_{\text{abs},\nu,h}$$
 (6.50)

$$\alpha_{\text{abs},\nu,v} \equiv \rho_d \kappa_{\text{abs},\nu,v}$$
 (6.51)

We can define I, Q, U and V in terms of the electric field components E_x and E_y . The electric field components for a perfectly coherent wave can be written as

$$E_x = E_{x,0}\cos(\omega t - \Delta_x) \tag{6.52}$$

$$E_v = E_{v,0}\cos(\omega t - \Delta_v) \tag{6.53}$$

where Δ_x and Δ_y are phase lags. The phase lag between the y and x-fields is $\Delta = \Delta_y - \Delta_x$, meaning that for positive Δ the y-field lags behind the x-field. We then define the Stokes components as:

$$I = E_{x,0}^{2} + E_{y,0}^{2}$$

$$Q = E_{x,0}^{2} - E_{y,0}^{2}$$

$$U = 2E_{x,0}E_{y,0}\cos\Delta$$

$$(6.54)$$

$$(6.55)$$

$$Q = E_{x,0}^2 - E_{y,0}^2 (6.55)$$

$$U = 2E_{x,0}E_{y,0}\cos\Delta \tag{6.56}$$

$$V = 2E_{x,0}E_{y,0}\sin\Delta \tag{6.57}$$

Note that for V = I ($\Delta = \pi/2$, i.e. the E_y lags $\pi/2$ behind E_x) we have right-handed circularly polarized light, meaning that the tip of the \vec{E} field at a fixed point in space, when looking into the light (the propagation of light is toward the reader) rotates counter-clockwise (when the x-coordinate points right, and the y-coordinate points up). The 3-D helix of his field will be *left-handed* (when the z-coordinate points into the propagation direction of the

³While helicity may be needed to radiatively spin up grains, we assume that on average the helicity of the grains is zero.

light, i.e. toward the reader, i.e. a right-handed coordinate system). For Q = I we have linearly polarized light in which the \vec{E} -field lies in the x-direction. For U=I we have linearly polarized light in which \vec{E} lies along the x = y line (when looking into the light). These definitions are consistent with the IAU 1974 definitions (Hamaker & Bregman 1996, A&AS 117, pp.161).

The E_x and E_y get absorbed in the following way:

$$E'_{x,0} = E_{x,0}e^{-\frac{1}{2}\alpha_{\text{abs},\nu,h}s}$$
 (6.58)

$$E'_{y,0} = E_{y,0}e^{-\frac{1}{2}\alpha_{\text{abs},\nu,v}s}$$
 (6.59)

where s is a length along the ray.

For this kind of problem it is convenient to introduce the so-called *modified Stokes parameters* I_h and I_v :

$$I_{\rm h} = \frac{1}{2}(I+Q) \tag{6.60}$$

$$I_{\rm v} = \frac{1}{2}(I - Q) \tag{6.61}$$

so that we have

$$I = I_{\rm h} + I_{\rm v} \tag{6.62}$$

$$Q = I_{\rm h} - I_{\rm v} \tag{6.63}$$

so that one can say, for perfectly coherent light,

$$I_{\rm h} = E_{x,0}^2 (6.64)$$

$$I_{\rm v} = E_{y,0}^2 \tag{6.65}$$

With this we get the following extinction law:

$$I'_{\rm h} = I_{\rm h} e^{-\alpha_{\rm abs}, \nu, h s}$$
 (6.66)
 $I'_{\rm v} = I_{\rm v} e^{-\alpha_{\rm abs}, \nu, v s}$ (6.67)

$$I_{\rm w}' = I_{\rm v} e^{-\alpha_{\rm abs}, \nu, v}$$

$$\tag{6.67}$$

How do U and V extinct? If we use Eqs. (6.56, 6.57), and assume that the phase lag Δ will not change during the extinction, then

$$U' = Ue^{-\frac{1}{2}\alpha_{\text{abs},\nu,h}s}e^{-\frac{1}{2}\alpha_{\text{abs},\nu,v}s}$$

$$= Ue^{-\frac{1}{2}(\alpha_{\text{abs},\nu,h} + \alpha_{\text{abs},\nu,v})s}$$
(6.68)

This means that

$$\alpha_{\text{abs},\nu,\text{uv}} = \frac{1}{2} \left(\alpha_{\text{abs},\nu,\text{h}} + \alpha_{\text{abs},\nu,\text{v}} \right) \tag{6.69}$$

and

$$I'_{\rm u} = I_{\rm u}e^{-\alpha_{\rm abs,\nu,uv}s}$$
 (6.70)
 $I'_{\rm v} = I_{\rm v}e^{-\alpha_{\rm abs,\nu,uv}s}$ (6.71)

$$I_{\rm v}' = I_{\rm v} e^{-\alpha_{\rm abs}, \nu, {\rm uv}s} \tag{6.71}$$

In matrix notation

$$\frac{d}{ds} \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix} = - \begin{pmatrix} \alpha_{\rm h} & 0 & 0 & 0 \\ 0 & \alpha_{\rm v} & 0 & 0 \\ 0 & 0 & \alpha_{\rm uv} & 0 \\ 0 & 0 & 0 & \alpha_{\rm uv} \end{pmatrix} \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix}$$
(6.72)

If we translate this to the usual Stokes components we get

$$\frac{d}{ds} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix} = - \begin{pmatrix} \alpha_1 & \alpha_2 & 0 & 0 \\ \alpha_2 & \alpha_1 & 0 & 0 \\ 0 & 0 & \alpha_1 & 0 \\ 0 & 0 & 0 & \alpha_1 \end{pmatrix} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix}$$
(6.73)

with

$$\alpha_1 = \frac{1}{2} \left(\alpha_{\text{abs},\nu,h} + \alpha_{\text{abs},\nu,v} \right) = \alpha_{\text{abs},\nu,uv}$$
(6.74)

$$\alpha_2 = \frac{1}{2} \left(\alpha_{\text{abs},\nu,h} - \alpha_{\text{abs},\nu,v} \right) \tag{6.75}$$

The emission will be also independently in horizontal and vertical direction. But nothing will be emitted in U or V direction. So it is most convenient to express the emission/absorption process in terms of the modified Stokes parameters:

$$\frac{dI_{\nu,h}}{ds} = \alpha_{\text{abs},\nu,h} (\frac{1}{2} B_{\nu}(T) - I_{\nu,h})$$
(6.76)

$$\frac{dI_{\nu,h}}{ds} = \alpha_{\text{abs},\nu,h} \left(\frac{1}{2}B_{\nu}(T) - I_{\nu,h}\right) \tag{6.76}$$

$$\frac{dI_{\nu,v}}{ds} = \alpha_{\text{abs},\nu,v} \left(\frac{1}{2}B_{\nu}(T) - I_{\nu,v}\right) \tag{6.77}$$

$$\frac{dU_{\nu}}{ds} = -\alpha_{\text{abs},\nu,uv}U_{\nu} \tag{6.78}$$

$$\frac{dV_{\nu}}{ds} = -\alpha_{\text{abs},\nu,uv}V_{\nu} \tag{6.79}$$

$$\frac{dU_{\nu}}{ds} = -\alpha_{\text{abs},\nu,\text{uv}}U_{\nu} \tag{6.78}$$

$$\frac{dV_{\nu}}{ds} = -\alpha_{\text{abs},\nu,\text{uv}}V_{\nu} \tag{6.79}$$

In terms of matrix notation this becomes

$$\frac{d}{ds} \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix} = \begin{pmatrix} \frac{1}{2} \alpha_{\rm h} B_{\nu}(T) \\ \frac{1}{2} \alpha_{\rm v} B_{\nu}(T) \\ 0 \\ 0 \end{pmatrix} - \begin{pmatrix} \alpha_{\rm h} & 0 & 0 & 0 \\ 0 & \alpha_{\rm v} & 0 & 0 \\ 0 & 0 & \alpha_{\rm uv} & 0 \\ 0 & 0 & 0 & \alpha_{\rm uv} \end{pmatrix} \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix}$$
(6.80)

In terms of the normal Stokes parameters this becomes

$$\frac{d}{ds} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix} = \begin{pmatrix} \alpha_1 B_{\nu}(T) \\ \alpha_2 B_{\nu}(T) \\ 0 \\ 0 \end{pmatrix} - \begin{pmatrix} \alpha_1 & \alpha_2 & 0 & 0 \\ \alpha_2 & \alpha_1 & 0 & 0 \\ 0 & 0 & \alpha_1 & 0 \\ 0 & 0 & 0 & \alpha_1 \end{pmatrix} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix}$$
(6.81)

or written slightly differently:

$$\frac{d}{ds} \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix} = \begin{pmatrix} \alpha_1 & \alpha_2 & 0 & 0 \\ \alpha_2 & \alpha_1 & 0 & 0 \\ 0 & 0 & \alpha_1 & 0 \\ 0 & 0 & 0 & \alpha_1 \end{pmatrix} \begin{bmatrix} B_{\nu}(T) \\ 0 \\ 0 \\ 0 \end{pmatrix} - \begin{pmatrix} I \\ Q \\ U \\ V \end{pmatrix} \tag{6.82}$$

So to sum things up: We need only the absorption opacity for light with \vec{E} perpencidular to the symmetry axis $(\kappa_{{\rm abs},\nu,h})$ and the absorption opacity for light with \vec{E} parallel to the symmetry axis $(\kappa_{{\rm abs},\nu,v})$.

Implementation in RADMC-3D

Polarized emission in the images and spectra

When creating images (and spectra) the camera module of RADMC-3D performs a ray-tracing calculation ("volume renderung") through the grid. Normally (for randomly oriented grains) the extinction along the line of sight is always unpolarized, i.e. each Stokes component is extincted equally much. The thermal emission along the line of sight is also unpolarized.

Now, however, we wish to include the effect of grain alignment in the ray-tracing. We assume that at position \vec{x} in the grid our oblate grain is aligned such that the minor axis points in the direction of the orientation vector $\vec{n}_{\text{align}}(\vec{x})$. If the grain is prolate, we assume that it spins along one of its minor axes such that this spin axis is pointing along $\vec{n}_{\text{align}}(\vec{x})$, so that, in effect, it acts as if it were an oblate grain again. In practice the alignment vector $\vec{n}_{\text{align}}(\vec{x})$ does not lie always in the plane of the sky of the observer. Instead it will have an angle θ with the line-of-sight direction vector $\vec{n}_{\rm los}$ (note that this θ angle is different from the scattering angle θ), defined as

$$\cos \theta \equiv |\vec{n}_{\text{align}} \cdot \vec{n}_{\text{los}}| \tag{6.83}$$

Here we assume that the grains have top/bottom symmetry so that we only have to concern ourselves with the positive values of $\cos \theta$, hence the ||. If $\cos \theta = 1$ then we see the oblate grain from the top or the bottom, so that we do not expect any polarized emission. The strongest polarized emission is expected when $\cos \theta = 0$, which means that the oblate grain is seen edge-on.

We can now define the "projected alignment vector" $\vec{n}_{\text{align,proj}}$, which is the alignment vector projected into the image plane:

$$\vec{n}_{\text{align,proj}} = \vec{n}_{\text{align}} - (\vec{n}_{\text{align}} \cdot \vec{n}_{\text{los}}) \, \vec{n}_{\text{los}}$$
 (6.84)

To use the equations from Section 6.9.1 we must first rotate our image plane coordinates (x, y) to new coordinates (x', y') such that the y' (vertical) direction points along the $\vec{n}_{\text{align,proj}}$ vector while the x' (horizontal) direction points perpendicular to it. Let us write the Stokes vector of the radiation along the line of sight $(I_{\rm in}, Q_{\rm in}, U_{\rm in}, V_{\rm in})$, where we implicitly know that these are also a function of frequency ν . This Stokes vector is defined with respect to the vector \vec{S} which is perpendicular to the line-of-sight direction vector \vec{n}_{los} and defines the direction in which the y-coordinate of the image plane points. We must now express this incoming radiation (at the start of the segment) in the new (x', y') image plane coordinates, i.e. with respect to the new vector \vec{S}' that points along $\vec{n}_{\text{align.proj}}$ (i.e. \vec{S}' is the normalized version of $\vec{n}_{\text{align,proj}}$). This rotation is performed using

$$\begin{pmatrix} I' \\ Q' \\ U' \\ V' \end{pmatrix} = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \cos(2\alpha) & \sin(2\alpha) & 0 \\ 0 & -\sin(2\alpha) & \cos(2\alpha) & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} I_{\rm in} \\ Q_{\rm in} \\ U_{\rm in} \\ V_{\rm in} \end{pmatrix}$$
(6.85)

where α is the angle between \vec{S}' and \vec{S} such that if (as seen by the observer) \vec{S}' lies counter-clockwise from \vec{S} , α is positive (the usual definition). With this new Stokes vector (I', Q', U', V') we will now use the equations of Section 6.9.1.

To be able to perform this rotation in a uniquely defined way, it is necessary that along each segment along the line of sight this new (x', y') orientation stays fixed (but can vary from segment to segment). As the line-of-sight ray enters a cell and leaves it again, this line element (segment) will have its image-plane coordinates rotated according to the alignment vector of that cell. As a result, the integration must be done first order (assuming all source terms to be constant along the segment). In principle second order integration would also be possible, but then the trick with the rotation of the image coordinate plane such that y' points along the orientation vector does no longer work, and the integration of the formal transfer equation would become much more complex, involving the full Müller matrix formulation. We will not do this, so we will stick to first order integration of Eq. 6.80.

For convenience we will leave out the primes (') from here on, so while we write (I, Q, U, V) we mean in fact (I', Q', U', V'). We now compute I_h and I_v using Eqs. (6.60, 6.61). Now, along this segment of the ray, we can write Eq. 6.80 in the following form:

$$\frac{d}{ds} \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix} = \begin{pmatrix} \alpha_{\rm h} & 0 & 0 & 0 \\ 0 & \alpha_{\rm v} & 0 & 0 \\ 0 & 0 & \alpha_{\rm uv} & 0 \\ 0 & 0 & 0 & \alpha_{\rm uv} \end{pmatrix} \begin{bmatrix} \frac{1}{2}B_{\nu}(T) \\ \frac{1}{2}B_{\nu}(T) \\ 0 \\ 0 \end{bmatrix} - \begin{pmatrix} I_{\rm h} \\ I_{\rm v} \\ U \\ V \end{pmatrix} \tag{6.86}$$

It becomes clear that it is easy to perform the first order integration of this equation along this ray segment:

$$I_{\text{h.end}} = e^{-\tau_h} I_{\text{h.start}} + \frac{1}{2} e^{-\tau_h} B_{\nu}(T)$$
 (6.87)

$$I_{\text{h,end}} = e^{-\tau_h} I_{\text{h,start}} + \frac{1}{2} e^{-\tau_h} B_{\nu}(T)$$

$$I_{\text{v,end}} = e^{-\tau_v} I_{\text{v,start}} + \frac{1}{2} e^{-\tau_v} B_{\nu}(T)$$

$$U_{\text{end}} = e^{-\tau_{uv}} U_{\text{start}}$$
(6.89)

$$U_{\rm end} = e^{-\tau_{uv}} U_{\rm start} \tag{6.89}$$

$$V_{\rm end} = e^{-\tau_{uv}} V_{\rm start} \tag{6.90}$$

where "start" stands for the start of the ray segment, and "end" the end of the ray segment (which becomes the start of the next ray segment), and $\tau_h = \alpha_h \Delta s$, $\tau_v = \alpha_v \Delta s$ and $\tau_{uv} = \alpha_{uv} \Delta s$, with Δs being the length of the segment.

We now compute I_{end} and Q_{end} , and rotate back to the (x,y) image plane coordinate system (i.e. using \vec{S} instead of \vec{S}' to define the Stokes parameters) by applying Eq. 6.85 but now with $\alpha \to -\alpha$, and we have the values of the Stokes parameter at the end of the ray segment. Now we repeat this whole procedure for the next ray segment.

Polarized emission as source term in the Monte Carlo simulation

The polarization effects and anisotropic emission by aligned grains will also affect the Monte Carlo simulations.

For the thermal Monte Carlo (see Section 6.1) this effect is not included. In principle it should be included, but it would slow the code down, and it is unlikely to play a significant role for the dust temperature, in particular since the anisotropy of thermal emission is not expected to be so strong (and the polarization state is irrelevant for computing the dust temperature). It is clear that we make a small error here, but we believe that this is well within the much stronger uncertainties of the dust opacities.

For the scattering Monte Carlo (see Section 6.6.5), however, this effect may be important! The polarization caused by scattering of light off dust grains yields of course different results if the incident light is unpolarized or if it is already strongly polarized through, for instance, polarized thermal emission. In RADMC-3D this is therefore built into the scattering Monte Carlo. This will not slow down the code much because (in contrast to the thermal Monte Carlo) the polarized thermal emission only has to be computed at the start of each photon path, if the photon is emitted by the dust.

The way this is included is that when a photon is emitted by the dust inside a cell, RADMC-3D first randomly chooses which of the dust species emits the photon (the probabilities are weighted by the contribution each dust species makes to the emissivity at the given wavelength). Then the emission direction is randomly chosen, based on the θ -dependent probability function (where θ is the angle with the alignment direction) given by the average of the orthogonal (horizontal) and parallel (vertical) absorption opacities. Once the emission direction is chosen, the polarization state of the photon package is computed based on the orthogonal and parallel absorption opacities. Then the photon package is sent on its way.

Note that if alignment_mode = -1 then the polarized (and anisotropic) thermal emission by aligned grains is only included in the ray-tracing for images and spectra, while for alignment_mode = 1 it is also included in the scattering Monte Carlo computation.

6.9.3 Consistency with other radiative processes

The above equations assume that the absorption/emission is the only radiative process included. However, in practice we also have other processes involved, such as line emission/absorption or the scattering source function. The way this can be treated here is to simply add these additional opacities to all four components of the extinction matrix of Eq. (6.80) and to add the additional emissivities to the vector with the Planck functions in Eq. (6.80). For the scattered light emissivity (which is a Stokes vector) we must also first perform a rotation from S to S' using the Stokes rotation formula of Eq. (6.85) before we add this emissivity to the equation. If we include the effect of alignment on the scattering (see Section 6.9.5) then also the scattering extinction will be different for the orthogonal (horizontal) and parallel (vertical) Stokes components. That is easy to include in this formalism.

6.9.4 Input files for RADMC-3D for aligned grains

In RADMC-3D we implement the functions $\kappa_{abs,\nu,h}$ and $\kappa_{abs,\nu,v}$ as a function of angle θ which the alignment axis makes with the light of sight. For θ we see the oblate grain from the top (face-on), so that there is no asymmetry between horizontal (orthogonal to the alignment orientation vector) and vertical (parallel to the alignment orientation vector). Then we will have $\kappa_{abs,\nu,h} = \kappa_{abs,\nu,v}$. For $\theta = 90^{\circ}$ we will have the maximum difference between $\kappa_{abs,\nu,h}$ and $\kappa_{abs,\nu,v}$. We write

$$\kappa_{\text{abs }\nu h}(\theta) = \kappa_{\text{abs }\nu} k_{\nu h}(\theta) \tag{6.91}$$

$$\kappa_{\text{abs},\nu,h}(\theta) = \kappa_{\text{abs},\nu} k_{\nu,h}(\theta)
\kappa_{\text{abs},\nu,v}(\theta) = \kappa_{\text{abs},\nu} k_{\nu,v}(\theta)$$
(6.91)

where $k_{\nu,h}(\theta)$ and $k_{\nu,\nu}(\theta)$ are dimensionless functions, and where we take $\theta \in [0,90]$ (in degrees), or equivalently $\cos(\theta) \in [0,1]$. We impose the condition that if we randomly orient this grain, the average opacity becomes the one we computed for the randomly oriented grains:

$$\int_0^\infty \frac{1}{2} \left[\kappa_{\text{abs},\nu,h}(\theta) + \kappa_{\text{abs},\nu,v}(\theta) \right] d\mu = \kappa_{\text{abs},\nu}$$
 (6.93)

This yields the following integration condition on the dimensionless $k_{\nu,h}$ and $k_{\nu,v}$:

$$\int_0^\infty \frac{1}{2} \left[k_{\nu,h}(\theta) + k_{\nu,v}(\theta) \right] d\mu = 1$$
 (6.94)

If we set, for all values of θ , $k_{\nu,h}(\theta) = k_{\nu,\nu}(\theta) = 1$ then we retrieve the result for spherical grains.

In RADMC-3D the functions $k_{\nu,h}(\theta)$ and $k_{\nu,v}(\theta)$ are read in via the file dustkapalignfact_*.inp. This file has the following structure:

```
# Any amount of arbitrary
# comment lines that tell which opacity this is.
# Each comment line must start with an # or ; or ! character
                                    <=== Typically 1 at present
                                    <=== Nr of wavelengths
nlam
nmu
                                    <=== Nr of angles sampled
lambda[1]
                                    <=== Wavelength grid in micron
lambda[nlam]
                                    <=== Angle grid in degrees
theta[1]
theta[nmu]
k_{orth[1,1]}
                  k_para[1,1]
                                    <=== The arrays k_orth and k_para
k_orth[nmu,1]
                  k_para[nmu,1]
k_{orth[1,2]}
                  k_para[1,2]
. . .
k_orth[nmu,2]
                  k_para[nmu,2]
. . .
                  k_para[1,nlam]
k_orth[1,nlam]
k_orth[nmu,nlam] k_para[nmu,nlam]
```

The angles theta are in degrees and must start at 0 and end at 90, or vice versa. The nmu does not have to be the same (and the angles do not have to be the same) as those in the dustkapscatmat_*.inp file. But the wavelength grid must be identical to the one in the dustkapscatmat_*.inp file.

In order to make RADMC-3D read this file dustkapalignfact_*.inp the dustopac.inp file should, for this particular dust species, have "20" as the way in which this dust species is read (instead of 10 which is used for polarized scattering with the Z matrix).

In addition, RADMC-3D also needs to know the orientation direction of the grains. This is a vector field $\vec{p}_{\rm align}(\vec{x})$. The length of these vectors should be between 0 and 1, where 1 means that the grains are perfectly aligned and 0 means they are not aligned at all. The efficiency $\epsilon_{\rm align}$ is thus given by

$$\epsilon_{\text{align}}(\vec{x}) = |\vec{p}_{\text{align}}(\vec{x})|$$
 (6.95)

The directional unit-vector of alignment $\vec{n}_{\text{align}}(\vec{x})$ is thus

$$\vec{n}_{\text{align}}(\vec{x}) = \left(\epsilon_{\text{align}}(\vec{x})\right)^{-1} \vec{p}_{\text{align}}(\vec{x})$$
 (6.96)

The $\vec{p}_{\mathrm{align}}(\vec{x})$ vector field is in the file grainalign_dir.inp (or its binary formatted version grainalign_dir.binp). The format of this file is exactly the same as that of the gas velocity file gas_velocity.inp. The ascii format looks like:

Note that $|\vec{p}_{\text{align}}(\vec{x})|$ should never be > 1. If it is found to be significantly > 1 at some point in the grid, then an error occurs. If it is only a tiny bit above 1, due to rounding errors, it will be normalized to 1.

The way in which partial alignment ($0 < \epsilon_{\rm align} < 1$) is treated in RADMC-3D is to treat the opacities and emissivities as simple linear sums of fully aligned and non aligned versions. For instance, Eqs. (6.91, 6.92) then become

$$\kappa_{\text{abs},\nu,h}(\theta) = \kappa_{\text{abs},\nu} \left[\epsilon_{\text{align}} k_{\nu,h}(\theta) + 1 - \epsilon_{\text{align}} \right]$$
(6.97)

$$\kappa_{\text{abs},\nu,v}(\theta) = \kappa_{\text{abs},\nu} \left[\epsilon_{\text{align}} k_{\nu,v}(\theta) + 1 - \epsilon_{\text{align}} \right]$$
(6.98)

In order to tell RADMC-3D that it should include the effect of alignment on the thermal emission of dust grains one must add a line in the radmc3d.inp file with

alignment_mode = 1

The example model in examples/run_simple_1_align/ demonstrates how the input files have to be made to have RADMC-3D treat the aligned dust grains for thermal emission.

6.9.5 Effect of aligned grains on the scattering

This is, currently, not yet implemented.

6.10 Quantum-heated grains: PAHs and VSGs

Very small dust grains are like very large molecules: they are partly classical objects, partly quantum objects. Polycyclic aromatic hydrocarbons (PAHs) are examples of such grains. The very smallest PAHs (such as naphtalene or anthracene) are still so small that they behave more in a molecular fashion: their vibrational states should be described as individual quantum energy levels. PAHs with many rings, however, have so many vibrational energy levels, that their vibrational state can be described with a temperature, making them pseudo-classic objects. However, they are still too small to be treated as "normal" dust grains in a radiative transfer model, because when they are exposed to UV photons, their temperature fluctuates. The reason is because a single UV photon contains enough energy to heat such a tiny grain from 0 K all the way up to hundreds of Kelvins. The heat capacity of these tiny grains is simply too small to allow for a steady equilibrium temperature to be attained. They therefore require a special radiative transfer treatment.

PAHs are one class of such grains. The opacities of such grains show characteristic peaks in the near- and midinfrared, among which are the 3.3 μ m C-H stretching mode, the 6.2 μ m and 7.7 μ m C-C stretching mode, the 8.6 μ m in-plane C-H bending mode and the 11.3 μ m out-of-plane C-H bending mode. The diversity of possible PAHs, however, means that no single "PAH opacity" exists. In space there is presumably a plethora of different polycyclic grains mixed together. An ab-initio prediction for the radiative-transfer appearance of an object containing PAHs is therefore impossible. Instead, "effective models" such as the Drude profile model of Li & Draine (2001, ApJ 554, 778) are a pragmatic way to compute useful PAH opacities.

In the interstellar medium there are also somewhat bigger carbonaceous grains which do not show the typical PAH spectral peaks, yet they are still small enough that in very cold environments they might still display fluctuating temperatures. These are often called "Very Small Grains" (VSGs).

The RADMC-3D code can treat the temperature-fluctuating aspect of PAHs and VSGs. This is called "quantum heating" because a single (or a few) individual photons (quantums) can cause the temperature of these grains to change drastically. In RADMC-3D the quantum_module.f90 is the module taking care of this.

We follow the "temperature distribution function" approach to treat these temperature fluctuations (Guharthakurta & Draine 1989, ApJ, 345, 230; Siebenmorgen, Kruegel & Mathis 1992, A&A, 266, 501). In this model the grain has an opacity κ_{ν} like any other grain. But instead of a given (non-changing) temperature T, it has a temperature distribution function as P(T), which is normalized as

$$\int_0^\infty P(T)dT = 1 \tag{6.99}$$

The grain will have, at any given time, a well-defined temperature T, but this varies strongly with time. Most of the time the grain is receiving no photons, while it is emitting infrared radiation and thus gradually cools. The cooling is assumed to go smoothly (i.e. the energy of each infrared photon it emits is much less than the heat capacity of the grain). Every now and then the grain absorbs a UV photon, and thus its temperature makes a quantum jump to a much higher value. After that, it gradually cools again, until the next UV photon hits the grain.

The quantum heating and classical cooling of these grains depends on the heat capacity of the grains, which depends on material properties. In RADMC-3D we rarely have material properties hard-coded inside: mostly we read them in from file (e.g. dust opacities or molecules). But here, as an exception, we have the heat capacity of carbon-based materials built in, and we assume that the quantum-heated grains are always made of such substance. This is built into the function enthalpy_pah_gram(temp) in the quantum_module.f90 file. If the user wishes to use another kind of material, then he/she will have to modify the code here. The enthalpy in erg per gram of PAH material is taken from Siebenmorgen & Kruegel (1992), who took it from Chase et al. (1985).

$$H(T) = \frac{4.15 \times 10^{-22}}{12 m_p} \frac{T^{3.3}}{1 + 6.51 \times 10^{-3} T + 1.5 \times 10^{-6} T^2 + 8.3 \times 10^{-7} T^{2.3}} \frac{\text{erg}}{\text{g}}$$
(6.100)

where m_p is the proton mass and the 12 comes from the atomic mass of carbon. The specific heat c_p is then given by $c_p = dH(T)/dT$. The quantum heating by absorbing a UV photon with frequency ν results in a temperature jump from T_{before} to T_{after} which such that

$$H(T_{\text{after}}) - H(T_{\text{before}}) = \frac{h\nu}{m_{\text{grain}}}$$
 (6.101)

where we approximate $m_{\rm grain} \simeq 12 m_p n_C$ where n_C is the number of carbon atoms in the grain. We ignore the mass contribution by the H atoms that might be attached to the outside of the PAH or VSG.

For any given $T_{\rm before}$ and ν Eq. (6.101) is solved for $T_{\rm after}$ using a simple bisection algorithm. The rate of absorption of UV photons is simply computed using the dust opacity given by the user and the radiation field computed by RADMC-3D. This radiation field is computed by RADMC-3D using the same method as for computing the mean intensity at a given set of frequencies (Section 6.5). The frequency grid used for this calculation must be specified by the used in a file called quantum_wavelength_micron.inp which has the same format as the file wavelength_micron.inp (see Section A.12). Given the mean intensity J_{ν} , the rate of absorption of UV photons of energy $h\nu$ per gram of dust per Herz is

$$R_{\nu} = \kappa_{\text{abs},\nu} \frac{J_{\nu}}{h_{\nu}} \tag{6.102}$$

The cooling is a continuous and time-dependent process. The temperature decreases with time as

$$c_p \frac{dT}{dt} = 4\pi \int_0^\infty \kappa_{\text{abs},\nu} B_\nu(T) d\nu \tag{6.103}$$

The frequency grid used for the cooling is *not* the one from quantum_wavelength_micron.inp, but instead it is the normal global frequency grid from wavelength_micron.inp (see Section A.12). This means that in practice you want to set the wavelengths in quantum_wavelength_micron.inp to the UV and optical domain, while you would set wavelength_micron.inp to the entire UV to millimeter wavelength range.

Given the rate of UV photon absorption events per gram of (PAH or VSG) dust, the corresponding rate of quantum jumps of temperature and the rate of cooling, RADMC-3D attempts to find an equilibrium solution for the temperature distribution function P(T). The formal integro-differential equation that P(T) obeys is somewhat difficult to formulate in continuous form. The time-dependent version of the quantum heating part of this equation can be (admittedly rather cryptically) formulated as

$$\frac{\partial P(T,t)}{\partial t} = \int_0^T P(T')R_{\nu(T',T)}dT' - P(T)\int_T^\infty R_{\nu(T,T')}dT'$$
(6.104)

where $\nu(T',T)$ is the frequency of the photon needed to heat the grain from T to T' according to Eq. (6.101) and the rate $R_{\nu(T',T)}$ is the corresponding absorption rate of such photons given by Eq. (6.102), but with a conversion factor (a Jacobian factor) to convert between $d\nu$ and dT':

$$R_{\nu(T,T')}dT' = R_{\nu}d\nu \tag{6.105}$$

which leads to

$$R_{\nu(T,T')} = \frac{c_p}{h} R_{\nu}$$
 (6.106)

The first term in Eq. (6.104) accounts for grains that were quantum heated to temperature T. The second term in Eq. (6.104) accounts for grains that get heated from T to a higher temperature. Since the integral in the second term is independent of P(T), it can be computed independently: it is simply the total number of photons absorbed per second per gram of dust. If we include all frequencies, including the very low ones (radio wavelengths), then this number diverges. But low-energy photons will also hardly heat up the grain, so the two terms in Eq. (6.104) will then effectively cancel out for these photons. In RADMC-3D the lowest included photon energy is that of the lowest frequency (longest wavelength) in the file quantum_wavelength_micron.inp.

The time-dependent cooling equation (Eq. 6.103) becomes a conservative advection equation

$$\frac{\partial P(T,t)}{\partial t} - \frac{\partial [P(T,t)c_p(T)]}{\partial T} = 0 \tag{6.107}$$

where $-c_p$ is the "velocity" in P-space.

A stationary state is found by solving the combination of these two equations and settling $\partial P/\partial t=0$:

$$\int_{0}^{T} P(T')R_{\nu(T',T)}dT' - P(T)\int_{T}^{\infty} R_{\nu(T,T')}dT' - \frac{\partial[P(T,t)c_{p}(T)]}{\partial T} = 0$$
 (6.108)

Since in the computer it is anyway solved in a discrete manner, the method is usually described in a discrete form. In this approach the P(T) is mapped onto a grid of temperatures $\{T_i\}$, where RADMC-3D takes a logarithmic spacing (i.e. equal spacing in $\log(T)$). The function P(T) is thus mapped onto a set of probabilities $\{P_i\}$ such that

$$P_i \equiv \int_{T_{i-1/2}}^{T_{i+1/2}} P(T)dT \tag{6.109}$$

where the half-indices are mean to denote the "cell walls" of the discrete temperature bins (the usual notation in the numerical hydrodynamics literature). Eq. (6.108) is then formulated in matrix equation form:

$$\sum_{i} M_{ij} P_{j} = 0 ag{6.110}$$

where the matrix elements are the discrete version of the differential and integral operators in Eq. (6.108). The last row of Eq. (6.110) is, however, replaced by

$$\sum_{j} P_j = 1 \tag{6.111}$$

to assure that Eq. (6.99) is fulfilled. Solving this matrix equation using LU decomposition yields the solution $\{P_i\}$, which are the relative fractions of the time that the grain is found with temperature between $T_{i-1/2}$ and $T_{i+1/2}$. This is the discrete version of the function P(T).

Once we have computed P(T), we can compute the time-averaged emissivity j_{ν} (in erg s⁻¹ cm⁻² Hz⁻¹ ster⁻¹) as

$$j_{\nu} = \int_0^\infty \kappa_{\nu} B_{\nu}(T) P(T) dT \tag{6.112}$$

This is the emissivity that is then used in the ray-tracing routine of RADMC-3D to produce images and spectra.

6.10.1 Approximations to quantum-heating in RADMC-3D

In RADMC-3D we only treat stellar photons or external photons as being capable of quantum-heating the grains. The thermal photons re-emitted by the dust (and the PAHs/VSGs) are assumed to behave as classical light. This means that in the thermal Monte Carlo simulation a photon emitted by a star, a stellar source or by the external interstellar radiation field, will (for the quantum grains) not contribute to the usual absorbed energy in each cell, because this radiation will (at another stage in the algorithm) be used to compute the temperature distribution function of that dust in the quantum way. However, PAHs and VSGs can also contribute to the thermal radiative

diffusion deep into optically thick regions. There they behave entirely classically. To make sure that they indeed do so in RADMC-3D, the code will treat these grains after the first absorption/re-emission event as any other (thermal) grain. These grains will then also acquire a "normal" temperature (in addition to the temperature distribution function). Physically speaking this is the low-end peak in the P(T) function. But it is algorithmically more stable to treat this low-temperature peak in the P(T) distribution simply as the usual equilibrium temperature like for the normal "thermal" grains. So the "quantum" part only treats the effect of the absorption by stellar or external photons. Strictly speaking the P(T) can (and often will) have a low-T tail that goes even below the equilibrium temperature. This is an artifact of our artificial splitting between "quantum heating" and "thermal heating". However, this does not make a significant difference in the results.

6.10.2 Dust opacities for PAHs and VSGs

In order to treat a dust species in RADMC-3D as a quantum-heated grain, the opacity input files must specify that this grain is indeed quantum-heated. This is one in the dustopac.inp file (see Section A.14). Here is an example of the content of the file dustopac.inp which specifies opacity dustkappa_silicate.inp as normal grain and dustkappa_pah.inp as quantum grain:

The "6" tells RADMC-3D that this grain is quantum-heated, and tells RADMC-3D to read the next two lines as the number of C atoms and the sublimation tempeature, respectively. Why 6? Historical reasons: there were various other modes of reading the PAH/VSG properties into the original RADMC code in the past. In this example the PAH has 50 C atoms (neccesary information for computing the heat capacity of the grain). It will sublimate once the grain exceeds 2000 Kelvin.

For the rest the PAH or VSG opacities are treated just like normal grains. For instance, in the above example we would need to specify the dust opacity files dustkappa_silicate.inp and dustkappa_pah.inp (see Section A.14).

6.10.3 Quantum-heated grains in RADMC-3D: How to do it

First it is important to have an opacity file for the quantum-heated grains. For PAHs one can, for instance, use the Drude-Profile model of Li & Draine (2001, ApJ 554, 778). Typically you would have "normal" grains as well, so that you would, for instance, have one "normal grain" opacity and one "PAH grain" opacity. In the dustopac.inp file you specify these two opacities (see Section A.14 and Section 6.10.2) and for the "PAH grain" you specify that it is a quantum-heated grain, you give the number of C atoms of that grain and you give a sublimation temperature (all described in Section 6.10.2).

For both dust opacities ("normal" and "PAH") you specify the spatial density distribution in the dust_density.inp (Section A.3).

You must also specify a grid of wavelengths at which the quantum-heating radiation is computed using the Monte Carlo module. This should typically be a wavelength grid in the UV wavelength range (because it is typically ultraviolet photons that excite PAH modules and VSGs). This is done by creating a file quantum_wavelength_micron.inp, which has exactly the same format as the file wavelength_micron.inp (see Section A.12). This file must contain at least two wavelengths. If only two wavelength are specified, the quantum-exciting radiation field is computed only at one wavelength (the average between the two specified wavelengths), and the total number of photons is then the integral of the radiation field over this wavelength bin. With three wavelengths specified, two bins are used,

etc. The usefulness of specifying only one or a few bins is to keep the memory requirement and computational cost low, and also perhaps for simplifications for testing purposes.

Finally, you must explicitly activate the quantum-heating, by adding the following line to radmc3d.inp:

```
incl_quantum = 1
```

If you now perform the usual thermal Monte Carlo with

radmc3d mctherm

RADMC-3D will perform the usual thermal Monte Carlo run according to the Bjorkman & Wood algorithm, where the normal grains are treated as usual, and the quantum grains are included only starting after the first absorption/re-emission event. For stellar photons (before the first absorption/re-emission event) the quantum grains can absorb photons, but they will not be immediately re-emitted during the Monte Carlo. Instead these photons are destroyed (**This is planned to be improved soon**). The inclusion of the quantum grains also during the thermal Monte Carlo run guarantees that that deep in optically thick regions the quantum grains behave as normal grains. Each quantum grain thus has not only a temperature distribution (excited by the UV photons) but also an equilibrium temperature (excited by all radiation *except* the UV photons). This may sound strange, but one could think of the equilibrium temperature as being a delta-function added to the temperature distribution function.

Now if you wish to make an image and you call the code as

```
radmc3d image lambda 11.3
```

(for instance), then RADMC-3D will first perform monochromatic Monte Carlo runs for all the wavelengths specified in quantum_wavelength_micron.inp. Then it will calculate, for the quantum-grains, the temperature distribution function at each grid point. *Note that this can be memory-demanding for large models!* It will also read in the dust temperature file, for the normal grains and for the thermal part of the quantum grains. The code will compute the emissivity caused by the temperature distribution function for the quantum-grains. Finally it will perform the ray-tracing and save the image to file.

Chapter 7

Line radiative transfer

RADMC-3D is capable of modeling radiative transfer in molecular and/or atomic lines. Due to the complexity of line radiative transfer, and the huge computational and memory requirements of full-scale non-LTE line transfer, RADMC-3D has various different modes of line transfer. Some modes are very memory efficient, but slower, while others are faster, but less memory efficient, yet others are more accurate but much slower and memory demanding. The default mode (and certainly recommended initially) is LTE ray-tracing in the slow but memory efficient way: the *simple LTE mode* (see Section 7.3). Since this is the default mode, you do not need to specify anything to have this selected.

7.1 Quick start for adding line transfer to images and spectra

Do properly model line transfer requires dedication and experimentation. This is *not* a simple task. See Section 7.11 for an analysis of several pitfalls one may encounter. However, nothing is better than experimenting and thus gaining hands-on experience. So the easiest and quickest way to start is to start with one of the simple line transfer test models in the examples / directory.

So simply visit examples/run_test_lines_1/, examples/run_test_lines_2/ or examples/run_test_lines_3/ and follow the directions in the README file. The main features of adding line ray tracing to a model is to add the following files into any previously constructed model with dust radiative transfer:

- lines.inp: A control file for line transfer.
- molecule_co.inp: or any other molecular data file containing properties of the molecule or atom.
- numberdens_co.inp (or its binary version, see Chapter B) or that of another molecule: The number density of that molecule in units of cm⁻³.
- gas_temperature.inp (or its binary version, see Chapter B): The gas temperature at each grid cell. You do not need to specify this file if you add the keyword tgas_eq_tdust = 1 into the radmc3d.inp file.

and then start the viewimage viewer (see Section 14.3) with keyword "/lines". Or you can use the makeimage or doimage routines from the readradmc.pro.

7.2 Some definitions for line transfer

The formal transfer equation is:

$$\frac{dI_{\nu}(\omega)}{ds} = j_{\nu}(\omega) - \alpha_{\nu}(\omega)I_{\nu}(\omega)$$
(7.1)

which is true also for the lines. Here ω is the direction, ν the frequency, I the intensity. The emissivity j_{ν} and extinction α_{ν} for each line (given by i=upper level and j=lower level) is given by:

$$j_{ij}(\Omega,\nu) = \frac{h\nu}{4\pi} N n_i A_{ij} \varphi_{ij}(\omega,\nu)$$
 (7.2)

$$\alpha_{ij}(\omega,\nu) = \frac{h\nu}{4\pi} N(n_j B_{ji} - n_i B_{ij}) \varphi_{ij}(\omega,\nu)$$
(7.3)

Here N is the number density of the molecule, n_i is the *fraction* of the molecules that are in level i, A_{ij} is the Einstein coefficient for spontaneous emission from level i to level j, and B_{ij} and B_{ji} are the Einstein-B-coefficients which obey:

$$A_{ij} = \frac{2h\nu_{ij}^3}{c^2} B_{ij} \qquad B_{ji}g_j = B_{ij}g_i \tag{7.4}$$

where g are the statistical weights of the levels, h the Planck constant and c the light speed. The symbol $\varphi_{ij}(\omega,\nu)$ is the line profile function. For zero velocity field $\varphi_{ij}(\omega,\nu) = \tilde{\varphi}_{ij}(\nu)$, i.e. the line profile function is independent of direction. The tilde is to say that this is the comoving line profile. It is given by

$$\tilde{\varphi}_{ij}(\nu) = \frac{c}{a_{\text{tot}}\nu_{ij}\sqrt{\pi}} \exp\left(-\frac{c^2(\nu - \nu_{ij})^2}{a_{\text{tot}}^2\nu_{ij}^2}\right)$$
(7.5)

where ν_{ij} is the line-center frequency for the line and a_{tot} is the line width in units of cm/s. For pure thermal broadning we have

$$a_{\text{tot}} = a_{\text{therm}} = \sqrt{\frac{2kT_{\text{gas}}}{m_{\text{mol}}}}$$
 (7.6)

where $m_{\rm mol}$ is the weight of the molecule in gram, k is the Boltzmann constant, $T_{\rm gas}$ the gas temperature in K. As we shall discuss in Section 7.4.8: we can also add "microturbulent line broadning" $a_{\rm turb}$, also in cm/s:

$$a_{\text{tot}} = \sqrt{a_{\text{turb}}^2 + a_{\text{therm}}^2} = \sqrt{a_{\text{turb}}^2 + \frac{2kT_{\text{gas}}}{m_{\text{mol}}}}$$
(7.7)

When we have macroscopic velocities in our model, then the line profile becomes angle-dependent (at a given lab-frame frequency):

$$\varphi_{ij}(\omega,\nu) = \tilde{\varphi}_{ij} \left(\nu (1 - \vec{\omega} \cdot \vec{v}/c) - \nu_{ij} \right) \tag{7.8}$$

The radiative transfer equation for non overlapping lines is then

$$\frac{dI_{ij}(\omega,\nu)}{ds} = j_{ij}(\omega,\nu) - \alpha_{ij}(\omega,\nu)I_{ij}(\omega,\nu). \tag{7.9}$$

But RADMC-3D naturally includes overlapping lines, at least in the ray-tracing (for spectra and images). For non-LTE modes the line overlapping is not yet (as of December 2011) included.

7.3 Line transfer modes and how to activate the line transfer

Line transfer can be done in various different ways. This is controlled by the global variable lines_mode (see below) and by the nature of the molecular/atomic data (see discussion in Section 7.4.2).

7.3.1 Two different atomic/molecular data file types

Let us start with the latter: RADMC-3D does not have any atomic or molecular data hard-coded inside. It reads these data from data files that you provide. There are two fundamentally different ways to feed atomic/molecular data into RADMC-3D:

- Files containing the full level and line information (named molecule_XXX.inp, where XXX is the name of
 the molecule or atom). Atoms or molecules for which this data is provided can be treated in LTE as well as
 in non-LTE.
- Files containing only a line list (named linelist_XXX.inp, where XXX is the name of the molecule or atom). Atoms or molecules for which this data is provided can only be treated in LTE.

7.3.2 The different line modes (the lines_mode parameter)

For the atoms or molecules for which the full data are specified (the molecule_XXX.inp files) RADMC-3D has various different line transfer modes, including different treatments of LTE or non-LTE. Which of the modes you want RADMC-3D to use can be specified in the radmc3d.inp file by setting the variable lines_mode, for instance, by adding the following line to radmc3d.inp:

```
lines_mode = 3
```

for LVG + Escape Probability populations. If no option is given, then the LTE mode (lines_mode=1) is used.

The various line modes are:

- LTE mode (=default mode): [lines_mode=1]
 In this mode the line radiative transfer is done under LTE assumptions.
- *User-defined populations:* [lines_mode=2]

 This calls the routine userdef_compute_levelpop() to compute the level populations. This allows the user to specify the populations of the levels of the molecules freely.
- Large Velocity Gradient (Sobolev) populations: [lines_mode=3]
 This is one of the non-LTE modes of RADMC-3D. This mode calculates the angle-averaged velocity gradient, and uses this to compute the level populations according to the Large Velocity Gradient method (also often called Sobolev's method). This method is like an escape probability method, where the escape probability is calculated based on the velocity gradient. For this mode to work, the velocity field has to be read in, as well as at least one of the number densities of the collision partners of the molecule. See Section 7.6.
- Optically Thin non-LTE level populations method: [lines_mode=4]

 This is one of the non-LTE modes of RADMC-3D. This mode calculates the non-LTE level populations under the assumption that all emitted line radiation escapes and is not reabsorbed. For this mode to work, at least one of the number densities of the collision partners of the molecule. See Section 7.7.
- User-defined populations: [lines_mode=-10]
 This calls the routine userdef_general_compute_levelpop() on-the-fly during the ray-tracing. This is very much like userdef_compute_levelpop(), except that it leaves the entire line-related stuff to the user: It does not read the molecular data from a file. NOTE: This is a rather tricky mode, to be used only if you know very well what you are doing...
- Full non-LTE modes: Not yet ready

The default of the lines_mode variable is lines_mode=1.

NOTE 1: Line emission is automatically included in the images and spectra if RADMC-3D finds the file lines.inp in the model directory. You can switch off the lines with the command-line option 'noline'.

NOTE 2: The viewimage.pro image viewer also automatically includes line emission. But you would have to seek the precise wavelength of the lines yourself. If, however, you call viewimage with option /lines, then some extras appear that allow you to directly find the right wavelength of the lines. Try it out, and you will see how it works.

NOTE 3: If you are very limited by memory, and if you use LTE, LVG+EscProb or optically thin populations, you can also ask RADMC-3D to *not* precalculate the level populations before the rendering, but instead compute them on-the-fly. This makes the code slower, but requires less memory. You can do this by choosing e.g. lines_mode=-3 instead of lines_mode=3 (for LVG+EscProb).

7.4 The various input files for line transfer

7.4.1 INPUT: The line transfer entries in the radmc3d.inp file

Like all other modules of radmc3d, also the line module can be steered through keywords in the radmc3d.inp file. Here is a list:

• tgas_eq_tdust (default: 0)

Normally you must specify the gas temperature at each grid cell using the gas_temperature.inp file (or directly in the userdef_module.f90, see Chapter 13). But sometimes you may want to compute first the dust temperature and then set the gas temperature equal to the dust temperature. You can do this obviously by hand: read the output dust temperature and create the equivalent gas temperature input file from it. But that is cumbersome. By setting tgas_eq_tdust=1 you tell radmc3d to simply read the dust_temperature.inp file and then equate the gas temperature to the dust temperature. If multiple dust species are present, only the first species will be used.

7.4.2 INPUT: The line.inp file

Like with the dust (which has this dustopac.inp master file, also the line module has a master file: lines.inp. It specifies which molecules/atoms are to be modeled and in which file the molecular/atomic data (such as the energy levels and the Einstein A coefficients) are to be found.

The N is the number of molecular or atomic species you wish to model. Typically this is 1. But if you want to *simultaneously* model for instance the ortho- H_2O and para- H_2O infrared lines, you would need to set this to 2.

The N lines following N (i.e. lines 3 to N+2) specify the molecule or atom, the kind of input file format (explained below), and two integers which, at least for now, can be simply set to 0 (see Section 7.15 for the meaning of these integers - for experts only), plus finally third integer, which has to do with non-LTE transfer: the number of collision partners (set to 0 if you only intend to do LTE transfer).

The molecule name can be e.g. co for carbon monoxide. The file containing the data should then be called molecule_co.inp (even if it is an atom rather than a molecule; I could not find a good name which means both molecule or atom). This file should be either generated by the user, or (which is obviously the preferred option) taken from one of the databases of molecular/atomic radiative properties. Since there are a number of such databases and I want the code to be able to read those files without the need of casting them into some special RADMC-3D format, radmc3d allows the user to select which *kind* of file the molecule_co.inp (for CO) file is. At present only one format is supported: the Leiden database. But more will follow. To specify to radmc3d to use the Leiden style, you put the inpstyle to "leiden". So here is a typical example of a lines.inp file:

```
2
1
co leiden 0 0 0
```

This means: one molecule will be modeled, namely CO (and thus read from the file molecule_co.inp), and the data format is the Leiden database format.

NOTE: Since version 0.26 the file format number of this file lines.inp has increased. It is now 2, because in each line an extra integer is added.

NOTE: The files from the Leiden LAMDA database (see Section 7.4.3) are usually called something like co.dat. You will have to simply rename to molecule_co.inp.

Most molecular data files have, in addition to the levels and radiative rates, also the collision rates listed. See Section 7.4.3. For non-LTE radiative transfer this is essential information. The number densities of the collision partners (the particles with which the molecule can collide and which can collisionally excited or de-excite the molecule) are given in number density files with the same format as those of the molecule itself (see Section 7.4.10). However, we must tell RADMC-3D to which collision partner particle the rate tables listed in the molecule_co.inp are associated (see Section 7.4.10 for a better explanation of the issue here). This can be done with the last of the integers in each line. Example: if the lines.inp file reads

1

```
co leiden 0 0 2
p-h2
o-h2
```

this means that the first collision rate table (starting with the number 3.2e-11 in the example of Section 7.4.3) is for collisions with particles for which the number density is given in the file numberdens_p-h2.inp and the second collision rate table (starting with the number 4.1e-11 in the example of Section 7.4.3) is for collisions with particles for which the number density is given in the file numberdens_o-h2.inp.

We could also decide to ignore the difference between para- H_2 and ortho- H_2 , and simply use the first table (starting with the number 3.2e-11 in the example of Section 7.4.3), which is actually for para- H_2 only, as a proxy for the overall mixture of H_2 molecules. After all: The collision rate for para- H_2 and ortho- H_2 are not so very different. In that case we may simply ignore this difference and only provide a file numberdens_h2.inp, and link that to the first of the two collision rate tables:

```
2
1
co leiden 0 0 1
h2
```

(Note: we cannot, in this way, link this to the second of the two tables, only to the first). But if we would do this:

```
2
1
co leiden 0 0 3
p-h2
o-h2
h
```

we would get an error, because only two collision rate tables are provided in molecule_co.inp.

Finally, as we will explain in Section 7.4.4, there is an alternative way to feed atomic/molecular data into RADMC-3D: By using linelists. To tell RADMC-3D to read a linelist file instead of a Leiden-style molecular/atomic data file, just write the following in the lines.inp file:

```
2
1
h2o linelist 0 0 (
```

(example here is for water). This will make RADMC-3D read the linelist_h2o.inp file as a linelist file (see Section 7.4.4). Note that lines from a linelist will always be in LTE.

You can also have multiple species, for which some are of Leiden-style and some are linelist style. For instance:

```
2 2 co leiden 0 0 2 p-h2 o-h2 h2o linelist 0 0 0
```

Here the CO lines can be treated in a non-LTE manner (depending on what you put for lines_mode, see Section 7.3), and the H_2O is treated in LTE.

7.4.3 INPUT: Molecular/atomic data: The molecule_XXX.inp file(s)

As mentioned in Section 7.4.2 the atomic or molecular fundamental data such as the level diagram and the radiative decay rates (Einstein A coefficients) are read from a file (or more than one files) named molecule_xxx.inp, where the xxx is to be replaced by the name of the molecule or atom in question. For these files RADMC-3D uses the Leiden LAMDA database format. Note that, instead of a molecule_xxx.inp file you can also give a linelist file, but this will be discussed in Section 7.4.4.

The precise format of the Leiden database data files is of course described in detail on their web page¹. Here we only give a very brief overview, based on an example of CO in which only the first few levels are specified (taken

¹ http://www.strw.leidenuniv.nl/~moldata/

from the LAMDA database):

```
!MOLECULE (Data from the LAMDA database)
CO
!MOLECULAR WEIGHT
28.0
!NUMBER OF ENERGY LEVELS
!LEVEL + ENERGIES(cm^-1) + WEIGHT + J
         0.000000000 1.0 0
   1
         3.845033413 3.0 1
   2
      11.534919938 5.0 2
   4
      23.069512649 7.0 3
        38.448164669 9.0 4
   5
!NUMBER OF RADIATIVE TRANSITIONS
!TRANS + UP + LOW + EINSTEINA(s^-1) + FREQ(GHz) + E_u(K)
   1 2 1 7.203e-08 115.2712018 5.53
             2 6.910e-07
3 2.497e-06
                               230.5380000
345.7959899
   2
         3
                                               16.60
   3
         4
                                               33.19
              4 6.126e-06
                               461.0407682
                                            55.32
```

The next first few lines are self-explanatory. The first of the two tables is about the levels. Column one is simply a numbering. Column 2 is the energy of the level E_k , specified in units of 1/cm. To get the energy in erg you multiply this number with hc/k where h is the Planck constant, c the light speed and k the Boltzmann constant. Column 3 is the degeneration number, i.e. the the g parameter of the level. Column 4 is redundant information, not used by the code.

The second table is the line list. Column 1 is again a simple counter. Column 2 and 3 specify which two levels the line connects. Column 4 is the radiative decay rate in units of 1/seconds, i.e. the Einstein A coefficient. The last two columns are redundant information that can be easily derived from the other information.

If you are interested in LTE line transfer, this is enough information. However, if you want to use one of the non-LTE modes of RADMC-3D, you must also have the collisional rate data. An example of a molecule_XXX.inp file that also contains these data is:

```
!MOLECULE (Data from the LAMDA database)
CO
!MOLECULAR WEIGHT
28.0
!NUMBER OF ENERGY LEVELS
!LEVEL + ENERGIES(cm^-1) + WEIGHT + J
        0.000000000 1.0 0
   1
   2
        3.845033413 3.0 1
   3
       11.534919938 5.0 2
        23.069512649
                     7.0
   5
        38.448164669 9.0 4
!NUMBER OF RADIATIVE TRANSITIONS
!TRANS + UP + LOW + EINSTEINA(s^-1) + FREQ(GHz) + E_u(K)
       2 1 7.203e-08 115.2712018 5.53
3 2 6.910e-07 230.5380000 16.60
   1
   2
   3
         4
             3 2.497e-06
                              345.7959899
                                              33.19
        5 4 6.126e-06
   4
                              461.0407682
                                              55.32
!NUMBER OF COLL PARTNERS
!COLLISIONS BETWEEN
2 CO-pH2 from Flower (2001) & Wernli et al. (2006) + extrapolation
!NUMBER OF COLL TRANS
10
!NUMBER OF COLL TEMPS
7
!COLL TEMPS
   5.0 10.0 20.0 30.0 50.0 70.0 100.0
!TRANS + UP + LOW + COLLRATES(cm^3 s^-1)
             1 3.2e-11 3.3e-11 3.3e-11 3.4e-11 3.4e-11 3.4e-11
   1
         3
             1 2.9e-11 3.0e-11 3.1e-11 3.2e-11 3.2e-11 3.2e-11
        3 2 7.9e-11 7.2e-11 6.5e-11 6.1e-11 5.9e-11 6.0e-11 6.5e-11
             1 4.8e-12 5.2e-12 5.6e-12 6.0e-12 7.1e-12 8.4e-12 1.2e-11
        4
```

```
4.7e-11 5.0e-11 5.1e-11 5.1e-11 5.1e-11 5.1e-11
               3 9.0e-11 7.9e-11 7.1e-11 6.7e-11 6.5e-11 6.6e-11 7.2e-11
              1 2.8e-12 3.1e-12 3.4e-12 3.7e-12 4.0e-12 4.4e-12 4.0e-12
   7
               2 8.0e-12 9.6e-12 1.1e-11 1.2e-11 1.4e-11 1.6e-11 2.2e-11
               3 5.9e-11 6.2e-11 6.2e-11 6.1e-11 6.0e-11 5.9e-11 5.8e-11
   q
             4 8.5e-11 8.2e-11 7.5e-11 7.1e-11 6.9e-11 6.9e-11 7.3e-11
  10
!COLLISIONS BETWEEN
3 CO-oH2 from Flower (2001) & Wernli et al. (2006) + extrapolation
!NUMBER OF COLL TRANS
!NUMBER OF COLL TEMPS
!COLL TEMPS
   5.0 10.0 20.0 30.0 50.0 70.0 100.0
!TRANS + UP + LOW + COLLRATES(cm^3 s^-1)
        2 1 4.1e-11 3.8e-11 3.4e-11 3.3e-11 3.4e-11 3.5e-11 3.9e-11
             1 5.8e-11 5.6e-11 5.2e-11 5.0e-11 4.7e-11 4.7e-11 6.2e-11
              2 7.5e-11 7.1e-11 6.6e-11 6.2e-11 6.1e-11 6.2e-11 7.1e-11
              1 6.6e-12 7.1e-12 7.3e-12 7.5e-12 8.1e-12 9.0e-12 1.3e-11
             2 7.9e-11 8.3e-11 8.1e-11 7.8e-11 7.4e-11 7.3e-11 8.5e-11
             3 8.0e-11 7.5e-11 7.0e-11 6.8e-11 6.7e-11 6.9e-11 7.7e-11
             1 5.8e-12 6.1e-12 6.1e-12 6.1e-12 6.2e-12 6.3e-12 7.8e-12
               2 1.0e-11 1.2e-11 1.4e-11 1.4e-11 1.6e-11 1.8e-11 2.2e-11
   9
               3 8.3e-11 8.9e-11 9.0e-11 8.8e-11 8.3e-11 8.1e-11 8.7e-11
               4 8.0e-11 7.9e-11 7.5e-11 7.2e-11 7.1e-11 7.1e-11 7.6e-11
```

As you see, the first part is the same. Now, however, there is extra information. First, the number of collision partners, for which these collisional rate data is specified, is given. Then follows the reference to the paper containing these data (this is not used by RADMC-3D; it is just for information). Then the number of collisional transitions that are tabulated (since collisions can relate any level to any other level, this number should ideally be nlevels*(nlevels-1)/2, but this is not strictly enforced). Then the number of temperature points at which these collisional rates are tabulated. Then follows this list of temperatures. Finally we have the table of collisional transitions. Each line consists of, first, the ID of the transition (dummy), then the upper level, then the lower level, and then the $K_{\rm up,low}$ collisional rates in units of [cm³/s]. The same is again repeated (because in this example we have two collision partners: the para- H_2 molecule and the ortho- H_2 molecule).

To get the collision rate $C_{\rm up,low}$ per molecule (in units of [1/sec]) for the molecule of interest, we must multiply $K_{\rm up,low}$ with the number density of the collision partner (see Section 7.4.10). So in this example, the $C_{\rm up,low}$ becomes:

$$C_{\text{up,low}} = N_{\text{p-H}_2} K_{\text{up,low}}^{\text{p-H}_2} + N_{\text{o-H}_2} K_{\text{up,low}}^{\text{o-H}_2}$$
 (7.10)

The rates tabulated in this file are always the *downward* collision rate. The upward rate is internally computed by RADMC-3D using the following formula:

$$C_{\text{low,up}} = C_{\text{up,low}} \frac{g_{\text{up}}}{g_{\text{low}}} \exp\left(-\frac{\Delta E}{kT}\right)$$
 (7.11)

where the g factors are the statistical weights of the levels, ΔE is the energy difference between the levels, k is the Boltzmann constant and T the gas temperature.

Some notes:

- When doing LTE transfer *and* you make RADMC-3D read a separate file with the partition function (Section 7.4.9), you can limit the molecule_XXX.inp files to just the levels and lines you are interested in. But again: You *must* then read the partition function separately, and not let RADMC-3D compute it internally based on the molecule_XXX.inp file.
- When doing non-LTE transfer and/or when you let RADMC-3D compute the partition function internally you *must* make sure to include all possible levels that might get populated, otherwise you may overpredict the strength of the lines you are interested in.
- The association of each of the collision partners in this file to files that contain their spatial distribution is a bit complicated. See Section 7.4.10.

7.4.4 INPUT: Molecular/atomic data: The linelist_XXX.inp file(s)

In many cases molecular data are merely given as lists of lines (e.g. the HITRAN database, the Kurucz database, the Jorgensen et al. databases etc.). These line lists contain information about the line wavelength λ_0 , the line strength $A_{\rm ud}$, the statistical weights of the lower and upper level and the energy of the lower or upper level. Sometimes also the name or set of quantum numbers of the levels, or additional information about the line profile shapes are specified. These line lists contain no *direct* information about the level diagram, although this information can be extracted from the line list (if it is complete). These lines lists also do not contain any information about collisional (de-)excitation, so they cannot be used for non-LTE line transfer of any kind. They only work for LTE line transfer. But such line lists are nevertheless used often (and thus LTE is then assumed).

RADMC-3D can read the molecular data in line-list-form (files named linelist_XXX.inp). RADMC-3D can in fact use both formats mixed (the line list one and the "normal" one of Section 7.4.3). Some molecules may be specified as line lists (linelist_XXX.inp) while simultaneously others as full molecular files (molecule_XXX.inp, see Section 7.4.3). For the "linelist molecules" RADMC-3D will then automatically use LTE, while for the other molecules RADMC-3D will use the mode according to the lines_mode value. This means that you can use this to have mixed LTE and non-LTE species of molecules/atoms within the same model, as long as the LTE ones have their molecular/atomic data given in a line list form. This can be useful to model situations where most of the lines are in LTE, but one (or a few) are non-LTE.

Now coming back to the linelist data. Here is an example of such a file (created from data from the HITRAN database):

```
! RADMC-3D Standard line list
! Format number:
1
! Molecule name:
h2o
! Reference: From the HITRAN Database (see below for more info)
! Molecular weight (in atomic units)
  18.010565
! Include table of partition sum? (0=no. 1=ves)
! Include additional information? (0=no, 1=yes)
! Nr of temperature points for the partition sum
    2931
! Temp [K]
                PartSum
 7.000000E+01 2.100000E+01
 7.100000E+01
              2.143247E+01
 7.200000E+01 2.186765E+01
 7.300000E+01 2.230553E+01
. . . .
 2.997000E+03 1.594216E+04
 2.998000E+03 1.595784E+04
 2.999000E+03 1.597353E+04
 3.000000E+03 1.598924E+04
! Nr of lines
  37432
      Lambda [mic] Aud [sec^-1] E_lo [cm^-1] E_up [cm^-1] g_lo g_up
                                                                      9.
     1 1.387752E+05 5.088000E-12 1.922829E+03 1.922901E+03
                                                              11.
       2.496430E+04 1.009000E-09 1.907616E+03 1.908016E+03
                                                                21.
                                                                      27.
     3 1.348270E+04 1.991000E-09 4.465107E+02 4.472524E+02
                                                                33.
                                                                      39.
     4 1.117204E+04 8.314000E-09 2.129599E+03 2.130494E+03
                                                                27.
                                                                      33.
     5 4.421465E+03 1.953000E-07 1.819335E+03 1.821597E+03
                                                                21.
                                                                      27.
. . . .
 37429 3.965831E-01 3.427000E-05 7.949640E+01 2.529490E+04
                                                                15.
                                                                      21.
 37430 3.965250E-01 1.508000E-04 2.121564E+02 2.543125E+04
                                                                21.
                                                                      27.
 37431 3.964335E-01 5.341000E-05 2.854186E+02 2.551033E+04
                                                                21.
                                                                      27.
 37432 3.963221E-01 1.036000E-04 3.825169E+02 2.561452E+04
```

The file is pretty self-explanatory. It contains a table for the partition function (necessary for LTE transfer) and a table with all the lines (or any subset you wish to select). The lines table columns are as follows: first column is

just a dummy index. Second column is the wavelength in micron. Third is the Einstein-A-coefficient (spontaneous downward rate) in units of sec⁻¹. Fourth and fifth are the energies above the ground state of the lower and upper levels belonging to this line in units of cm⁻¹. Sixth and seventh are the statistical weights (degenracies) of the lower and upper levels belonging to this line.

Note that you can tell RADMC-3D to read linelist_h2o.inp (instead of search for molecule_h2o.inp) by specifying linelist instead of leiden in the lines.inp file (see Section 7.4.2).

7.4.5 INPUT: The number density of each molecular species

For the line radiative transfer we need to know how many molecules of each species are there per cubic centimeter. For molecular/atom species XXX this is given in the file numberdens_XXX.inp (see Chapter B for the binary version of this file, which is more compact, and which you can use instead of the ascii version). For each molecular/atomic species listed in the lines.inp file there must be a corresponding numberdens_XXX.inp file. The structure of the file is very similar (though not identical) to the structure of the dust density input file dust_density.inp (Section A.3). For the precise way to address the various cells in the different AMR modes, we refer to Section A.3, where this is described in detail.

For formatted style (numberdens_XXX.inp):

The number densities are to be specified in units of molecule per cubic centimeter.

7.4.6 INPUT: The gas temperature

For line transfer we need to know the gas temperature. You specify this in the file <code>gas_temperature.inp</code> (see Chapter B for the binary version of these files, which are more compact, and which you can use instead of the ascii versions). The structure of this file is identical to that described in Section 7.4.5, but of course with number density replaced by gas temperature in Kelvin. For the precise way to address the various cells in the different AMR modes, we refer to Section A.3, where this is described in detail.

Note: Instead of literally specifying the gas temperature you can also tell radmc3d to copy the dust temperature (if it know it) into the gas temperature. See the keyword tgas_eq_tdust described in Section 7.4.1.

7.4.7 INPUT: The velocity field

Since gas motions are usually the main source of Doppler shift or broadening in astrophysical settings, it is obligatory to specify the gas velocity. This can be done with the file gas_velocity.inp (see Chapter B for the binary version of these files, which are more compact, and which you can use instead of the ascii versions). The structure is again similar to that described in Section 7.4.5, but now with three numbers at each grid point instead of just one. The three numbers are the velocity in x, y and z direction for Cartesian coordinates, or in r, θ and ϕ direction for spherical coordinates. Note that both in cartesian coordinates and in spherical coordinates all velocity components have the same dimension of cm/s. For spherical coordinates the conventions are: positive v_r points outwards, positive v_θ points downward (toward larger θ) for $0 < \theta < \pi$ (where "downward" is toward smaller z), and positive v_ϕ means velocity in counter-clockwise direction in the x, y-plane.

For the precise way to address the various cells in the different AMR modes, we refer to Section A.3, where this is described in detail.

7.4.8 INPUT: The local microturbulent broadening (optional)

The radmc3d code automatically includes thermal broadening of the line. But sometimes it is also useful to specify a local (spatially unresolved) turbulent width. This is not obligatory (if it is not specified, only the thermal broadening

is used) but if you want to specify it, you can do so in the file microturbulence.inp (see Chapter B for the binary version of these files, which are more compact, and which you can use instead of the ascii versions). The file format is the same structure as described in Section 7.4.5. For the precise way to address the various cells in the different AMR modes, we refer to Section A.3, where this is described in detail.

Here is the way it is included into the line profile:

$$a_{\text{linewidth}}^2 = a_{\text{turb}}^2 + \frac{2kT_{\text{gas}}}{\mu} \tag{7.12}$$

where $T_{\rm gas}$ is the temperature of the gas, μ the molecular weight, k the Boltzmann constant and $a_{\rm turb}$ the microturbulent line width in units of cm/s. The $a_{\rm linewidth}$ is then the total (thermal plus microturbulent) line width.

7.4.9 INPUT for LTE line transfer: The partition function (optional)

If you use the LTE mode (either lines_mode=-1 or lines_mode=1), then the partition function is required to calculate, for a given temperature the populations of the various levels. Since this involves a summation over *all* levels of all kinds that can possibly be populated, and since the molecular/atomic data file may not include all these possible levels, it may be useful to look the partition function up in some literature and give this to radmc3d. This can be done with the file partitionfunction_XXX.inp, where again XXX is here a placeholder for the actual name of the molecule at hand. If you do not have this file in the present model directory, then radmc3d will compute the partition function itself, but based on the (maybe limited) set of levels given in the molecular data file. The structure of the partitionfunction_XXX.inp file is:

NOTE: RADMC-3D assumes the partition function to be defined in the following way:

$$Z(T) = \sum_{i=1} g_i e^{-(E_i - E_1)/kT}$$
(7.13)

In other words: the first level is assumed to be the ground state. This is done so that one can also use an energy definition in which the ground state energy is non-zero (example: Hydrogen $E_1 = -13.6 \,\text{eV}$). If you use molecular line datafiles that contain only a subset of levels (which is in principle no problem for LTE calculations) then it is essential that the ground state is included in this list, and that it is the first level (ilevel=1).

7.4.10 INPUT: The number density of collision partners (for non-LTE transfer)

For non-LTE line transfer (see e.g. Sections 7.6, 7.7) the molecules can be collisionally excited. The collision rates for each pair of molecule + collision partner are given in the molecular input data files (Section 7.4.3). To find how often a molecular level of a single molecule is collisionally excited to another level we also need to know the number density of the collision partner molecules. In the example in Section 7.4.3 these were para-H₂ and ortho-H₂. We must therefore somehow tell RADMC-3D what the number densities of these molecules are. This is done by reading in the number densities for this(these) collision partner(s). The file for this has exactly the same format as that for the number density of any molecule (see Section 7.4.5). So for our example we would thus have two files, which could be named numberdens_p-h2.inp and numberdens_o-h2.inp respectively. See Section 7.4.5 for details.

However, how does RADMC-3D know that the first collision partner of CO is called "p-h2" and the second "o-h2"? In principle the file molecule_co.inp give some information about the name of the collision partners. But this is often not machine-readable. Example, in molecule_co.inp of Section 7.4.3 the line that should tell this reads

```
2 CO-pH2 from Flower (2001) & Wernli et al. (2006) + extrapolation
```

for the first of the two (which is directly from the LAMDA database). This is hard to decipher for RADMC-3D. Therefore you have to tell this explicitly in the file lines.inp, and we refer to Section 7.4.2 for how to do this.

7.5 Making images and spectra with line transfer

Making images and spectra with/of lines works in the same way as for the continuum. RADMC-3D will check if the file lines.inp is present in your directory, and if so, it will automatically switch on the line transfer. If you insist on *not* having the lines switched on, in spite of the presence of the lines.inp file, you can add the option noline to radmc3d on the command line. If you don't, then lines are normally automatically switched on, except in situations where it is obviously not required.

You can just make an image at some wavelength and you'll get the image with any line emission included if it is there. For instance, if you have the molecular data of CO included, then

```
radmc3d image lambda 2600.757
```

will give an image right at the CO 1-0 line center. The code will automatically check if (and if yes, which) line(s) are contributing to the wavelength of interest. Also it will include all the continuum emission (and absorption) that you would usually obtain.

There is, however, an exception to this automatic line inclusion: If you make a spectral energy distribution (with the command sed, see Section 9.3), then lines are not included. The same is true if you use the loadcolor command. But for normal spectra or images the line emission will automatically be included. So if you make a spectrum at wavelength around some line, you will get a spectrum including the line profile from the object, as well as the dust continuum.

It is not always convenient to have to know by heart the exact wavelengths of the lines you are interested in. So RADMC-3D allows you to specify the wavelength by specifying which line of which molecule, and at which velocity you want to render:

```
radmc3d image iline 2 vkms 2.4
```

If you have CO as your molecule, then iline 2 means CO 2-1 (the second line in the rotational ladder).

By default the first molecule is used (if you have more than one molecule), but you can also specify another one:

```
radmc3d image imolspec 2 iline 2 vkms 2.4
```

which would select the second molecule instead of the first one.

If you wish to make an entire spectrum of the line, you can do for instance:

```
radmc3d spectrum iline 1 widthkms 10
```

which produces a spectrum of the line with a passband going from -10 km/s to +10 km/s. By default 40 wavelength points are used, and they are evenly spaced. You can set this number of wavelengths:

```
radmc3d spectrum iline 1 widthkms 10 linenlam 100
```

which would make a spectrum with 100 wavelength points, evenly spaced around the line center. You can also shift the passband center:

```
radmc3d spectrum iline 1 widthkms 10 linenlam 100 vkms -10
```

which would make the wavelength grid 10 kms shifted in short direction.

For more details on how to specify the spectral sampling, please read Section 9.4. Note that keywords such as incl, phi, and any other keywords specifying the camera position, zooming factor etc, can all be used in addition to the above keywords.

7.5.1 Speed versus realism of rendering of line images/spectra

As usual with numerical modeling: including realism to the modeling goes at the cost of rendering speed. A "fully realistic" rendering of a model spectrum or image of a gas line involves (assuming the level populations are already known):

- 1. Doppler-shifted emission and absorption.
- 2. Inclusion of dust thermal emission and dust extinction while rendering the lines.
- 3. Continuum emission scattered by dust into the line-of-sight
- 4. Line emission from (possibly obscured) other regions is allowed to scatter into the line-of-sight by dust grains (see Section 7.5.2).

RADMC-3D always includes the Doppler shifts. By default, RADMC-3D also includes dust thermal emission and extinction, as well as the scattered continuum radiation.

For many lines, however, dust continuum scattering is a negligible portion of the flux, so you can speed things up by not including dust scattering! This can be easily done by adding the noscat option on the command-line when you issue the command for a line spectrum or multi-frequency image. This way, the scattering source function is not computed (is assumed to be zero), and no scattering Monte Carlo runs are necessary. This means that the ray-tracer can now render all wavelength simultaneously (each ray doing all wavelength at the same time), and the local level populations along each ray can now be computed once, and be used for all wavelengths. This may speed up things drastically, and for most purposes virtually perfectly correct. Just beware that when you render short-wavelength lines (optical) or you use large grains, i.e. when the scattering albedo at the wavelength of the line is not negligible, this may result in a mis-estimation of the continuum around the line.

7.5.2 Line emission scattered off dust grains

NOTE: The contents of this subsection may not be 100% implemented yet.

Also any line emission from obscured regions that get scattered into the line of sight by the dust (if dust scattering is included) will be included. Note, however, that any possible Doppler shift *induced* by this scattering is *not* included. This means that if line emission is scattered by a dust cloud moving at a very large speed, then this line emission will be scattered by the dust, but no Doppler shift at the projected velocity of the dust will be added. Only the Doppler shift of the line-emitting region is accounted for. This is rarely a problem, because typically the dust that may scatter line emission is located far away from the source of line emission and moves at substantially lower speed.

7.6 Non-LTE Transfer: The Large Velocity Gradient (LVG) + Escape Probability (EscProb) method

The assumption that the energy levels of a molecule or atom are always populated according to a thermal distribution (the so-called "local thermodynamic equilibrium", or LTE, assumption) is valid under certain circumstances. For instance for planetary atmospheres in most cases. But in the dilute interstellar medium this assumption is very often invalid. One must then compute the level populations consistent with the local density and temperature, and often also consistent with the local radiation field. Part of this radiation field might even be the emission from the lines themselves, meaning that the molecules radiatively influence their neighbors. Solving the level populations self-consistently is called "non-LTE radiative transfer". A full non-LTE radiative transfer calculation is, however, in most cases (a) too numerically demanding and sometimes (b) unnecessary. Sometimes a simple approximation of the non-LTE effects is sufficient.

One such approximation method is the "Large Velocity Gradient" (LVG) method, also called the "Sobolev approximation". Please read for instance the paper by Ossenkopf (1997) "The Sobolev approximation in molecular clouds", New Astronomy, 2, 365 for more explanation, and a study how it works in the context of molecular clouds. The LVG mode of RADMC-3D has been used for the first time by Shetty et al. (2011, MNRAS 412, 1686), and a description

of the method is included in that paper. The nice aspect of this method is that it is, for most part, local. The only slightly non-local aspect is that a velocity gradient has to be computed by comparing the gas velocity in one cell with the gas velocity in neighboring cells.

As of RADMC-3D Version 0.33 the LVG method is combined with an escape probability (EscProb) method. In fact, LVG *is* a kind of escape probability method itself. It is just that for the classic EscProb method the photons can escape due to the finite size of the object, and thus the finite optical depth in the lines. In the LVG the object size is not the issue, but the gradient of the velocity. The line width combined with the velocity gradient give a length scale over which a photon can escape.

In the LVG + EscProb method the line-integrated mean intensity J_{ij} is given by

$$J_{ij} = (1 - \beta_{ij})S_{ij} + \beta_{ij}J_{ij}^{\text{bg}}$$
(7.14)

where $J_{ij}^{\rm bg}$ is the mean intensity of the background radiation field at frequency $\nu = \nu_{ij}$ (default is blackbody at 2.73 K, but this temperature can be varied with the lines_tbg variable in radmc3d.inp), while β_{ij} is the escape probability for line $i \to j$. This is given by

$$\beta_{ij} = \frac{1 - \exp(-\tau_{ij})}{\tau_{ij}} \tag{7.15}$$

where τ_{ij} is the line-center optical depth in the line.

For the LVG method this optical depth is given by the velocity gradient:

$$\tau_{ij}^{\text{LVG}} = \frac{ch}{4\pi} \frac{N_{\text{molec}}}{1.064 |\nabla \vec{v}|} [n_j B_{ji} - n_i B_{ij}]
= \frac{c^3}{8\pi \nu_{ij}^3} \frac{A_{ij} N_{\text{molec}}}{1.064 |\nabla \vec{v}|} \left[\frac{g_i}{g_j} n_j - n_i \right]$$
(7.16)

(see e.g. van der Tak et al. 2007, A&A 468, 627), where n_i is the fractional level population of level i, $N_{\rm molec}$ the total number density of the molecule, $|\nabla \vec{v}|$ the absolute value of the velocity gradient, g_i the statistical weight of level i and ν_{ij} the line frequency for transition $i \to j$. In comparing to Eq. 21 of van der Tak's paper, note that their $N_{\rm mol}$ is a column density (cm⁻²) and their ΔV is the line width (cm/s), while our $N_{\rm molec}$ is the number density (cm⁻³) and $|\nabla \vec{v}|$ is the velocity gradient (s⁻¹). Their formula is thus in fact EscProb while ours is LVG.

For the EscProb method *without* velocity gradients, we need to be able to compute the total column depth Σ_{molec} in the direction where this Σ_{molec} is minimal. This is something that, at the moment, RADMC-3D cannot yet do. But this is something that can be estimated based on a "typical length scale" L, such that

$$\Sigma_{\text{molec}} \simeq N_{\text{molec}} L$$
 (7.17)

RADMC-3D allows you to specify L separately for each cell (in the file escprob_lengthscale.inp or its binary version). The simplest would be to set it to a global value equal to the typical size of the object we are interested in. Then the line-center optical depth, assuming a Gaussian line profile with width $a_{\rm linewidth}$, is

$$\tau_{ij}^{\text{EscProb}} = \frac{hc\Sigma_{\text{molec}}}{4\pi\sqrt{\pi}\,a_{\text{linewidth}}} \left[n_j B_{ji} - n_i B_{ij} \right] \tag{7.18}$$

because $\phi(\nu = \nu_{ij}) = c/(a\nu_{ij}\sqrt{\pi})$.

The optical depth of the combined LVG + EscProb method is then:

$$\tau_{ij} = \min\left(\tau_{ij}^{\text{LVG}}, \tau_{ij}^{\text{EscProb}}\right) \tag{7.19}$$

This is then the τ_{ij} that needs to be inserted into Eq. (7.15) for obtaining the escape probability β_{ij} (which includes escape due to LVG as well as the finite length scale L).

The LVG+EscProb method solves at each location the following statistical equilibrium equation:

$$\sum_{j>i} \left[n_j A_{ji} + (n_j B_{ji} - n_i B_{ij}) J_{ji} \right]$$

$$- \sum_{j

$$+ \sum_{j\neq i} \left[n_j C_{ji} - n_i C_{ij} \right] = 0$$
(7.20)$$

Replacing J_{ij} (and similarly J_{ji}) with the expression of Eq. (7.14) and subsequently replacing S_{ij} with the well-known expression for the line source function

$$S_{ij} = \frac{n_i A_{ij}}{n_j B_{ji} - n_i B_{ij}} \tag{7.21}$$

leads to

$$\sum_{j>i} \left[n_{j} A_{ji} \beta_{ji} + (n_{j} B_{ji} - n_{i} B_{ij}) \beta_{ji} J_{ji}^{\text{bg}} \right]$$

$$- \sum_{j

$$+ \sum_{j\neq i} \left[n_{j} C_{ji} - n_{i} C_{ij} \right] = 0$$
(7.22)$$

A few iteration steps are necessary, because the β_{ij} depends on the optical depths, which depend on the populations. But since this is only a weak dependence, the iteration should converge rapidly.

To use the LVG+EscProb method, the following has to be done:

- Make sure that you use a molecular data file that contains collision rate tables (see Section 7.4.3).
- Make sure to provide file(s) containing the number densities of the collision partners, e.g. numberdens_p-h2.inp (see Section 7.4.10).
- Make sure to link the rate tables to the number density files in lines.inp (see Section 7.4.2).
- Set the lines_mode=3 in the radmc3d.inp file.
- You may want to also specify the maximum number of iterations for non-LTE iterations, by setting lines_nonlte_maxiter in the radmc3d.inp file. The default is 100 (as of version 0.36). If convergence is not reached within lines_nonlte_maxiter iterations, RADMC-3D stops.
- You may want to also specify the convergence criterion for non-LTE iterations, by setting lines_nonlte_converit in the radmc3d.inp file. The default is 1d-2 (which is not very strict! Smaller values may be necessary).
- Specify the gas velocity vector field in the file gas_velocity.inp (or .binp), see Section 7.4.7. If this file is not present, the gas velocity will be assumed to be 0 everywhere, meaning that you have pure escape probability.
- Specify the "typical length scale" *L* at each cell in the file escprob_lengthscale.inp (or .binp). If this file is not present, then the length scale is assumed to be infinite, meaning that you are back at pure LVG. The format of this file is identical to that of the gas density.

Note that having no escproblengthscale.inp nor gas_velocity.inp file in your model directory means that the photons cannot escape at all, and you should find LTE populations (always a good test of the code).

Note that it is essential, when using the Large Velocity Gradient method without specifying a length scale, that the gradients in the velocity field (given in the file gas_velocity.inp, see Section 7.4.7) are indeed sufficiently large. If they are zero, then this effectively means that the optical depth in all the lines is assumed to be infinite, which means that the populations are LTE again. If you use LVG but *also* specify a length scale in the escprob_lengthscale.inp file, then this danger of unphysically LTE populations is avoided.

NOTE: Currently this method does not yet include radiative exchange with the dust continuum radiation field.

NOTE: Currently this method does not yet include radiative pumping by stellar radiation. Will be included soon.

7.7 Non-LTE Transfer: The optically thin line assumption method

An even simpler non-LTE method is applicable in *very* dilute media, in which the lines are all optically thin. This means that a photon that is emitted by the gas will never be reabsorbed. If this condition is satisfied, then the

non-LTE level populations can be computed even easier than in the case of LVG (Section 7.6). No iteration is then required. So to activate this, the following has to be done:

- Make sure that you use a molecular data file that contains collision rate tables (see Section 7.4.3).
- Make sure to provide file(s) containing the number densities of the collision partners, e.g. numberdens_p-h2.inp (see Section 7.4.10).
- Make sure to link the rate tables to the number density files in lines.inp (see Section 7.4.2).
- Set the lines_mode=4 in the radmc3d.inp file (see Section A.1).

NOTE: Currently this method does not yet include radiative pumping by stellar radiation. Will be included soon.

NOTE: This mode does not **make** a model optically thin. Only the populations of the levels are computed under the **assumption** that the lines are optically thin. If you subsequently make a spectrum or image of your model, all absorption effects are again included.

7.8 Non-LTE Transfer: Full non-local modes (FUTURE)

In the near future RADMC-3D will hopefully also feature full non-LTE transfer, in which the level populations are coupled to the full non-local radiation field. Methods such as *lambda iteration* and *accelerated lambda iteration* will be implemented. For nomenclature we will call these "non-local non-LTE modes".

For these non-local non-LTE modes the level population calculation is done separately from the image/spectrum ray-tracing: You will run RADMC-3D first for computing the non-LTE populations. RADMC-3D will then write these to file. Then you will call RADMC-3D for making images/spectra. This is very similar to the dust transfer, in which you first call RADMC-3D for the Monte Carlo dust temperature computation, and after that for the ray-tracing. It is, however, different from the *local non-LTE* modes, where the populations are calculated automatically before any image/spectrum ray-tracing, and the populations do not have to be written to file (only if you want to inspect them: Section 7.9).

For now, however, RADMC-3D still does not have the non-local non-LTE modes. Stay tuned...

7.9 Non-LTE Transfer: Inspecting the level populations

When doing line radiative transfer it is often useful to inspect the level populations. For instance, you may want to inspect how far from LTE your populations are, or just check if the results are reasonable. There are two ways to do this:

1. When making an image or spectrum, add the command-line option writepop, which will make RADMC-3D create output files containing the level population values. Example:

```
radmc3d image lambda 2300 writepop
```

2. Just calling radmc3d with the command-line option calcpop, which will ask RADMC-3D to compute the populations and write them to file, even without making any images or spectra. Example:

```
radmc3d calcpop
```

NOTE: For (future) non-local non-LTE modes (Section 7.8) these level populations will anyway be written to a file, irrespective of the writepop command.

The resulting files will have names such as levelpop_co.dat (for the CO molecule). The structure is as follows:

```
popul[level1,2] popul[level2,2] ..... <=== Populations (for subset) at cell 2
.
.
popul[level1,nrcells] popul[level2,nrcells] ....</pre>
```

The first number is the format number, which is simply for RADMC-3D to be backward compatible in the future, in case we decide to change/improve the file format. The nrcells is the number of cells.

Then follows the number of levels (written as "nrlevels_subset" above). Note that this is *not necessarily* equal to the number of levels found in the molecule_co.inp file (for our CO example). It will only be equal to that if the file has been produced by the command radmc3d calcpop. If, however, the file was produced after making an image or spectrum (e.g. through the command radmc3d image lambda 2300 writepop), then RADMC-3D will only write out those levels that have been used to make the image or spectrum. See Section 7.13 for more information about this. It is for this reason that the file in fact contains a list of levels that are included (the level1 level 2 . . . in the above file format example).

After these header lines follows the actual data. Each line contains the populations at a spatial cell in units of cm⁻³.

This file format is a generalization of the standard format which is described for the example of dust density in Section A.3. Please read that section for more details, and also on how the format changes if you use "layers".

Also the unformatted style is described in Section A.3. We have, however, here the extra complication that at each cell we have more than one number. Essentially this simply means that the length of the data per cell is larger, so that fewer cells fit into a single record.

7.10 Non-LTE Transfer: Reading the level populations from file

Sometimes you may want to make images and/or spectra of lines based on level populations that you calculated using another program (or calculated using RADMC-3D at some earlier time). You can ask RADMC-3D to read these populations from files with the same name and same format as, for example, levelpop_co.dat (for CO) as described in Section 7.9. The way to do this is to add a line:

```
lines_mode = 50
```

to the radmc3d.inp file.

You can test that it works by calculating the populations using another lines_mode and calling radmc3d calcpop writepop (which will produce the levelpop_xxx.dat file); then change lines_mode to 50, and call radmc3d image iline 1. You should see a message that RAMDC-3D is actually reading the populations (and it may, for 3-D models, take a bit of time to read the large file).

Because of the rather lage size of these files for 3-D models, it might be worthwhile to make sure to reduce the number of levels of the molecule_xx.inp files to only those you actually need.

7.11 What can go wrong with line transfer?

Even the simple task of performing a ray-tracing line transfer calculation with given level populations (i.e. the so-called *formal transfer equation*) is a non-trivial task in complex 3-D AMR models with possibly highly supersonic motions. I recommend the user to do extensive and critical experimentation with the code and make many simple tests to check if the results are as they are expected to be. In the end a result must be understandable in terms of simple argumentation. If weird effects show up, please do some detective work until you understand why they show up, i.e. that they are either a *real* effect or a numerical issue. There are many numerical artifacts that can show up that are *not* a bug in the code. The code simply does a numerical integration of the equations on some spatial- and wavelength-grid. If the user chooses these grids unwisely, the results may be completely wrong even if the code is formally OK. These possible pitfalls is what this section is about.

So here is a list of things to check:

1. Make sure that the line(s) you want to model are indeed in the molecular data file you use. Also make sure




Figure 7.1. Left: Pictographic representation of the doppler jumping problem with ray-tracing through a model with strong cell-to-cell velocity differences. Right: Pictographic representation of the doppler catching method to prevent this problem: First of all, second order integration is done instead of first order. Secondly, the method automatically detects a possibly dangerous doppler jump and makes sub-steps to neatly integrate over the line that shifts in- and out of the wavelength channel of interest.

that it/they are included in the line selection (if you are using this option; by default all lines and levels from the molecular/atomic data files are included; see Section 7.13).

- 2. If you do LTE line transfer, and you do not let radmc3d read in a special file for the partition function, then the partition function will be computed internally by radmc3d. The code will do so based on the levels specified in the molecule_XXX.inp file for molecule XXX. This requires of course that all levels that may be excited at the temperatures found in the model are in fact present in the molecule_XXX.inp file. If, for instance, you model 1.3 mm and 2.6 mm rotational lines of CO gas of up to 300 K, and your file molecule_co.inp only contains the first three levels because you think you only need those for your 1.3 and 2.6 mm lines, and you don't specify the partition function explicitly, then radmc3d will compute the partition function for all temperatures including 300 K based on only the first three levels. This is evidently wrong. The nasty thing is: the resulting lines won't be totally absurd. They will just be too bright. But this can easily go undetected by you as the user. So please keep this always in mind. Note that if you make a selection of the first three levels (see Section 7.15) but the file molecule_XXX.inp contains many more levels, then this problem will not appear, because the partition function will be calculated on the original data from the molecule_XXX.inp file, not from the selected levels. Of course it is safer to specify the true partition function directly through the file partitionfunction_XXX.inp (see Section 7.4.9).
- 3. If you have a model with non-zero gas velocities, and if these gas velocities have cell-to-cell differences that are larger than or equal to the intrinsic (thermal+microturbulent) line width, then the ray-tracing will not be able to pick up signals from intermediate velocities. In other words, because of the discrete gridding of the model, only discrete velocities are present, which can cause numerical problems. See Fig. 7.1-Left for a pictographic representation of this problem. There are two possible solutions. One is the wavelength band method described in Section 9.5. But a more systematic method is the "doppler catching" method described in Section 7.12 (which can be combined with the wavelength band method of Section 9.5 to make it even more perfect).

7.12 Preventing doppler jumps: The "doppler catching method"

If the local co-moving line width of a line (due to thermal/fundamental broadning and/or local subgrid "microturbulence") is much smaller than the typical velocity fields in the model, then a dangerous situation can occur. This can happen if the co-moving line width is narrower than the doppler shift between two adjacent cells. When a ray is traced, in one cell the line can then have a doppler shift substantially to the blue of the wavelength-of-sight, while in the next cell the line suddenly shifted to the red side. If the intrinsic (= thermal + microturbulent) line width is smaller than these shifts, neither cell gives a contribution to the emission in the ray. See Fig. 7.1-Left for a pictographic representation of this problem. In reality the doppler shift between these two cells would be smooth, and thus the line would smoothly pass over the wavelength-of-sight, and thus make a contribution. Therefore the numerical integration may thus go wrong.

The problem is described in more detail in Section 9.5, and one possible solution is proposed there. But that solution does not always solve the problem.

RADMC-3D has a special method to catch situations like the above, and when it detects one, to make sub-steps in the integration of the formal transfer equation so that the smooth passing of the line through the wavelength-of-sight can be properly accounted for. Here this is called "doppler catching", for lack of a better name. The technique was discussed in great detail in Pontoppidan et al. (2009, ApJ 704, 1482). The idea is that the method automatically tests if a line might "doppler jump" over the current wavelength channel. If so, it will insert substeps in the integration at the location where this danger is present. See Fig. 7.1-Right for a pictographic representation of this method. Note that this method can only be used with the second order ray-tracing (see Section 9.8); in fact, as soon as you switch the doppler catching on, RADMC-3D will automatically also switch on the second order ray-tracing.

To switch on doppler catching, you simply add the command-line option doppcatch to the image or spectrum command. For instance:

```
radmc3d spectrum iline 1 widthkms 10 doppcatch
```

(again: you do not need to add secondorder, because it is automatic when doppcatch is used).

The Doppler catching method will assure that the line is integrated over with small enough steps that it cannot accidently get jumped over. How fine these steps will be can be adjusted with the <code>catch_doppler_resolution</code> keyword in the <code>radmc3d.inp</code> file. The default value is 0.2, meaning that it will make the integration steps small enough that the doppler shift over each step is not more than 0.2 times the local intrinsic (thermal+microturbulent) line width. That is usually enough, but for some problems it might be important to ensure that smaller steps are taken. By adding a line

```
catch_doppler_resolution = 0.05
```

to the radmc3d.inp file you will ensure that steps are small enough that the doppler shift is at most 0.05 times the local line width.

So why is doppler catching an *option*, i.e. why would this not be standard? The reason is that doppler catching requires second order integration, which requires RADMC-3D to first map all the cell-based quantities to the cell-corners. This requires extra memory, which for very large models can be problematic. It also requires more CPU time to calculate images/spectra with second order integration. So if you do not need it, i.e. if your velocity gradients are not very steep compared to the intrinsic line width, then it saves time and memory to not use doppler catching.

It is, however, important to realize that doppler catching is not the golden bullet. Even with doppler catching it might happen that some line flux is lost, but this time as a result of too low *image resolution*. This is less likely to happen in problems like ISM turbulence, but it is pretty likely to happen in models of rotating disks. Suppose we have a very thin local line width (i.e. low gas temperature and no microturbulence) in a rotating thin disk around a star. In a given velocity channel (i.e. at a given observer-frame frequency) a molecular line in the disk emits only in a very thin "ear-shaped" ring or band in the image. The thinner the intrinsic line width, the thinner the band on the image. See Pontoppidan et al. (2009, ApJ 704, 1482) and Pavlyuchenkov et al. (2007, ApJ 669, 1262) for example. If the pixel-resolution of the image is smaller than that of this band, the image is simply underresolved. This has nothing to do with the doppler jumping problem, but can be equally devastating for the results if the user is unaware of this. There appears to be only one proper solution: assure that the pixel-resolution of the image is sufficiently fine for the problem at hand. This is easy to find out: The image would simply look terribly noisy if the resolution is insufficient. However, if you are not interested in the images, but only in the spectra, then some amount of noisiness in the image (i.e. marginally sufficient resolution) is OK, since the total flux is an integral over the entire image, smearing out much of the noise. It requires some experimentation, though.

Here are some additional issues to keep in mind:

• The doppler catching method uses second order integration (see Section 9.8), and therefore all the relevant quantities first have to be interpolated from the cell centers to the cell corners. Well inside the computational domain this amounts to linear interpolation. But at the edges of the domain it would require *extra*polation² RADMC-3D does not do extrapolation but simply takes the average values of the nearest cells. Also the gas velocity is treated like this. This means that over the edge cells the gradient in the gas velocity tends to be (near) 0. Since for the doppler catching it is the gradient of the velocity that matters, this might yield some

 $^{^2}$ In 1-D this is more easily illustrated, because there the cell corners are in fact cell interfaces. Cells i and i+1 share cell interface i+1/2. If we have N cells, i.e. cells $i=1,\cdots,N$, then we have N+1 interfaces, i.e. interfaces $i=\frac{1}{2},\cdots,N+\frac{1}{2}$. To get physical quantities from the cell centers to cell interfaces $i=\frac{3}{2},\cdots,N-\frac{1}{2}$ requires just interpolation. But to find the physical quantities at cell interfaces $i=\frac{1}{2}$ and $i=N+\frac{1}{2}$ one has to extrapolate or simply take the values at the cell centers i=1 and i=N.

artifacts in the spectrum if the density in the border cells is high enough to produce substantial line emission. Avoiding this numerical artifact is relatively easy: One should then simply put the number density of the molecule in question to zero in the boundary cells.

- If you are using RADMC-3D on a 3-D (M)HD model which has strong shocks in its domain, then one must be careful that (magneto-)hydrodynamic codes tend to smear out the shock a bit. This means that there will be some cells that have intermediate density and velocity in the smeared out region of the shock. This is unphysical, but an intrinsic numerical artifact of numerical hydrodynamics codes. This might, under some conditions, lead to unphysical signal in the spectrum, because there would be cells at densities, temperatures and velocities that would be in between the values at both sides of the shock and would, in reality, not be there. It is very difficult to avoid this problem, and even to find out if this problem is occurring and by how much. One must simply be very careful of models containing strong shocks and do lots of testing. One way to test is to use the doppler catching method and vary the doppler catching resolution (using the catch_doppler_resolution keyword in radmc3d.inp).
- If using line transfer in spherical coordinates using doppler catching, the linear interpolation of the line shift between the beginning and the end of a segment may not always be enough to accurately prevent doppler jumps. This is because in addition to the physical gradient of gas velocity, the projected gas velocity along a ray changes also along the ray due to the geometry (the use of spherical coordinates). Example: a spherically symmetric radially outflowing wind with constant outward velocity v_r =const. Although v_r is constant, the 3-D vector \vec{v} is not constant, since it always points outward. A ray through this wind will thus have a varying $\vec{n} \cdot \vec{v}$ along the ray. In the cell where the ray reaches its closest approach to the origin of the coordinate system the $\vec{n} \cdot \vec{v}$ will vary the strongest. This may be such a strong effect that it could affect the reliability of the code. As of version 0.41 of this code a method is in place to prevent this. It is switched on by default, but it can be switched off manually for testing purposes. See Section 9.8.1 for details.

7.13 Background information: Calculation and storage of level populations

If RADMC-3D makes an image or a spectrum with molecular (or atomic) lines included, then the level populations of the molecules/atoms have to be computed. In the standard method of ray-tracing of images or spectra, these level populations are first calculated in each grid cell and stored in a global array. Then the raytracer will render the image or spectrum.

The storage of the level populations is a tricky matter, because if this is done in the obvious manner, it might require a huge amount of memory. This would then prevent us from making large scale models. For instance: if you have a molecule with 100 levels in a model with $256x256x256 \simeq 1.7 \times 10^7$ cells, the global storage for the populations alone (with each number in double precision) would be roughly $100x8x256x256 \simeq 13$ Gigabyte.

However, if you intend to make a spectrum in just 1 line, you do not need all these level populations. To stick to the above example, let us take the CO 1-0 line, which is then line 1 and which connects levels J=1 and J=0, which are levels 2 and 1 in the code (if you use the Leiden database CO data file). Once the populations have been computed, we only need to store the levels 1 and 2. This would then require $2x8x256x256x256x256 \approx 0.26$ Gigabyte, which would be *much* less memory-costly.

As of version 0.29 RADMC-3D automatically figures out which levels have to be stored in a global array, in order to be able to render the images or the spectrum properly. RADMC-3D will go through all the lines of all molecules and checks if they contribute to the wavelength(s), of the image(s) or the spectrum. Once it has assembled a list of "active" lines, it will make a list of "active" levels that belong to these lines. It will then declare this to be the "subset" of levels for which the populations will be stored globally.

In other words: RADMC-3D now takes care of the memory-saving storage of the populations automatically.

How does RADMC-3D decide whether a line contributes to some wavelength λ ? A line i with line center λ_i is considered to contribute to an image at wavelength λ if

$$|\lambda_i - \lambda| \le C_{\text{margin}} \Delta \lambda_i \tag{7.23}$$

where $\Delta \lambda_i$ is the line width (including all contributions) and C_{margin} is a constant. By default

$$C_{\text{margin}} = 12 \tag{7.24}$$

But you can change this to another value, say 24, by adding in the radmc3d.inp file a line containing, e.g. lines_widthmargin = 24.

Note that if you use RADMC-3D as a child process (e.g. with the viewimage.pro widget; see Chapters 12 and 14), then RADMC-3D will re-use the calculated populations for further images/spectra, if those new images/spectra contain the same lines as the previous image/spectrum. That could save time. Example: You start viewimage.pro and you get an image at some standard wavelength at first. You select a wavelength right at line center for the CO 2-1 transition (i.e. in the code this is from level nr 3 to 2) and make a new image. RADMC-3D now notices that it will need to calculate and store the populations for levels 2 and 3, it allocates an array for two levels, it computes the populations for levels 2 and 3 and stores these into the global array. Then it will raytrace the image. Now, if you now change the orientation of the object (e.g. by changing the inclination, for instance), then it will skip the level population calculation because it recognizes that it has them already available. If you now change the wavelength a bit (by, say, 2 km/s), it will also re-use the populations. But if you now change the wavelength to the 1-0 transition, it will deallocate the current array, create a brand new array and recalculate the populations.

You can in fact get a dump of the level populations that have been computed and used for the image(s)/spectrum you created, by adding writepop on the command line. Example:

```
radmc3d spectrum iline 1 widthkms 10 writepop
```

This then creates (in addition to the spectrum) a file called (for our example of the CO molecule) levelpop_co.dat. In the IDL file readradmc.pro there is a subroutine called read_levelpop() that can read the data from levelpop_co.dat into IDL for visualization. You will then find that indeed only the necessary levels have been used.

If, for some reason, you want always *all* levels to be stored (and you can afford to do so with the size of your computer's memory), you can make RADMC-3D do so by adding noautosubset as a keyword to the command line, or by adding lines_autosubset = 0 to the radmc3d.inp file. However, for other than code testing purposes, it seems unlikely you will wish to do this.

7.14 In case it is necessary: On-the-fly calculation of populations

There might be rare circumstances in which you do not want to have to store the level populations in a global array. For example: you are making a spectrum of the CO bandhead, in which case you have many tens of lines in a single spectrum. If your model contains 256x256x256 cells (see example in Section 7.13) then this might easily require many Gigabytes of memory just to store the populations.

For the LTE, LVG and optically thin level population modes there is a way out: You can force RADMC-3D to compute the populations *on-the-fly* during the ray-tracing, which does not require a global storage of the level populations.

The way to do this is simple: Just make the lines_mode negative. So for on-the-fly LTE mode use lines_mode=-1, for on-the-fly user-defined populations mode use lines_mode=-2, for on-the-fly LVG mode use lines_mode=-3 and for on-the-fly optically thin populations use lines_mode=-4.

NOTE: The drawback of this method is that, under certain circumstances, it can slow down the code dramatically. This slow-down happens if you use e.g. second-order integration (Section 9.8) and/or doppler catching (Section 7.12) together with non-trivial population solving methods like LVG. So please use the on-the-fly method only when you are forced to do so (for memory reasons).

7.15 For experts: Selecting a subset of lines and levels "manually"

As explained in Section 7.13, RADMC-3D automatically makes a selection of levels for which it will allocate memory for the global level population storage.

If, for some reason, you wish to make this selection yourself "by hand", this can also be done. However, please be informed that there are very few circumstances under which you may want to do this. The automatic subset selection of RADMC-3D is usually sufficient!

If you decided to really want to do this, here is how:

- 1. Switch off the automatic subset selection by adding noautosubset as a keyword to the command line, or by adding lines_autosubset = 0 to the radmc3d.inp file.
- 2. In the lines.inp file, for each molecule, modify the '0 0' (the first two zeroes after 'leiden') in the way described below.

In Section 7.4.2 you can see that each molecule has a line like:

```
co leiden 0 0 0
```

or so (here for the example of CO). In Section 7.4.2 we explained the meaning of the third number, but we did not explain the meaning of the first and second ones. These are meant for this subset selection. If we want to store only the first 10 levels of the CO molecule, then replace the above line with:

```
co leiden 0 10 0
```

If you want to select specific levels (let us choose the ilevel=3 and ilevel=4 levels of the above example), then write:

```
co leiden 1 2 0 3 4
```

The '1' says that a list of levels follows, the '2' says that two levels will be selected and the next line with '3' and '4' say that levels 3 and 4 should be selected.

Chapter 8

Gas continuum opacities and emissivities

In addition to dust and line radiative transfer, RADMC-3D can also handle gas continuum opacities. Here is a list of features that are now already working, marked with [+], and those which are not yet (!!) built in, marked with [-]. Those that are currently being developed are marked with [.] and those that are ready, but are still in the testing phase are marked with [t].

The following processes are included:

- [t] Gas free-free absorption/emission
- [.] Gas bound-free absorption/emission

[.] Self-consistent determination of the gas temperature, based on the continuum opacity and possibly also the lines. Perhaps also various non-thermal heating processes (photoelectric heating etc) will be included. But this is future work.

8.1 Gas continuum opacities and emissivities

While under most circumstances gas emission is mostly in the form of lines, there are also continuum sources of emission and opacity. Gas continuum opacities can be included in a way very similar to the dust opacities. Since currently we envisage thermalized gas (i.e. no accelerated particle distributions, for instance), we can then use Kirchhoff's law to compute, with the gas temperature, the emissivities. Normally the user will have to determine all the locally required quantities, including the gas temperature, the ion and/or electron density etc. In the first version(s) of this module the gas temperature will not be computed self-consistently, but instead have to be given by the user. The processes will be discussed one-by-one below.

Each process can be switched on or off independently:

Process:	Command-line switch on	Command-line switch off	radmc3d.inp variable (0/1)
All processes	inclgascont	nogascont	incl_gascont
Thermal free-free	inclfreefree	nofreefree	incl_freefree

The main switch is the incl_gascont. If this is 0, all gas continuum processes are switched off. If it is 1, then gas continuum processes that have their own switch on will be included. Typically, by switching on one of the processes, the main switch will also be automatically switched on. But the reverse is not true: if you switch off one of the processes, the main switch remains on.

8.1.1 Thermal free-free emission/absorption

The process of thermal free-free emission and absorption is given by the following formula (Eq. 2.96 of Gordon & Sorochenko, 2002, Kluwer Academic Publishers):

$$\alpha_{\nu}^{\text{ff}} = 0.2120 \frac{N_e N_i}{\nu^{2.1} T^{1.35}} \tag{8.1}$$

in units of cm⁻¹ (i.e. the mean free photon path is $1/\alpha_{\nu}^{\rm ff}$).

This mode requires the electron_numdens(:), ion_numdens(:), and gastemp(:) arrays to be set. This is typically done by providing the files electron_numdens.inp, ion_numdens.inp and gas_temperature.inp (see Chapter A), or by allocating and setting the arrays directly in the userdef_module.f90.

8.2 Self-consistent gas temperature iteration

In future versions of RADMC-3D the gas temperature can, like the dust temperature, be determined through a Monte Carlo procedure. In contrast to the dust, however, the gas opacities change with temperature. The Monte Carlo simulation must therefore be repeated a few times to converge on the right temperatures.

At the moment this method is, however, not yet implemented. Instead, the gas temperature must be set by the user, either in the form of a file called gas_temperature.inp or in the userdef_module.f90 module.

Chapter 9

Making images and spectra

Much has already been said about images and spectra in the chapters on dust radiative transfer and line radiative transfer. But here we will combine all this and go deeper into this material. So presumably you do not need to read this chapter if you are a beginning user. But for more sophisticated users (or as a reference manual) this chapter may be useful and presents many new features and more in-depth insight.

9.1 Basics of image making with RADMC-3D

Images and spectra are typically made after the dust temperature has been determined using the thermal Monte Carlo run (see Chapter 6). An image can now be made with a simple call to radmc3d¹:

```
radmc3d image lambda 10
```

This makes an image of the model at wavelength $\lambda=10\mu m$ and writes this to the file image.out. We refer to Section A.16 for details of this file and how to interpret the content. See Chapter 14 for an extensive IDL tool set that make it easy to read and handle these files. The vantage point is at infinity at a default inclination of 0, i.e. pole-on view. You can change the vantage point:

```
radmc3d image lambda 10 incl 80 phi 30
```

which now makes the image at inclination 80 degrees away from the z-axis (i.e. almost edge-on with respect to the x-y plane), and rotates the location of the observer by 30 degrees clockwise around the z-axis² (i.e. with respect to the observer the model is rotated counter-clockwise around the z-axis by 30 degrees). You can also rotate the camera in the image plane with

```
radmc3d image lambda 10 incl 45 phi 30 posang 20
```

which rotates the camera by 20 degrees clockwise (i.e. the image rotates counter-clockwise). Figure 9.1 shows the definitions of all three angles. Up to now the camera always pointed to one single point in space: the point (0,0,0). You can change this:

```
radmc3d image lambda 10 incl 45 phi 30 posang 20 pointau 3.2 0.1 0.4
```

which now points the camera at the point (3.2,0.1,0.4), where the numbers are in units of AU. The same can be done in units of parsec:

```
radmc3d image lambda 10 incl 45 phi 30 posang 20 pointpc 3.2 0.1 0.4
```

Note that pointau and pointpc are always 3-D positions specified in cartesian coordinates. This remains also true when the model-grid is in spherical coordinates and/or when the model is 2-D (axisymmetric) or 1-D (spherically symmetric): 3-D positions are always specified in x,y,z.

¹Please also read Section 14.1.3 for IDL routines that do all of this for you conveniently. The choice is up to you: you can either do this directly as described here, or use the IDL routines.

²Here clockwise is defined with the z-axis pointing toward you.




Figure 9.1. Figure depicting how the angles "incl", "phi" and "posang" orient the camera for images and spectra made with RADMC-3D. The code uses a right-handed coordinate system. The left figure shows from which direction the observer is looking at the system, where $i_{\rm obs}$ is the "incl" keyword and $\phi_{\rm obs}$ is the "phi" keyword. The $x_{\rm image}$ and $y_{\rm image}$ are the horizontal (left-to-right) and vertical (bottom-to-top) coordinates of the image. For $i_{\rm obs}=0$ and $\phi_{\rm obs}=0$ the $x_{\rm image}$ aligns with the 3-D x-coordinate and $y_{\rm image}$ aligns with the 3-D y-coordinate. The right figure shows the way the camera can be rotated in the image plane using "posang". Positive "posang" means that the camera is rotated clockwise, so the object shown is rotated counter-clockwise with respect to the image coordinates.

Let's now drop the pointing again, and also forget about the posang, and try to change the number of pixels used:

```
radmc3d image lambda 10 incl 45 phi 30 npix 100
```

This will make an image of 100x100. You can also specify the x- and y- direction number of pixels separately:

```
radmc3d image lambda 10 incl 45 phi 30 npixx 100 npixy 30
```

Now let's forget again about the number of pixels and change the size of the image, i.e. which zooming factor we have:

```
radmc3d image lambda 10 incl 45 phi 30 sizeau 30
```

This makes an image which has 30 AU width and 30 AU height (i.e. 15 AU from the center in both directions). Same can be done in units of parsec

```
radmc3d image lambda 10 incl 45 phi 30 sizepc 30
```

Although strictly speaking redundant is the possibility to zoom-in right into a selected box in this image:

```
radmc3d image lambda 10 incl 45 phi 30 zoomau -10 -4. 0 6
```

which means that we zoom in to the box given by $-10 \le x \le -4$ AU and $0 \le y \le 6$ AU on the original image (note that zoomau -15 15 -15 15 gives the identical result as sizeau 30). This possibility is strictly speaking redundant, because you could also change the pointau and sizeau to achieve the same effect (unless you want to make a non-square image, in which case this is the only way). But it is just more convenient to do any zooming-in this way. Please note that when you make non-square images with zoomau or zoompc, the code will automatically try to keep the pixels square in shape by adapting the number of pixels in x- or y- direction in the image and adjusting one of the sizes a tiny bit to assure that both x- and y- size are an integer times the pixel size. These are very small adjustments (and only take place for non-square zoom-ins). If you want to force the code to take *exactly* the zoom area, and you don't care that the pixels then become slightly non-square, you can force it with truezoom:

```
radmc3d image lambda 10 incl 45 phi 30 sizeau 30 zoomau -10 -4. 0 3.1415 truezoom
```

If you do not want the code to adjust the number of pixels in x- and y- direction in its attempt to keep the pixels square:

```
radmc3d image lambda 10 incl 45 phi 30 sizeau 30 zoomau -10 -4. 0 3.1415 npixx 100 npixy 4 truepix
```

Now here are some special things. Sometimes you would like to see an image of just the dust, not including stars (for stars in the image: see Section 9.7). So blend out the stars in the image, you use the nostar option:

```
radmc3d image lambda 10 incl 45 phi 30 nostar
```

Another special option is to get a 'quick image', in which the code does not attempt assure flux conservation in the image (see Section 9.6 for the issue of flux conservation). Doing the image with flux conservation is slower than if you make it without flux conservation. Making an image without flux conservation can be useful if you want to have a 'quick look', but is strongly discouraged for actual scientific use. But for a quick look you can do:

```
radmc3d image lambda 10 incl 45 phi 30 nofluxcons
```

Note: In the IDL widget interface viewimage.pro the default is to use this 'quick look' option, because you typically want to make images quickly if you use the viewimage.pro interface. But there is a button (called "preview") that if you unclick it, it will do flux-conserving imaging.

If you want to produce images with a smoother look (and which also are more accurate), you can ask RADMC-3D to use second order integration for the images:

```
radmc3d image lambda 10 incl 45 phi 30 secondorder
```

NOTE: The resulting intensities may be slightly different from the case when first order integration (default) is used, in particular if the grid is somewhat course and the objects of interest are optically thick. Please consult Section 9.8 for more information.

Important for polarized radiative transfer: If you use polarized scattering, then you may want to creat images with polarization information in them. You have to tell RADMC-3D to do this by adding stokes to the command line:

```
radmc3d image lambda 10 incl 45 phi 30 stokes
```

The definitions of the Stokes parameters (orientation etc) can be found in Section 6.7.1 and the format of image.out in this case can be found in Section A.16.

Note: All the above commands call radmc3d separately. If it needs to load a large model (i.e. a model with many cells), then the loading may take a long time. If you want to make many images in a row, this may take too much time. Then it is better to call radmc3d as a child process and pass the above commands through the biway pipe (see Chapter 12).

9.2 Making multi-wavelength images

Sometimes you want to have an image of an object at multiple wavelength simultaneously. Rather than calling RADMC-3D separately to make an image for each wavelength, you can make all images in one command. The only thing you have to do is to tell RADMC-3D which wavelengths it should take. There are various different ways you can tell RADMC-3D what wavelengths to take. This is described in detail in Section 9.4. Here we will focus as an example on just one of these methods. Type, for instance,

```
radmc3d image incl 45 phi 30 lambdarange 5. 20. nlam 10
```

This will create 10 images at once, all with the same viewing perspective, but at 10 wavelengths regularly distributed between 5 μ m and 20 μ m. All images are written into a single file, image, out (See Section A.16 for its format).

In IDL you simply type:

```
.r readradmc
a=readimage()
```

and you will get all images at once. To plot one of them:

```
plotimage,a,ilam=3
```

which will plot image number 3 (out of images number 0 to 9). To find out which wavelength this image is at:

```
print,a.lambda[3]
```

which will return 7.9370053 in this example.

Note that all of the commands in Section 9.1 are of course also applicable to multi-wavelength images, except for the lambda keyword, as this conflicts with the other method(s) of specifying the wavlengths of the images. Now

please turn to Section 9.4 for more information on how to specify the wavelengths for the multiple wavelength images.

9.3 Making spectra

The standard way of making a spectrum with radmc3d is in fact identical to making 100x100 pixel images with flux conservation (i.e. recursive sub-pixeling, see Section 9.6) at multiple frequencies. You can ask radmc3d to make a spectral energy distribution (SED) with the command

```
radmc3d sed incl 45 phi 30
```

This will put the observer at inclination 45 degrees and angle phi 30 degrees, and make a spectrum with wavelength points equal to those listed in the wavelength_micron.inp file.

The output will be a file called spectrum.out (see Section A.15). In Section 14.4 it is discussed how to read this file into IDL.

You can also make a spectrum on a set of wavelength points of your own choice. There are multiple ways by which you can specify the set of frequencies/wavelength points for which to make the spectrum: they are described in Section 9.4. If you have made your selection in such a way, you can make the spectrum at this wavelength grid by

```
radmc3d spectrum incl 45 phi 30 < COMMANDS FOR WAVELENGTH SELECTION>
```

where the last stuff is telling radmc3d how to select the wavelengths (Section 9.4). An example:

```
radmc3d spectrum incl 45 phi 30 lambdarange 5. 20. nlam 100
```

will make a spectrum with a regular wavelength grid between 5 and 20 μ m and 100 wavelength points. But see Section 9.4 for more details and options.

The output file spectrum out will have the same format as for the sed command.

Making a spectrum can take RADMC-3D some time, especially in the default mode, because it will do its best to shoot its rays to pick up all cells of the model (see Section 9.6.2). In particularly in spherical coordinates RADMC-3D can be perhaps *too* conservative (and thus slow). For spherical coordinates there are ways to tell RADMC-3D to be somewhat less careful (and thereby faster): see Section 9.6.4.

Note that you can adjust the fine-ness of the images from which the spectrum is calculated using npix:

```
radmc3d sed incl 45 phi 30 npix 2
```

What this does is use a 2x2 pixel image instead of a 100x100 pixel image as the starting resolution. Of course, if it would really be just a 2x2 pixel image, the flux would be entirely unreliable and useless. However, using the above mentioned "sub-pixeling" (see Section 9.6.2) it will automatically try to recursively refine these pixels until the required level of refinement is reached. So under normal circumstances even npix=2 is enough, and in earlier versions of RADMC-3D this 2x2 top-level image resolution was in fact used as a starting point. But for safety reasons this has now been changed to the standard 100x100 resolution which is also the default for normal images. If 100x100 is not enough, try e.g.:

```
radmc3d sed incl 45 phi 30 npix 400
```

which may require some patience.

9.3.1 What is "in the beam" when the spectrum is made?

As mentioned above, a spectrum is simply made by making a rectangular image at all the wavelengths points, and integrating over these images. The resulting fluxes at each wavelength point is then the spectral flux at that wavelength point. This means that the integration area of flux for the spectrum is (a) rectangular and (b) of the same size at all wavelengths.

So, what *is* the size of the image that is integrated over? The answer is: it is the same size as the default size of an image. In fact, if you make a spectrum with

```
radmc3d spectrum incl 45 phi 30 lambdarange 5. 20. nlam 10
```

then this is the same as if you would type

```
radmc3d image incl 45 phi 30 lambdarange 5. 20. nlam 10
```

and read in the file image.out in into IDL (see Section 9.2) or your favorite other data language, and integrate the images to obtain fluxes. In other words: the command spectrum is effectively the same as the command image but then instead of writing out an image.out file, it will integrate over all images and write a spectrum.out file.

If you want to have a quick look at the area over which the spectrum is to be computed, but you don't want to compute all the images, just type e.g.:

```
radmc3d image lambda 10 incl 45 phi 30
```

then you see an image of your source at $\lambda = 10 \mu m$, and the integration area is precisely this area – at all wavelengths. Like with the images, you can specify your viewing area, and thus your integration area. For instance, by typing

```
radmc3d image lambda 10 incl 45 phi 30 zoomau -2 -1 -0.5 0.5
```

makes an image of your source at $\lambda=10\mu m$ at inclination 45 degrees, and orientation 30 degrees, and zooms in at an are from -2 AU to -1 AU in x-direction (in the image) and from -0.5 AU to 0.5 AU in y-direction (in the image). To make an SED within the same integration area:

```
radmc3d sed incl 45 phi 30 zoomau -2 -1 -0.5 0.5
```

In this case we have an SED with a "beam size" of 1 AU diameter, but keep in mind that the "beam" is square, not circular.

9.3.2 Can one specify more realistic "beams"?

Clearly, a wavelength-independent beam size is unrealistic, and also the square beam is unrealistic. So is there a way to do this better? In reality one should really know exactly how the object is observed and how the flux is measured. If you use an interferometer, for instance, maybe your flux is meant to be the flux in a single synthesized beam. For a spectrum obtained with a slit, the precise flux is dependent on the slit width: the wider the slit, the more signal you pick up, but it is a signal from a larger area.

So if you really want to be sure that you know exactly what you are doing, then the best method is to do this youself by hand. You make multi-wavelength images:

```
radmc3d image incl 45 phi 30 lambdarange 5. 20. nlam 10
```

and integrate over the images in the way you think best mimics the actual observing procedure. You can do so, for instance, in IDL. See Section 9.2 for more information about multi-wavelength images.

But to get some reasonable estimate of the effect of the wavelength-dependent size and circular geometry of a "beam", RADMC-3D allows you to make spectra with a simplistic circular mask, the radius of which can be specified as a function of wavelength in the file aperture_info.inp (see Section A.17.2). This file should contain a table of mask radii at various wavelengths, and when making a spectrum with the command-line keyword useapert the mask radii will be found from this table by interpolation. In other words: the wavelength points of the aperture_info.inp file do not have to be the same as those used for the spectrum. But their range *must* be larger or equal than the range of the wavelengths used for the spectrum, because otherwise interpolation does not work. In the most extreme simplistic case the aperture_info.inp file contains merely two values: one for a very short wavelength (shorter than used in the spectrum) and one for a very long wavelength (longer than used in the spectrum). The interpolation is then done double-logarithmically, so that a powerlaw is used between sampling points. So if you use a telescope with a given diameter for the entire range of the spectrum, two sampling points would indeed suffice.

You can now make the spectrum with the aperture in the following way:

```
radmc3d sed useapert dpc 100
```

The keyword dpc 100 is the distance of the observer in units of parsec³, here assumed to be 100. This distance is necessary because the aperture information is given in arcseconds, and the distance is used to convert this is image size.

Important note: Although you specify the distance of the observer here, the spectrum.out file that is produced is still normalized to a distance of 1 parsec.

Note also that in the above example you can add any other keywords as shown in the examples before, as long as you add the useapert keyword and specify dpc.

A final note: the default behavior of RADMC-3D is to use the square field approach described before. You can explicitly turn off the use of apertures (which may be useful in the child mode of RADMC-3D) with the keyword noapert, but normally this is not necessary as it is the default.

9.4 Specifying custom-made sets of wavelength points for the camera

If you want to make a spectrum at a special grid of wavelengths/frequencies, with the spectrum command (see Section 9.3), you must tell radmc3d which wavelengths you want to use. Here is described how to do this in various ways.

9.4.1 Using lambdarange and (optionally) nlam

The simplest way to choose a set of wavelength for a spectrum is with the lambdarange and (optionally) nlam command line options. Here is how to do this:

```
radmc3d spectrum incl 45 phi 30 lambdarange 5. 20.
```

This will make a spectrum between 5 and 20 μ m. It will use by default 100 wavelength points logarithmically spaced between 5 and 20 μ m. You can change the number of wavelength points as well:

```
radmc3d spectrum incl 45 phi 30 lambdarange 5. 20. nlam 1000
```

This will do the same, but creates a spectrum of 1000 wavelength points.

You can use the lambdarange and nlam options also for multi-wavelength images:

```
radmc3d image incl 45 phi 30 lambdarange 5. 20. nlam 10
```

but it is wise to choose nlam small, because otherwise the output file, containing all the images, would become too large.

9.4.2 Using allwl

You can also tell RADMC-3D to simply make an image at all of the wavelengths in the wavelength_micron.inp file:

```
radmc3d image incl 45 phi 30 allwl
```

The keyword allwl stands for "all wavelengths".

9.4.3 Using loadcolor

By giving the command loadcolor on the command line, radmc3d will search for the file color_inus.inp. This file contains integers selecting the wavelengths from the file wavelength_micron.inp. The file is described in Section A.17.1.

³This is still (and only) valid in the observer-at-infinity default mode. But the distance is necessary for internal computations as described in the text.

9.4.4 Using loadlambda

By giving the command loadlambda on the command line, radmc3d will search for the file camera_wavelength_micron.inp. This file contains a list of wavelengths in micron which constitute the grid in wavelength. This file is described in Section A.13.

9.4.5 Using iline, implied etc (for when lines are included)

By adding for instance iline 3 to the command line you specify a window around line number 3 (by default of molecule 1). By also specifying for instance imolspec 2 you select line 3 of molecule 2. By adding widthkms 3 you specify how wide the window around the line should be (3 km/s in this example). With vkms 2 you set the window offset from line center by 2 km/s in this example. By adding linenlam 30 you set the number of wavelength points for this spectrum to be 30 in this example. So a complete (though different) example is:

radmc3d spectrum incl 45 phi 30 iline 2 imolspec 1 widthkms 6.0 vkms 0.0 linenlam 40

9.5 Heads-up: In reality wavelength are actually wavelength bands

In a radiative transfer program like RADMC-3D the images or spectral fluxes are calculated at *exact* wavelengths. This would correspond to making observations with infinitely narrow filters, i.e. filters with $\Delta\lambda=0$. This is not how real observations work. In reality each wavelength channel has a finite width $\Delta\lambda$ and the measured flux (or image intensity) is an average over this range. To be even more precise, each wavelength channel i has some profile $\Phi_i(\lambda)$ defined such that

$$\int_0^\infty \Phi_i(\lambda) d\lambda = 1 \tag{9.1}$$

For wide filters such as the standard photometric systems (e.g. UVBRI in the optical and JHK in the near infrared) these profiles span ranges with a width of the order of λ itself. Many instruments have their own set of filters. Usually one can download these profiles as digital tables. It can, under some circumstances, be important to include a treatment of these profiles in the model predictions. As an example take the N band. This is a band that includes the $10~\mu m$ silicate feature, which is a strong function of wavelength within the N band. If you have a wide filter in the N band, then one cannot simply calculate the model spectrum in one single wavelength. Instead one has to calculate it for a properly finely sampled set of wavelengths λ_i for $1 \le i \le n$, where n is the number of wavelength samples, and then compute the filter-averaged flux with:

$$F_{band} = \int_0^\infty \Phi_i(\lambda) F(\lambda) d\lambda = \sum_{i=1}^n \Phi_i F_i \delta\lambda$$
 (9.2)

where $\delta\lambda$ is the wavelength sampling spacing used. The same is true for image intensities. RADMC-3D will not do this automatically. You have to tell it the λ_i sampling points, let it make the images or fluxes, and you will then have to perform this sum yourself. *Note that this will not always be necessary!* In many (most?) cases the dust continuum is not expected to change so dramatically over the width of the filter that such degree of accuracy is required. So you are advised to think carefully: "do I need to take care of this or can I make do with a single wavelength sample for each filter?". If the former, then do the hard work. If the latter: then you can save time.

9.5.1 Using channel-integrated intensities to improve line channel map quality

When you make line channel maps you may face a problem that is somehow related to the above issue of single- λ -sampling versus filter-integrated fluxes/intensities. If the model contains gas motion, then doppler shift will shift the line profile around. In your channel map you may see regions devoid of emission because the lines have doppler shifted out of the channel you are looking at. However, as described in Section 7.11, if the intrinsic line width of the gas is smaller than the cell-to-cell velocity differences, then the channel images may look very distorted (they will look "blocky", as if there is a bug in the code). Please refer to Section 7.11 for more details and updates on this important, but difficult issue. It is not a bug, but a general problem with ray-tracing of gas lines in models with large velocity gradients.

As one of the β -testers of RADMC-3D, Rahul Shetty, has found out, this problem can often be alleviated a lot if you treat the finite width of a channel. By taking multiple λ_i points in each wavelength channel (i.e. multiple v_i points in each velocity channel) and simply averaging the intensities (i.e. assuming a perfectly square Φ function) and taking the width of the channels to be not smaller (preferably substantially wider) than the cell-to-cell velocity differences, this "blocky noise" sometimes smoothes out well. However, it is always safer to use the "doppler catching" mode (see Section 7.12) to automatically prevent such problems (though this mode requires more computer memory).

9.6 The issue of flux conservation: recursive sub-pixeling

9.6.1 The problem of flux conservation in images

If an image of nx×ny pixels is made simply by ray-tracing one single ray for each pixel, then there is the grave danger that certain regions with high refinement (for instance with AMR in cartesian coordinates, or near the center of the coordinate system for spherical coordinates) are not properly 'picked up'. An example: suppose we start with a circumstellar disk ranging from 0.1 AU out to 1000 AU. Most of the near infrared flux comes from the very inner regions near 0.1 AU. If an image of the disk is made with 100x100 pixels and image half-size of 1000 AU, then none of the pixels in fact pass through these very bright inner regions, for lack of spatial resolution. The problem is then that the image, when integrated over the entire image, does not have the correct flux. What *should* be is that the centermost pixels contain the flux from this innermost region, even if these pixels are much larger than the entire bright region. In other words, the intensity of these pixels must represent the average intensity, averaged over the entire pixel. Strictly speaking one should trace an infinite continuous 2-D series of rays covering the entire pixel and then average over all these rays; but this is of course not possible. In practice we should find a way to estimate the average intensity with only a finite number of rays.

9.6.2 The solution: recursive sub-pixeling

In RADMC-3D what we do is to use some kind of 'adaptive grid refinement' of the pixels of the image. For each pixel in the image the intensity is computed through a call to a subroutine called <code>camera_compute_one_pixel()</code>. In this subroutine a ray-tracing is performed for a ray that ends right in the middle of our pixel. During the ray-tracing, however, we check if we pass regions in the model grid that have grid cells with sizes S that are smaller than the pixel size divided by some factor $f_{\rm ref}$ (where pixel size is, like the model grid size S itself, measured in centimeters⁴). If this is found *not* to be true, then the pixel size was apparently ok, and the intensity resulting from the ray-tracing is now returned as the final intensity of this pixel. If, however, this condition <code>is</code> found to be true, then the result of this ray is rejected, and instead 2x2 sub-pixels are computed by calling the <code>camera_compute_one_pixel()</code> subroutine recursively. We thus receive the intensity of each of these four sub-pixels, and we return the average of these 4 intensities.

Note, by the way, that each of these 2x2 subpixels may be split even further into 2x2 sub-pixels etc until the desired resolution is reached, i.e. until the condition that S is larger or equal to the pixel size divided by $f_{\rm ref}$ is met. By this recursive calling, we always end up at the top level with the average intesity of the entire top-level pixel. This method is very similar to quad-tree mesh refinement, but instead of retaining and returning the entire complex mesh structure to the user, this method only returns the final average intensity of each (by definition top level) pixel in the image. So the recursive sub-pixeling technique described here is all done internally in the RADMC-3D code, and the user will not really notice anything except that this sub-pixeling can of course be computationally more expensive than if such a method is not used.

Note that the smaller we choose $f_{\rm ref}$ the more accurate our image becomes. In the radmc3d.inp file the value of $f_{\rm ref}$ can be set by setting the variable camera_refine_criterion to the value you want $f_{\rm ref}$ to be. Not setting this variable means RADMC-3D will use the default value which is reasonable as a choice (default is 1.0). The smaller you set camera_refine_criterion, the more accurate and reliable the results become (but the heavier the calculation becomes, too).

NOTE: The issue of recursive sub-pixeling becomes tricky when stars are treated as spheres, i.e. non-point-like (see Section 9.7 and Chapter 11).

⁴This is not possible for images for local observers, but see Section 9.11 for details.

9.6.3 A danger with recursive sub-pixeling

It is useful to keep in mind that for each pixel the recursive sub-pixeling is triggered if the ray belonging to that pixel encounters a cell that is smaller than the pixel size. This *normally* works well if f_{ref} is chosen small enough. But if there exist regions in the model where one big non-refined cell lies adjacent to a cell that is refined, say, 4 times (meaning the big cell has neighbors that are 16 times smaller!), then if the ray of the pixel just happens to miss the small cells and only passes the big cell, it won't "notice" that it may need to refine to correctly capture the tiny neighboring cells accurarely.

Such a problem only happens if refinement levels jump by more than 1 between adjacent cells. If so, then it may be important to make $f_{\rm ref}$ correspondingly smaller (by setting camera_refine_criterion in radmc3d.inp to the desired value). A bit of experimentation may be needed here.

9.6.4 Recursive sub-pixeling in spherical coordinates

In spherical coordinates the recursive sub-pixeling has a few issues that you may want to be aware of. First of all, in 1-D spherical coordinates each cell is in fact a shell of a certain thickness. In 2-D spherical coordinates cells are rings. In both cases the cells are not just local boxes, but have 2 or 1 (respectively) extended dimensions. RADMC-3D takes care to still calculate properly how to define the recursive sub-pixeling scale. But for rays that go through the central cavity of the coordinate system there is no uniquely defined pixel resolution to take. The global variable camera_spher_cavity_relres (with default value 0.05) defines such a relative scale. You can change this value in the radmc3d.inp file.

A second issue is when the user introduces extreme "separable refinement" (see Section 10.2 and Figure 10.2-right) in the R, Θ or Φ coordinate. This may, for instance, be necessary near the inner edge of a dusty disk model in order to keep the first cell optically thin. This may lead, however, to extremely deep sub-pixeling for rays that skim the inner edge of the grid. This leads to a huge slow-down of the ray-tracing process although it is likely not to give much a different result. By default RADMC-3D plays it safe. If you wish to prevent this excessive sub-pixeling (at your own risk) then you can set the following variables in the radmc3d.inp file:

- camera_min_drr which sets a lower limit to the $\Delta R/R$ taken into account for the sub-pixeling (region "B" in Figure 10.2-left). The default is 0.003. By setting this to e.g. 0.03 you can already get a strong speed-up for models with strong R-refinement.
- camera_min_dangle which sets a lower limit to $\Delta\Theta$ (region "C" in Figure 10.2-left) and/or $\Delta\Phi$. The default is 0.05. By setting this to e.g. 0.1 you can already get some speed-up for models with e.g. strong Θ -refinement.

It is important to keep in mind that the smaller you make this number, the more accurate and reliable the results. It may be prudent to experiment with smaller values of <code>camera_min_drr</code> for models with extremely optically thick inner edges, e.g. a protoplanetary disk with an abrupt inner edge and a high dust surface density. For a disk model with a very thin vertical extent it will be important to choose small values of <code>camera_min_dangle</code>, perhaps even smaller than the default value.

For your convenience: Because it can be sometimes annoying to always have to play with the camera_min_drr, camera_min_dangle and camera_spher_cavity_relres values, and since it is usually (!) not really necessary to have such extremely careful subpixeling, RADMC-3D now has a new command line option called sloppy. This command-line option will set: camera_min_drr=0.1, camera_min_dangle=0.1 and camera_spher_cavity_relres=0.1. So if you have an image like this:

```
radmc3d image lambda 10 incl 45 phi 30 sloppy
```

then it will make the image with moderate, but not excessive subpixeling. This may, under some circumstances, speed up the image-making in spherical coordinates by a large factor. Similar for making spectra. For instance:

```
radmc3d sed incl 45 phi 30 sloppy
```

can be, under some circumstances, very much faster than without the sloppy option.

Note,however, that using the sloppy option and/or setting the values of camera_min_drr, camera_min_dangle and camera_spher_cavity_relres in the radmc3d.inp file by hand, is all at your own risk! It is always prudent to check your results, now and then, against a non-sloppy calculation.

9.6.5 How can I find out which pixels RADMC-3D is recursively refining?

Sometimes you notice that the rendering of an image or spectrum takes much more time than you expected. When recursive sub-pixeling is used for imaging, RADMC-3D will give diagnostic information about how many more pixels it has rendered than the original image resolution. This factor can give some insight if extreme amount of sub-pixeling refinement has been used. But it does not say where in the image this occurs. If you want to see exactly which pixels and subpixels RADMC-3D has rendered for some image, you can use the following command-line option:

```
radmc3d image lambda 10 diag_subpix
```

This diag_subpix option will tell RADMC-3D to write a file called subpixeling_diagnostics.out which contains four columns: One for the x-coordinate of the (sub-)pixel, one for the y-coordinate of the (sub-)pixel, one for the x-width of the (sub-)pixel and a final one for the y-width of the (sub-)pixel. In IDL, if you use for instance the astrolib library, you can use the readcol procedure to read these columns. So *inside IDL* you then type

```
.r readcol
readcol, 'subpixeling_diagnostics.out',px,py
plot,px,py,psym=3
```

and you get a plot of all the pixel-centers and sub-pixel-centers used. As of version 0.35 you can also do:

```
.r readradmc
a=readsubpixels()
plotsubpixels,a,ps=3
```

You can also plot a single subpixeling level:

```
plotsubpixels,a,ps=3,level=2
or a range of them:
plotsubpixels,a,ps=3,minlev=1,maxlev=2
```

If this diagnostic shows that the subpixeling is excessive (which can particularly happen in spherical coordinates) then you might want to read Section 9.6.4.

9.6.6 Alternative to recursive sub-pixeling

As an alternative to using this recursive sub-pixeling technique to ensure flux conservation for images, one can simply enhance the spatial resolution of the image, for instance

```
radmc3d image lambda 10 npix 400
```

Or even 800 or so. This has the clear advantage that the user gets the complete information of the details in the image (while in the recursive sub-pixeling technique only the averages are retained). The clear disadvantages are that one may need rediculously high-resolution images (i.e. large data sets) to resolve all the details and one may waste a lot of time rendering parts of the image which do not need that resolution. The latter is typically an issue when images are rendered from models that use AMR techniques.

9.7 Stars in the images and spectra

Per default, stars are still treated as point sources. That means that none of the rays of an image can be intercepted by a star. Starlight is included in each image as a post-processing step. First the image is rendered without the stars (though with of course all the emission of dust, lines etc *induced* by the stars) and then for each star a ray tracing is done from the star to the observer (where only extinction is taken into account, because the emission is already




Figure 9.2. Pictographic representation of the integration of the transfer equation along a ray (red line with arrow head) through an AMR grid (black lines). The grid cuts the ray into ray segments A, B, C and D. At the bottom it is shown how the integrands are assumed to be along these four segments. Left: When using first order integration. The emissivity function j_{ν} and extinction function α_{ν} are constant within each cell and thus constant along each ray segment. Right: When using second order integration. The emissivity function j_{ν} and extinction function α_{ν} are given at the cell corners (solid blue circles), and linearly interpolated from the cell corners to the locations where the ray crosses the cell walls (open blue circles). Then, along each ray segment the emissivity and extinction functions are assumed to be linear functions, so that the integration result is quadratic. The thin blue horizontal dashed lines are the same as those in the Left panel, and are just there for comparison. Note that these figures are 2-D, whereas this actually happens in 3-D. See Section 9.8 for more information.

taken care of) and the flux is then added to the image at the correct position. You can switch off the inclusion of the stars in the images or spectra with the nostar command line option.

However, as of version 0.17, stars can also be treated as the finite-size spheres they are. This is done with setting istar_sphere = 1 in radmc3d.inp. However, this mode can slow down the code a bit or even substantially. And it may still be partly under development, so the code may stop if it is required to handle a situation it cannot handle yet. See Chapter 11 for details.

9.8 Second order ray-tracing (Important information!)

Ideally we would like to assure that the model grid is sufficiently finely spaced everywhere. But in many cases of interest one does not have this luxury. One must live with the fact that, for memory and/or computing time reasons, the grid is perhaps a bit coarser than would be ideal. In such a case it becomes important to consider the "order" of integration of the transfer equation. By default, for images and spectra, RADMC-3D uses first order integration: The source term and the opacity in each cell are assumed to be constant over the cell. This is illustrated in Fig. 9.2-Left. The integration over each cell proceeds according to the following formula:

$$I_{\text{result}} = I_{\text{start}} e^{-\tau} + (1 - e^{-\tau})S$$
 (9.3)

where $S=j/\alpha$ is the source function, assumed constant throughout the cell, $\tau=\alpha \Delta s$ is the optical depth along the path that the ray makes through the cell, and $I_{\rm start}$ is the intensity upon entering the cell. This is the default used by RADMC-3D because the Monte Carlo methods also treat cells as having constant properties over each cell. This type of simple integration is therefore the closest to how the Monte Carlo methods (thermal MC, scattering MC and mono MC) "see" the grid. However, with first order integration the images look somewhat "blocky": you can literally see the block structure of the grid cells in the image, especially if you make images at angles aligned with the grid. For objects with high optical depths you may even see grid patterns in the images.

RADMC-3D can also use second order integration for its images and spectra. This is illustrated in Fig. 9.2-Right. This is done with a simple "secondorder" option added on the command line, for instance:

radmc3d image lambda 10 secondorder

The integration now follows the formula (Olson et al. 1986):

$$I_{\text{result}} = I_{\text{start}} e^{-\tau} + (1 - e^{-\tau} - \beta) S_{\text{start}} + \beta S_{\text{end}}$$

$$(9.4)$$

with

$$\beta = \frac{\tau - 1 + e^{-\tau}}{\tau} \tag{9.5}$$

and

$$\tau = \frac{\alpha_{\text{start}} + \alpha_{\text{end}}}{2} \Delta s \tag{9.6}$$

For $\tau \to 0$ we have the limit $\beta \to \tau/2$, while for $\tau \to \infty$ we have the limit $\beta \to 1$.

The values of α , S etc., at the "start" position are obtained at the cell interface where the ray enters the cell. The values at the "end" position are obtained at the cell interface where the ray leaves the cell. The above formulas represent the exact solution of the transfer equation along this ray-section if we assume that all variables are linear functions between the "start" and "end" positions.

The next question is: How do we determine the physical variables at the cell interfaces ("start" and "end")? After all, initially all variables are stored for each cell, not for each cell interface or cell corner. The way that RADMC-3D does this is:

- First create a "grid of cell corners", which we call the *vertex grid* (see the solid blue dots in Fig. 9.2-Right). The cell grid already implicitly defines the locations of all the cell corners, but these corners are, by default, not explicitly listed in computer memory. When the secondorder option is given, however, RADMC-3D will explicitly find all cell corners and assign an identity (a unique integer number) to each one of them. NOTE: Setting up this vertex grid costs computer memory!
- At each vertex (cell corner) the physical variables of the (up to) 8 cells touching the vertex are averaged with equal weight for each cell. This now maps the physical variables from the cells to the vertices.
- Whenever a ray passes through a cell wall, the physical variables of the 4 vertices of the cell wall are interpolated bilinearly onto the point where the ray passes through the cell wall (see the open blue circles in Fig. 9.2-Right). This gives the values at the "start" or "end" points.
- Since the current "end" point will be the "start" point for the next ray segment, the physical variables need only be obtained once per cell wall, as they can be recycled for the next ray segment. Each set of physical variables will thus be used twice: once for the "end" and once for the "start" of a ray segment (except of course at the very beginning and very end of the ray).

If you compare the images or spectra obtained with first order integration (default) or second order integration (Fig. 9.3) you see that with the first order method you still see the cell structure of the grid very much. Also numerical noise in the temperature due to the Monte Carlo statistics is much more prominent in the first order method. The second order method makes much smoother results.

For line transfer the second order mode can be even improved with the "doppler catching method", see Section 7.12.

WARNING: Second order integration for the images and spectra from dust continuum emission can in some cases lead to overestimation of the fluxes. This is because the dust temperature calculated using the thermal Monte Carlo algorithm assumes the temperature to be constant over each cell. The second order integration for the images and spectra will, however, smear the sources a bit out. This then leads to "leaking" of emissivity from optically thick cells into optically thin cells. These optically thin cells can then become too bright.

9.8.1 Second order integration in spherical coordinates: a subtle issue

The second order integration (as well as the doppler-catching method, see Section 7.12) work in cartesian coordinates as well as in spherical coordinates. In spherical coordinates in 1-D (spherical symmetry) or 2-D (axial




Figure 9.3. First-order integration of transfer equation in ray-tracing (left two panels), versus second order integration (right two panels). Upper: 60 degrees inclination, Lower: 4 degrees inclination. Shown here is the run_simple_1_layers model (in the examples directory) at $\lambda = 10~\mu m$ at some zoom factor. See Section 9.8 for more information.

symmetry) there is, however, a very subtle issue that can lead to inaccuracies, in particular with line transfer. The problem arises in the cell where a ray reaches its closest approach to the origin of the coordinate system (or closest approach to the symmetry axis). There the ray segment can become fairly long, and its angle with respect to the symmetry axis and/or the origin can drastically change within this single ray-segment. This can sometimes lead to inaccuracies.

As of version 0.41 of RADMC-3D a new global variable is introduced, camera_maxdphi, which has as default the value 0.1, but which can be set to another value in the radmc3d.inp file. It sets the maximum angle (in radian) which a ray segment in spherical coordinates is allowed to span with respect to the origin of the coordinate system. If a ray segment spans an angle larger than that, the ray-segment is cut into smaller segments. This means that in that cell the ray will consist of more than one segment.

If camera_maxdphi=0 this segment cutting is switched off (for backward compatibility to earlier versions of RADMC-3d).

9.9 Visualizing the $\tau = 1$ surface

To be able to interpret the outcome of the radiative transfer calculations it is often useful to find the spatial location of the $\tau=1$ surface (or, for that matter, the $\tau=0.1$ surface or any $\tau=\tau_s$ surface) as seen from the vantage point of the observer. This makes it easier to understand where the emission comes from that you are seeing. RADMC-3D makes this possible. Thanks to Peter Schilke and his team, for suggesting this useful option.

The idea is to simply replace the command-line keyword image with tausurf 1.0. The 1.0 stands for $\tau_s = 1.0$, meaning we will find the $\tau = 1.0$ surface. Example: Normally you might make an image with e.g. the following command:

radmc3d image lambda 10 incl 45 phi 30

Now you make a $\tau = 1$ surface with the command:

```
radmc3d tausurf 1.0 lambda 10 incl 45 phi 30 or a \tau=0.2 surface with radmc3d tausurf 0.2 lambda 10 incl 45 phi 30
```

The image output file image out will now contain, for each pixel, the position along the ray in centimeters where $\tau = \tau_s$. The zero point is the surface perpendicular to the direction of observation, going through the pointing position (which is, by default (0,0,0), but see the description of pointau in Section 9.1). Positive values mean that the surface is closer to the observer than the plane, while negative values mean that the surface is behind the plane.

If, for some pixel, there exists no $\tau = \tau_s$ point because the total optical depth of the object for the ray belonging to that pixel is less than τ_s , then the value will be -1D91.

You can also get the 3-D (i.e. x, y, z) positions of each of these points on the $\tau = \tau_s$ surface. They are stored in the file tausurface_3d.out. There is a special IDL routine in the readradmc.pro file called read_tausurf_3d(). Also here the values of x, y, z will be -1D91 for rays that have total optical depth small than τ_s .

If you do not use IDL for data handling, you can at least see the format of the tausurface_3d.out file there. For most purposes, however, the projected data in the image.out file should be enough, however.

Note that if you make multi-frequency images, you will also get multi-frequency $\tau = \tau_s$ surfaces. This can be particularly useful if you want to understand the sometimes complex origins of the shapes of molecular/atomic lines.

You can also use this option in the local observer mode, though I am not sure how useful it is. Note, however, that in that mode the value stored in the image.out file will describe the distance in centimeter to the local observer. The larger the value, the farther away from the observer (contrary to the case of observer-at-infinity).

Example usage:

```
radmc3d tausurf 1 lambda 10 incl 45 phi 30
idl
.r readradmc
a=readimage()
surface,a.image>(-1d15)
```

This should, if your model is optically thick, show the $\tau = \tau_s$ surface. The >(-1d15) in the last line is an IDL trick to truncate the values of a image to larger or equal to -1d15 centimeters (which is a few AU). This is necessary because for all rays where the total optical depth is less than τ_s (in this case 1) the value would be -1D91.

9.10 Using circularly arranged pixels for spectra (special topic)

For the moment, this mode is not yet finished

9.11 For public outreach work: local observers inside the model

While it may not be very useful for scientific purposes (though there may be exceptions), it is very nice for public outreach to be able to view a model from the inside, as if you, as the observer, were standing right in the middle of the model cloud or object. One can then use physical or semi-physical or even completely ad-hoc opacities to create the right 'visual effects'. RADMC-3D has a viewing mode for this purpose. You can use different projections:

- *Projection onto flat screen:*The simplest one is a projection onto a screen in front (or behind) the point-location of the observer. This gives an image that is good for viewing in a normal screen. This is the default (camera_localobs_projection=1).
- Another projection is a projection onto a sphere, which allow fields of view that are equal or larger than 2π of the sky. It may be useful for projection onto an OMNIMAX dome. This is projection mode camera_localobs_projection=2.

You can set the variable camera_localobs_projection to 1 or 2 by adding on the command line projection 2 (or 1), or by setting it in the radmc3d.inp as a line camera_localobs_projection = 2 (or 1).

To use the local projection mode you must specify the following variables on the command line:

• sizeradian:

This sets the size of the image in radian (i.e. the entire width of the image). Setting this will make the image width and height the same (like setting sizeau in the observer-at-infinity mode, see Section 9.1).

• zoomradian:

Instead of sizeradian you can also specify zoomradian, which is the local-observer version of zoomau orzoompc (see Section 9.1).

• posang:

The position angle of the camera. Has the same meaning as in the observer-at-infinity mode.

• locobsau or locobspc:

Specify the 3-D location of the local observer inside the model in units of AU or parsec. This requires 3 numbers which are the x, y and z positions (also when using spherical coordinates for the model setup: these are still the cartesian coordinates).

• pointau or pointpc:

These have the same meaning as in the observer-at-infinity model. They specify the 3-D location of the point of focus for the camera (to which point in space is the camera pointing) in units of AU or parsec. This requires 3 numbers which are the x, y and z positions (also when using spherical coordinates for the model setup: these are still the cartesian coordinates).

• zenith (optional):

For Planetarium Dome projection (camera_localobs_projection=2) it is useful to make the pointing direction not at the zenith (because then the audience will always have to look straight up) but at, say, 45 degrees. You can facilitate this (optionally) by adding the command line option zenith 45 for a 45 degrees offset. This means that if you are sitting under the OMNIMAX dome, then the camera pointing (see pointau above) is 45 degrees in front of you rather than at the zenith. This option is highly recommended for dome projections, but you may need to play with the angle to see which gives the best effect.

Setting sizeradian, zoomradian, locobsau or locobspc on the command line automatically switches to the local observer mode (i.e. there is no need for an extra keyword setting the local observer mode on). To switch back to observer-at-infinity mode, you specify e.g. incl or phi (the direction toward which the observer is located in the observer-at-infinity mode). Note that if you accidently specify both e.g. sizeradian and incl, you might end up with the wrong mode, because the mode is set by the last relevant entry on the command line.

The images that are produced using the local observer mode will have the x- and y- pixel size specifications in radian instead of cm. The first line of an image (the format number of the file) contains then the value 2 (indicating local observer image with pixel sizes in radian) instead of 1 (which indicates observer-at-infinity image with pixel sizes in cm).

NOTE: For technical reasons dust scattering is (at least for now) not included in the local observer mode! It is discouraged to use the local observer mode for scientific purposes.

9.12 Multiple vantage points: the "Movie" mode

It can be useful, both scientifically and for public outreach, to make movies of your model, for instance by showing your model from different vantage points or by "travelling" through the model using the local observer mode (Section 9.11). For a movie one must make many frames, each frame being an image created by RADMC-3D's image capabilities. If you call radmc3d separately for each image, then often the reading of all the large input files takes up most of the time. One way to solve this is to call radmc3d in "child mode" (see Chapter 12). But this is somewhat complicated and cumbersome. A better way is to use RADMC-3D's "movie mode". This allows you to ask RADMC-3D to make a sequence of images in a single call. The way to do this is to call radmc3d with the movie keyword:

radmc3d movie

This will make radmc3d to look for a file called movie.inp which contains the information about each image it should make. The structure of the movie.inp file is:

```
iformat
nframes
<<information for frame 1>>
<<information for frame 2>>
<<information for frame 3>>
...
<<information for frame nframes>>
```

The iformat is an integer that is described below. The nframes is the number of frames. The <<information for frame xx>> are lines containing the information of how the camera should be positioned for each frame of the movie (i.e. for each imag). It is also described below.

There are multiple ways to tell RADMC-3D how to make this sequence of images. Which if these ways RADMC-3D should use is specified by the iformat number. Currently there are 2, but later we may add further possibilities. Here are the current possibilities

• iformat=1:

The observer is at infinity (as usual) and the <<information for frame xx>> consists of the following numbers (separated by spaces):

```
pntx pnty pntz hsx hsy pa incl phi
```

These 8 numbers have the following meaning:

- pntx,pnty,pntz
 - These are the x, y and z coordinates (in units of cm) of the point toward which the camera is pointing.
- hsx, hsy
 - These are the image half-size in horizontal and vertical direction on the image (in units of cm).
- **–** pa
 - This is the position angle of the camera in degrees. This has the same meaning as for a single image.
- incl,phi
 - These are the inclination and phi angle toward the observer in degrees. These have the same meaning as for a single image.

iformat=-1:

The observer is local (see Section 9.11) and the <<information for frame xx>> consists of the following numbers (separated by spaces):

```
pntx pnty pntz hsx hsy pa obsx obsy obsz
```

These 9 numbers have the following meaning:

- pntx,pnty,pntz,hsx,hsy,paSame meaning as for iformat=1.
- obsx,obsy,obsz

These are the x, y and z position of the local observer (in units of cm).

Apart from the quantities that are thus set for each image separately, all other command-line options still remain valid.

Example, let us make a movie of 360 frames of a model seen at infinity while rotating the object 360 degrees, and as seen at a wavelength of $\lambda = 10 \mu \text{m}$ with 200x200 pixels. We construct the movie.inp file:

```
1
360
0. 0. 0. 1d15 1d15 0. 60. 1.
0. 0. 0. 1d15 1d15 0. 60. 2.
0. 0. 0. 1d15 1d15 0. 60. 3.
```

```
0. 0. 0. 1d15 1d15 0. 60. 358. 
0. 0. 0. 1d15 1d15 0. 60. 359. 
0. 0. 0. 1d15 1d15 0. 60. 360.
```

We now call RADMC-3D in the following way:

```
radmc3d movie lambda 10. npix 200
```

This will create image files image_0001.out, image_0002.out, all the way to image_0360.out. The images will have a full width and height of 2×10^{15} cm (about 130 AU), will always point to the center of the image, will be taken at an inclination of 60 degrees and with varying ϕ -angle.

Another example: let us move through the object (local observer mode), approaching the center very closely, but not precisely:

```
-1
101
0. 0. 0. 0. 0.8 0.8 0. 6.d13 -1.0000d15 0.
0. 0. 0. 0. 0.8 0.8 0. 6.d13 -0.9800d15 0.
0. 0. 0. 0. 0.8 0.8 0. 6.d13 -0.9600d15 0.

.
.
0. 0. 0. 0.8 0.8 0. 6.d13 -0.9600d15 0.
0. 0. 0. 0.8 0.8 0. 6.d13 -0.0200d15 0.
0. 0. 0. 0.8 0.8 0. 6.d13 0.0000d15 0.
.
.
.
0. 0. 0. 0.8 0.8 0. 6.d13 0.0200d15 0.
.
.
0. 0. 0. 0.8 0.8 0. 6.d13 0.9800d15 0.
0. 0. 0. 0.8 0.8 0. 6.d13 0.9800d15 0.
0. 0. 0. 0.8 0.8 0. 6.d13 0.9800d15 0.
0. 0. 0. 0.8 0.8 0. 6.d13 1.0000d15 0.
```

Here the camera automatically rotates such that the focus remains on the center, as the camera flies by the center of the object at a closest-approach to the center of 6×10^{13} cm. The half-width of the image is 0.8 radian.

Important note: If you have scattering switched on, then every rendering of an image makes a new scattering Monte Carlo run. Since Monte Carlo produces noise, this would lead to a movie that is very jittery (every frame has a new noise set). It is of course best to avoid this by using so many photon packages that this is not a concern. But in practice this may be very CPU-time consuming. You can also fix the noise in the following way: add resetseed to the command-line call:

```
radmc3d movie resetseed
```

and it will force each new scattering Monte Carlo computation to start with the same seed, so that the photons will exactly move along the same trajectories. Now only the scattering phase function will change because of the different vantage points, but not the Monte Carlo noise. You can in fact set the actual value of the initial seed in the radmc3d.inp file by adding a line

```
iseed = -5415
```

(where -5415 is to be replaced by the value you want) to the radmc3d.inp file. Note also that if your movie goes through different wavelengths, the resetseed will likely not help fixing the noisiness, because the paths of photons will change for different wavelengths, even with the same initial seed.

Chapter 10

More information about the gridding

We already discussed the various types of grids in Section 5.4, and the grid input file structure is described in Section A.2. In this chapter let us take a closer look at the gridding possibilities and things to take special care of.

10.1 Regular grids

A regular grid is called "grid style 0" in RADMC-3D. It can be used in Cartesian coordinates as well as in spherical coordinates (Section 5.3).

A regular grid, in our definition, is a multi-dimensional grid which is separable in x, y and z (or in spherical coordinates in r, θ and ϕ). You specify a 1-D monotonically increasing array of values $x_1, x_2, \cdots, x_{nx+1}$ which represent the cell walls in x-direction. You do the same for the other directions: $y_1, y_2, \cdots, y_{ny+1}$ and $z_1, z_2, \cdots, z_{nz+1}$. The value of, say, x_2 is the same for every position in y and z: this is what we mean with "separable".

In Cartesian coordinates RADMC-3D enforces perfectly cubic grid cells (i.e. linear grids). But that is only to make the image sub-pixeling easier (see Section 9.6.2). For spherical grids this is not enforced, and in fact it is strongly encouraged to use non-linear grids in spherical coordinates. Please read Section 10.2 if you use spherical coordinates!

In a regular grid you specify the grids in each direction separately. For instance, the x-grid is given by specifying the cell walls in x-direction. If we have, say, 10 cells in x-direction, we must specify 11 cell wall positions. For instance: $x_i = \{-5, -4, -3, -2, -1, 0, 1, 2, 3, 4, 5\}$. For the y-direction and z-direction likewise. Fig. 10.1 shows an example of a 2-D regular grid of 4x3 cells. In Cartesian coordinates we typically define our model in full 3-D. However, if your problem has translational symmetries, you might also want to consider the 1-D plane-parallel mode (see Section 10.6) or the 2-D pencil-parallel mode (see Section 10.7).

In full 3-D Cartesian coordinates the cell sizes *must* be perfectly cubical, i.e. the spacing in each direction must be the same. If you need a finer grid in some location, you can use the AMR capabilities discussed below.

In spherical coordinates you can choose between 1-D spherically symmetric models, 2-D axisymmetric models or fully 3-D models. In spherical coordinates you do *not* have restrictions to the cell geometry or grid spacing. You can choose any set of numbers r_1, \dots, r_{nr} as radial grid, as long as this set of numbers is larger than 0 and monotonically increasing. The same is true for the θ -grid and the ϕ -grid.

The precise way how to set up a regular grid using the amr_grid.inp file is described in Section A.2.1. The input of any spatial variables (such as e.g. the dust density) uses the sequence of grid cells in the same order as the cells are specified in that amr_grid.inp file.

For input and output data to file, for stuff on a regular grid, the order of nested loops over coordinates would be:




Figure 10.1. Example of a regular 2-D grid with nx=4 and ny=3.

enddo

For spherical coordinates we have the following association: $x \to r, y \to \theta, z \to \phi$.

10.2 Separable grid refinement in spherical coordinates (important!)

Spherical coordinates are a very powerful way of dealing with centrally-concentrated problems. For instance, collapsing protostellar cores, protoplanetary disks, disk galaxies, dust tori around active galactic nuclei, accretion disks around compact objects, etc. In other words: problems in which a single central body dominates the problem, and material at all distances from the central body matters. For example a disk around a young star goes all the way from 0.01 AU out to 1000 AU, covering 5 orders of magnitude in radius. Spherical coordinates are the easiest way of dealing with such a huge radial dynamic range: you simply make a radial grid, where the grid spacing $r_{i+1} - r_i$ scales roughly with r_i .

This is called a *logarithmic radial grid*. This is a grid whith a spacing in which $(r_{i+1} - r_i)/r_i$ is constant with r. In this way you assure that you have always the right spatial resolution in r at each radius. In spherical coordinates it is highly recomended to use such a log spacing. But you can also refine the r grid even more (in addition to the log-spacing). This is also strongly recommended near the inner edge of a circumstellar shell, for instance. Or at the inner dust rim of a disk. There you must refine the r grid (by simply making the spacing smaller as you approach the inner edge from the outside) to assure that the first few cells are optically thin and that there is a gradual transition from optically thin to optically thick as you go outward. This is particularly important for, for instance, the inner rim of a dusty disk.

In spherical coordinates you can vary the spacing in r, θ and ϕ completely freely. That means: you could have for instance r to be spaced as $1.00, 1.01, 1.03, 1.05, 1.1, 1.2, 1.35, \cdots$. There is no restriction, as long as the coordinate points are monotonically increasing. In Figure 10.2 this is illustrated.

Note that in addition to separable refinement, also AMR refinement is possible in spherical coordinates. See Section 10.3.

For models of accretion disks it can, for instance, be useful to make sure that there are more grid points of θ near the equatorial plane $\theta=\pi/2$. So the grid spacing between $\theta=0.0$ and $\theta=1.0$ may be very coarse while between $\theta=1.0$ and $\theta=\pi/2$ you may put a finer grid. All of this "grid refinement" can be done without the "AMR" refinement technique: this is the "separable" grid refinement, because you can do this separately for r, for θ and for ϕ .

Sometimes, however, separable refinement may not help you to refine the grid where necessary. For instance: if you model a disk with a planet in the disk, then you may need to refine the grid around the planet. You could refine the




Figure 10.2. Example of a spherical 2-D grid in which the radial and θ grids are refined in a "separable" way. In radial direction the inner cells are refined ("B" in the right figure) and in θ direction the cells near the equatorial plane are refined ("C" in the right figure). This kind of grid refinement does not require oct-tree AMR: the grid remains separable. For models in which the inner grid edge is also the inner model edge (e.g. a simple model of a protoplanetary disk with a sharp inner cut-off) this kind of separable grid refinement in R-direction may be essential to avoid problems with optically thick inner cells (see e.g. Fig. 19.1 for an example of what could go wrong if you do not do this). Separable grid refinement in Θ -direction is typically important for protoplanetary disk models, where the midplane and surface layers of the disk need to have sufficient resolution, but any possible surrounding spherical nebula may not. Left: When making an image, RADMC-3D will automatically make "sub-pixels" to ensure that all structure of the model as projected on the sky of the observer are spatially resolved. Extreme grid refinement leads thus to extreme sub-pixeling. See Section 9.6.4 for details, and ways to prevent excessive sub-pixeling when this is not necessary.




Figure 10.3. Example of a 2-D grid with oct-tree refinement. The base grid has nx=4 and ny=3. Three levels of refinement are added to this base grid.

grid in principle in a separable way, but you would then have a large redundancy in cells that are refined by far away from the planet. Or if you have a disk with an inner rim that is not exactly at $r = r_{\rm rim}$, but is a rounded-off rim. In these cases you need refinement exactly located at the region of interest. For that you need the "AMR" refinement (Sections 10.3 and 10.4).

Important note: When using strong refinement in one of the coordinates r, θ or ϕ , image-rendering and spectrum-rendering can become very slow, because of the excessive sub-pixeling this causes. There are ways to limit the sub-pixeling for those cases. See the Section on sub-pixeling in spherical coordinate: Section 9.6.4.

10.3 Oct-tree Adaptive Mesh Refinement

An oct-tree refinened grid is called "grid style 1" in RADMC-3D. It can be used in Cartesian coordinates as well as in spherical coordinates (Section 5.3).

You start from a normal regular base grid (see Section 10.1), possibly even with "separable refinement" (see Section 10.2). You can then split some of the cells into 2x2x2 subcells (or more precisely: in 1-D 2 subcells, in 2-D 2x2 subcells and in 3-D 2x2x2 subcells). If necessary, each of these 2x2x2 subcells can also be split into further subcells. This can be repeated as many times as you wish until the desired grid refinement level is reached. Each refinement step refines the grid by a factor of 2 in linear dimension, which means in 3-D a factor of 8 in volume. In this way you get, for each refined cell of the base grid, a tree of refinement. The base grid can have any size, as long as the number of cells in each direction is an even number. For instance, you can have a 6x4 base grid in 2-D, and refine cell (1,2) by one level, so that this cell splits into 2x2 subcells.

Note that it is important to set which dimensions are "active" and which are "non-active". For instance, if you have a 1-D model with 100 cells and you tell RADMC-3D (see Section A.2.2) to make a base grid of 100x1x1 cells, but you still keep all three dimensions "active" (see Section A.2.2), then a refinement of cell 1 (which is actually cell (1,1,1)) will split that cell into 2x2x2 subcells, i.e. it will also refine in y and z direction. Only if you explicitly switch the y and z dimensions off the AMR will split it into just 2 subcells.

Oct-tree mesh refinement is very powerful, because it allows you to refine the grid exactly there where you need it. And because we start from a regular base grid like the grid specified in Section 10.1, we can start designing our model on a regular base grid, and then refine where needed. See Fig. 10.3

The AMR stand for "Adaptive Mesh Refinement", which may suggest that RADMC-3D will refine internally. At the moment this is not yet the case. The "adaptive" aspect is left to the user: he/she will have to "adapt" the grid such that it is sufficiently refinened where it is needed. In the future we may allow on-the-fly adaption of the grid, but that is not yet possible now.

One problem with oct-tree AMR is that it is difficult to handle such grids in external plotting programs, or even in programs that set up the grid. While it is highly flexible, it is not very user-friendly. Typically you may use this oct-tree refinement either because you import data from a hydrodynamics code that works with oct-tree refinement (e.g. FLASH, RAMSES), or when you internally refine the grid using the userdef_module.f90 (see Chapter 13). In the former case you are anyway forced to manage the complexities of AMR, while in the latter case you can make use of the AMR modules of RADMC-3D internally to handle them. But if you do not need to full flexibility of oct-tree refinement and want to use a simpler kind of refinement, then you can use RADMC-3D's alternative refinement mode: the layer-style AMR described in Section 10.4 below.

The precise way how to set up such an oct-tree grid using the amr_grid.inp file is described in Section A.2.2. The input of any spatial variables (such as e.g. the dust density) uses the sequence of grid cells in the same order as the cells are specified in that amr_grid.inp file.

10.4 Layered Adaptive Mesh Refinement

A layer-style refinened grid is called "grid style 10" in RADMC-3D. It can be used in Cartesian coordinates as well as in spherical coordinates (Section 5.3).

This is an alternative to the full-fledged oct-tree refinement of Section 10.3. The main advantage of the layer-style refinement is that it is far easier to handle by the human brain, and thus easier for model setup and the analysis of the results.

The idea here is that you start again with a regular grid (like that of Section 10.1), but you can now specify a rectangular region which you want to refine by a factor of 2. The way you do this is by choosing the starting indices of the rectangle and specifying the size of the rectangle by setting the number of cells in each direction from that starting point onward. For instance, setting the starting point at (2,3,1) and the size at (1,1,1) will simply refine just cell (2,3,1) of the base grid into a set of 2x2x2 sub-cells. But setting the starting point at (2,3,1) and the size at (2,2,2) will split cells (2,3,1), (3,3,1), (2,4,1), (3,4,1), (2,3,2), (3,3,2), (2,4,2) and (3,4,2) each into 2x2x2 subcells. This in fact is handled as a 4x4x4 regular sub-grid patch. And setting the starting point at (2,3,1) and the size at (4,6,8) will make an entire regular sub-grid patch of 8x12x16 cells. Such a sub-grid patch is called a *layer*.

The nice thing of these layers is that each layer (i.e. subgrid patch) is handled as a regular sub-grid. The base grid is layer number 0, and the first layer is layer number 1, etc. Each layer (including the base grid) can contain multiple sub-layers. The only restriction is that each layer fits entirely inside its parent layer, and layers with the same parent layer should not overlap. Each layer can thus have one or more sub-layers, each of which can again be divided into sub-layers. This builds a tree structure, with the base layer as the trunk of the tree (this is contrary to the oct-tree structure, where each base grid *cell* forms the trunk of its own tree). In Fig. 10.4 an example is shown of two layers with the same parent (= layer 0 = base grid), while in Fig. 10.5 an example is shown of two nested layers.

If you now want to specify data on this grid, then you simply specify it on each layer separately, as if each layer is a separate entity. Each layer is treated as a regular grid, irrespective of whether it contains sub-layers or not. So if we have a base grid of 4x4x4 grid cells containing two layers: one starting at (1,1,1) and having (2,2,2) size and another starting at (3,3,3) and having (1,1,2) size, then we first specify the data on the 4^3 =64 base grid, then on the $(2*2)^3$ =64 grid cells of the first layer and then on the 2x2x4=16 cells of the second layer. Each of these three layers are regular grids, and the data is inputted/outputted in the same way as if these are normal regular grids (see Section 10.1). But instead of just one such regular grid, now the data file (e.g. dust_density.inp) will contain three successive lists of numbers, the first for the base grid, the second for the first layer and the last for the second layer. You may realize at this point that this will introduce a redundancy. See Subsection 10.4.1 for a discussion of this redundancy.

The precise way how to set up such an oct-tree grid using the amr_grid.inp file is described in Section A.2.3. The input of any spatial variables (such as e.g. the dust density) uses the sequence of grid cells in the same order as the cells are specified in that amr_grid.inp file.

10.4.1 On the "successively regular" kind of data storage, and its slight redundancy

With the layered grid refinement style there will be *redundant* data in the data files (such as e.g. the dust_density.inp file. Each layer is a regular (sub-)grid and the data will be specified in each of these grid cells of that regular (sub-




Figure 10.4. Example of a 2-D base grid with nx=4 and ny=3, with two AMR-layers added to it. This example has just one level of refinement, as the two layers (brown and gree) are on the same level (they have the same parent layer = layer 0).




Figure 10.5. Example of a 2-D base grid with nx=4 and ny=3, with two nested AMR-layers added to it. This example has two levels of refinement, as layer 1 (brown) is the parent of layer 2 (green).

)grid. If then some of these cells are overwritten by a higher-level layer, these data are then redundant. We could of course have insistent that only the data in those cells that are not refined by a layer should be written to (or read from) the data files. But this would require quite some clever programming on the part of the user to a-priori find out where the layers are and therefore which cells should be skipped. We have decided that it is far easier to just insist that each layer (including the base grid, which is layer number 0) is simply written to the data file as a regular block of data. The fact that some of this data will be not used (because they reside in cells that are refined) means that we write more data to file than really exists in the model. This makes the files larger than strictly necessary, but it makes the data structure by far easier. Example: suppose you have a base grid of 8x8x8 cells and you replace the inner 4x4x4 cells with a layer of 8x8x8 cells (each cell being half the size of the original cells). Then you will have for instance a dust_density.inp file containing 1024 values of the density: 83=512 values for the base grid and again 8^3 =512 values for the refinement layer. Of the first 8^3 =512 values 4^3 =64 values are ignored (they could have any value as they will not be used). The file is thus 64 values larger than strictly necessary, which is a redundancy of 64/1024=0.0625. If you would have used the oct-tree refinement style for making exactly the same grid, you would have only 1024-64=960 values in your file, making the file 6.25% smaller. But since 6.25% is just a very small difference, we decided that this is not a major problem and the simplicity of our "successively regular" kind of data format is more of an advantage than the 6.25% redundance is a disadvantage.

10.5 Unstructured grids

In a future version of RADMC-3D we will include unstructured gridding as a possibility. But at this moment such a gridding is not yet implemented.

10.6 1-D Plane-parallel models

Sometimes it can be useful to make simple 1-D plane parallel models, for instance if you want to make a simple 1-D model of a stellar atmosphere. RADMC-3D is, however, by nature a 3-D code. But as of version 0.31 it features a genuine 1-D plane-parallel mode as well. This coordinate type has the number 10. In this mode the x- and y-coordinates are the in-plane coordinates, while the z-coordinate is the 1-D coordinate. We thus have a 1-D grid in the z-coordinate, but no grid in x- or y-directions.

You can make a 1-D plane-parallel model by setting some settings in the amr_grid.inp file. Please consult Section A.2 for the format of this file. The changes/settings you have to do are (see example below): (1) set the coordinate type number to 10, (2) set the x and y dimensions to non-active and (3) setting the cell interfaces in x to -1d90, +1d90, and likewise for y. Here is then how it looks:

```
<=== Format number = 1
0
                                       <=== Grid style (0=regular grid)
10
                                       <=== Coordinate type (10=plane-parallel)</pre>
0
                                       <=== (obsolete)
0 0 1
                                       <=== x and y are non-active, z is active
1 1 100
                                       <=== x and y are 1 cell, in z we have 100 cells
-1d90 1d90
                                       <=== cell walls in x are at "infinity"
-1d90 1d90
                                       <=== cell walls in y are at "infinity"
             zi[2]
                          zi[3]
zi[1]
                                       ....zi[nz+1]
```

The other input files are for the rest as usual, as in the 3-D case.

You can now make your 1-D model as usual. For 1-D plane-parallel problems it is often useful to put a thermal boundary at the bottom of the model. For instance, if the model is a stellar atmosphere, you may want to cap the grid from below with some given temperature. See Section 10.8 for details on how to set up thermal boundaries.

In the 1-D plane-parallel mode some things work a bit different than in the "normal" 3-D mode:

- Images are by default 1x1 pixels, because in a plane-parallel case it is useless to have multiple pixels.
- Spectra cannot be made, because "spectrum" is (in RADMC-3D 'language') the flux as a function of frequency as seen at a very large distance of the object, so that the object is in the "far field". Since the concept of "far-field" is no longer meaningful in a plane-parallel case, it is better to make frequency-dependent 1x1 pixel images. This gives you the frequence-dependent intensity, which is all you should need.

Stars are not allowed, as they have truly 3-D positions, which is inconsistent with the plane-parallel assumption.

But for the rest, most stuff works similarly to the 3-D version. For instance, you can compute dust temperatures with

```
radmc3d mctherm
```

as usual.

10.6.1 Making a spectrum of the 1-D plane-parallel atmosphere

As mentioned above, the "normal" 3-D way of making a spectrum of the 1-D plane-parallel atmosphere is not possible, because formally the atmosphere is infinitely extended. Instead you can obtain a spectrum in the form of an intensity (erg s⁻¹ cm⁻² Hz⁻¹ ster⁻¹) as a function of wavelength. To do this you ask RADMC-3D to make a multi-wavelength image of the atmosphere under a certain inclination (inclination 0 meaning face-on), e.g.:

```
radmc3d image allwl incl 70
```

This make an SED at $\lambda=10\,\mu\mathrm{m}$ for the observer seeing the atmosphere at an inclination of 70 degrees. This produces a file image.out, described in Section A.16. The image is, in fact, a 1x1 pixel multi-wavelength image. The allwl (which stands for "all wavelengths") means that the spectral points are the same as those in the wavelength_micron.inp file (see Section A.12). You can also specify the wavelengths in a different way, e.g.:

```
radmc3d image lambdarange 5 20 nlam 10
```

In fact, see Section 9.2 and Section 9.4 for details.

10.6.2 In 1-D plane-parallel: no star, but incident parallel flux beams

In 1-D plane-parallel geometry it is impossible to include meaningful stars as sources of photons. This is not a technical issue, but a mathematical truth: a point in 1-D is in reality a plane in 3-D. As a replacement RADMC-3D offers (only in 1-D plane-parallel geometry) the possibility of illuminating the 1-D atmosphere from above with a flux, incident onto the atmosphere in a prescribed angle. This allows you to model, e.g., the Earth's atmosphere being illuminated by the sun at a given time of the day. This is done by providing an ascii file called illum.inp which has the following form (similar, but not identical, to the stars.inp file, see Section A.7):

Here nillum is the number of illuminating beams you want to specify. Normally this is 1, unless you have, e.g., a planet around a double star. The theta is the angle (in degrees) under which the beam impinges onto the

atmosphere. If you have theta=0, then the flux points vertically downward (sun at zenith). If you have theta=89, then the flux points almost parallel to the atmosphere (sunset). It is not allowed to put theta=90.

You can, if you wish, also put the source behind the slab, i.e. theta; 90. Please note, however, that if you compute the spectrum of the plane-parallel atmosphere the direct flux from these illumination beams does not get picked up in the spectrum.

10.6.3 Similarity and difference between 1-D spherical and 1-D plane-parallel

Note that this 1-D plane-parallel mode is only available in z-direction, and only for cartesian coordinates! For spherical coordinates, a simple switch to 1-D yields spherically symmetric 1-D radiative transfer, which is, however, geometrically distinct from 1-D plane-parallel radiative transfer. However, you can also use a 1-D spherically symmetric setup to "emulate" 1-D plane parallel problems: You can make, for instance, a radial grid in which $r_{\rm nr}/r_1-1\ll 1$. An example: $r=\{10000.0,10000.1,10000.2,\cdots,10001.0\}$. This is not perfectly plane-parallel, but sufficiently much so that the difference is presumably indiscernable. The spectrum is then automatically that of the entire large sphere, but by dividing it by the surface area, you can recalculate the local flux. In fact, since a plane-parallel model usually is meant to approximate a tiny part of a large sphere, this mode is presumably even more realistic than a truly 1-D plane-parallel model.

10.7 2-D Pencil-parallel models

[IN PREPARATION]

10.8 Thermal boundaries in Cartesian coordinates

By default all boundaries of the computational domain are open, in the sense that photons can move out freely. The only photons that move into the domain from the outside are those from the interstellar radiation field (see Section 11.4) and from any stars that are located outside of the computational domain (see Section A.7). For some purposes it might, however, be useful to have one or more of the six boundaries in 3-D to be closed. RADMC-3D offers the possibility, in cartesian coordinates, to convert the boundaries (each of the six separately) to a thermal boundary, i.e. a blackbody emitter at some user-secified temperature. If you want that the left X-boundary is a thermal wall at T=100 Kelvin, then you add the following line to the radmc3d.inp file:

```
thermal_boundary_xl = 100
```

and similarly for xr (right X-boundary), yl, yr, zl and/or zr. You can set this for each boundary separately, and particularly you can choose to set just one or just two of the boundaries to thermal boundaries. Note that setting thermal_boundary_xl = 0 is equivalent to switching off the thermal boundary.

Note that if you now make an image of the box, the ray-tracer will show you still the inside of the box, through any possible thermal boundary. In other words: for the imaging or spectra these thermal boundaries are opaque for radiation entering the grid, while they are transparent for radiation exiting the grid. In other words, we see the blackbody emission from the backside walls, but not of the frontside walls. In this way we can have a look inside the box in spite of the thermal walls.

More information about the treatment of stars

How stars are treated in RADMC-3D is perhaps something that needs some more background information. This is the structure:

1. Stars as individual objects:

The most standard way of injecting stellar light into the model is by putting one or more individual stars in the model. A star can be placed anywhere, both inside the grid and outside. The main input file specifying their location and properties is: stars.inp. The stars can be treated in two different ways, depending on the setting of the variable istar_sphere that can be set to 0 or 1 in the file radmc3d.inp file.

- The default is to treat stars as zero-size point sources. This is the way it is done if (as is the default) istar_sphere=0. The stars are then treated as point sources in spite of the fact that their radius is specified as non-zero in the stars.inp file. This default mode is the easiest and quickest. For most purposes it is perfectly fine. Only if you have material very close to a stellar surface it may be important to treat the finite size(s) of the star(s).
- If istar_sphere=1 in the radmc3d.inp file, then all stars are treated as spheres, their radii being the radii specified in the stars.inp file. This mode can be tricky, so please read Section 11.2.

2. Smooth distributions of zillions of stars:

For modeling galaxies or objects of that size scale, it is of course impossible and unnecessary to treat each star individually. So *in addition to the individual stars* you can specify spatial distributions of stars, assuming that the number of stars is so large that there will always be a very large number of them in each cell. Please note that using this possibility does *not* exclude the use of individual stars as well. For instance, for a galaxy you may want to have distributions of unresolved stars, but one single "star" for the active nucleus and perhaps a few individual "stars" for bright star formation regions or O-star clusters or so. The distribution of stars is described in Section 11.3.

3. An external "interstellar radiation field":

Often an object is affected not only by the stellar radiation from the stars inside the object itself, but also by the diffuse radiation from the many near and far stars surrounding the object. This "Interstellar Radiation Field" can be treated by RADMC-3D as well. This is called the "external source" in RADMC-3D. It is described in Section 11.4.

11.1 Stars treated as point sources

By default the stars are treated as point-sources. Even if the radius is specified as non-zero in the stars.inp file, they are still treated as points. The reason for this is that it is much easier and faster for the code to treat them as point-sources. Point sources cannot occult anything in the background, and nothing can partly occult them (they are

only fully or not occulted, of course modulo optical depth of the occulting object). This approximation is, however, not valid if the spatial scales you are interested in are not much larger (or even the same or smaller) than the size of the star. For instance, if we are interested in modeling the radiative transfer in a disk around a Brown Dwarf, where dust can survive perhaps even all the way down to the stellar surface, we must take the non-point-like geometry of the star into account. This is because due to its size, the star can shine *down* onto the disk, which would not be possible if the star is treated as a point source. However, for a dust disk arounda Herbig Ae star, where the dust evaporation radius is at about 0.5 AU, the star can be treated as a point-source without problems.

So if you just use RADMC-3D as-is, or if you explicitly set istar_sphere = 0 in the file radmc3d.inp, then the stars are all treated as point sources.

11.2 Stars treated as spheres

For problems in which the finite geometrical size of the star (or stars) is/are important, RADMC-3D has a mode by which the stars are treated as spheres. This can be necessary for instance if you model a disk around a Brown Dwarf, where the dusty disk goes all the way down to the stellar surface. The finite size of the star can thus shine *down* onto the disk, but only if its finite size is treated as such. In the default point-source approximation the surface layers of such a disk would be too cold, because this "shining down onto the disk" phenomenon is not treated.

You can switch this mode on by setting istar_sphere = 1 in the file radmc3d.inp. Note that no limb darkening or brightening is included in this mode, and currently RADMC-3D does not have such a mode available.

This mode is, however, somewhat complex. A sphere can partly overlap the grid, while being partly outside the grid. A sphere can also overlap multiple cells at the same time, engulfing some cells entirely, while only partly overlapping others. The correct and fast treatment of this makes the code a bit slower, and required some complex programming. So the user is at the moment advised to use this mode only if necessary and remain aware of possible errors for now (as of version 0.17).

For the Monte Carlo simulations the finite star size means that photon packages are emitted from the surface of the sphere of the star. It also means that any photon that re-enters the star during the Monte Carlo simulation is assumed to be lost.

11.3 Distributions of zillions of stars

For models of galaxies it is important to be able to have distributed stellar sources instead of individual stars. The way to implement this in a model for RADMC-3D is to

- 1. Prepare one or more *template stellar spectra*, for instance, one for each stellar type you wish to include. These must be specified in the file stellarsrc_templates.inp (see Section A.8). Of course the more templates you have, the more memory consuming it becomes, which is of particular concern for models on large grids. You can of course also take a sum of various stellar types as a template. For instance, if we wish to include a 'typical' bulge stellar component, then you do not need to treat each stellar type of bulge stars separately. You can take the 'average spectrum per gram of average star' as the template and thus save memory.
- 2. For each template you must specify the *spatial distribution*, i.e. how many stars of each template star are there per unit volume in each cell. The stellar density is, in fact, given as gram-of-star/cm³ (i.e. not as number density of stars). The stellar spatial densities are specified in the file stellarsrc_density.inp (see Section A.9).

Note that if you have a file stellarsrc_templates.inp in your model directly, then the stellar sources are automatically switched on. If you do not want to use them, then you must delete this file.

The smooth stellar source distributions are nothing else than source functions for the radiative transfer with the spectral shape of the template stellar spectra from the stellarsrc_templates.inp. You will see that if you make a spectrum of your object, then even if the dust temperature etc is zero everywhere, you still see a spectrum: that of the stellar template(s). In the Monte Carlo simulations these stellar templates act as net sources of photons, that subsequently move through the grid in a Monte Carlo way.

Note that the smooth stellar source distributions assume that the zillions of stars that they represent are so small that they do not absorb any appreciable amount of radiation. They are therefore pure sources, not sinks.

11.4 The interstellar radiation field: external source of energy

You can include an *isotropic* interstellar radiation field in RADMC-3D. This will take effect both in the making of spectra and images, as well as in the Monte Carlo module.

The way to activate this is to make a file external_source.inp and fill it with the information needed (see Section A.10).

11.4.1 Role of the external radiation field in Monte Carlo simulations

For the Monte Carlo simulations this means that photons may be launched from outside inward. The way that this is done is that RADMC-3D will make a sphere around the entire grid, just large enough to fit in the entire grid but not larger. Photon packages can freely leave this sphere. But if necessary, photon packages can be launched from this sphere inward. RADMC-3D will then calculate the total luminosity of this sphere, which is $L=4\pi^2Ir_{\rm sphere}^2$ where I is the intensity. For monochromatic Monte Carlo it is simply $I=I_{\nu}$, while for the thermal Monte Carlo it is $I=\int_0^{\infty}I_{\nu}d\nu$, where I_{ν} is the intensity as specified in the file external_source.inp. Note that if the sphere would have been taken larger, then the luminosity of the external radiation field would increase. This may seem anti-intuitive. The trick, however, is that if the sphere is larger, then also more of these interstellar photons never enter the grid and are lost immediately. That is why it is so important that RADMC-3D makes the sphere as small as possible, so that it limits the number of lost photon packages. It also means that you, the user, would make the grid much larger than the object you are interested in, then RADMC-3D is forced to make a large sphere, and thus potentially many photons will get lost: they may enter the outer parts of the grid, but there they will not get absorbed, nor will they do much.

In fact, this is a potential difficulty of the use of the external sources: since the photon packages are lauchned from outside-inward, it may happen that only few of them will enter in the regions of the model that you, the user, are interested in. For instance, you are modeling a 3-D molecular cloud complex with a few dense cold starless cores. Suppose that no stellar sources exist in this model, only the interstellar radiation field. The temperature in the centers of these starless cores will be determined by the interstellar radiation field. But since the cores are very small compared to the total model (e.g. you have used AMR to refine the grid around/in these cores), the chance of each external photon package to 'hit' the starless core is small. It means that the larger the grid or the smaller the starless core, the more photon packages (nphot, see Section 6.1) one must use to make sure that at least some of them enter the starless cores. If you choose nphot too small in this case, then the temperature in these cores would remain undetermined (i.e. they will be zero in the results).

11.4.2 Role of the external radiation field in images and spectra

The interstellar radiation field also affects the images and spectra that you make. Every ray will start at minus-infinity with the intensity given by the external radiation field, instead of 0 as it would be if no external radiation field is specified. If you make an image, the background of your object will then therefore not be black. You can even make silhouette images like those of the famous silhouette disks in Orion.

But there is a danger: if you make spectra, then also the background radiation is inside the beam, and will thus contribute to the spectrum. In fact, the larger you make the beam the more you will pick up of the background. This could thus lead to the spectrum of your source to be swamped by the background if you do not specify a beam in the spectrum.

11.5 Internal heat source

Sometimes the gas and dust inside the object of interest gets heated up by some internal process such as friction, magnetic reconnection, chemical reactions, etc. A nice example is the "viscous heating" inside an accretion disk.

This net heat source can be included in RADMC-3D by creating a file heatsource.inp. The format of the file is described in Section A.11. It is the same as for other scalar fields.

With this input file you have to specify in each cell how much energy per second per cubic centimeter is released in the form of heat. This energy will then be emitted as radiation by the dust. The way the code does this in the Bjorkman & Wood algorithm is that it will launch photon packages from these cells. The difference with the stellar energy input (see Section 11.3) is that the energy is first injected into the dust of the cell, and then emitted as thermal dust emission. The launching of the photon package is therefore always a thermal dust emission. In contrast, in the stellar energy input method of Section 11.3 the photon package is launched directly, with a wavelength randomly drawn from the local stellar spectrum shape. The difference between these two methods will be most apparent for optically thin models. For very optically thick cases, where the heat source is released deep inside an optically thick object, both methods will presumably yield the same result. Nevertheless, it is recommended to use the heat source method for cases such as chemical or viscous heating of the gas and dust, even for optically thick cases.

A note of caution: in spite of the fact that this heat source method allows you to add additional energy sources, the object of study must still be in local thermodynamic equilibrium (LTE). If the gas+dust mixture is flowing and experiences significant adiabatic heating and cooling events, then the LTE condition is no longer met and RADMC-3D will not be able to give reliable answers. Sometimes one may be able to fudge this in some clever way, but one should always be aware that strictly speaking the Bjorkman & Wood Monte Carlo method only works if in each cell all energy input (be it radiative absorption or an internal heat source) is balanced exactly by the same amount of radiative energy output. The algorithm computes the dust temperature on that assumption: it computes how much energy the cell gains (by the heat source or by absorbing photons) and then it requires that the temperature of the dust is such that precisely the same amount of radiative energy is emitted.

11.5.1 Slow performance of RADMC-3D with heat source

For very optically thick models, such as the inner regions of actively accreting dusty protoplanetary disks, the use of this heat source can lead to extremely slow performance. The reason is that all photons originating from this heat source will start their journey right in the middle of the most optically thick regions, requiring these photons to make gazillions of absorption/re-emission events before finally diffusing out. It should in principle work if the code runs long enough. But one must have some patience. The use of the Modified Random Walk method (see Section 6.1.1) would then be useful to speed things up, but still it can take time.

A few things might be useful to consider. One is that protoplanetary disks only have such insane optical depths $(au\gtrsim 10^5)$ if none of the dust has coagulated to bigger grains. This might be the correct assumption, especially in the very early phases of protoplanetary disk evolution. But dust coagulation is known to be quick, so it might equally well be that, say, 90% of the small grain dust has already grown to larger grains, which have less opacity. This is of course just a pure guess. Another thing is that many MHD models of disk turbulence show that most of the energy is not released near the midplane, but instead at one or two scale heights above the midplane. Both considerations would lower the optical depth for the energy to get out of the disk, speeding up the calculation. And the outcoming spectrum or image it will presumably not be affected that much, because at the end of the day the effective temperature of the disk surface must anyway be such that it radiates away the internal heat, independent of how deep inside the disk this heat is released.

Using RADMC-3D in child mode (optional)

For large datasets it may take a considerable amount of time for RADMC-3D to read the entire dataset into memory. Having to wait such a long time for every action one wants to take (e.g. re-making an image at a different vantage point or a different wavelength) quickly gets on one's nerves and strongly inhibits the interactivity between RADMC-3D and the user. The "child mode" is designed to circumvent this problem. It allows RADMC-3D to be started as a child process of another process, stay in memory (with all the data loaded once-and-for-all) for as long as the parent process lives, and have communication with its parent process via a bi-way pipe. A bi-way pipe is like a file to which you can write or from which you can read. Your parent process, which calls RADMC-3D as a child, can give RADMC-3D the command to do something by writing to the pipe file unit, and then receiving the results from RADMC-3D by reading from that same file unit.

The IDL program viewimage.pro (see chapter 14), which is part of the RADMC-3D package, calls RADMC-3D as a child process and communicates with it in precisely this way.

NOTE: Currently there appears to be a problem when trying to use RADMC-3D in child mode on some systems. For instance, viewimage may freeze. This appears to be a problem with buffering of the standard I/O unit. I have been trying to figure out what causes this, and particularly, why it happens on some machines and not on other machines (in fact it happened on one Macbook but not on another, while the systems were seemingly identical). I will continue to work on this. When calling viewimage and the thing freezes, try calling viewimage,/nochild. That is slower, but should work.

In IDL this is done with the keyword unit=unit in the spawn command. For instance, in viewimage.pro there is a line

```
spawn,'nice radmc3d child',unit=iounit
```

The nice is simply to let RADMC-3D run at a low priority under Linux or Mac OS X, the child command line option is a RADMC-3D specific command line option that tells RADMC-3D that it should not exit after its first action, but wait further orders. The unit=iounit gets the file unit through which we can communicate with RADMC-3D. Of course, by virtue of the fact that RADMC-3D is called by IDL in the first place, it is naturally IDL's child process. But by asking RADMC-3D not to exit after the first action, and by getting the file unit from the keyword unit=, RADMC-3D will wait for our commands and only exit when we tell it so by giving it the command quit.

The way we can communicate with RADMC-3D is by writing to the file iounit commands like the ones on the command line. But contrary to the normal command line, they are now given one word per line. For instance, to let RADMC-3D make an image at wavelength number ilambda (from IDL):

```
printf,iounit,'image'
printf,iounit,'npix'
printf,iounit,strcompress(string(npix),/remove_all)
printf,iounit,'ilambda'
printf,iounit,strcompress(string(ilambda),/remove_all)
printf,iounit,'incl'
printf,iounit,strcompress(string(incl),/remove_all)
printf,iounit,'phi'
printf,iounit,strcompress(string(phi),/remove_all)
printf,iounit,strcompress(string(phi),/remove_all)
printf,iounit,'enter'
```

The enter is meant to tell RADMC-3D: now go and do your work. In fact, you rarely have to interact like this with RADMC-3D youself, because you can use the IDL subroutine makeimage() in the readradmc.pro file that does all these things for you; just set the keyword iounit to the value you obtained from starting radmc3d in child mode.

In child mode the results from radmc3d are not returned immediately to the parent. To ask radmc3d for the results of its latest calculation (for instance an image), you do:

```
printf, iounit, 'writeimage'
```

followed by

```
iformat=0
nx=0
ny=0
nf=0
readf,iounit,iformat
readf,iounit,nx,ny
readf,iounit,nf
readf,iounit,sizepix_x,sizepix_y
lambda=dblarr(nf)
readf,iounit,lambda
image=fltarr(nx,ny,nf)
readf,iounit,image
```

But again you don't have to do this complex stuff yourself. Instead this is done for you by the readimage() IDL routine in the readradmc.pro file, again when iounit is specified.

So IDL users can simply do (in IDL):

```
.r readradmc
;
; Start RADMC-3D
;
spawn,'nice radmc3d child',unit=iounit
;
; Make an image
;
makeimage,incl=45.,phi=10.,npix=200,ifreq=10,iounit=iounit
;
; Read the image from RADMC-3D
;
a=readimage(iounit=iounit)
;
; Plot the image on the screen
;
plotimage,a
;
: ...and here many more images or spectra...
; ....
; ....
; And when we are done, quit RADMC-3D and free the file number
;
printf,iounit,'quit'
close,iounit
free_lun,iounit
```

Tip: If you use RADMC-3D in child mode, then all the usual output that normally would go to screen will now be redirected to a separate file called radmc3d.out. This is useful for debugging the code when using it in child mode. So if RADMC-3D fails somehow when in child mode, then have a look at radmc3d.out to see what went wrong.

Using the userdef_module.f90 file for internal model setup and user-defined emission/absorption processes (optional)

It has been mentioned several times before that as an alternative to the standard 'compile once-and-for-all' philosophy, one can also use RADMC-3D by modifying the code directly so that radmc3d will have new functionality that might be of use for you. We refer to Section 4.7 for an in-depth description of how to modify the code in a way that is *non-invasive* to the main code. We urge the reader to read Section 4.7 first before continuing to read this chapter. In all of the following we assume that the editings to the fortran files are done in the local way described in Section 4.7 so that the original source files in the src/directory stay unaffected, and only local copies are edited.

13.1 Setting up a model inside of RADMC-3D

The most common reason for editing the code itself is for setting up the model *internally* rather than reading in all data via input files. For a list of advantages and disadvantages of setting models up internally as opposed to the standard way, see Section 13.3 below. Setting up a model within RADMC-3D is done by making a local copy of the file userdef_module.f90 and editing it (see Section 4.7). This file contains a set of standard subroutines that are called by the main program at special points in the code. Each subroutine has a special purpose which will be described below. By keeping a subroutine empty, nothing is done. By filling it with your own code lines, you can set up the density, temperature or whatever needs to be set up for the model. In addition to this you can do the following as well:

- Add new variables or arrays in the module header (above the contains command), which you can use in the subroutines of the userdef_module.f90 module. You are completely free to add any new variables you like. A small tip: it may be useful (though not required) to start all their names with e.g. userdef_to make sure that no name conflicts with other variables in the code happen.
- Add new subroutines at will (below the contains command) which you can call from within the standard subroutines.
- Introduce your own radmc3d command-line options (see Section 13.2).
- Introduce your own radmc3d.inp namelist variables (see Section 13.2).

Often you still want some of the input data to be still read in in the usual way, using input files. For instance, you may want to still read the dustopac.inp and the opacities using the dustkappa_xxx.inp files. This is all possible. Typically, you simply keep the files you still want RADMC-3D to read, and omit the files that contain data that you allocate and set in the userdef_module.f90. This is all a bit complicated, so the best way to learn how to do this is to start from the example directories in which a model is set up with the userdef_module.f90 method.




Figure 13.1. Pictographic representation of the dataflow for the case when you define your model *internally* using the userdef_module.f90.

In Fig. 13.1 the dataflow for the user-defined model setup is graphically depicted.

13.2 The pre-defined subroutines of the userdef_module.f90

The idea of the userdef_module.f90 is that it contains a number of standard pre-defined subroutines that are called from the main.f90 code (and *only* from there). Just browse through the main.f90 file and search for the sequence "call userdef_" and you will find all the points where these standard routines are called. It means that at these points you as the user have influence on the process of model setup. Here is the list of standard routines and how they are used. They are ordered roughly in chronological order in which they are called.

- userdef_defaults()
 - This subroutine allows you to set the default value of any new parameters you may have introduced. If neither on the command line nor in the radmc3d.inp file the values of these parameters are set, then they will simply retain this default value.
- userdef_commandline(buffer,numarg,iarg,fromstdi,gotit)
 This subroutine allows you to add your own command-line options for radmc3d. The routine has a series of standard arguments which you are not allowed to change. The buffer is a string containing the current command line option that is parsed. You will check here if it is an option of your module, and if yes, activate it. An example is listed in the code. You an also require a second argument, for which also an example is listed in the original code.
- userdef_commandline_postprocessing()
 After the command line options have been read, it can be useful to check if the user has not asked for conflicting things. Here you can do such checks.
- userdef_parse_main_namelist()
 Here you can add your own namelist parameters that read from the radmc3d.inp file. An example is provided in the original code.
- userdef_main_namelist_postprocessing()
 Also here, after the entire radmc3d.inp file has been read and interpreted, you can do some consistency checks and postprocessing here.
- userdef_prep_model()
 - This routine can be used if you wish to set up the grid not from input files but internally. You will have to know how to deal with the amr_module.f90 module. You can also set your own global frequency grid here. And finally, you can set your own stellar sources here. In all cases, if you set these things here (which requires you to make the proper memory allocations, or in case of the gridding, let the amr_module.f90 do the memory allocations for you) the further course of radmc3d will skip any of its own settings (it will simply detect if these arrays are allocated already, and if yes, it will simply not read or allocate them anymore).
- userdef_setup_model()
 - This is the place where you can actually make your own model setup. By the time this subroutine is called, all your parameters have been read in, as well as all of the other parameters from the original radmc3d code. So you can now set up the dust density, or the gas velocity or you name it. For all of these things you will have to allocate the arrays youself (!!!). Once you did this, the rest of the radmc3d code won't read those data anymore, because it detects that the corresponding arrays have already been allocated (by you). This allows you to completely circumvent the reading of any of the following files by making these data yourself here at this location:

- amr_grid.inp or in the future the input files for any of the other griding types.
- dust_density.inp
- dust_temperature.dat
- gas_density.inp
- gas_temperature.inp
- gas_velocity.inp
- microturbulence.inp
- levelpop_XXX.dat
- numberdens_XXX.inp

To learn how to set up a model in this way, we refer you for now to the <code>ioput_module.f90</code> or <code>lines_module.f90</code> and search for the above file names to see how the arrays are allocated and how the data are inserted. I apologise for not explaining this in more detail at this point. But examples are or will be given in the <code>examples/directory</code>.

• userdef_dostuff()

This routine will be called by the main routine to allow you to do any kind of calculation after the main calculation (for instance after the monte carlo simulation). This is done within the execution-loop, so that if you use RADMC-3D in child mode, this routine will be called after each calculation.

• userdef_myaction()

If RADMC-3D is called as radmc3d myaction, then the user-defined routine userdef_myaction() is called, just like the spectrum making routine is called if you type radmc3d sed. This allows the user to make RADMC-3D do special things on demand. Note that this can be used in combination with many of the above subroutines to interpret command-line options and radmc3d.inp entries. *Not yet working in version 0.15*.

• userdef_compute_levelpop()

This is a subroutine that can be called by the camera module for on-the-fly calculation of level populations according to your own recipe. This may be a bit tricky to use, but I hope to be able to provide some example(s) in the near future.

• userdef_srcalp()

This subroutine allows you to add any emission/absorption process you want, even fake ones. For instance, you could use this to create nicely volume-rendered images of your 3-D models with fake opacities, which are chosen to make the image look nice and/or insight-giving. You can also use this to add physical processes that are not yet implemented in RADMC-3D. This subroutine allows you full freedom and flexibility to add emissivity and extinction whereever/however you like. To activate it you must set incl_userdef_srcalp = 1 in the radmc3d.inp file.

• userdef_writemodel()

This allows the user to dump any stuff to file that the user computed in this module. You can also use this routine to write out files that would have been used normally as input file (like amr_grid.inp or dust_density.inp) so that the IDL routines can read them if they need. In particular the grid information may be needed by these external analysis tools. Here is a list of standard subroutines you can call for writing such files:

- write_grid_file()
- write_dust_density()
- ...more to come...

• userdef_reset_flags()

If the user wants some flags to be reset after each command (in the child mode, see Chapter 12), then here it can be done.

For now this is it, more routines will be included in the future.

Note that the userdef_compute_levelpop() subroutine, in contrast to all the others, is called not from the main.f90 program but from the camera_module.f90 module. This is why the camera module is the only module that is higher in compilation ranking than the userdef module (i.e. the userdef module will be compiled before the camera module). For this reason the userdef module has no access to the variables of the camera module. For the rest, the userdef module has access to the variables in all other modules.

Note also that not all input data is meant to be generated in this way. The following types of data are still supposed to be read from file:

- Dust opacity data
- Molecular fundamental data

Please have a look in the examples / directory for models which are set up in this internal way.

13.3 Some caveats and advantages of internal model setup

Setting up the models internally has several advantages as well as disadvantages compared to the standard way of feeding the models into radmc3d via files. The advantages are, among others:

- You can modify the model parameters in radmc3d.inp and/or in the command line options (depending on how you allow the user to set these parameters, i.e. in the userdef_parse_main_namelist() routine and/or in the userdef_commandline() routine. You then do not need to run IDL anymore (except for setting up the basic files; see examples). Some advantages of this:
 - 1. It allows you, for instance, to create a version of the radmc3d code that acts as if it is a special-purpose model. You can specify model parameters on the command line (rather than going through the cumbersome IDL stuff).
 - 2. It is faster: even a large model is built up quickly and does not require a long read from large input files.
- You can make use of the AMR module routines such as the amr_branch_refine() routine, so you can
 adaptively refine the grid while you are setting up the model.

Some of the disadvantages are:

- The model needs to be explicitly written out to file and read into IDL or any other data plotting package before you can analyze the density structure to test if you've done it right. You can explicitly ask ./radmc3d to call the userdef_writemodel() subroutine (which is supposed to be writing out all essential data; but that is the user's responsibility) by typing ./radmc3d writemodel.
- Same is true for the grid, and this is potentially even more dangerous if not done. You can explicitly ask ./radmc3d to write out the grid file by typing ./radmc3d writegridfile. Note that if you call the write_grid_file() subroutine from within userdef_writemodel(), then you do not have to explicitly type ./radmc3d writegridfile as well. Note also that radmc3d will automatically call the write_grid_file() subroutine when it writes the results of the thermal Monte Carlo computation, if it has its grid from inside (i.e. it has not read the grid from the file amr_grid.inp.
- It requires a bit more knowledge of the internal workings of the radmc3d code, as you will need to directly
 insert code lines in the userdef_module.f90 file.

13.4 Using the userdef module to compute integrals of J_{ν}

With the monochromatic Monte Carlo computation (see Section 6.5) we can calculate the mean intensity J_{ν} at every location in the model at a user-defined set of wavelengths. However, as mentioned before, for large models and large

numbers of wavelengths this could easily lead to a data volume that is larger than what the computer can handle. Since typically the main motivation for computing J_{ν} is to compute some integral of the the form:

$$Q = \int_0^\infty J_\nu K_\nu d\nu \tag{13.1}$$

where K_{ν} is some cross section function or so, it may not be necessary to store the entire function J as a function of nu. Instead we would then only by interested in the result of this integral at each spatial location.

So it would be useful to allow the user to do this computation internally. We should start by initializing Q(x,y,z)=0 (or $Q(r,\theta,\phi)=0$ if you use spherical coordinates). Then we call the monochromatic Monte Carlo routine for the first wavelength we want to include, and multiply the resulting mean intensities with an appropriate $\Delta\nu$ and add this to Q(x,y,z). Then we do the monochromatic Monte Carlo for the next wavelength and again add to Q everywhere. We repeat this until our integral (at every spatial location on the grid) is finished, and we are done. This saves a huge amount of memory.

Since this is somewhat hard to explain in this PDF document, we refer to the example model run_example_jnu_integral/. STILL IN PROGRESS.

13.5 Some tips and tricks for programming user-defined subroutines

Apart from the standard subroutines that *must* be present in the userdef_module.f90 file (see Section 13.2), you are free to add any subroutines or functions that you want, which you can call from within the predefined subroutines of Section 13.2. You are completely free to expand this module as you wish. You can add your own variables, your own arrays, allocate arrays, etc.

Sometimes you may need to know "where you are" in the grid. For instance, the subroutine userdef_compute_levelpop() is called with an argument index. This is the index of the current cell from within which the subroutine has been called. You can now address, for instance, the dust temperature at this location:

```
temp = dusttemp(1,index)
```

(for the case of a single dust species). You may also want to know the coordinates of the center of the cell. For this, you must first get a pointer to the AMR-tree structure of this cell. The pointer b is declared as

```
type(amr_branch), pointer :: b
```

Then you can point the pointer to that cell structure

```
b => amr_index_to_leaf(index)%link
```

And now you can get the x,y,z-coordinates of the center of the cell:

```
xc = amr_finegrid_xc(b%ixyzf(1),1,b%level)
yc = amr_finegrid_xc(b%ixyzf(2),2,b%level)
zc = amr_finegrid_xc(b%ixyzf(3),3,b%level)
```

Or the left and right cell walls:

```
xi_l = amr_finegrid_xi(b%ixyzf(1),1,b%level)
yi_l = amr_finegrid_xi(b%ixyzf(2),2,b%level)
zi_l = amr_finegrid_xi(b%ixyzf(3),3,b%level)
xi_r = amr_finegrid_xi(b%ixyzf(1)+1,1,b%level)
yi_r = amr_finegrid_xi(b%ixyzf(2)+1,2,b%level)
zi_r = amr_finegrid_xi(b%ixyzf(3)+1,3,b%level)
```

13.6 Creating your own emission and absorption processes

RADMC-3D Allows you to add your own physics to the ray-tracing images and spectra. At every point during the ray-tracing process, when it computes the emissivity and extinction coefficients j_{ν} and α_{ν} it calls the userdef_srcalp() subroutine, giving it the index in which cell we are, the frequencies of the different image channels and the src and alp arrays which are for resp. j_{ν} and α_{ν} . You can add any process by

```
src(:) = src(:) + ....

alp(:) = alp(:) + ....
```

where is your formula. You can find the local variables like density and temperature using the index, e.g.:

```
rho_g = gasdens(index)
```

You can be completely free in your choices. If you need some information that is not usually read into RADMC-3D, you can add read commands in the userdef_setup_model() subroutine, e.g.:

```
call read_gas_density(1)
```

See the example directory examples/run_simple_userdefsrc for more ideas.

13.7 Using RADMC-3D as a fancy volume-rendering tool

Sometimes you want to make nice 3-D volume rendering images of e.g. your 3-D hydrodynamics simulation. You may, in that case, not be interested in *real* emission/extinction processes, but rather some artificial transfer function – as long as the outcoming image looks nice.

RADMC-3D offers a number of advantages over off-the-shelf programs for volume rendering:

- It has AMR refinement, so you do not need to first convert into non-AMR grids which are necessary for many volume rendering codes.
- It allows you full control over the transfer function, i.e. the dependence of the emission/extinction coefficients on any quantities such as density, temperature, magnetic field etc.

The example directory

```
examples/run_simple_userdefsrc
```

gives an example of how this can be done. It also shows how you can link this to the viewimage.pro routine, and allow on-the-fly modification of the transfer function, so that you can experiment to get the nicest image output.

Model analysis (I): The IDL model analysis tool set

While the code RADMC-3D is written in fortran-90, there is an extensive set of tools written in IDL that make it easier for the user to set up models and interpret results. See Section 4.5 for where they are and how they can be properly installed so that they are easy to use. Here we describe these tools.

14.1 The readradmc.pro tools

The readradmc.pro program file contains a series of subroutines for reading RADMC-3D output into IDL so that the user can do post-processing and analysis on these data. The file also contains subroutines for operating RADMC-3D directly from within IDL.

14.1.1 Function readimage

The readimage() function reads the latest produced image into IDL. This image is (i.e. should be) located in the file image.out, which is produced by RADMC-3D. The readimage() function returns an IDL structure containing the image (be it a single-frequency image or a multi-frequency image) in units of intensity (erg/s/cm²/Hz/ster), as well as information about the pixel grid and at which frequency(ies) the image was taken. With the "help" command you can see the full contents of the returned structure:

```
.r readradmc.pro
a=readimage()
help,a,/str
```

This will show you the contents of the structure. Here is a quick summary of these contents:

nx, ny: The number of pixels in x- and y- direction in the image

nrfr: The number of frequencies (wavelengths), i.e. the number of images at different wavelengths

sizepix_x, _y: The size of the pixels in x- and y- directions in units of centimeters. This is of course only possible for images at semi-infinity (the default). For images made as a local observer, see Section 9.11 for details

image: The nx \times ny array of intensities of the image. If multiple colors (wavelengths, frequencies) are present, then the image array will be three-dimensional: nx \times ny \times nrfr. The intensities are in units of erg/cm²/s/Hz/ster.

flux: The integral of the intensity over the entire image, i.e. the flux in the image. The units are erg/cm²/s/Hz for an observer at 1 parsec distance. This "1 parsec" is just a normalization distance. If you make images of objects much larger than 1 parsec in size, this does *not* mean that the image is made by a local observer (unless explicitly specified, see Section 9.11). It is just so that you can compute the actually observed flux

by multiplying the flux by a factor $(pc/d)^2$, where d is the true distance of the observer (which must then be much larger than the size of the object to keep the far-field limit valid).

x,y: The actual image coordinates in cm (unless local observer, see Section 9.11). These are in principle redundant because you can calculate them yourself from the $sizepix_x$, y and nx, ny values. They are here just for convenience.

lambda: The wavelength (in micron) at which this image was made. For multiple colors/freqs/wavelengths this is an array.

The readimage() function can also be used to read from a pipe between IDL and RADMC (see "child mode" in Chapter 12). One then gives it as an argument the file number of the pipe (see example shown in Chapter 12). This is in fact what is done by viewimage.pro below.

14.1.2 Subroutine plotimage

The subroutine plotimage plots the image read by readimage() to screen (or postscript file) in a proper way.

Check out the following example (to be executed only after the dust temperatures have been written to file dust_temperature.dat):

```
.r readradmc.pro
a=readimage()
plotimage,a,/au
```

This subroutine is in fact used by the viewimage.pro below to display images on the drawing pane of the GUI widget. The plotimage subroutine has a large number of optional arguments:

/au or /pc: Display spatial scales in units of AU or parsec.

/log: Display the image using logarithmic spacing of the brightness levels. This allows you to gain far greater depth in the image.

/contour: Overplot contours over the image

nlevels: Number of levels for the contours

/noimage: If set, only plot axes

position: An array of 4 numbers specifying position of plot on the canvas. Like position keyword in typical IDL plotting routines.

maxlog: Set the maximum number of factors of 10 the log brightness color coding will span

saturate: Allows you to enhance the contrast of very weak emission regions by saturating bright regions

/jpg: Write the image to a JPEG file

1grange: A two-valued array specifying the range in brightness (in 10-log) that the image will show

filenr: (For case of /jpg): if set to e.g. 6 it will write the JPEG image to file image_6.jpg.

ilam: If the image is a multi-color image, ilam specfies which of the images you wish to plot

coltune: If set to 1, then rescale the brightness of all channels the same value, to get the best color depth. If set to a 3-element array, you can directly specify the weight of each color. In this way you can really fine-tune the colors.

zoom: If set to a 4-valued array, it makes plotimage put the proper x- and y- axis scaling for the particular zoom-in. Normally the center of the image is taken to be (0,0), but with this zoom keyword you can set exactly what the x- and y-axes should display. Warning: it overrides the pixel size specifications in the image.

14.1.3 Subroutine makeimage

The subroutine makeimage allows the user to interact with RADMC-3D for making images in an easy way, although a direct calling of the radmc3d command with the corresponding keywords is almost just as easy. So one can also consider this as an example routine for calling RADMC-3D for making images. From within IDL you can call makeimage as follows:

```
makeimage,incl=34.,phi=40.,lambda=11.3
```

Here are the keywords:

incl: The inclination of the object on the sky of the observer. incl=0 means a view from the northpole downward, incl=180 means a view from the southpole upward and incl=90 means an edge-on view.

phi: The rotation of the object along its z-axis. A positive phi means that the object rotates counter-clockwise, i.e. that the observer rotates clockwise around the object.

npix: Number of pixels (assumed to be the same for x and y)

sizecm / sizeau / sizepc: The size of the image in units of centimeter / AU / parsec. The size means the full width and full height of the square image.

posang: The rotation of the image in the image plane, i.e. the position angle of the image on the sky. Default is 0

nofluxcons: If set to 1 (/nofluxcons) we use the fast ray-tracing method, while if not set (default) we use the accurate method with sub-pixeling for flux conservation (see Section 9.6).

pointcm / pointau / pointpc: A three-valued array giving the 3-D coordinates of the point toward which we aim our camera. Default is (0.,0.,0.). Units are cm / AU / parsec.

ifreq: If specifying ifreq (putting it to an integer value of 1 or higher) then the wavelength at which the image is going to be taken is taken from the global frequency array from the wavelength_micron.inp file. The integer ifreq is then the index of the wavelength you want to use. Note that this integer starts with 1 (fortran convention).

lambda: If lambda is specified, this will be the wavelength at which the image is to be taken. This wavelength does not have to be part of the global frequency array. It can be any value, even a value in between wavelength grid points of the dust opacity files or so. In that case, a linear interpolation of these opacities will then allow RADMC-3D to nevertheless make the image. So any positive value of lambda is allowed. NOTE: You cannot specify both lambda and ifreq simultaneously.

nostar: If set, then the star(s) in the model are not included in the images.

zoomau / zoompc: Specify the precise window on the image plane which you like to zoom in to. Note that (0.,0.) is the location in the image plane that points to the pointing location specified by pointem / pointau / pointpc. NOTE: You cannot specify both sizecm / sizeau / sizepc and zoomau / zoompc simultaneously.

plottau: If set to 1, the images will not show the emission at that wavelength but instead the total integrated optical depth of the ray at that wavelength. This is only useful for debugging purposes.

iounit: For child mode (See chapter 12).

NOTE: If you want to make multiple images of the same object, then it may be much too slow if each time a new image is to be taken, the RADMC-3D code must be restarted and the entire model must be re-read into RADMC-3D. You can use RADMC-3D in "child mode" to have it start up just once (and reading all input data just once) and keeping alive until explicitly told to end. By communicating with it via a pipe you can then quickly get your images one-by-one while having the slow I/O only once. You do this by starting RADMC-3D in the way described in Chapter 12, and then calling makeimage with keyword iounit equal to the unit of the pipe. See chapter 12 for an example.

14.1.4 Subroutine read_data()

It is always useful to analyze the dust temperature structure that RADMC-3D produces. The function read_data() (or readdata() in abbreviated form) is meant to do that. In IDL, the way it works is:

```
.r readradmc
a=read_data(/dtemp)
```

The /dtemp stands for "read the dust temperature". You can also read the dust density (which is an input, not an output of RADMC-3D):

```
a=read_data(/ddens)
```

You can find what is contained in the structure a by

```
help,a,/struct
```

The structure a contains a sub-structure grid:

```
help,a.grid,/struct
```

which contains all the information of the grid. We come back to that later.

If you just read the dust temperature (with /dtemp) then you can see that the structure contains a large array called a.temp. Its dimensionality depends on which kind of grid you are using:

• Regular grid:

The array a.temp(or any other data array) will have dimensions a.temp(nx,ny,nz,nspec), where nx,ny,nz are the number of cells in x, y and z direction and nspec is the number of dust species. If nspec=1, then the array automatically becomes a.temp(nx,ny,nz) (this is IDL convention).

• Oct-tree AMR grid:

The array a.temp(or any other data array) will have dimensions a.temp(ncells,nspec), where ncells is the number of real cells (excluding the branches that are divided into subcells: only the leafs count) in the AMR oct-tree. How the (complex!) oct-tree is structured is specified in a.grid. The nspec is again the number of dust species.

• Layer-style AMR grid:

The array a.temp (or any other data array) will have dimensions a.temp (nxmax, nymax, nzmax, nspec, nlayers+1), where nxmax, nymax, nzmax are the maximum of number of cells in x, y and z direction of all the layers (including the base grid). The nspec is again the number of dust species. The nlayers is the number of refinement layers (patches), where 0 means that there is only the base grid, 1 means there is one single patch of refinement, etc. The last index of the a.temp array goes from 0 to nlayers. Here 0 means the base grid, 1 the first layer of refinement, etc. Note that if you just read the dust temperature in this way, the regions in the parent layers (including the base grid) that are replaced by a refined layer will have the value 0. This makes a "hole" in the dust temperature distribution. If you want IDL to fill these holes with the rebinned values of the refined layers, then you can call read_data with the /fill keyword, i.e. read_data(/dtemp,/fill).

Now coming back to the a.grid sub-structure. This contains all the information about the grid. Again the content of this structure depends on which gridding you use:

• Regular grid:

The structure contains x,y,z which are 1-dimensional arrays with the cell-centered x,y and z coordinates (for spherical coordinates they are r,θ and ϕ , but then the grid also contains, for your convenience, the entries r, theta and phi). It also contains xi,yi,zi which are again 1-D arrays with the x,y and z coordinates of the cell walls (for spherical coordinates ri, thetai and phii). nx, ny, nz are the number of cells in x,y and z direction.

• Oct-tree AMR grid:

The x,y,z and xi,yi,zi (and in addition to that in spherical coordinates r, theta, phi, ri, thetai and phii) still have the same meaning as in the regular grid case. In this case, however, this "regular grid" is just the "base grid" of the oct-tree refinement. The oct-tree structure is now specified by the 1-D byte-array octtree, which contains only the values 0 and 1. See Section A.2 for details about their meaning. The order of the values of the data are the same as the order of the cells given by octtree.

• Layer-style AMR grid:

Again, as in the oct-tree case, the x,y,z and xi,yi,zi and their spherical-coordinates counterparts now have their meaning for the base grid. The nlayers tells how many layers (in addition to the base grid) there are. The iparent(nlayers+1) give the parent layer for each layer, where 0 means base grid. The ixyz(3,nlayers+1) give the starting point of the layer in the parent grid, nxyz(3,nlayers+1) the size of the layer in the parent grid and nnxyz(3,nlayers+1) the size of the layer in its own grid. The layer_x(nxmax,nlayers+1),layer_y(nxmax,nlayers+1),layer_z(nxmax,nlayers+1),layer_xi(nxmax,nlayers+1) and layer_zi(nxmax,nlayers+1) are like the x,y,z and xi,yi,zi, but now for each layer separately. Note that e.g. layer_x[*,0] = x[*], etc, because layer 0 is identical to the base grid. Note also that ixyz[*,0] and nxyz[*,0] have no meaning, but nnxyz[*,0] are the same as nx, ny, nz.

For all the above griddings, the following additional elements are present in a.grid. For instance, gridstyle (=0,1,10) specifies which of the above griddings is used, coordsys is the coordinate system, mirror (=0,1) a flag whether equatorial mirror symmetry is present (only for spherical coordinates), ncell gives you the total number of actual cells, ncellinp gives you the total number of read-in cell values (in case of layer-type refinement this is generally larger than ncell, incx, incy, incz (=0,1) are flags whether the x, y or z dimensions are active or not.

Note that even if you have e.g. a regular grid, the ixyz etc elements are still in the structure, but they are simply 0.

14.2 Support for FITS

Many people in astronomy use the FITS format (Flexible Image Transport System) for analyzing images or other observational data. Many software packages are geared toward reading and processing FITS data. For instance, the ds9 image viewer¹ is very powerful, but requires its images in FITS format.

We provide a conversion routine from the standard image.out image format produced by RADMC-3D to FITS format. The routine is called radmcimage_to_fits and is located in the file idl/radmc3dfits.pro. To use this, you must have the ASTROLIB ² library of IDL installed.

To convert to FITS format, you must specify the distance at which the observer stands from the object. The reason is that the <code>image.out</code> file produced by RADMC-3d is *distance independent!* The pixel size in <code>image.out</code> is specified in centimeters, not as an angular size. The <code>radmcimage_to_fits</code> routine automatically converts this to pixel scale in degrees, but it must know the distance.

Here is how you convert image.out into image.fits. First go into IDL and then:

```
.r radmc3dfits
radmcimage_to_fits,'image.out','image.fits',140.
```

where the last number (140.) is the distance to the object in units of parsec. In the FITS file the unit of the intensity is Jansky/Pixel. The pixel sizes are specified in degrees. Once you have made this conversion, you can, for instance, use ds9 (if it is installed on your system!) to view your image. From the unix shell you type:

```
ds9 image.fits
```

Just for your information, in case you want to know more about the FITS conversion: The FITS header looks for example like this:

```
SIMPLE = T /image conforms to FITS standard
```

http://hea-www.harvard.edu/RD/ds9/

²http://idlastro.gsfc.nasa.gov/

```
BITPIX =
                          -64 /bits per data value
NAXIS =
                            2 /number of axes
                          100 /
NAXIS1 =
NAXIS2
                          100 /
EXTEND
                           T /file may contain extensions
       = 'Intensity'
BTYPE
BUNIT
       = 'JY/PIXEL'
CDELT1 = 6.9418601352850E-07
CUNIT1
       = 'deg
       = 5.00000000000E+01
CRPIX1
CDELT2 = 6.9418601352850E-07
CUNIT2 = 'deg
CRPIX2 = 5.000000000000E+01
           2.997924580000E+13
RESTFREO=
END
```

which you can see if you type less image.fits in the Unix shell and rescale the width of your shell window to 80 characters. If you want to know more about the details of the FITS format, please consult the various papers by E.W. Greisen, for instance Greisen & Calabretta (2002) A&A 395, 1061-1075.

14.3 The image viewing GUI: viewimage

Making images of a model can be done "by hand" using the tools in the readradmc.pro file (see Section 14.1). But it is much more convenient to use the fully widget-based graphical user interface viewimage (see Fig. 14.2)³.

Important notice: As of version 0.38 of RADMC-3D there is not only the original IDL-version of the viewimage tool (viewimage.pro) but also a new version that is not dependent on having an IDL-license: it is a stand-alone package written by Farzin Sereshti and uses the Qt cross-platform widget library⁴. You can find this version in the viewimage_QT_GUI/ directory.

This interface can be used once the dust temperatures (in case of dust continuum radiative transfer) have been computed using e.g. the thermal monte carlo method (i.e. after having called radmc3d mctherm). Or more precisely: the file dust_temperature.dat should be present and consistent with the other files. If this is satisfied, then one can go into IDL (does not work on the IDL-clone "GDL") and type:

```
.r viewimage
viewimage
```

and one should get the GUI shown in Fig. (14.2). Alternatively (if you don't have an IDL license) you install the Qt-version of the viewimage (in the viewimage_QT_GUI/ directory; there is an extensive manual for that tool in that directory). NOTE: It may take a while for RADMC-3D to load all the data into memory the first time, so before the first image appears on the screen it may take some time. From that point on, further ray-trace actions should go much quicker. Here is a list of controls and their functions:

- ''Quit Viewer'' button: Ends this viewer and quits RADMC-3D.
- ``Write Image'' button: Writes a idl.ps postscript version of the plot on the screen.
- ''mouse rotate'' switch: If unset (default), the mouse clicks on the plotting pane act to select a zoomin box. If set, the mouse clicks on the plotting pane act to rotate the object. Note that the rotation can also be done by hand by setting the values of ''Inclination'' and ''Phi'' and redoing an image rendering with the ''Render Image'' button.
- 'lin' switch: Switch between linear color table of intensity and logarithmic color table of intensity.
- ''preview'' switch: If set (default) then the ray-traced image is done without sub-pixeling in regions where the model has higher spatial resolution than the image resolution can resolve. This is a fast mode (i.e.

³NOTE: Currently there appears to be a problem that viewimage will freeze, which happens on some machines and not on other machines (in fact it happened on one Macbook but not on another, while the systems were seemingly identical). This is somehow related to the way radmc3d and IDL communicate with each other in child mode (see chapter 12): it must be a buffering problem. So far I could not figure out what is going wrong, but I will continue to work on this. If you experience this problem, try calling viewimage,/nochild. That is slower, but should work.

⁴http://qt-project.org




Figure 14.1. Pictographic representation of the dataflow of RADMC-3D when the viewimage GUI is used. RADMC-3D is then called from within viewimage. Note that the two-stage procedure is shown here, e.g. when dust temperatures are computed in stage 1. Only the imaging stage (stage 2) is done by the viewimage-radmc3d symbiosis. In case of single-stage procedures (e.g. LTE line transfer with a given temperature) we go straight from the .inp files via viewimage-radmc3d to the image in the GUI.

hence the name "preview"). If unset, then the ray-tracer always ensures that if a pixel of the image does not resolve details of the model, it will internally refine the pixel in 2x2 (and recursively repeat this until the resolution matches that of the model), and finally integrate the flux of all the sub-pixels to find the flux of the parent pixel. The intensity it then puts into this pixel is then the true average intensity over all the pixel. The sub-pixels will never be seen by the user. They are only made internally in RADMC-3D to ensure the correct flux in the pixel, and then dropped again. For science-quality images the 'preview' button should be unset. It may take longer, however, to render. Please read Section 9.6 for details about this procedure.

- '`contour'' switch: If set: overplot contours.
- 'star' switch: If set (default): Include the flux of all the point-source stars in the image. Not setting it has the potential advantage that you can concentrate on the circumstellar material and not be 'blinded' by the strong starlight.
- slider in this box: The slider in the same box as the above switches selects the IDL color table for monochromatic images.
- 'MaxLog'' textbox (editable): The maxlog is the maximum number of factors of 10 that we will include in the color table. A high number gives more extreme "depth" to the image, but may also wash out details.
- ``Saturate'' textbox (editable): Saturate the image with this factor. Default is 1.0, i.e. no saturation.
- ''Nr Cont'' textbox (editable): Set how many contours you want if the contour switch is 'on'.
- 'Render Spectrum' button: Render a complete SED. This may take a long time!
- ''Render Image'' button: Render a single image. See entries below for the settings.
- ''Unzoom'' button: If you are zoomed in, and you want to zoom out again, push this button. Note: Zoomin in is done by selecting a region with the moise in the image pane (make sure the "mouse rotate" switch is off) and pressing ''Render Image''.
- ''Npix'' textbox (editable): The number of x and y pixels of the image.
- "Size" textbox (editable): The size of the image. [BUG HERE: This does not seem to work.]
- ''Inclination'' textbox (editable): The inclination where the observer is placed (at large distance).
- ``Phi'' textbox (editable): The azimuthal angle where the observer is placed (at large distance).




Figure 14.2. The graphical user interface (GUI) to the ray-trace-based imager module of RADMC-3D. NOTE: As of version 0.38 we now have also a non-IDL version of viewimage using the Qt library.

- slider below: The wavelength slider. These are the wavelengths from the wavelength_micron.inp file and using the slider you can select one of these values. BUT: you can also select the wavelength by directly editing the textbox next to it, see below.
- textbox next to slider: The current wavelength in micron. This is automatically set when the slider is moved. BUT you can also put in any value of the wavelength you want and type return to get the image at the precise wavelength of interest. That may be a wavelength that is not one of the wavelength_micron.inp values, but somewhere in between or even outside that grid. You can try any value.

The image is of course independent of observer distance (except for the local observer mode). The total flux, however, is a distance-dependent quantity. Written in the image is the total flux, normalized to a distance of 1 parsec. Clearly, if the model is far bigger than 1 parsec, then this number has no physical meaning. But by scaling the image flux to a reasonale distance you will get reasonable answers.

The viewimage routines will print to the command line the radmc3d command sequence used to make the image you see now on your screen. This is just for the user's convenience, that it is clearly seen which commands radmc3d receives. You can simply copy-paste such a line to the shell command line and you will see that RADMC-3D will do precisely that command (note that if already another RADMC-3D is running a huge model, you may get memory problems when doing this in parallel to that model).

Note also that each time a new image is made and is shown in the viewer, the same image is also stored in the file image.out in the current directory. This means that you can read the latest image using the readimage() routine in the readradmc.pro file. As an example of such a complete sequence:

```
.r viewimage
viewimage
<<< NOW MAKE WITH THIS WIDGET SOME NICE IMAGE YOU WANT TO STUDY MORE >>>
.r readradmc
a=readimage()
window,0
surface,a.image
```

In this example you make a surface plot in window 0 of the image you see in the viewer.

There are further capabilities of viewimage, which can be switched on with keyword options to the viewimage subroutine. Here is a list of such keyword options (i.e. type e.g. viewimage, /color to enable the first option):

/color: When /color is set then you will find three wavelength sliders which can be independently shifted.

These three sliders represent the red, green and blue channels of the image. This way you can make false color images.

/au / /pc: When setting either /au or /pc the axis will not be drawn with centimeter units, but instead with AU or parsec units.

/small: If set, the widget will be smaller, so that it fits on low-resolution screens.

/verti: If set, the widget will put the controls below the image instead of next. Can be useful on high-resolution screens to save screen real estate.

/nochild: When setting /nochild, the RADMC-3D code will be called separately for each image rendering. This can be very slow, but it has the advantage that in case of problems the debugging might be easier, because all I/O of the radmc3d executable will then go to screen.

/lines: This includes entry fields such as imol, iline and vkms to make it easier to specify the precise wavelength of the image in case of lines.

Tip: If viewimage unexpectedly quits or freezes, please have a look at the file radmc3d.out which contains the messages that RADMC-3D outputs. This may give hints what went wrong. If you have called viewimage with the option /nochild, then the output will have been written to screen, not to radmc3d.out.

Another thing to keep in mind is that when RADMC-3D makes images, it will run a small Monte Carlo simulation beforehand to compute the scattering source function (see).

14.4 Making and reading spectra with IDL

[THIS STILL HAS TO BE WRITTEN]

14.5 A general-purpose 3-D datacube analysis GUI

Although this is not specific for RADMC-3D, we thought it would anyway be useful to provide this: a super-fast interactive IDL GUI for analyzing 3-D data cubes called render3d.pro. This code is a general-purpose adaption of one of IDL's example codes, so this is not in any way copyrighted by the RADMC-3D authors, even though we made extensive changes to it for the better. The tool can be used also for any other 3-D datacube data: it is not at all limited to RADMC-3D.

The render3d.pro tool can only handle 3-D regularly spaced data. No AMR-based models can be *directly* analyzed in this way. But in Chapter 15 we describe a feature of the radmc3d code that allows you to easily create 3-D regularly spaced boxes from anywhere in your model at any spatial resolution you like. You can then subsequently feed that datablock into render3d.pro for 3-D viewing.

Using render3d.pro is simple:

```
q = <some 3-D array of floats or double precisions> .r render3d render3d,q
```

Have fun! For all the functionality, just try things out. It should be reasonably self-explanatory. See Fig. 14.3 for a screen-shot. Note: Apart from all the sliders and buttons, try also out how you can interactively rotate the 3-D datacube with the mouse: just click on the plotting window and drag while keeping clicked.




Figure 14.3. The graphical user interface (GUI) render3d.pro that allows you to analyze 3-D regularly spaced datacubes. In Chapter 15 it is described how to create regularly spaced datacubes of any variable in the model from a complex AMR-based model. Shown in this figure is in fact the run_disk_1/ model, which is an AMR-based model, in which the trick of Chapter 15 is applied to create a regularly spaced box.

Model analysis (II): Tools inside of radmc3d

There are also some special purpose features in the Fortran-90 radmc3d code that can be useful for analyzing complex AMR-gridded models.

15.1 Making a regularly-spaced datacube ('subbox') of AMR-based models

Because handling AMR-based models in IDL or other data analysis packages can be rather cumbersome, we decided that it would be useful to create the possibility in radmc3d to generate 1-D, 2-D or 3-D regularly spaced 'cut-outs' or 'sub-boxes' (whatever you want to call them) of any variable of the model. An example of how this all works, and how these 1-D, 2-D or 3-D sub-boxes can be used with the render3d.pro tool set described in Section 14.5, is given in the model examples/run_disk_1/.

15.1.1 Creating and reading a subbox from within IDL

If all the IDL tools are set up properly, you can make use of this datacube creation feature of radmc3d entirely through IDL. An example, type in IDL:

```
.r readradmc.pro
q=subbox('dust_density')
```

This creates a box with the size of the original model box, but this time regularly spaced. The data is in q.data. You can see this by typing:

```
help,q,/str
```

You will see that q.data is a 3-D array of 64x64x64 (default size).

The box contains the dust density. You can specify the size and the number of grid points of the regularly-spaced box:

```
.r readradmc.pro
@natconst.pro
q=subbox('dust_density',nxyz=64,size=2*100*AU)
.r render3d.pro
render3d,alog10(q.data>1d-20)
```

NOTE: The size keyword is the *full-width* size of the box! So if you want to capture a disk with radius 100 AU, then you must have a box size of 200 AU.

You can also make and read in separate steps:

```
.r readradmc.pro
@natconst.pro
makesubbox,'dust_density',nxyz=64,size=200*AU
q=readsubbox('dust_density_subbox.out')
.r render3d.pro
render3d,alog10(q.data>1d-20)
```

You can specify the box location with the keyword pos:

```
q=subbox('dust_density',nxyz=64,size=200*AU,pos=[30,30,30]*AU)
```

or by specifying the corners of the box directly:

```
q=subbox('dust_density',nxyz=64,box=[-1,1,-1,1,-1,1]*80*AU)
```

Note that if you have radmc3d already running in the background using the child mode (see Chapter 12) then you can do the above commands more quickly by directly communicating through the pipe by passing the keyword iounit=<myiounitnumber> (where the thing in between < and > should be the unit number of the biway pipe to radmc3d) to the above routines makesubbox or subbox.

Currently available quantities you can write out as a subbox are:

- *Dust density:* Give 'dust_density' as first argument to the subbox command.
- Dust temperature: Give 'dust_temperature' as first argument to the subbox command.
- *Molecular/atomic level populations:* Give 'levelpop' as first argument to the subbox command. Note that it will write out a subbox file for each molecule separately. For instance, for CO it would produce a file called 'levelpop_co_subbox.out'. Each of these files can be read with the readsubbox command (see above).

15.1.2 Creating and reading a subbox by directly communicating with radmc3d

You can also call radmc3d directly from the shell asking it to make the subbox. Here is an example:

```
./radmc3d subbox_dust_temperature subbox_nxyz 64 64 64 \subbox xyz01 -2.d15 2.d15 -2.d15 2.d15 -2.d15 2.d15
```

An example for the level populations would be:

```
./radmc3d subbox_levelpop subbox_nxyz 64 64 \
subbox_xyz01 -2.d15 2.d15 -2.d15 2.d15 -2.d15 2.d15
```

Note about subbox for level populations: By default all level populations will be written out. However, if you would add the subbox_levelpop keyword in a call to RADMC-3D for making an image or spectrum, then it will only write out the level populations that have been used for that image. Example:

```
./radmc3d image lambda 2600 subbox_levelpop subbox_nxyz 64 64 ^{\circ} subbox xyz01 -2.d15 2.d15 -2.d15 2.d15 -2.d15
```

would give a much smaller 'levelpop_co_subbox.out' file, because only the first two levels are included (remember that $\lambda = 2600 \, \mu \text{m}$ is the J1-0 line of CO). See Section 7.13 for more information on how RADMC-3D automatically selects a subset of levels for storage in the global array (and thus also for writing out to file).

15.1.3 Format of the subbox output files

All the files produced by the subbox method have the following format:

and they are always in ascii format. For a subbox of the level populations the identification numbers are the levels. For instance, if only the populations of levels 4 and 8 are in this file, then nv=2 and the line with the identification numbers will be 4 8. For all other quantities (dust density, dust temperature) this line of identification numbers is simply 1 2 3 etc.

15.2 Alternative to subbox: arbitrary sampling of AMR-based models

For some purposes it is useful to sample values of various quantities at arbitrary positions in the grid. The idea is very much like the subbox method of Section 15.1, but instead of a regular subbox grid the user provides a list of 3-D points where he/she wants to sample the variables of the model. Here is how to do this. First you must produce a file containing the list of 3-D positions. The file is called sample_points.inp and is an ascii file that looks as follows:

An example for the case in which you want to sample at just one point:

```
1
1
1.49d13 4.02d14 1.03d12
```

If you want to let RADMC-3D do the sampling of the dust density and temperature, type (after you have calculated the temperature using radmc3d mctherm):

```
radmc3d sample-dustdens sample-dusttemp
```

You can also do the dust temperature calculation and the sampling in one go:

```
radmc3d mctherm sample-dustdens sample-dusttemp
```

You can also do only sample-dusttemp or only sample-dustdens. The output is written to files dust_density_sample.out resp. dust_temperature_sample.out. The format of these files is (take dust density as example):

where nv is in this case the nr of species of dust and iv=ispecies.

For a sample of the level populations the identification numbers are the levels. For instance, if only the populations of levels 4 and 8 are in this file, then nv=2 and the line with the identification numbers will be 4 8. For all other quantities (dust density, dust temperature) this line of identification numbers is simply 1 2 3 etc.

Later we will add other possible arrays to sample (at the moment it is only dust density, dust temperature and level populations). But you can also implement this yourself. Search in the following files for the following parts to add your own sampling:

- In rtglobal_module.f90: Search for do_sample_dustdens and add your own variable, e.g. do_sample_myvariable.
- In main.f90: Search for do_sample_dustdens and you will find all places where you have to add your own stuff, i.e. where you will have to add statements like if(do_sample_myvariable) or where you have to set do_sample_myvariable=.true. or reset do_sample_myvariable=.false. etc.

That should do it.

Model analysis (III): Visualization with VTK tools (e.g. Paraview or VisIt)

Since 3-D models can be very hard to visualize, and since RADMC-3D is not made for quick rendering, it can be very useful to make use of a number of freely available 3-D rendering tools, for example:

- Paraview (www.paraview.org)
- VisIt (visit.llnl.gov)

RADMC-3D can create data files for use with these tools. The file format is VTK (Visual Tool Kit), which is a simple ascii file format which is used by various programs. Those tools are not only useful for visualizing the 3-D structure of the model, but also for visualizing the structure of the grid which can be, when using AMR, rather complex.

The file that RADMC-3D writes is called model.vtk. You should be able to open it directly from within e.g. paraview. Figure 16.1 gives an example of how you can analyze a complex geometry with AMR refinement with Paraview. The file *always* includes the information about the grid. In addition you can also make RADMC-3D add scalar fields or vector fields.

To create a VTK file for viewing the grid only, type:

```
radmc3d vtk_grid
```

To create a VTK file for viewing the gas density (this file then also includes the grid of course) type:

```
radmc3d vtk_gas_density
```

Since density can span a huge range, the 10-log of the density (in units of gram/cm³) is written instead. For the gas temperature:

```
radmc3d vtk_gas_temperature
```

which is written in Kelvin (and linearly, not log). For the dust density of dust species 1:

```
radmc3d vtk_dust_density 1
```

and for dust species 2:

```
radmc3d vtk_dust_density 2
```

Also these densities are 10-log. RADMC-3D typically computes the dust temperature using a Monte Carlo approach. By typing

```
radmc3d vtk_dust_temperature 1
```

RADMC-3D will try to read the dust temperature from the file dust_temperature.dat (if this file has been created earlier by a radmc3d mctherm call) and then create the VTK file. You can also let RADMC-3D compute the temperature directly and write it out to VTK right afterward:




Figure 16.1. Example of image created with Paraview, using the VTK output of RADMC-3D. The model shown here is a warped disk model by Katherine Rosenfeld, in 3-D cartesian coordinates with oct-tree AMR refinement.

```
radmc3d mctherm vtk_dust_temperature 1
```

If you are doing line transfer you may wish to visualize the number density of the molecules (or atoms):

```
radmc3d vtk_molspec 1
```

(for molecular species 1). This number density (in cm^{-3}) is also written in 10-log form. You may also wish to visualize the polulations of level 1 (ground state) of molecule 2:

```
radmc3d vtk_levelpop 2 1
```

The gas velocity field can be written to VTK file by

```
radmc3d vtk_velocity
```

This is a vector field.

Note: The VTK mode works for 3-D cartesian and 3-D spherical coordinates (thanks, Attila Juhasz, for the 3-D spherical mode!).




Figure 16.2. Example of image created with Paraview, using the VTK output of RADMC-3D. The model shown here is a warped disk model by Attila Juhasz, in 3-D spherical coordinates with separable refinement, but without AMR refinement. The model is kept low-resolution on purpose, to show the grid structure better.

Creating Protoplanetary Disk Models using a GUI

Author: A. Juhasz

Attila Juhasz has created an IDL-driven graphical user interface (GUI) for modeling protoplanetary disks. The GUI for RADMC-3D was developed for YSO disks/envelopes but can also be used (to some extent) as a general purpose user interface. Or it may serve as a template for other users to create GUIs for their own models. The GUI is written in IDL and consits of five IDL routines; radmc3d_gui.pro, read_params_radmc3d.pro, problem_params.pro, problem_setup_yso.pro, my_gap_function.pro.

- radmc3d_gui.pro This file contains all the widget definitions and basically everything related to the visualization.
- read_params_radmc3d.pro This file contains two functions to read and write the parameters into a file.
- problem_params.pro Those, who have actually worked with the 2D version of RADMC, this file should look familiar. This file contains all parameters required to set up the problem and create the input files for RADMC 3D.
- **problem_setup.pro** This file has also the same function as in the 2D version of RADMC. On the basis of the parameters stored in problem_params.pro, it creates the input files to RADMC 3D.
- my_gap_function.pro This is a small routine to cut a gap in the disk to demonstrate, how one can use this GUI with one's own dust density setup.
- my_gap2_function.pro This is a small routine to cut a second gap in the disk (in the exact same way as my_gap_function.pro) to demonstrate, how one can use this GUI with one's own dust density setup.

17.1 How to run the GUI

The GUI can be run in a very simple way. First an IDL should be started and the radmc3d_gui.pro routine should be compiled.

```
IDL> .r radmc3d_gui
```

With this step not only radmc3d_gui.pro, but also all other necessary files/routines will be compiled (Note: it assumes that you are in the examples/run_whatever directory and the readradmc.pro file is located in the ../../idl/directory). After the compilation the GUI is ready to be run with the command radmc3d_gui:

```
IDL> radmc3d qui
```




Figure 17.1. The graphical user interface for a protoplanetary disk model. Author: A. Juhasz.

After this command has been executed the user should see a window similar to that in Fig 17.1.

To make things easy (especially for those ones who use a radiative transfer code for the first time) the GUI comes with a simple 'default' setup for the dust density distribution. This setup is based on a common parametrization of a protoplanetary disk and a surrounding envelope. However, the user may want to change the whole density distribution or may want to add extension(s) to this setup (e.g. a gap in the disk). One can add his/her own extension(s) to the model setup so, that the GUI will recognize them and new tabs will automatically open to access the parameters of these extensions.

17.2 Create your own setup and/or open your own tab

Adding new extension to the code which appears as a new tab in the dust density setup frame is relatively easy, one only needs to keep a few rules. To make it clear how this can be done it is useful to understand what the GUI does behind the buttons and windows. In a few steps the GUI does the following;

- 1. Write the parameter values to problem_params.pro
- 2. Run problem_setup_yso.pro to create all necessary input files for RADMC3D
- 3. Run RADMC3D metherm to calculate the temperature structure
- 4. Run RADMC3D to calculate images/spectra

After Step 2. any arbitrary IDL procedure can be run to modify (or even completely re-create) the dust density distribution. Such a procedure can be integrated to the GUI in the following way;

• The procedure should not accept any keywords or input variable, instead, the user should add the @problem_params.pro line after the procedure name, allowing the procedure to access the variables in problem_params.pro;

```
pro my_arbitrary_procedure
@problem_params.pro
```

 Create a new section of parameters in problem_params.pro which will be used in the user's procedure. For examle:

```
; My extra function - example
; Cut a gap in the disk reducing the density by an arbitrary factor
;
extra_gap_tab_name = 'My gap function'; Name of the tab in the GUI
extra_gap_enable = 1 ; 0-Enable, 1-Disable this function
extra_gap_func = 'my_gap_function'; Name of the user defined function
extra_gap_rin = 5.0*AU; Inner radius of the gap
extra_gap_rout = 10.*AU; Outer radius of the gap
extra_gap_drfact = 1d-4; Density reduction factor in the gap
```

- The parameter names should look like; extra_secname_pname. The 'extra' means that this is an additional parameter for which a new tab should be opened. The 'secname' will be the identifier of this section of parameters within the widgets and should be the same for all parameters within this section. The 'pname' is the actual parameter name, that can be any arbitrary name.
- Each new section should contain a parameter called 'extra_secname_tab_name', which will be the title of the new tab which will open in the dust density setup frame.
- Each new section should contain a parameter called 'extra_secname_func', which should be the name of the user's procedure.
- Each new section should contain a parameter called 'extra_secname_enable', which should have a value of 0 or 1 and disables or enables the execution of the user's procedure after problem_setup_yso.pro.

If the user followed the instructions above and start the GUI a new tab in the density setup frame should open for the user's procedure. Input fields for the parameters will have the parameter names as titles. If one made comments in problem_params.pro at the end of a line to explain the meaning of the parameter at the beginning of the line, this explanation/comment will be available in the Help menu under "Help on parameters". Two examples were given in the current problem_params.pro to open gaps in the dust density distribution.

How to convert old-style RADMC models to RADMC-3D

Some users of RADMC-3D may have used the predecessor program RADMC before. The input files of RADMC are different from those used by RADMC-3D. You may have model setups created for RADMC which you would like to feed into RADMC-3D. The best way would be of course to edit your problem_***.pro files and make sure that they create the RADMC-3D input files instead of the RADMC input files. But that costs quite some work, and you may make errors.

We offer the IDL routine radmc2radmc3d.pro in the idl/ directory that automatically converts all the RADMC input files into RADMC-3D input files. In particular, it will do the following conversion:

RADMC	RADMC-3D
radius.inp $\&$ theta.inp	amr_grid.inp
starinfo.inp & starspectrum.inp	stars.inp
dustdens.inp	dust_density.inp
-	radmc3d.inp

The file radmc.inp is ignored for now, and instead a fresh radmc3d.inp is created. While RADMC-3D would read radmc.inp if no radmc3d.inp is present, the presence of radmc3d.inp means that RADMC-3D will read radmc3d.inp (and not read radmc.inp).

The opacity files are kept as they are. While the recommended style for the opacities is the dustkappa_*.inp file, RADMC-3D can also read the old style dustopac_*.inp files. Also the frequency.inp file is kept as it is.

NOTE: For now the quantum-heated grains are not ported to RADMC-3D. Also some specialties of the RADMC code may not yet work in RADMC-3D – just keep this in mind.

So if you have a working model for RADMC, and you want to run it with RADMC-3D, then just go into the model directory, go into IDL and type:

.r radmc2radmc3d.pro

and this should convert the files from RADMC-style to RADMC-3D-style, as described above. Note that you must now redo the thermal Monte Carlo, because RADMC-3D reads its own style of dust temperature file. So go out of IDL and type (on the shell):

radmc3d mctherm

wait until it is finished, and now you can make your spectra and images.

Tips, tricks and problem hunting

19.1 Tips and tricks

RADMC-3D is a large software package, and the user will in all likelihood not understand all its internal workings. In this section we will discuss some issues that might be useful to know when you do modeling.

• Things that can drastically slow down ray-tracing:

When you create images or spectra, radmc3d will perform a ray-tracing calculation. You may notice that sometimes this can be very fast, but for other problems it can be very slow. This is because, depending on which physics is switched on, different ray-tracing strategies must be followed. For instance, if you use a dust opacity without scattering opacity (or if you switch dust scattering off by setting scattering mode_max to 0 in the radmc3d.inp file), and you make dust continuum images, or make SEDs, this may go very rapidly: less than a minute on a modern computer for grids of 256x256x256. However, when you include scattering, it may go slower. Why is that? That is because at each wavelength radmc3d will now have to make a quick Monte Carlo scattering model to compute the dust scattering source function. This costs time. And it will cost more time if you have nphot_scat set to a high value in the radmc3d.inp file, although it will create better images. Furthermore, if you also include gas lines using the simple LTE or simple LVG methods, then things become even slower, because each wavelength channel image is done after each other, and each time all the populations of the molecular levels have to be re-computed. If dust scattering would be switched off (which is for some wavelength domains presumably not a bad approximation; in particular for the millimeter domain), then no scattering Monte Carlo runs have to be done for each wavelength. Then the code can raytrace all wavelength simultaneously: each ray is traced only once, for all wavelength simultaneously. Then the LTE/LVG level populations have to be computed only once at each location along the ray. So if you use dust and lines simultaneously, it can be advantageous for speed if you can afford to switch off the dust scattering, for instance, if you model sub-millimeter lines in regions with dust grains smaller than 10 micron or so. If you must include scattering, but your model is not so big that you may get memory limitation problems, then you may also try the fast LTE or fast LVG modes: in those modes the level populations are pre-computed before the ray-tracing starts, which saves time. But that may require much memory.

19.2 Bug hunting

Although we of course hope that radma3d will not run into troubles or crash, it is nevertheless possible that it will. There are several ways by which one can hunt for bugs, and we list here a few obvious ones:

- In principle the Makefile should make sure that all dependencies of all modules are correct, so that the most dependent modules are compiled last. But during the further development of the code perhaps this may be not 100% guaranteed. So try do make clean followed by make (or make install) to assure a clean make.
- In the Makefile you can add (or uncomment) the line

 BCHECK = -fbounds-check, if you use gfortran. Find the array boundary check switch on your own

compiler if it is not gfortran.

Make sure that in the main.f90 code the variable debug_check_all is set to 1. This will do some on-the-fly
checks in the code.

19.3 Some tips for avoiding troubles and for making good models

Here is a set of tips that we recommend you to follow, in order to avoid troubles with the code and to make sure that the models you make are OK. This list is far from complete! It will be updated as we continue to develop the code.

- Make a separate directory for each model. This avoids confusion with the many input and output files from the models.
- 2. When experimenting: regularly keep models that work, and continue experimenting with a fresh model directory. If things go wrong later, you can always fall back on an older model that *did* work well.
- 3. Keep model directories within a parent directory of the code, just like it is currently organized. This ensures that each model is always associated to the version of the code for which it was developed. If you update to a new version of the code, it is recommended to simply copy the models you want to continue with to the new code directory (and edit the SRC variable in the Makefile if you use the techniques described in Section 4.7 and Chapter 13).
- 4. If you make a new model, try to start with as clean a directory as possible. This avoids that you accidently have a old files hanging around, their presence of which may cause troubles in your new model. So if you make a model update, make a new directory and then copy only the files that are necessary (for instance, problem_setup.pro, dustkappa_silicate.inp, Makefile and other necessary files). One way of doing this easily is to write a little perl script or csh script that does this for you.
- 5. In the example model directories there is always a Makefile present, even if no local *.f90 files are present. The idea is that by typing make cleanall you can safely clean up the model directory and restore it to pre-model status. This can be useful for safely cleaning model directories so that only the model setup files remain there. It may save enormous amounts of disk space. But of course, it means that if you revisit the model later, you would need to redo the Monte Carlo simulations again, for instance. It is a matter of choice between speed of access to results on the one hand and disk space on the other hand.
- 6. If you use LVG or escape probability to compute the level populations of molecules, please be aware that you must include all levels that could be populated, not only the levels belonging to the line you are interested in.

19.4 Careful: Things that might go wrong

In principle RADMC-3D should be fine-tuned such that it produced reliable results in most circumstances. But radiative transfer modeling, like all kinds of modeling, is not an entirely trivial issue. Extreme circumstances can lead to wrong results, if the user is not careful in doing various sanity checks. This section gives some tips that you, the user, may wish to do to check that the results are ok. This is not an exhaustive list! So please remain creative yourself in coming up with good tests and checks.

1. Too low number of photon packages for thermal Monte Carlo

If the number of photon packages for the thermal Monte Carlo simulation (Section 6.1) is too low, the dust temperatures are going to be very noisy. Some cells may even have temperature zero. This may not only lead to noisy images and spectra, but also simply wrong results. However, deep inside optically thick clouds (or protoplanetary disks) it will be hard to avoid this problem. Since those regions are very deep below the $\tau=1$ surface, it might not be always too critical in that case. A bit of experimenting might be necessary.

2. Too low number of photon packages for scattering

When making images or spectra in which dust scattering is important, the scattered light emissivity is computed by a quick Monte Carlo simulation before the ray-tracing (see Section 6.6.5). This requires the setting of the number of photon packages used for this (the variable nphot_scat for images and equivalently




Figure 19.1. Example of what can go wrong with radiative transfer if the inner cells of a model are optically thick (i.e. if no grid refinement is used, see Section 10.2). Shown here are scattered light images at $\lambda=0.7\mu\mathrm{m}$ wavelength of the inner rim of a protoplanetary disk, but with the star removed with an ideal choronograph. The color scale is linear. The radial grid is taken to be logarithmically spaced with $\Delta R/R=0.04$. Left image: the inner cells are marginally optically thin $\Delta \tau \simeq 1$, creating a bright inner ring, as is expected. Right image: ten times higher optical depth, making the inner cells optically thick with roughly $\Delta \tau \simeq 10$, resulting in a wrong image in which the emission near the midplane is strongly reduced. The reason for that is that the scattering source function, due to photons scattering at the inner 10% of the inner cell, is diluted over the entire cell, making the scattered light brighness 10x lower than it should be.

nphot_spec for spectra, both can be set in the radmc3d.inp file). If you see too much "noise" in your scattering image, you can improve this by setting nphot_scat to a larger value (default = 100000). If your spectrum contains too much noise, try setting nphot_spec to a larger value (default = 10000).

3. Too optically thick cells at the surface or inner edge

You may want to experiment with grid resolution and refinement. Strictly speaking the transition from optically thin to optically thick, as seen both by the radiation entering the object and by the observer, has to occur over more than one cell. That is for very optically thick models, one may need to introduce grid refinement in various regions. As an example: an optically thick protoplanetary disk may have an extremely sharp thin-thick transition near the inner edge. To get the spectra and images right, it is important that these regions are resolved by the grid (note: once well inside the optically thick interior, it is no longer necessary to resolve individual optical mean free paths, thankfully). It should be said that in practice it is often impossible to do this in full strictness. But you may want to at least experiment a bit with refining the grid (using either "separable refinement", see Section 10.2, or AMR refinement, see Section A.2.2). An example how wrong things can go at the inner edge of a protoplanetary disk, if the inner cells are not assured to be optically thin through grid refinement (and possibly additionally a bit of smoothing of the density profile too) is given in Fig. 19.1.

4. Model does not fit onto the grid (or onto the refined part of the grid)

The grid must be large enough to contain the entire $\tau_{\lambda}=1$ surface of a model at all relevant wavelengths. If you use grid refinement, the same is true for the $\tau_{\lambda}=1$ surface being within the refinened part of the grid. This is not trivial! If you, for instance, import a 3-D hydrodynamic model into RADMC-3D, then it is a common problem that the $\tau_{\lambda}=1$ surface "wants" to be outside of the grid (or outside of the higher-resolution part of the θ -grid if you use separable grid refinement: see Fig. 10.2). For example: if you make a hydrodynamic model of a protoplanetary disk in R, Θ and Φ coordinates, you typically want to model only the lower 2 pressure scale heights of the disk, since that contains 99.5% of the mass of the disk. However, for radiative transfer this may not be enough, since if the disk has an optical depth of $\tau=10^3$, the optically thin surface layer is less than 0.1% of the disk mass, meaning that you need to model the lower 3 (not 2!) pressure scale heights. Simply inserting the hydrodynamics model with the first 2 scale heights would lead to an artifical cut-off of the disk. In other words, the real $\tau_{\lambda}=1$ surface "wants" to be outside of the grid (or outside of the refined part of the grid). This leads to wrong results.

19.5 Common technical problems and how to fix them

When using a complex code such as RADMC-3D there are many ways you might encounter a problem. Here is a list of common issues and tips how to fix them.

- 1. *After updating RADMC-3D to a new version, some setups don't work anymore.* This problem can be due to several things:
 - (a) When your model makes a local radmc3d executable (see Section 4.7), for instance when you use the userdef_module.f90 to set up the model, then you may need to edit the SRC variable in the Makefile again to point to the new code directory, and type make clean followed by make.
 - (b) Are you sure to have recompiled radmc3d again and installed it (by going in src/ and typing make install)?
 - (c) Try going back to the old version and recheck that the model works well there. If that works, and the above tricks don't fix the problem, then it may be a bug. Please contact the author.
- 2. After updating RADMC-3D to a new version: the new features are not present/working. Maybe again the Makefile issue. See point 1 above.
- 3. After updating RADMC-3D to a new version: model based on userdef_module fails to compile

 If you switch to a new version of the code and try to 'make' an earlier model that uses the userdef_module.f90, it might sometimes happen that the compilation fails because some subroutine userdef_*** is not known (here *** is some name). Presumably what happened is that a new user-defined functionality has been added to the code, and the corresponding subroutine userdef_*** has been added to the userdef_module.f90.

 If, however, in your own userdef_module.f90 this subroutine is not yet built in, then the compiler can't find this subroutine and complains. Solution: just add a dummy subroutine to your userdef_module.f90 with that name (have a look at the userdef_module.f90 in the src/ directory). Then recompile and it should now work.
- 4. After switching back from the userdef_module.f90-driven model setup to the original IDL-driven setup style, suddenly lots of IDL routines produce problems or do not give the right results.

 Check if an old radmc3d executable is still present. If so, remove it, because the way the IDL tools check which radmc3d executable to use (local or global) is by checking if a local radmc3d executable is present.
- 5. The viewimage GUI aborts with message "Aborting: RADMC-3D does not respond..."

 This means that the radmc3d code, which is a child process of IDL, has unexpectedly quit. Since the standard IO channel of radmc3d is used for commincation with IDL, the usual standard output is now redirected to the file radmc3d.out. Have a look at that file to see what caused radmc3d to abort.
- 6. RADMC-3D stops with message "ERROR: dust_density.inp does not have same number of cells as the grid. -32768 32768" or similar

This message means that the file dust_density.inp specifies the dust density in a different number of cells than which is specified in the amr_grid.inp file. In the above example this is in fact caused by the fact that in the IDL routines for generating the setup the number of cells got an overflow over the maximum range of two-byte signed integers. To avoid this, use long integers. In IDL this is done like nx=100L instead of nx=100.

- 7. While reading an input file, RADMC-3D says "Fortran runtime error: End of file" This can of course have many reasons. Some common mistakes are:
 - In amr_grid.inp you may have specified the coordinates of the nx*ny*nz grid centers instead of (nx+1)*(ny+1)*(nz+1) grid cell interfaces.
 - You may have no line feed at the end of one of the ascii input files. Some fortran compilers can read only lines that are officially ended with a return or line feed. Solution: Just write an empty line at the end of such a file.
- 8. My changes to the main code do not take effect
 Did you type, in the src/directory, the full make install? If you type just make, then the code is compiled but not installed as the default code.
- 9. My userdef_module.f90 stuff does not work
 If you run radmc3d with own userdefined stuff, then you must make sure to run the right executable. Just typing radmc3d in the shell might cause you to run the standard compilation instead of your special-purpose one. Try typing ./radmc3d instead, which forces the shell to use the local executable.

10. When I make images from the command line, they take longer than with viewimage.pro

If you make images with radmc3d image (plus some keywords) from the command line, the default is that
a flux-conserving method of ray-tracing is used, which is called recursive sub-pixeling (see Section 9.6).
This takes, under some circumstances, much longer than if you make images without recursive sub-pixeling.
In the viewimage widget (see Section 14.3) the default is to use no sub-pixeling (though by pressing the
"preview" button off, the sub-pixeling is used again). You can make an image without sub-pixeling with the
command-line option nofluxcons.

11. My line channel maps (images) look bad

If you have a model with non-zero gas velocities, and if these gas velocities have cell-to-cell differences that are larger than or equal to the intrinsic (thermal+microturbulent) line width, then the ray-tracing will not be able to pick up signals from intermediate velocities. In other words, because of the discrete gridding of the model, only discrete velocities are present, which can cause numerical problems. There are two possible solutions to this problem. One is the wavelength band method described in Section 9.5. But a more systematic method is the "doppler catching" method described in Section 7.12 (which can be combined with the wavelength band method of Section 9.5 to make it even more perfect).

12. My line spectra look somewhat noisy

If you include dust continuum scattering (Section 6.6) then the ray-tracer will perform a scattering Monte Carlo simulation at each wavelength. If you look at lines where dust scattering is still a strong source of emission, and if nphot_scat (Section 6.6.5) is set to a low value, then the different random walks of the photon packages in each wavelength channel may cause slightly different resulting fluxes, hence the noise.

- 13. My dust continuum images look very noisy/streaky: many "lines" in the image There are two possible reasons:
 - (a) Photon noise in the thermal Monte Carlo run: If you have too few photon packages for the thermal Monte Carlo computation (see Chapter 6), then the dust temperatures are simply not well computed. This may give these effects. You must then increase nphot in the radmc3d.inp file to increase the photon statistics for the thermal Monte Carlo run.
 - (b) Photon noise in the scattering Monte Carlo run: If you are making an image at a wavelength at which the disk is not emitting much thermal radiation, then what you will see in the image is scattered light.

 RADMC-3D makes a special Monte Carlo run for scattered light before each image. This Monte Carlo run has its own variable for setting the number of photon packages: nphot_scat. If this value is set too low, then you can see individual "photon"-trajectories in the image, making the image look bad. It is important to note that this can only be remedied by increasing nphot_scat (in the radmc3d.inp file, see Section 6.6.5), not by setting nphot (which is the number of photon packages for the thermal Monte Carlo computation). Please also read Section 6.6.6 for a detailed discussion about the effects of multiple scattering and the possibility of it leading to streaks in the images.

However, it might also mean that something is wrong with the setup. A few common setup-errors that could cause these issues are:

• Accidently created a way too massive object. Let us discuss this with an example of a protoplanetary disk: suppose you created, in spherical coordinates, not a protoplanetary disk with $M_{\rm disk}=0.01\,M_{\odot}$ but accidently one with $M_{\rm disk}=10\,M_{\odot}$. In such a case a lot of things will go wrong. First of all the inner edge of the disk will almost certainly behave strangely (see Fig. 19.1). Secondly, the surface of the disk will almost certainly be cut-off in the way decribed in Section 19.4, in which case the surface of the disk will be hardly illuminated by the star, because the disk surface is then exactly conical (i.e. starlight will not be able to impinge on the surface). This will lead to very low photon statistics at the surface.

Appendix A

Main input and output files of RADMC-3D

RADMC-3D is written in fortran-90. It is written in such a way that the user prepares input files (ending in .inp) for the program and then calls radmc3d with some command-line options. The program then reads the input files, and based on the command-line options will perform a certain calculation, and finally outputs the results to output files (ending in .out) or intermediate files (ending in .dat) which need further processing. In principle the user therefore needs to compile the program only once, and can then use the executable from that point onward. In this chapter we will describe the various input/output and intermediate files and their formats. Just for clarity: the IDL routines in the idl/directory are only meant to make it easier for the user to prepare the .inp files, and to make sense of the .out and .dat files. They are not part of the main code radmc3d.

A few comments on RADMC-3D input and output files:

- Most (though not all) files start with a *format number*. This number simply keeps track of the version of the way the information is stored the file. The idea is that if new versions of RADMC-3D come out in the future, it would be good to have the possibility that new information is added to the files. The format number is there to tell RADMC-3D whether a file is the new version or still an older version. NOTE: Do not confuse *format number* with *unformatted/formatted I/O* (see below for the latter). These are unrelated issues.
- RADMC-3D is no longer backward compatible with the older RADMC code input files. It has proven to be too messy to maintain this option.
- RADMC-3D has four types of I/O files:
 - 1. Files ending with .inp or .uinp or .binp are input files that allow the user to specify to RADMC-3D which problem to solve.
 - 2. Files ending with .dat or .udat or .bdatare intermediate files that are typically created by RADMC-3D itself, but can also be read by RADMC-3D for further processing. For instance, the dust temperature is computed by the Monte Carlo method, but can also be read in later for ray-tracing.
 - 3. Files ending with .out or .uout or .bout are final products of RADMC-3D, such as an image or spectrum.
 - 4. File ending with .info are small files containing some numbers that are useful to better interpret the output files of RADMC-3D. They are typically not very important for every-day use.
- For many of the I/O files RADMC-3D can read and write formatted (i.e. text style: ascii) files, fortran-style unformatted (i.e. with "records") files as well as binary files (i.e. C-style unformatted). This is specified by the file extension. See Chapter B for more details.

A.1 INPUT: radmc3d.inp

The radmc3d.inp file is a namelist file with the main settings for RADMC-3D¹. The namelist is not a standard Fortran namelist style, but a simple *name* = *value* list. If a name is not specified, the default values are taken. So if the radmc3d.inp file is empty, then all settings are standard. Note that some of these settings can be overwritten by command-line options!! Here is a non-exhaustive list of the variables that can be set.

- incl_dust (default: depends on which input files are present)

 Normally RADMC-3D will recognize automatically whether dust continuum emission, absorption and scattering must be included: if e.g. a file called dustopac.inp is present, it assumes that the dust must be included. But with this flag you can explicitly tell RADMC-3D whether it must be included (1) or not (0).
- incl_lines (default: depends on which input files are present)

 Normally RADMC-3D will recognize automatically whether line emission and absorption must be included: if e.g. a file called lines.inp is present, it assumes that molecular/atomic lines must be included. But with this flag you can explicitly tell RADMC-3D whether it must be included (1) or not (0).
- incl_freefree (default: 0)

 If 1, then include free-free emission and absorption (Bremsstrahlung). For this, the gas temperature must be known (but see option tgas_eq_tdust below).
- nphot or nphot_therm (default: 100000)

 The number of photon packages used for the thermal Monte Carlo simulation.
- nphot_scat (default: 100000)

 The number of photon packages for the scattering Monte Carlo simulations, done before image-rendering.
- nphot_spec (default: 10000)

 The number of photon packages for the scattering Monte Carlo simulations, done during spectrum-calculation. This is actually the same functionality as for nphot_scat, but it is used (and only used) for the spectrum and SED calculations. The reason to have a separate value for this is that for spectra you may not need as many photon packages as for imaging, because you anyway integrate over the images. Many of the annoying "stripe noise" in images when using insufficiently large nphot_scat will cancel each other out in the flux calculation. So nphot_spec is usually taken smaller than nphot_scat.
- iseed (default: -17933201) [Fine-tuning only]
 A starting value of the random seed for the Monte Carlo simulation.
- ifast (default: 0) [Fine-tuning only]
 By setting this to 1 or 2 you will get a faster thermal Monte Carlo simulation, at the cost of being less accurate.
- enthres (default: 0.01) [Fine-tuning only]

 This is the fraction by which the energy in each cell may increase before the temperature is recalculated in the Monte Carlo simulation. The smaller this value, the more accurate the thermal Monte Carlo simulation, but the more computationally costly. 0.01 has proven to be fine.
- itempdecoup (default: 1)

 If set to 0, then the temperatures of all coexisting dust species are always forced to be the same. If 1, then each dust species is thermally independent of the other.
- istar_sphere (default: 0)

 If 0 (=default), then all stars are treated as point-sources. If 1, then all stars are treated as finite-size spheres. This mode is more accurate and more realistic, but the applications are a bit more restricted. Such finite-size stars are (for technical reasons) not always allowed anywhere in the model. But for problems of circumstellar disks and envelopes in spherical coordinates, it is recommended to set this to 1. Typically, if a star is outside the grid (in spherical coordinates this can also be at the origin of the coordinate system, as long as the inner radius of the coordinate system is larger than the stellar radius!) the use of the finite-size star mode is always possible. But if the star is on the grid, there are technical limitations.

¹Originally this was called the radmc.inp file. If no radmc3d.inp is present, but radmc.inp is present, then RADMC-3D will read the latter. But if both are present, then RADMC-3D will read the radmc3d.inp file.

- ntemp (default: 1000) [Fine-tuning only]

 The temperatures are determined in the Monte Carlo method using tabulated pre-computed integrals. This saves time. This is the number of temperatures for which this is precalculated. The temperatures are sampled in a logarithmic way, i.e. log(temp) is linearly equally spaced between log(temp0) and log(temp1), see below.
- temp0 (default: 0.01) [Fine-tuning only] The lowest pre-calculated temperature.
- temp1 (default: 1e5) [Fine-tuning only]
 The highest pre-calculated temperature.
- scattering_mode_max

When radmc3d reads the dust opacity files it checks if one or more of the opacity files has scattering opacity included. If yes, the scattering_mode will automatically be set to 1. It will also check if one or more includes anisotropic scattering. If yes, the scattering_mode will automatically be set to 2. But the user may nevertheless want to exclude anisotropic scattering or exclude scattering altogether (for instance for testing purposes, or if the user knows from experience that the scattering or anisotropic nature of scattering is not important for the problem at hand). Rather than editing the opacity files to remove the scattering and/or Henyey-Greenstein g-factors, you can limit the value that radmc3d is allowed to make scattering_mode by setting the variable scattering_mode_max. If you set scattering_mode_max=0 then no matter what opacity files you have, scattering will not be treated. If you set scattering_mode_max=1, then no matter what opacity files you have, scattering will be treated in an isotropic way.

- unformatted (Obsolete)
- rto_style (default=1)

 This determines whether the output of space-dependent data will be in ASCII form (rto_style=1), f77-unformatted form (rto_style=2) or binary form (rto_style=3). See Chapter B for details.
- camera_tracemode (default: 1)

 If camera_tracemode=-1, the images that are rendered by RADMC-3D will instead by the column depth traced along each ray. If camera_tracemode=-2, the images that are rendered by RADMC-3D will instead by the continuum optical depth traced along each ray. By default camera_tracemode=1, which is the normal mode, where real images are being created.
- camera_nrrefine (default: 100)

For images: to assure that flux is correctly sampled, the image pixels will not just be rendered one ray per pixel. Instead, if necessary, a pixel will spawn 2x2 sub-pixels recursively (each of which can split again into 2x2 until the required resolution is obtained) so as to assure that the flux in each pixel is correct. Nrrefine tells how deep RADMC-3D is allowed to recursively refine. 100 is therefore effectively infinite. Putting this to 0 means that you go back to 1 ray per pixel, which is fast, but may seriously misrepresent the flux in each pixel. NOTE: The recursive pixel refinement is done internally and the user will not notice it except for getting better answers. In the output image only the original pixels are shown; all subpixels have been integrated over to get the flux of the original pixel. So you can keep this to the default value of 100 without having to worry about handling complex data structures. The only drawback is that it may take longer to compute. See Section 9.6 for more details.

- camera_refine_criterion (default: 1.0) [Fine-tuning only]
 Setting this value to smaller than 1 means that you refine the recursive pixeling until a tighter criterion is met.
 The smaller this value, the more accurate the fluxes in each pixel, but the longer it takes to render. See Section 9.6 for more details.
- camera_incl_stars (default: 1)

 If 0, then only the interstellar/circumstellar material is rendered for the images and spectra. If 1, then also the stellar flux is included in the spectra and images. So far, stars are treated always as point sources.
- camera_starsphere_nrpix (default: 20) [Fine-tuning only]
 For rectangular images and for the spectra/SEDs (but not for spectra/SEDs created with circular pixel arrangements), this number tells RADMC-3D how much it should do sub-pixeling over the stellar surface. That is:

20 means that at least 20 sub-pixels are assured over the stellar surface. This is important for flux conservation (see Section 9.6).

- camera_spher_cavity_relres (default: 0.05) [Fine-tuning only]

 Determines the size of sub-pixels inside the inner grid radius of spherical coordinates.
- camera_localobs_projection (default: 1)
 (Only for local observer mode) The type of projection on the sphere of observation.
- camera_min_dangle (default 0.05) [Fine-tuning only]
 Fine-tuning parameter for recursive subpixeling, for spherical coordinates, assuring that not too fine subpixeling would slow down the rendering of images or spectra too much.
- camera_max_dangle (default 0.3) [Fine-tuning only]
 Fine-tuning parameter for recursive subpixeling, for spherical coordinates, preventing that too coarse subpixeling would reduce the accuracy.
- camera_min_dr (default 0.003) [Fine-tuning only]
 Fine-tuning parameter for recursive subpixeling, for spherical coordinates, assuring that not too fine subpixeling would slow down the rendering of images or spectra too much.
- camera_diagnostics_subpix (default: 0)
 Setting this to 1 forces RADMC-3D to write out a file called subpixeling_diagnostics.out which contains four columns, for respectivly: px,py,pdx,pdy, i.e. the pixel position and its size. This is for all pixels, including the sub-pixels created during the recursive subpixeling procedure (Section 9.6.2). This allows the user to find out if the recursive subpixeling went well or if certain areas were over/under-resolved. This is really only meant as a diagnostic.
- camera_secondorder (default: 0)
 If set to 1, RADMC-3D will interpolate all emission/absorption quantities to the cell corners, and then use a second order integration routine with bilinear interpolation of the source terms to integrate the ray-tracing formal transfer equations. See Section 9.8 for more information about the second order integration: It is recommended to read it!
- camera_interpol_jnu (default: 0) [Fine-tuning only] Fine-tuning parameter for ray-tracing, only used for when second order integration is done (i.e. if camera_secondorder=1). If 0 (default), then the source function S_{ν} is the one that is interpolated on the grid, while if 1, then the emissivity j_{ν} is the one that is interpolated on the grid. The differences are minimal, but if strange results appear (when using second order integration) then you may want to experiment a bit with this parameter.
- mc_weighted_photons (default: 1) [Fine-tuning only]

 If mc_weighted_photons=1 (default) then in Monte Carlo simulations not all photon packages will have the same energy (see Section 6.8). The energy will be weighted such that each star or emission mechanism will emit, on average, the same number of photon packages. As an example: If you have a stellar binary consisting of an O-star surrounded by a Brown Dwarf, but the Brown Dwarf is surrounded by a disk, then although the O star is much brighter than the O-star, the very inner regions of the Brown Dwarf disk is still predominantly heated by the Brown Dwarf stellar surface, because it is much closer to that material. If you do not have weighted photon packages, then statistically the Brown Dwarf would emit perhaps 1 or 2 photon packages, which makes the statistics of the energy balance in the inner disk very bad. By mc_weighted_photons=1 both the Brown Dwarf and the O-star will each emit the same number of photon packages; just the energy of the photon packages emitted by the Brown Dwarf are much less energetic than those from the O-star. This now assures a good photon statistics everywhere.
- optimized_motion (default: 0) [Fine-tuning only]
 If optimized_motion is set to 1, then RADMC-3D will try to calculate the photon motion inside cells more efficiently. This may save computational time, but since it is still not very well tested, please use this mode with great care! It is always safer not to use this mode.
- lines_mode (default: 1)

 This mode determines how the level populations for line transfer are computed. The default is 1, which means: Local Thermodynamic Equilibrium (LTE). For other modes, please consult Chapter 7.

- lines_maxdoppler (default: 0.3) [Fine-tuning only]

 If the doppler catching mode is used, this parameter tells how fine RADMC-3D must sample along the ray, in units of the doppler width, when a line is doppler-shifting along the wavelength-of-sight.
- lines_partition_ntempint (default 1000) [Fine-tuning only]

 Number of temperature sampling points for the internally calculated partition function for molecular/atomic lines.
- lines_partition_temp0 (default 0.1) [Fine-tuning only]
 Smallest temperature sampling point for the internally calculated partition function for molecular/atomic lines.
- lines_partition_temp1 (default 1E5) [Fine-tuning only]
 Largest temperature sampling point for the internally calculated partition function for molecular/atomic lines.
- lines_show_pictograms (default 0)

 If 1, then print a pictogram of the levels of the molecules/atoms.
- tgas_eq_tdust (default: 0)

 By setting tgas_eq_tdust=1 you tell radmc3d to simply read the dust_temperature.inp file and then equate the gas temperature to the dust temperature. If multiple dust species are present, only the first species will be used.
- subbox_nx, subbox_ny, subbox_nz, subbox_x0, subbox_x1, subbox_y0, subbox_y1, subbox_z0, subbox_z1

 Parameters specifying the subbox size for the subbox extraction. See Section 15.1 for details.

A.2 INPUT (required): amr_grid.inp

This is the file that specifies what the spatial grid of the model looks like. See Chapter 10. This file is essential, because most other .inp and .dat files are simple lists of numbers which do not contain any information about the grid. All information about the grid is contained in the amr_grid.inp, also for non-AMR regular grids. Note that in the future we will also allow for unstructured grids. The corresponding grid files will then be named differently.

There are three possible AMR grid styles:

- Regular grid: No mesh refinement. This is grid style 0.
- Oct-tree-style AMR ("Adaptive Mesh Refinement", although for now it is not really "adaptive"). This is grid style 1.
- Layer-style AMR. This is grid style 10.

A.2.1 Regular grid

For a regular grid, without grid refinement, the amr_grid.inp looks like:

```
iformat
                                     <=== Typically 1 at present
                                     <=== Grid style (regular = 0)
coordsystem
gridinfo
incl_x
           incl_y
                     incl_z
           ny
                      nz
                     xi[3]
xi[1]
           xi[2]
                                  ..... xi[nx+1]
yi[1]
           yi[2]
                       yi[3]
                                  ..... yi[ny+1]
                                  ..... zi[nz+1]
zi[1]
           zi[2]
                      zi[3]
```

The meaning of the entries are:

iformat: The format number, at present 1. For unformatted files this must be 4-byte integer.

coordsystem: If coordsystem<100 the coordinate system is cartesian. If 100<=coordsystem<200 the coordinate system is spherical (polar). If 200<=coordsystem<300 the coordinate system is cylindrical. For unformatted files this must be 4-byte integer.

gridinfo: If gridinfo==1 there will be abundant grid information written into this file, possibly useful for post-processing routines. Typically this is redundant information, so it is advised to set gridinfo=0 to save disk space. In the following we will assume that gridinfo=0. For unformatted files this must be 4-byte integer.

incl_x, incl_y, incl_z: These are either 0 or 1. If 0 then this dimension is not active (so upon grid refinement no refinement in this dimension is done). If 1 this dimension is fully active, even if the number of base grid cells in this direction is just 1. Upon refinement the cell will also be splitted in this dimension. For unformatted files these numbers must be 4-byte integer.

nx, **ny**, **nz**: These are the number of grid cells on the base grid in each of these dimensions. For unformatted files these numbers must be 4-byte integer.

xi[1] ... xi[nx+1]: The edges of the cells of the base grid in x-direction. For nx grid cells we have nx+1 cell walls, hence nx+1 cell wall positions. For unformatted files these numbers must be 8-byte reals (=double precision).

yi[1] ... yi[ny+1]: Same as above, but now for y-direction.

zi[1] ... zi[nz+1]: Same as above, but now for z-direction.

Example of a simple 2x2x2 regular grid in cartesian coordinates:

A.2.2 Oct-tree-style AMR grid

For a grid with oct-tree style grid refinement, the amr_grid.inp looks like:

```
iformat
                                       <=== Typically 1 at present
1
                                       <=== Grid style (1 = Oct-tree)
coordsystem
gridinfo
                     incl_z
nz
            incl_y
incl_x
nx
           ny
levelmax nleafsmax nbranchmax
                                      <=== This line only if grid style == 1
xi[1]
           xi[2] xi[3] ..... xi[nx+1]
                       yi[3]
           yi[2]
                                   . . . . . . . .
yi[1]
                                             yi[ny+1]
           zi[2]
                        zi[3]
                                    ..... zi[nz+1]
zi[1]
                      <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
                      <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
(0/1)
                       <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
                       <=== 0=leaf, 1=branch (only if amrstyle==1)
                       <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
(0/1)
                      <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
                      <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
                      <=== 0=leaf, 1=branch (only if amrstyle==1)
                       <=== 0=leaf, 1=branch (only if amrstyle==1)
(0/1)
. . .
```

The keywords have the same meaning as before, but in addition we have:

(0/1): NOTE: Only for amrstyle==1. These are numbers that are either 0 or 1. If 0, this means the current cell is a leaf (= a cell that is not refined and is therefore a "true" cell). If 1, the current cell is a branch with 2 (in 1-D), 4 (in 2-D) or 8 (in 3-D) daughter cells. In that case the next (0/1) numbers are for these daughter cells. In other words, we immediately recursively follow the tree. The order in which this happens is logical. In 3-D the first daughter cell is (1,1,1), then (2,1,1), then (1,2,1), then (2,2,1), then (1,1,2), then (2,1,2), then (1,2,2) and finally (2,2,2), where the first entry represents the x-direction, the second the y-direction and the third the z-direction. If one or more of the daughter cells is also refined (i.e. has a value 1), then first this sub-tree is followed before continuing with the rest of the daughter cells. If we finally return to the base grid at some point, the next (0/1) number is for the next base grid cell (again possibly going into this tree if the value is 1). The order in which the base grid is scanned in this way is from 1 to nx in the innermost loop, from 1 to ny in the middle loop and from 1 to nz in the outermost loop. For unformatted files these numbers must be 4-byte integers, one record per number.

NOTE: For this file the unformatted style is presumably not so useful, because for technical reasons each of the (0/1) numbers must be a separate record, requiring 12 bytes. The formatted version is smaller: each line being only 2 bytes (one character 0 or 1 and a return). In the future I will try to make this more efficient, but for now the user is advised to just use the unformatted style.

Example of a simple 1x1x1 grid which is refined into 2x2x2 and for which the (1,2,1) cell is refined again in 2x2x2:

```
1
1
0
1 1 1
   1
10 100 100
-1. 1.
-1. 1.
-1. 1.
Λ
1
0
0
0
0
0
0
0
0
0
0
0
0
```

A.2.3 Layer-style AMR grid

For a grid with layer-style grid refinement, the amr_grid.inp looks like:

```
iformat
                                      <=== Typically 1 at present
                                      <=== Grid style (10 = layer-style)
10
coordsystem
gridinfo
incl_x
            incl_y
                        incl_z
nx
            ny
                        nz
nrlevels
                                      <=== This line only if grid style == 10
           nrlayers
                        xi[3]
xi[1]
           xi[2]
                                   ..... xi[nx+1]
yi[1]
           yi[2]
                        yi[3]
                                   ..... yi[ny+1]
zi[1]
            zi[2]
                        zi[3]
                                    ..... zi[nz+1]
parentid
            ix iy iz
                        nx ny nz
parentid
            ix iy iz
                        nx ny
                               nz
            ix iy iz
parentid
                        nx ny
                               nz
            ix iy iz
parentid
                        nx ny nz
```

.

The keywords have the same meaning as before, but in addition we have:

nrlevels: How many levels you plan to go, where nrlevels==0 means no refinement, nrlevels==1 means one level of refinement (factor of 2 in resolution), etc.

nrlayers: How many layers do you have, with nrlayers==0 means no refinement, nrlayers==1 means one layer of refinement (factor of 2 in resolution), etc.

parentid: (For each layer) The parent layer for this layer. parentid==0 means parent is base grid. First layer has id==1.

ix, iy, iz: (For each layer) The location in the parent layer where the current layer starts.

nx, ny, nz: (For each layer) The size of the layer as measured in units of the the parent layer. So the actual size of the current layer will be (in 3-D): 2*nx, 2*ny, 2*nz. In 2-D, with only the x- and y- dimensions active, we have a size of 2*nx, 2*ny with of course size 1 in z-direction.

As you can see, this is a much easier and more compact way to specify mesh refinement. But it is also less "adaptive", as it is always organized in square/cubic patches. But it is much easier to handle for the user than full oct-tree refinement.

Note that this layer-style refinement is in fact, internally, translated into the oct-tree refinement. But you, as the user, will not notice any of that. The code will input and output entirely in layer style.

NOTE: The layers must be specify in increasing refinement level! So the first layer (layer 1) must have the base grid (layer 0) as its parent. The second layer can have either the base grid (layer 0) or the first layer (layer 1) as parent, etc. In other words: the parent layer must always already have been specified before.

Example of a simple 2-D 4x4 grid which has a refinement patch in the middle of again 4x4 cells (=2x2 on the parent grid), and a patch of 2x2 (=1x1 on the parent grid) starting in the upper left corner:

```
1

100

1

0

1 1 0

4 4 1

1 2

-2. -1. 0. 1. 2.

-2. -1. 0. 1. 2.

-0.5 0.5

0 2 2 1 2 2 1

0 1 1 1 1 1
```

This has just one level of refinement, but two patches at level 1.

Anothe example: two recursive layers. Again start with a 2-D 4x4 grid, now refine it in the middle with again a 4x4 sub-grid (=2x2 on the parent grid = layer 0) and then again a deeper layer of 4x4 (=2x2 on the parent grid = layer 1) this time starting in the corner:

```
1
100
1
0
1 1 0
4 4 1
2 2
-2. -1. 0. 1. 2.
-2. -1. 0. 1. 2.
-0.5 0.5
0 2 2 1 2 2 1
1 1 1 1 2 2 1
```

Note that with this layer-style grid, the input data will have to be speficied layer-by-layer: first the base grid, then the first layer, then the second etc. This is worked out in detail for dust_density.inp in Section A.3. This will include redundant data, because you specify the data on the entire base grid, also the cells that later will be replaced by a layer. Same is true for any layer that has sub-layers. The data that is specified in these regions will be simply ignored. But for simplicity we do still require it to be present, so that irrespective of the deeper layers, the data in any layer (including the base grid, which is layer number 0) is simply organized as a simple data cube. This redundancy makes the input and output files larger than strictly necessary, but it is much easier to handle as each layer is a datacube. For memory/hardisk-friendly storage you must use the oct-tree refinement instead. The layers are meant to make the AMR much more accessible, but are somewhat more memory consuming.

A.3 INPUT (required for dust transfer): dust_density.inp

This is the file that contains the dust densities. It is merely a list of numbers. Their association to grid cells is via the file amr_grid.inp (see Chapter B for the binary version of this file, which is more compact). Each dust species will have its own density distribution, completely independently of the others. That means that at each position in space several dust species can exist, and the density of these can be fully freely specified. The structure of this file is as follows. For formatted style (dust_density.inp):

Here nrspec is the number of independent dust species densities that will be given here. It can be 1 or larger. If it is 1, then of course the density[1,ispec=2] and following lines are not present in the file. The nrcells is the number of cells. For different kinds of grids this can have different meaning. Moreover, for different kinds of grids the order in which the density values are given is also different. So let us now immediately make the following distinction (See Chapter 10 on the different kinds of grids):

• For regular grid and oct-tree AMR grids:

The value of nrcells denotes the number of *true* cells, excluding the cells that are in fact the parents of 2x2x2 subcells; i.e. the sum of the volumes of all true cells (=leafs) adds up to the volume of the total grid). The order of these numbers is always the same "immediate recursive subtree entry" as in the amr_grid.inp (Section A.2).

• For layer-style AMR grids:

The value of nrcells denotes the number of values that are specified. This is generally a bit more than the true number of cells specified in the oct-tree style AMR (see above). In the layer-style AMR mode you specify the dust density (or any other value) first at all cells of the base grid (whether a cell is refined or not does not matter), the at all cells of the first layer, then the second layer etc. Each layer is a regular (sub-)grid, so the order of the values is simply the standard order (same as for regular grids). This means, however, that the values of the density in the regular grid cells that are replaced by a layer are therefore redundant. See Section 10.4.1 for a discussion of this redundancy. The main advantage of this layer-style grid refinement is that the input and output always takes place on *regular* grids and subgrids (=layers). This is much easier to handle than the complexities of the oct-tree AMR.

A.3.1 Example: dust_density.inp for a regular grid

Now let us look at an example of a dust_density.inp file, starting with one for the simplified case of a regular 3-D grid (see Sections A.2.1 and 10.1):




Figure A.1. Example of a regular 2-D grid with nx=4 and ny=3 (as Fig. 10.1), with the order of the cells shown as numbers in the cells.

A.3.2 Example: dust_density.inp for an oct-tree refined grid

For the case when you have an oct-tree refined grid (see Sections A.2.2 and 10.3), the order of the numbers is the same as the order of the cells as specified in the amr_grid. (u)inp file (Section A.2). Let us take the example of a simple 1x1x1 grid which is refined into 2x2x2 and for which the (1,2,1) cell is refined again in 2x2x2 (this is exactly the same example as shown in Section A.2.2, and for which the amr_grid.inp is given in that section). Let us also assume that we have only one dust species. Then the dust_density.inp file would be:




Figure A.2. Example of a 2-D grid with oct-tree refinement (as Fig. 10.3) with the order of the cells shown as numbers in the cells.

```
density[1,2,1;2,1,1]
density[1,2,1;1,2,1]
density[1,2,1;1,2,1]
density[1,2,1;1,2]
density[1,2,1;2,1,2]
density[1,2,1;1,2,2]
density[2,2,1]
density[2,2,1]
density[2,2,1]
density[2,2,2]
density[2,2,2]
density[2,2,2]

<=== This is the last refined cell
</pre>
```

A more complex example is shown in Fig. A.2. An unformatted version is also available, in the standard way (see above).

A.3.3 Example: dust_density.inp for a layer-style refined grid

For the case when you have an layer-style refined grid (see Sections A.2.3 and 10.4) you specify the density in a series of regular boxes (=layers). The first box is the base grid, the second the first layer, the third the second layer etc. The value nrcells now tells the combined sizes of the all the boxes. If we take the second example of Section A.2.3: a simple 2-D 4x4 grid which has a refinement patch (=layer) in the middle of again 4x4 cells, and again one patch of 4x4 this time, however, starting in the upper left corner (see the amr_grid.inp file given in Section A.2.3), then the dust_density.inp file has the following form:

```
density[4,1,1,layer=0]
density[1,2,1,layer=0]
density[2,2,1,layer=0]
                                          <=== This a redundant value
density[3,2,1,layer=0]
                                          <=== This a redundant value
density[4,2,1,layer=0]
density[1,3,1,layer=0]
density[2,3,1,layer=0]
                                          <=== This a redundant value
density[3,3,1,layer=0]
                                          <=== This a redundant value
density[4,3,1,layer=0]
density[1,4,1,layer=0]
density[2,4,1,layer=0]
density[3,4,1,layer=0]
density[4,4,1,layer=0]
                                          <=== This a redundant value
density[1,1,1,layer=1]
density[2,1,1,layer=1]
                                          <=== This a redundant value
density[3,1,1,layer=1]
density[4,1,1,layer=1]
density[1,2,1,layer=1]
                                          <=== This a redundant value
density[2,2,1,layer=1]
                                          <=== This a redundant value
density[3,2,1,layer=1]
density[4,2,1,layer=1]
density[1,3,1,layer=1]
density[2,3,1,layer=1]
density[3,3,1,layer=1]
density[4,3,1,layer=1]
density[1,4,1,layer=1]
density[2,4,1,layer=1]
density[3,4,1,layer=1]
density[4,4,1,layer=1]
density[1,1,1,layer=2]
density[2,1,1,layer=2]
density[3,1,1,layer=2]
density[4,1,1,layer=2]
density[1,2,1,layer=2]
density[2,2,1,layer=2]
density[3,2,1,layer=2]
density[4,2,1,layer=2]
density[1,3,1,layer=2]
density[2,3,1,layer=2]
density[3,3,1,layer=2]
density[4,3,1,layer=2]
density[1,4,1,layer=2]
density[2,4,1,layer=2]
density[3,4,1,layer=2]
density[4,4,1,layer=2]
```

An unformatted version is also available, in the standard way (see above).

It is clear that 48 is now the total number of values to be read, which is 16 values for layer 0 (= base grid), 16 values for layer 1 and 16 values for layer 2. It is also clear that some values are redundant (they can have any value, does not matter). But it at least assures that each data block is a simple regular data block, which is easier to handle. Note that these values (marked as redundant in the above example) *must* be present in the file, but they can have any value you like (typically 0).

Note that if you have multiple species of dust then we will still have 48 as the value of nrcells. The number of values to be read, if you have 2 dust species, is then simply 2*nrcells = 2*48 = 96.

A.4 INPUT/OUTPUT: dust_temperature.dat

The dust temperature file is an intermediate result of RADMC-3D and follows from the thermal Monte Carlo simulation. The name of this file is dust_temperature.dat (see Chapter B for the binary version of this file, which is more compact). It can be used by the user for other purposes (e.g. determination of chemical reaction rates), but also by RADMC-3D itself when making ray-traced images and/or spectra. The user can also produce his/her own dust_temperature.dat file (without invoking the Monte Carlo computation) if she/he has her/his own way of computing the dust temperature.

The structure of this file is identical to that of dust_density.inp (Section A.3), but with density replaced by temperature. We refer to section A.3 for the details.

A.5 INPUT/OUTPUT (only if required): electron_numdens.inp

For various gasopacity issues (see Chapter 8) the number density of free electrons may be required. This is given in a file called electron_numdens.inp (see Chapter B for the binary version of this file, which is more compact, and which you can use instead of the ascii versions). The structure of this file is identical to that of dust_density.inp (Section A.3), but with density replaced by the electron number density in units of 1/cm³. We refer to chapter 8 for the details.

A.6 INPUT/OUTPUT (only if required): ion_numdens.inp

For various gasopacity issues (see Chapter 8) the number density of ions may be required. This is given in a file called ion_numdens.inp (see Chapter B for the binary version of this file, which is more compact, and which you can use instead of the ascii versions). The structure of this file is identical to that of dust_density.inp (Section A.3), but with density replaced by the ion number density in units of 1/cm³. Here we need the overal ion number density. We refer to chapter 8 for the details.

A.7 INPUT (mostly required): stars.inp

This is the file that specifies the number of stars, their positions, radii, and spectra. Stars are sources of netto energy. For the dust continuum Monte Carlo simulation these are a source of photon packages. This file exists only in formatted (ascii) style. Its structure is:

which is valid only if iformat==2. The meaning of the variables:

iformat: The format number, at present better keep it at 2. If you put it to 1, the list of wavelengths (see below) will instead be a list of frequencies in Herz.

nstars: The number of stars you wish to specify.

nlam: The number of frequency points for the stellar spectra. At present this must be identical to the number of walvelength points in the file wavelength_micron.inp (see Section A.12).

rstar[i]: The radius of star i in centimeters.

mstar[i]: The mass of star i in grams. This is not important for the current version of RADMC-3D, but may be in the future.

xstar[i]: The x-coordinate of star i in centimeters.

ystar[i]: The y-coordinate of star i in centimeters.

zstar[i]: The z-coordinate of star i in centimeters.

lambda[i]: Wavelength point i (where $i \in [1,nlam]$) in microns. This must be identical (!) to the equivalent point in the file wavelength_micron.inp (see Section A.12). If not, an error occurs.

flux[i,star=n]: The flux F_{ν} at wavelength point i for star n in units of erg cm $^{-2}$ s $^{-1}$ Hz $^{-1}$ as seen from a distance of 1 parsec = 3.08572×10^{18} cm (for normalization).

Sometimes it may be sufficient to assume simple blackbody spectra for these stars. If for any of the stars the first (!) flux number (flux[1,star=n]) is negative, then the absolute value of this number is taken to be the blackbody temperature of the star, and no further values for this star are read. Example:

```
2
1 100
6.96e10 1.99e33 0. 0. 0
0.1
.
.
1000.
```

will make one star, at the center of the coordinate system, with one solar radius, one solar mass, on a wavelength grid ranging from 0.1 micron to 1000 micron (100 wavelength points) and with a blackbody spectrum with a temperature equal to the effective temperature of the sun.

Note: The position of a star can be both inside and outside of the computational domain.

A.8 INPUT (optional): stellarsrc_templates.inp

This is the file that specifies the template spectra for the smooth stellar source distributions. See Section 11.3. The file exists only in formatted (ascii) style. Its structure is:

which is valid only if iformat==2. The meaning of the variables:

iformat: The format number, at present better keep it at 2. If you put it to 1, the list of wavelengths (see below) will instead be a list of frequencies in Herz.

ntempl: The number of stellar templates you wish to specify.

nlam: The number of frequency points for the stellar template spectra. At present this must be identical to the number of walvelength points in the file wavelength_micron.inp (see Section A.12).

lambda[i]: Wavelength point i (where $i \in [1,nlam]$) in microns. This must be identical (!) to the equivalent point in the file wavelength_micron.inp (see Section A.12). If not, an error occurs.

flux[i,templ=n]: The "flux" at wavelength i for stellar template n. The units are somewhat tricky. It is given in units of erg / sec / Hz / gram-of-star. So multiply this by the density of stars in units of gram-of-star / cm³, and divide by 4*pi to get the stellar source function in units of erg / src / Hz / cm³ / steradian.

Sometimes it may be sufficient to assume simple blackbody spectra for these stellar sources. If for any of the stellar sources the first (!) flux number (flux[1,templ=n]) is negative, then the absolute value of this number is taken to be the blackbody temperature of the stellar source, and the following two numbers are interpreted as the stellar radius and stellar mass respectively. From that, RADMC-3D will then internally compute the stellar template. Example:

```
2
1
100
0.1
.
.
.
1000.
-5780.
6.9600000e+10
1.9889200e+33
```

will tell RADMC-3D that there is just one stellar template, assumed to have a blackbody spectrum with solar effective temperature. Each star of this template has one solar radius, one solar mass.

A.9 INPUT (optional): stellarsrc_density.inp

This is the file that contains the smooth stellar source densities. If you have the file stellarsrc_templates.inp specified (see Section A.8) then you *must* also specify stellarsrc_density.inp (or its binary form, see Chapter B). The format of this file is very similar to dust_density.inp (Section A.3), but instead different dust species, we have different templates. For the rest we refer to Section A.3 for the format. Just replace ispec (the dust species) with itempl (the template).

A.10 INPUT (optional): external_source.inp

This is the file that specifies the spectrum and intensity of the external radiation field, i.e. the "interstellar radiation field" (see Section 11.4). Its structure is:

which is valid only if iformat==2. The meaning of the variables:

iformat: The format number, at present better keep it at 2. If you put it to 1, the list of wavelengths (see below) will instead be a list of frequencies in Herz.

nlam: The number of frequency points for the stellar template spectra. At present this must be identical to the number of walvelength points in the file wavelength_micron.inp (see Section A.12).

lambda[i]: Wavelength point i (where $i \in [1,nlam]$) in microns. This must be identical (!) to the equivalent point in the file wavelength_micron.inp (see Section A.12). If not, an error occurs.

Intensity[i]: The intensity of the radiation field at wavelength i in units of erg / cm² / sec / Hz / steradian.

A.11 INPUT (optional): heatsource.inp

This file, if present (it is an optional file!), gives the internal heat source of the gas-dust mixture in every cell. For formatted style (heatsource.inp) the structure of this file is as follows.:

As with most input/output files of RADMC-3D, you can also specify the input data in binary form (heatsource.binp), see Chapter B.

The physical unit of heatsource is $erg cm^{-3} s^{-1}$. The total luminosity of the heat source would then be the sum over all cells of heatsource times the cell volume.

A.12 INPUT (required): wavelength_micron.inp

This is the file that sets the discrete wavelength points for the continuum radiative transfer calculations. Note that this is not the same as the wavelength grid used for e.g. line radiative transfer. See Section A.13 and/or Chapter 7 for that. This file is only in formatted (ascii) style. It's structure is:

```
nlam
lambda[1]
.
.
lambda[nlam]
```

where

nlam: The number of frequency points for the stellar spectra.

lambda[i]: Wavelength point i (where $i \in [1,nlam]$) in microns.

The list of wavelengths can be in increasing order or decreasing order, but must be monotonically increasing/decreasing.

IMPORTANT: It is important to keep in mind that the wavelength coverage must include the wavelengths at which the stellar spectra have most of their energy, and at which the dust cools predominantly. This in practice means that this should go all the way from 0.1 μ m to 1000 μ m, typically logarithmically spaced (i.e. equally spaced in $\log \lambda$). A smaller coverage will cause serious problems in the Monte Carlo run and dust temperatures may then be severely miscalculated. Note that the 0.1 μ m is OK for stellar temperatures below 10000 K. For higher temperatures a shorter wavelength lower limit must be used.

A.13 INPUT (optional): camera_wavelength_micron.inp

The wavelength points in the wavelength_micron.inp file are the global continuum wavelength points. On this grid the continuum transfer is done. However, there may be various reasons why the user may want to generate spectra on a different (usually more finely spaced) wavelength grid, or make an image at a wavelength that is not available in the global continuum wavelength grid. Rather than redoing the entire model with a different

wavelength_micron.inp, which may involve a lot of reorganization and recomputation, the user can specify a file called camera_wavelength_micron.inp. If this file exists, it will be read into RADMC-3D, and the user can now ask RADMC-3D to make images in those wavelength or make a spectrum in those wavelengths.

If the user wants to make images or spectra of a model that involves gas lines (such as atomic lines or molecular rotational and/or ro-vibrational lines), the use of a camera_wavelength_micron.inp file allows the user to do the line+dust transfer (gas lines plus the continuum) on this specific wavelength grid. For line transfer there are also other ways by which the user can specify the wavelength grid (see Chapter 7), and it is left to the user to choose which method to use.

The structure of the camera_wavelength_micron.inp file is identical to that of wavelength_micron.inp (see Section A.12).

Note that there are also various other ways by which the user can let RADMC-3D choose wavelength points, many of which may be even simpler and more preferable than the method described here. See Section 9.4.

A.14 INPUT (required for dust transfer): dustopac.inp and dustkappa_*.inp or dustkapscatmat_*.inp or dust_optnk_*.inp

These files specify the dust opacities to be used. More than one can be specified, meaning that there will be more than one co-existing dust species. Each of these species will have its own dust density specified (see Section A.3). The opacity of each species is specified in a separate file for each species. The dustopac.inp file tells which file to read for each of these species.

A.14.1 The dustopac.inp file

The file dustopac.inp has the following structure, where an example of 2 separate dust species is used:

where:

iformat: Currently the format number is 2, and in this manual we always assume it is 2.

nspec: The number of dust species that will be loaded.

inputstyle[i]: This number tells in which form the dust opacity of dust species i is to be read:

- 1 Use the dustkappa_<name>. inp input file style (see Section A.14.2).
- 10 Use the dustkapscatmat_<name>.inp input file style (see Section A.14.3).
- -1 Use the dustopac_<name>.inp input file style (see Section A.14.4). This is just a backward compatibility mode. Should be avoided if possible.

iquantum[i]: For normal thermal grains this is 0. If, however, this grain species is supposed to be treated as a quantum-heated grain, then non-zero values are to be specified. *NOTE:* At the moment the quantum heating is not yet implemented. Will be done in the near future. Until then, please set this to 0!

<name of dust species i>: This is the name of the dust species (without blank spaces). This name is then
glued to the base name of the opacity file (see above). For instance, if the name is enstatite, and
inputstyle==1, then the file to be read is dustkappa_enstatite.inp.

A.14.2 The dustkappa_<name>.inp files

If you wish to use dust opacities that include the mass-weighted absorption opacity $\kappa_{\rm abs}$, the (optionally) mass-weighted scattering opacity $\kappa_{\rm scat}$, and (optionally) the anisotropy factor g for scattering, you can do this with a file dustkappa_<name>.inp (set input style to 1 in dustopac.inp, see Section A.14.1). With this kind of opacity scattering is included either isotropically or using the Henyey-Greenstein function. Using an opacity of this kind does *not* allow for full realistic scattering phase functions nor for polarization. For that, you need dustkapscatmat_<name>.inp files (see Section A.14.3). Please refer to Section 6.6 for more information about how RADMC-3D treats scattering.

If for dust species <name> the inputstyle in the dustopac.inp file is set to 1, then the file dustkappa_<name>.inp is sought and read. The structure of this file is:

The meaning of these entries is:

iformat: If iformat==1, then only the lambda and kappa_abs colums are present. In that case the scattering opacity is assumed to be 0, i.e. a zero albedo is assumed. If iformat==2 also kappa_scat is read (third column). If iformat==3 (which is what is used in the above example) then *also* the anisotropy factor *g* is included.

nlam: The number of wavelength points in this file. This can be any number, and does not have to be the same as those of the wavelength_micron.inp. It is typically advisable to have a rather large number of wavelength points.

lambda[i]: The wavelength point i in micron. This does not have to be (and indeed typically is not) the same as the values in the wavelength_micron.inp file. Also for each opacity this list of wavelengths can be different (and can be a different quantity of points).

kappa_abs[i]: The absorption opacity κ_{abs} in units of cm² per gram of dust.

kappa_scat[i]: The scattering opacity κ_{abs} in units of cm² per gram of dust. Note that this column should only be included if iformat==2 or higher.

g[ilam]: The mean scattering angle $\langle \cos(\theta) \rangle$, often called g. This will be used by RADMC-3D in the Henyey-Greenstein scattering phase function. Note that this column should only be included if iformat==3 or higher.

Once this file is read, the opacities will be mapped onto the global wavelength grid of the wavelength_micron.inp file. Since this mapping always involve uncertainties and errors, a file dustkappa_<name>.inp_used is created which lists the opacity how it is remapped onto the global wavelength grid. This is only for you as the user, so that you can verify what RADMC-3D has internally done. Note that if the upper or lower edges of the wavelength domain of the dustkappa_<name>.inp file is within the domain of the wavelength_micron.inp grid, some extrapolation will have to be done. At short wavelength this will simply be constant extrapolation while at long wavelength a powerlaw extrapolation is done. Have a look at the dustkappa_<name>.inp_used file to see how RADMC-3D has done this in your particular case.

A.14.3 The dustkapscatmat_<name>.inp files

If you wish to treat scattering in a more realistic way than just the Henyey-Greenstein non-polarized way, then you must provide RADMC-3D with more information than is present in the dustkappa_xxx.inp files: RADMC-3D will need the full scattering Müller matrix for all angles of scattering (see e.g. the books by Mishchenko, or by Bohren & Huffman or by van de Hulst). For *randomly oriented particles* only 6 of these matrix elements can be non-zero: Z_{11} , $Z_{12} = Z_{21}$, Z_{22} , Z_{33} , $Z_{34} = -Z_{43}$, Z_{44} , where 1,2,3,4 represent the I,Q,U,V Stokes parameters.

Moreover, for randomly oriented particles there is only 1 scattering angle involved: the angle between the incoming and outgoing radiation of the scattering event. This means that we must give RADMC-3D, (for every wavelength and for a discrete set of scattering angles) a list of values of these 6 matrix elements. These can be provided in a file dustkapscatmat_xxx.inp (set input style to 10 in dustopac.inp, see Section A.14.1) which comes *instead* of the dustkappa_xxx.inp file. Please refer to Section 6.6 for more information about how RADMC-3D treats scattering.

If for dust species <name> the inputstyle in the dustopac.inp file is set to 10, then the file dustkapscatmat_<name>.inp is sought and read. The structure of this file is:

```
# Any amount of arbitrary
# comment lines that tell which opacity this is.
# Each comment line must start with an # or ; or ! character
              <== Format number must be 1
iformat
nang
               <== A reasonable value is 181 (e.g. angle = 0.0,1.0,...,180.0)</pre>
lambda[1]
             kappa_abs[1]
                                             g[1]
                             kappa_scat[1]
               .
  .
                                              .
lambda[nlam] kappa_abs[nlam] kappa_scat[nlam] g[nlam]
angle in degrees[1]
angle_in_degrees[nang]
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44 [all for ilam=1 and iang=1]
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44 [all for ilam=1 and iang=2]
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44 [all for ilam=1 and iang=3]
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44
                               [all for ilam=1 and iang=nang]
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44
                               [all for ilam=2 and iang=1]
Z 11 Z 12 Z 22 Z 33 Z 34 Z 44
                               [all for ilam=2 and iang=nang]
. . . .
Z_11 Z_12 Z_22 Z_33 Z_34 Z_44
                              [all for ilam=nlam and iang=1]
```

The meaning of these entries is:

iformat: For now this value should remain 1.

nlam: The number of wavelength points in this file. This can be any number, and does not have to be the same as those of the wavelength_micron.inp. It is typically advisable to have a rather large number of wavelength points.

nang: The number of scattering angle sampling points. This should be large enough that a proper integration over scattering angle can be carried out reliably. A reasonable value is 181, so that (for a regular grid in scattering angle θ) you have as scattering angles $\theta=0,1,2,\cdots,180$ (in degrees). But if you have extremely forward- or backward peaked scattering, then maybe even 181 is not enough.

lambda[ilam]: The wavelength point ilam in micron. This does not have to be (and indeed typically is not) the same as the values in the wavelength_micron.inp file. Also for each opacity this list of wavelengths can be different (and can be a different quantity of points).

angle_in_degrees[iang]: The scattering angle sampling point *iang* in degrees (0 degrees is perfect forward scattering, 180 degrees is perfect backscattering). There should be nang such points, where angle_in_degrees[1]

must be 0 and angle_in_degrees[nang] must be 180. In between the angle grid can be anything, as long as it is monotonic.

kappa_abs[ilam]: The absorption opacity κ_{abs} in units of cm 2 per gram of dust.

kappa_scat[ilam]: The scattering opacity $\kappa_{\rm scat}$ in units of cm² per gram of dust. RADMC-3D can (and will) in fact calculate $\kappa_{\rm scat}$ from the scattering matrix elements. It will then check (for every wavelength) if that is the same as the value listed here. If the difference is small, it will simply adjust the **kappa_scat[ilam]** value internally to get a perfect match. If it is larger than 1E-4 then it will, in addition to adjusting, make a warning. if it is larger than 1E-1, it will abort. Note that the fewer angles are used, the worse the match will be because the integration over angle will be worse.

g[ilam]: The mean scattering angle $\langle \cos(\theta) \rangle$, often called g. RADMC-3D can (and will) in fact calculate g from the scattering matrix elements. Like with **kappa_scat[ilam]** it will adjust if the difference is not too large and it will complain or abort if the difference is larger than some limit.

Z_xx These are the scattering matrix elements in units of cm² gram⁻¹ ster⁻¹ (i.e. they are angular differential cross sections). See Section 6.6 for more details.

NOTE: This only allows the treatment of *randomly oriented particles*. RADMC-3D does not, for now, have the capability of treating scattering off fixed-oriented particles².

Note that the scattering-angle grid of the dustkapscatmat_xxx.inp files can be chosen non-regular, e.g. to put a more finely spaced grid close to $\theta=0$ (forward scattering) and $\theta=\pi$ (backscattering). This can be useful for large grains and/or short wavelengths, where forward scattering can be extremely strongly peaked. Since multiple dust species can each have a different scattering θ -grid, it requires you to give an additional file to RADMC-3D that represents the scattering θ -grid for all grains. This file is called scattering_angular_grid.inp. The format is as follows:

NOTE: This file is not compulsory. If it is not given, then RADMC-3D will make its own internal scattering angle grid.

A.14.4 The dustopac_<name>.inp files: Backward compatibility with RADMC-2D

If you want to be able to redo a model from the old RADMC (2D-version) code with RADMC-3D, you require RADMC-3D to be able to read the old style dust opacity files dustopac_<name>.inp.

If for dust species <name> the inputstyle in the dustopac.inp file is set to -1, then the file dustopac_<name>.inp is sought and read. The structure of this file is:

```
nlam dummy
kappa_abs[1]
    .
    .
kappa_abs[nlam]
kappa_scat[1]
    .
    .
kappa_scat[nlam]
```

The meaning of these entries is:

²In fact, for oriented particles it would be impractical to use dust opacity files of this kind, since we would then have at least *three* scattering angles, which would require huge table. In that case it would be presumably necessary to compute the matrix elements on-the-fly.

nlam: The number of frequency (wavelength) points. This must be *identical* to those of the wavelength_micron.inp file or else the code stops.

dummy: Put this number to 1. It is here for historic reasons (and backward compatibility with older RADMC incarnations).

kappa_abs[i]: The absorption opacity at wavelength point i of the wavelength_micron.inp wavelength grid, in units of cm² per gram of dust.

kappa_scat[i]: The scattering opacity at wavelength point i of the wavelength_micron.inp wavelength grid, in units of cm² per gram of dust. *NOTE: Here isotropic scattering is assumed.*

Note that the opacities listed in this kind of file belong to the wavelength points in the file wavelength_micron.inp. So if you change the wavelength_micron.inp file, you also must change the dustopac_<name>.inp files. This is why this kind of opacity specification is not recommended.

A.15 OUTPUT: spectrum.out

Any spectrum that is made with RADMC-3D will be either called spectrum.out or *spectrum_<somename>.out* and will have the following structure:

where:

iformat: This format number is currently set to 1.

nlam: The number of wavelength points in this spectrum. This does not necessarily have to be the same as those in the wavelength_micron.inp file. It can be any number.

lambda[i]: Wavelength in micron. This does not necessarily have to be the same as those in the wavelength_micron.inp file. The wavelength grid of a spectrum file can be completely independent of all other wavelength grids. For standard SED computations for the continuum typically these will be indeed the same as those in the wavelength_micron.inp file. But for line transfer or for spectra based on the camera_wavelength_micron.inp they are not.

flux[i]: Flux in erg cm $^{-2}$ s $^{-1}$ Hz $^{-1}$ at this wavelength as measured at a standard distance of 1 parsec (just as a way of normalization).

NOTE: Maybe in the future a new iformat version will be possible where more telescope information is given in the spectrum file.

A.16 OUTPUT: image.out or image_****.out

Any images that are produced by RADMC-3D will be written in a file called image.out. The file has the following structure (for the case without Stokes parameters):

```
image[ix=2,iy=1,img=1]
...
image[ix=im_nx,iy=1,img=1]
image[ix=1,iy=2,img=1]
...
image[ix=im_nx,iy=2,img=1]
image[ix=im_nx,iy=2,img=1]
...
...
image[ix=im_nx,iy=im_ny,img=nlam]
image[ix=im_nx,iy=im_ny,img=nlam]
...
...
image[ix=im_nx,iy=im_ny,img=nlam]
```

In most cases the nr of images (nr of wavelengths) is just 1, meaning only one image is written (i.e. the img=2, img=nlam are not there, only the img=1). The meaning of the various entries is:

iformat: This format number is currently set to 1 for images from an observer at infinity (default) and 2 for a local observer. Note: For full-Stokes images it is 3, but then also the data changes a bit, see below.

im_nx, im_ny: The number of pixels in x and in y direction of the image.

nlam: The number of images at different wavelengths that are in this file. You can make a series of images at different wavelengths in one go, and write them in this file. The wavelength belonging to each of these images is listed below. The nlam can be any number from 1 to however large you want. Mostly one typically just makes an images at one wavelength, meaning nlam=1.

pixsize_x, pixsize_y: The size of the pixels in cm (for an observer at infinity) or radian (for local observer mode). This means that for the observer-at-infinity mode (default) the size is given in model units (distance within the 3-D model) and the user can, for any distance, convert this into arcseconds: pixel size in arcsec = (pixel size in cm / 1.496E13) / (distance in parsec). The pixel size is the full size from the left of the pixel to the right of the pixel (or from bottom to top).

lambda[i]: Wavelengths in micron belonging to the various images in this file. In case nlam=1 there will be here just a single number. Note that this set of wavelengths can be completely independent of all other wavelength grids.

image[ix,iy,img]: Intensity in the image at pixel ix, iy at wavelength img (of the above listed wavelength points) in units of erg cm⁻² s⁻¹ Hz⁻¹ ster⁻¹. *Important:* The pixels are ordered from left to right (i.e. increasing x) in the inner loop, and from bottom to top (i.e. increasing y) in the outer loop.

You can also make images with full Stokes parameters. For this you must have dust opacities that include the full scattering matrix, *and* you must add the keyword stokes to the radmc3d image command on the command-line. In that case the image.out file has the following form:

```
image_I[ix=1,iy=im_ny,img=1] (and so forth for Q U and V)
.
.
.
.
image_I[ix=im_nx,iy=im_ny,img=nlam] (and so forth for Q U and V)
image_I[ix=1,iy=1,img=1] (and so forth for Q U and V)
.
.
.
.
.
.
image_I[ix=im_nx,iy=im_ny,img=nlam] (and so forth for Q U and V)
```

That is: instead of 1 number per line we now have 4 numbers per line, which are the four Stokes parameters. Note that iformat=3 to indicate that we have now all four Stokes parameters in the image.

A.17 INPUT: (minor input files)

There is a number of lesser important input files, or input files that are only read under certain circumstances (for instance when certain command line options are given). Here they are described.

A.17.1 The color_inus.inp file (required with comm-line option 'loadcolor')

The file color_inus.inp will only be read by RADMC-3D if on the command line the option loadcolor or color is specified, and if the main action is image.

iformat: This format number is currently set to 1.

nlam: Number of wavelength indices specified here.

ilam[i]: The wavelength index for image i (the wavelength index refers to the list of wavelengths in the wavelength_micron.inp file.

A.17.2 INPUT: aperture_info.inp

If you wish to make spectra with wavelength-dependent collecting area, i.e. aperture (see Section 9.3.2), then you must prepare the file aperture_info.inp. Here is its structure:

with

iformat: This format number is currently set to 1.

nlam: Number of wavelength indices specified here. This does *not* have to be the same as the number of wavelength of a spectrum or the number of wavelengths specified in the file wavelength_micron.inp. It can be any number.

lambda[i]: Wavelength sampling point, in microns. You can use a course grid, as long as the range of wavelengths is large enough to encompass all wavelengths you may wish to include in spectra.

A.18 For developers: some details on the internal workings

There are several input files that can be quite large. Reading these files into RADMC-3D memory can take time, so it is important not to read files that are not required for the execution of the particular command at hand. For instance, if a model exists in which both dust and molecular lines are included, but RADMC-3D is called to merely make a continuum SED (which in RADMC-3D never includes the lines), then it would be a waste of time to let RADMC-3D read all the gas velocity and temperature data and level population data into memory if they are not used.

To avoid unnecessary reading of large files the reading of these files is usually organized in a 'read when required' way. Any subroutine in the code that relies on e.g. line data to be present in memory can simply call the routine read_lines_all(action) with argument action being 1, i.e.:

```
call read_lines_all(1)
```

This routine will check if the data are present: if no, it will read them, if yes, it will return without further action. This means that you can call read_lines_all(1) as often as you want: the line data will be read once, and only once. If you look through the code you will therefore find that many read_*** routines are called abundantly, whenever the program wants to make sure that certain data is present. The advantage is then that the programmer does not have to have a grand strategy for when which data must be read in memory: he/she simply inserts a call to the read routines for all the data she/he needs at that particular point in the program, (always with action=1), and it will organize itself. If certain data is nowhere needed, they will not be read.

All these read_*** routines with argument action can also be called with action=2. This will force the routine to (re-)read these data. But this is rarely needed.

Appendix B

Binary I/O files

B.1 Overview

By default all input and output files of RADMC-3D are in ASCII (i.e. text) form. This makes it easier to verify if the files are ok. Also, it is easier to produce files with the right format and read the output of RADMC-3D. The disadvantage is that ASCII files are substantially larger than strictly required to store their information content. For large models, i.e. models with many grid points, this may lead to unpractically large files.

RADMC-3D supports a more compact data format: binary data. In this form, a double precision variable occupies just 8 bytes, while a single precision variable occupies just 4 bytes.

Unfortunately, Fortran-90 and Fortran-95 did, for a long time, not support true binary files. Instead they offered "f77-unformatted" files. This is almost as good as true binary format, but the problem is data are organized in so-called "records". When you write, for instance, three double precision variables to a file, your file is not 3x8=24 bytes long, but 28 bytes, because it adds two bytes before and two bytes after each chunk of data. Also, the records were not allowed to be longer than $65536 (=2^{16})$ bytes. As a result, writing large datasets in f77-unformatted form is a pain. RADMC-3D *does* offer a f77-unformatted I/O style, because some compilers may still not support true binary I/O without records. Files that are f77-unformatted will have extensions such as .uinp, .udat or .uout. This file format is rather complex, because it has to overcome the limitations of the record-based I/O. But if you need to use it, please consult Section B.4.

Recently, however, many Fortran-90 and Fortran-95 compilers have introduced a true binary format, which is called "streaming access". It is, actually, a Fortran-2003 feature, but has been retroactively implemented into Fortran-90 and Fortran-95. The gfortran and g95 compilers have it. Also the ifort compiler has it. Presumably others as well.

So as of version 0.30 RADMC-3D now offers a true binary I/O capability. This is the kind of binary files that C-programs can read and in which no "records" are used at all. A file containing three double precision variables will have a length of exactly 24 bytes. Files with this format will have extensions such as .binp, .bdat or .bout.

Here is a (presumably incomplete) list of files that have unformatted versions:

Name	formatted	f77-unformatted	binary
dust_density	.inp	.uinp	.binp
dust_temperature	.inp	.uinp	.binp
dust_temperature	.dat	.udat	.bdat
gas_density	.inp	.uinp	.binp
gas_temperature	.inp	.uinp	.binp
electron_numdens	.inp	.uinp	.binp
ion_numdens	.inp	.uinp	.binp
levelpop_***	.dat	.udat	.bdat
numberdens_***	.inp	.uinp	.binp
gas_velocity	.inp	.uinp	.binp
microturbulence	.inp	.uinp	.binp
stellarsrc_density	.inp	.uinp	.binp
mean_intensity	.out	.uout	.bout
heatsource	.inp	.uinp	.binp

B.2 How to switch to binary (or back to ascii)

Specifying whether RADMC-3D should use ASCII or binary *input* is easy: It will simply look which extension each input file has, and read it accordingly. If you present RADMC-3D file input files with extension .binp, it will read these files as binaries.

More tricky is how to tell RADMC-3D to use binary files on *output*. By default, RADMC-3D will always write ASCII style (.out and .dat). However, if you add the following line to the radmc3d.inp file:

```
rto_style = 3
```

it will instead use binary output (.bout and .bdat). Setting rto_style=2 makes RADMC-3D write f77-unformatted output (.uout and .udat). And, for completeness (though it is the default anyway), if you set rto_style=1 RADMC-3D will write output in ASCII form.

For the binary form of output you can also tell RADMC-3D to use single-precision for the main data, to produce smaller output files. This is done by adding the following line to the radmc3d.inp file:

```
rto\_single = 1
```

By default RADMC-3D will always output double precision in the binary format.

Note: Images are still outputted in ascii even if you have rto_style=2 or rto_style=3. This is because images are rarely files of huge size, and ascii files are easier to analyze and check. However, sometimes images can be still quite big (e.g. if you make multi-frequency images). Then it might still be useful to output binary. If you want to also have the images in binary format, you must set

```
writeimage_unformatted = 1
```

in the radmc3d.inp file, or you add a keyword *imageunform*. This will write the images by default in *C-style* binary format (unless you explicitly have rto_style=2 set in which case it will use F77-style).

B.3 Binary I/O file format of RADMC-3D

The general format of the files listed in Section B.1 is similar to the ASCII versions, just binary this time. There is *one* additional number in the binary version: Right after the format number comes an integer that gives the precision of the main data. This number is either 4, meaning that the main data consists of 4-byte floating point numbers (i.e. single precision), or 8, meaning that the main data consists of 8-byte floating point numbers (i.e. double precision). Other than that additional number, the order of the data is the same.

The following rules apply:

- With the exception of the amr_grid.binp file (see below), all integers are 8-byte integers.
- Floating point numbers for the main data (i.e. the data that represents the space-dependent variables) are either 4-byte (single) or 8-byte (double) precision numbers. Which of the two is specified in the second integer of the file (the integer right after the format number, see above).
- All other floating point numbers are double precision (i.e. 8-byte floats).
- For AMR-grids the amr_grid.binp file contains a huge list of 0 or 1 numbers (see Section A.2.2). Since it is silly to use 8-byte integers for numbers that are either 0 or 1, the numbers in this list are 1-byte integers (bytes).

Example: According to Section A.3 the ASCII file dust_density.inp file has the following format:

```
iformat
nrcells
nrspec
density[1,ispec=1]
..
density[nrcells,ispec=1]
density[1,ispec=2]
..
..
density[nrcells,ispec=nrspec]
```

According to the above listed rules the binary file dust_density.binp file then has the following format:

```
<int8:iformat=1>
<int8:precis=8>
<int8:nrcells>
<int8:nrspec>
<dbl8:density[1,ispec=1]>
...
<dbl8:density[nrcells,ispec=1]>
<dbl8:density[1,ispec=2]>
...
...
<dbl8:density[nrcells,ispec=1]></dbl8:density[1,ispec=2]>
...
<dbl8:density[nrcells,ispec=nrspec]>
```

where the <int8:precis=8> means that this is an 8-byte integer that we call "precis" (the name is irrelevant here), and it has value 8, and <dbl8:density[1,ispec=1]> means that this is a double-precision number (8-byte float). In other words: the first 8 bytes of the file contain the format number (which is 1 at present). The second 8 bytes contain the number 8, telling that the main data (i.e. the density data) are double precision variables. The third set of 8 bytes gives the number of cells, while the fourth set gives the number of dust species. The data of density starts as of the 33rd byte of the file. If you want to compress the file even further, and you are satisfied with single-precision data, then the file would look like:

```
<int8:iformat=1>
<int8:precis=4>
<int8:nrcells>
<int8:nrspec>
<flt4:density[1,ispec=1]>
...
<flt4:density[nrcells,ispec=1]>
<flt4:density[1,ispec=2]>
...
...
<flt4:density[nrcells,ispec=1]>
```

Another example: According to Section 6.5 RADMC-3D can compute the mean intensity of radiation at each grid point at a set of pre-defined frequencies, and write this out to an ASCII file called mean_intensity.out. The contents of this file are:

```
iformat <=== Typically 2 at present nrcells
```

```
<=== Nr of frequencies
nfreq
freq_1 freq_2 ... freq_nfreq
                                          <=== List of frequencies in Hz
meanint[1,icell=1]
meanint[1,icell=2]
meanint[1,icell=nrcells]
meanint[2,icell=1]
meanint[2,icell=2]
meanint[2,icell=nrcells]
. . .
. . .
. . .
meanint[nfreq,icell=1]
meanint[nfreq,icell=2]
meanint[nfreq,icell=nrcells]
```

By setting rto_style=3 in the radmc3d.inp file, however, RADMC-3D will instead produce a binary file called mean_intensity.bout, which has the contents:

```
<int8:iformat=2>
<int8:precis=8>
<int8:nrcells>
<int8:nfreq>
<dbl8:freq_1>
<dbl8:freq_2>
<dbl8:freq_nfreq>
<dbl8:meanint[1,icell=1]>
<dbl8:meanint[1,icell=2]>
<dbl8:meanint[1,icell=nrcells]>
<dbl8:meanint[2,icell=1]>
<dbl8:meanint[2,icell=2]>
<dbl8:meanint[2,icell=nrcells]>
. . .
. . .
<dbl8:meanint[nfreq,icell=1]>
<dbl8:meanint[nfreq,icell=2]>
<dbl8:meanint[nfreq,icell=nrcells]>
```

If you also set rto_single=1 in the radmc3d.inp file, then you will get:

```
<int8:iformat=2>
<int8:precis=4>
<int8:nrcells>
<int8:nfreq>
<dbl8:freq_1>
<dbl8:freq_2>
<dbl8:freq_nfreq>
<flt4:meanint[1,icell=1]>
<flt4:meanint[1,icel1=2]>
<flt4:meanint[1,icell=nrcells]>
<flt4:meanint[2,icell=1]>
<flt4:meanint[2,icell=2]>
<flt4:meanint[2,icell=nrcells]>
. . .
. . .
<flt4:meanint[nfreq,icell=1]>
<flt4:meanint[nfreq,icell=2]>
<flt4:meanint[nfreq,icell=nrcells]>
```

B.4 F77-unformatted file structure used by RADMC-3D

This section explains the F77-style unformatted file I/O of RADMC-3D. It is strongly recommended *not* to use this (use binary I/O instead, see Section B.3) unless your compiler does not support access='stream' as keyword to the open() command.

If RADMC-3D does not compile with the compiler you are using, because your compiler complains about the access='stream' keyword to the open() command, you may need to find all locations in the RADMC-3D source code where this is used, and comment those open() commands out. Easier is to use the gfortran compiler, which does support steaming I/O.

All of the unformatted files listed in Section B.1 follow the same general structure.

- The very first record contains two 8-byte integers: The first is the format number (iformat), which is usually simply 1, but in later developments of RADMC-3D when certain file structures may change, could be upgraded to 2 or 3 or whatever. This number is just there for RADMC-3D to recognize old file structures (a backward compatibility feature). The second integer (reclen) is the general record length (in bytes) used for the main data of this file. See below for more information.
- The second record contains either one or two 8-byte integers. The first of these is (always) the number of cells of the model (i.e. the number of cells for which this file contains data). For some files there is this second integer. For instance, for dust_density.uinp this second integer tells the number of dust species.
- For levelpop_**.udat (or .usdat) there is a next record containing a single 8-byte integer that gives the number of levels for which the populations are given in each cell. For other files no such record exists.
- Now the main data records follow.

The number of records that follow can be calculated as follows. Let nfloats be the number of floating point (either double or single) numbers per grid point for this file. Let reclend be the number of cells for which the data fits in a record (please make sure that this fits exactly!). For double precision one thus has reclend = reclen/(nfloats*8) (relevant for files ending in .uinp or .udat). For single precision one thus has reclend = reclen/(nfloats*4) (relevant for files ending in .usinp or .usdat). For a double precision velocity field we have three double precision numbers per cell, so we get reclend = reclen/(3*8). Let ncells be the number of cells. Then the number of required records is then

```
nrecords = ( (ncells-1) / reclend ) + 1
```

where *integer division* is used, in which e.g. 5/4=1 while 3/4=0. The -1 and +1 are there to assure that we have enough space. For instance if we have 5 cells (ncells=5) and we have reclend=4 (i.e. the data of 4 cells fit into a single record) then we need 2 records, the second of which will contain only one cell (the rest being padded with 0).

Here are a few things to keep in mind:

- 1. Be sure that reclen (the length of each data record in units of bytes) is exactly an integer number times the required data storage of each cell. Example: For the dust_density.uinp file each cell contains only a single number: the density of dust¹. If we want to pack 1024 cells into a single record, then reclen must be exactly 8192.
- 2. It can happen that the last record is not fully filled. For instance, if we have 5 cells, but records of 4 cells each, then the file contains 2 data records, the first one filled with data of 4 cells, the second one only containing data of 1 cell. In the current version of RADMC-3D *you must still write the full record length: so simply pad the unused part with 0 or whatever.*
- 3. Because of the previous point (the padding) it is wise to do EITHER one of the following:

¹Different dust species are written in the outermost loop, see Section A.3.

- Make the record length exactly as big as needed to fit in all data in a single record.
- Take the record length moderate so that if you have a nearly empty record at the end you won't waste too much space (but again, don't take it too small either, so that you don't waste too much space with the record headers and footers). If you take reclend=32 or so (meaning reclen=256 for a double precision scalar field or reclen=768 for a double precision vector field) then you are on the safe side.

I apologise for the complicated stuff here.

Appendix C

Command-line options

This chapter deals with all the possible command-line options one can give when calling the radmc3d code.

C.1 Main commands

In addition to the radmc3d.inp file, which contains many 'steering' parameters, one can (and even must) give RADMC-3D also command-line options. The most important (and compulsory) options are the 'command' what RADMC-3D should do. At the moment you can choose from:

mctherm [setthreads]: Runs RADMC-3D for computing the dust temperatures using the Monte Carlo

method. The optional command setthreads can only be used in the OpenMP

parallelized version. See chapter 6.

spectrum: Runs RADMC-3D for making a spectrum based on certain settings. This option

requires further command-line specifications. See chapter 9.

sed: Runs RADMC-3D for making a SED based on certain settings. This option re-

quires further command-line specifications. Note that a SED is like a spectrum, but

for continuum processes only (no lines). See chapter 9 for more details.

image: Runs RADMC-3D for making an image. This option requires further command-

line specifications. See chapter 9.

movie: Like image, but now for a series of different vantage points. Useful for making

movies in one go, without having to call RADMC-3D time and again. NOTE: This

command is still under development. See chapter 9.

mcmono: (Only expect use). Runs RADMC-3D for computing the local radiation field at each

location in the model. This is only useful for when you wish to couple RADMC-3D to models of chemistry or so, which need the local radiation field. See Section 6.5.

Example:

radmc3d mctherm

runs the RADMC-3D code for computing the dust temperatures everywhere using the Monte Carlo method.

There are also some additional commands that may be useful for diagnostics:

subbox_****: where **** is one of the following: dust_density, dust_temperature. But other quan-

tities will follow in later versions. However, it may be better to use this option from within

IDL. See Section 15.1.

linelist: Write a list of all the lines included in this model.

C.2 Additional arguments: general

Here is a list of command line options, on top of the above listed main commands (Note: We'll try to be complete, but as the code develops we may forget to list new options here):

npix: [for images] The next number specifies the number of pixels in both x and y direction, as-

suming a square image.

npixx: [for images] The next number specifies the number of pixels in x direction only.

npixy: [for images] The next number specifies the number of pixels in y direction only.

nrrefine: [for images and spectra] Specifies a maximum depth of refinement of the pixels (see Section

9.6).

fluxcons: [for images and spectra] Puts nrrefine (see above) to a large value to assue flux conservation

(see Section 9.6).

norefine: [for images and spectra] Puts nrrefine (see above) to 0 so that each pixel of the image corre-

sponds only to 1 ray. This is fast but not reliable and therefore not recommended (see Section

9.6).

nofluxcons: [for images and spectra] As norefine above.

noscat: This option makes RADMC-3D ignore the dust scattering process (though not the scattering

extinction!) in the images, spectra and Monte Carlo simulations. For images and spectra this means that no scattering Monte Carlo run has to be performed before each image ray tracing (see Section 6.6.5). This can speed up the making of images or spectra enormously. This is even more so if you make images/spectra of gas lines with LTE, LVG or ESCP methods, because if no scattering Monte Carlo needs to be made, ray-tracing can be done multi-frequency for each ray, and the populations can be calculated once in each cell, and used for all frequencies. That can speed up the line rendering enormously – of course at the cost of not including dust scattering. For lines in the infrared and submillimeter, if no large grains are present, this is usually OK, because small grains (smaller than about 1 micron) have very low scattering

albedos in the infrared and submillimeter.

ilambda or inu: [for images] Specify the index of the wavelength from the wavelength_micron.inp file

for which a ray-trace image should be made.

color: [for images] Allows you to make multiple images (each at a different wavelength) in one go.

This will make RADMC-3D read the file color_inus.inp (see Section A.17) which is a list of indices i referring to the wavelength_micron.inp file for which the images should

be made. See Section 9.4 for details.

loadcolor: [for images] Same as color.

loadlambda: [for images] Allows you to make multiple images (each at a different wavelength) in one go.

This will make RADMC-3D read the file camera_wavelength_micron.inp or camera_frequency.inp (whichever is present) to read the precise wavelength points at which you wish to make the images. In contrast to loadcolor, which only allows you to pick from the global set of wavelength used by the Monte Carlo simulation (in the file wavelength_micron.inp or frequency.inp), with the camera_wavelength_micron.inp or camera_frequency.inp files you can specify any wavelength you want, and any number

of them. See Section 9.4 for details.

sizeau:

[for images and spectra] The next number specifies the image size in model space in units of AU (=1.496E13 cm). This image size is measured from the image left to right and top to bottom. This gives always square images. This image size in au is observer distance independent. The corresponding image size in arcsec is: image size in arcsec = image size in AU / (distance in parsec).

sizepc:

[for images and spectra] Same as sizeau, but now in parsec units.

zoomau:

[for images and spectra] The next four numbers set the image window precisely by specifying the xleft, xright, ybottom, ytop of the image in units of AU. The zero point of the image (the direction of the 2-D image point located at (0.0,0.0) in image coordinates) stays the same (i.e. it aims toward the 3-D point in model space given by pointau or pointpc). In this way you can move the image window left or with or up or down without having to change the pointau or pointpc 3-D locations. Also for local perspective images it is different if you move the image window in the image plane, or if you actually change the direction in which you are looking (for images from infinity this is the same). Note that if you use this option without the truepix option RADMC-3D will always make square pixels by adapting npixx or npixy such that together with the zoomau image size you get approximately square pixels. Furthermore, if truezoom is not set, RADMC-3D will alleviate the remaining tiny deviation from square pixel shape by slightly (!) adapting the zoomau window to obtain exactly square pixels.

zoompc:

[for images and spectra] Same as zoomau, but now the four numbers are given in units of parsec.

truepix:

[for images and spectra] If with zoomau or zoompc the image window is not square then when specifying npix one gets non-square pixels. Without the truepix option RADMC-3D will adapt the npixx or npixy number, and subsequently modify the zoom window a bit such that the pixels are square. With the truepix option RADMC-3D will not change npixx nor npixy and will allow non-square pixels to form.

truezoom:

[for images and spectra] If set, RADMC-3D will always assure that the exact zoom window (specified with zoomau or zoompc) will be used, i.e. if truepix is *not* set but truezoom is set, RADMC-3D will only (!) adapt npixx or npixy to get *approximately* square pixels.

pointau:

[for images and spectra] The subsequent three numbers specify a 3-D location in model space toward which the camera is pointing for images and spectra. The (0,0) coordinate in the image plane corresponds by definition to a ray going right through this 3-D point.

pointpc:

[for images and spectra] Same as pointau but now in units of parsec.

incl:

[for images and spectra] For the case when the camera is at infinity (i.e. at a large distance so that no local perspective has to be taken into account) this inclination specifies the direction toward which the camera for images and spectra is positioned. Incl = 0 means toward the positive z-axis (in cartesian space), incl=90 means toward a position in the x-y-plane and incl=180 means toward the negative z-axis. The angle is given in degrees.

phi:

[for images and spectra] Like incl, but now the remaining angle, also given in degrees. Examples: incl=90 and phi=0 means that the observer is located at infinity toward the negative y axis; incl=90 and phi=90 means that the observer is located at infinity toward the negative x axis; incl=90 and phi=180 means that the observer is located at infinity toward the positive y axis (looking back in negative y direction). Rotation of the observer around the object around the z-axis goes in clockwise direction. The starting point of this rotation is such that for incl=0 and phi=0 the (x,y) in the image plane correspond to the (x,y) in the 3-D space, with x pointing toward the right and y pointing upward. Examples: I if we fix the position of the observer at for instance incl=0 (i.e. we look at the object from the top from the positive z-axis at infinity downward), then increasing phi means rotating the object counter-clockwise in the image plane.

posang: [for images] This rotates the camera itself around the (0,0) point in the image plane.

imageunform: Write out images in unformatted form

imageformatted: Write out images in text form (default)

circ: When spectra or SEDs are made, and when spherical coordinates are used, then this option

will make RADMC-3D use a circular arrangement of pixels. This is an emulation of RADMC (the predecessor code), and has some advantages in terms of speed over RADMC-3D sub-

pixeling method. See Section 9.10.

tracetau: [for images] If this option is set, then instead of ray-tracing a true image, the camera will

compute the optical depth at the wavelength given by e.g. inu and puts this into an image

output as if it were a true image. Can be useful for analysis of models.

tracecolumn: [for images] Like tracetau but instead of the optical depth the simple column depth is

computed in g/cm². NOTE: for now only the column depth of the dust.

tracenormal: [for images: Default] Only if you specified tracetau or tracecolumn before, and you are

in child mode, you may sometimes want to reset to normal imaging mode.

apert or useapert: [for images/spectra] Use the image-plane aperture information from the file aperture_info.inp.

noapert: [for images/spectra] Do *not* use an image-plane aperture.

nphot_therm: [for MC] The nr of photons for the thermal Monte Carlo simulation. But it is better to use

the radmc3d.inp for this (see Section A.1), because then you can see afterward with which

photon statistics the run was done.

nphot_scat: [for MC] The nr of photons for the scattering Monte Carlo simulation done before each image

(and thus also in the spectrum). But it is better to use the radmc3d.inp for this (see Section A.1), because then you can see afterward with which photon statistics the run was done.

nphot_memono: [for MC] The nr of photons for the monochromatic Monte Carlo simulation. But it is better

to use the radmc3d.inp for this (see Section A.1), because then you can see afterward with

which photon statistics the run was done.

C.3 Switching on/off of radiation processes

You can switch certain radiative processes on or off with the following command-line options (though often the radmc3d.inp file also allows this):

inclstar: [for images and spectra] Include stars in spectrum or images.

nostar: [for images and spectra] Do *not* include stars in spectrum or images. Only the circumstellar /

interstellar material is imaged as if a perfect coronograph is used.

inclline: Include line emission and extinction in the ray tracing (for images and spectra).

noline: Do not include line emission and extinction in the ray tracing (for images and spectra).

incldust: Include dust emission, extinction and (unless it is switched off) dust scattering in ray tracing

(for images and spectra).

nodust: Do not include dust emission, extinction and scattering in ray tracing (for images and spectra).

maxnrscat 0: (if dust is included) Do not include scattering in the images/spectra created by the camera.

With maxnrscat 1 you limit the scattering in the images/spectra to single-scattering. With

maxnrscat 2 to double scattering, etc. Can be useful to figure out the relative importance

of single vs multiple scattering.

inclfreefree: Include the gas continuum free-free emission (Bremsstrahlung). See chapter 8.

nofreefree: Do not include the gas continuum free-free emission.

inclgascont: Include all gas continuum processes known by RADMC-3D (right now this is only free-free,

as of 04.07.2010, but this could become more in later versions).

nogascont: Do not include the gas continuum.

C.4 Commands for child mode

Here is a list of options that are only useful for when you use RADMC-3D in child mode (Chapter 12):

child: This prevents RADMC-3D from exiting after each main command is done. Instead, RADMC-

3D will wait for further commands being given on the RADMC-3D internal command line. This can be useful if multiple actions are to be taken, and the user does not want to wait for long file input reading. It is in fact used by the viewimage.pro GUI (see chapter 14) for making images. Note that with RADMC-3D command line each command has to be on a

separate line (i.e. ending with a return).

exit or quit: In child mode you can finish the command-line mode by entering exit or quit.

enter: In child mode enter says RADMC-3D that it can start executing the last set of commands.

After it is done a new set of commands (each on a new line) can be given, again ending with

the word enter (on a separate line).

writeimage: In child mode an image can be written to the standard output (in ascii form) with this

command.

writespec: In child mode a spectrum can be written to the standard output (in ascii form) with this

command.

Appendix D

Which options are mutually incompatible?

For algorithmic reasons not all options / coordinate systems and all grids are compatible with each other. Here is an overview of which options/methods work when. Note that only options/methods for which this is a possible issue are listed.

D.1 Coordinate systems

Some coordinate systems exclude certain possibilities. Here is a list.

Option/Method:	Cart 3D	Sph 3D	Sph 2D (axisymm)	Sph 1D
Second order ray-tracing (Sec. 9.8)	yes	yes	yes	yes
Isotropic scattering	yes	yes	yes	yes
An-isotropic scattering for thermal Monte Carlo	yes	yes	yes	yes
An-isotropic scattering for monochromatic Monte Carlo	yes	yes	yes	yes
An-isotropic scattering for images and spectra	yes	yes	no	no
Gas lines	yes	yes	yes	yes
Gas lines and Doppler-shift line catching	yes	yes	no	no
Circular images (backward compatibility with RADMC)	no	yes	yes	yes

D.2 Scattering off dust grains

The inclusion of the effect of scattering off dust grains in images and spectra typically requires a separate Monte Carlo computation for each image. This is done automatically by RADMC-3D. But it means that there are some technical limitations.

Option/Method:	No scattering	Isotropic approximation	Full anisotropic scattering
Fast multi-frequency ray tracing for spectra (auto)	yes	no	no
Multiple images at different vantage point at once (Sec. 9.12)	yes	yes	yes
Local observer (Sec. 9.11)	yes	yes	no

Whereever there is "(auto)" this means that the user does not need to set/choose anything: RADMC-3D will automatically make the choice correctly. It is listed here just to make clear to the user why things may work differently under different circumstances.

D.3 Local observer mode

The local observer mode (Sect. 9.11) is a special mode for putting the observer in the near-field of the object, or even right in the middle of the object. It is not meant to be really for science use (though it can be used for it, to a certain extent), but instead for public outreach stuff. However, it is kept relatively basic, because to make this mode compatible with all the functions of RADMC-3D would require much more development and that is not worth it at

the moment. So here are the restrictions: Option/Method: Dust isotropic scattering

Dust isotropic scattering	yes
Dust an-isotropic scattering	no
Multiple images at different vantage point at once (Sec. 9.12)	yes
Second-order ray-tracing (Sec. 9.8)	yes
Doppler-catching of lines (Sec. 7.12)	no

Local observer mode

Appendix E

Acquiring opacities from the WWW

Opacities are the basic ingredients necessary for any model with RADMC-3D. The example models in this package contain example opacities, but for professional usage of RADMC-3D it may be necessary to get specific opacity data from the web. These opacity data are usually in a wide variety of formats. To enable RADMC-3D to read them usually requires a conversion into RADMC-3D-readable form (see Section A.14 for dust opacities and Section 7.4.3 for gas line opacities).

To make it easier for the user to create RADMC-3D-readable input files from opacity data downloaded from the web, we now feature a new directory <code>opac/</code> in the RADMC-3D distribution in which, for several of the most common WWW databases, we provide IDL routines for the conversion. Please read the <code>README_*</code> files in this directory and its subdirectories for details.

Appendix F

Version tracker: Development history

This version overview is very rough, and has only been started as of version 0.25.

• Version 0.25

- Second order integration, based on a vertex-based grid (as opposed to the usual cell-based grid), implemented. This gives much smoother images, and you don't see the blocky cell structure anymore in the images. It requires extra memory, though. See Section 9.8.
- The number of photons for scattering Monte Carlo (i.e. the small MC run done before each image, if dust scattering is active) can now be chosen to be smaller for when you make a spectrum instead of an image. Reason: Since you anyway integrate over the images for a spectrum, you do not need the image to "look nice", i.e. you can afford more photon noise. You can set this in radmc3d.inp by setting nphot_spec = 10000, for instance. See Section 6.6.5.

• Version 0.26

- For line transfer: Added the "doppler catching" method to the code. This prevents bad numerical artifacts in images/spectra of regions with large velocity gradients, where the doppler-shift between two neighboring cells exceeds the intrinsic line width of the material in the cell. See Section 7.12.
- NOTE: Up to, and including, version 0.26_23.02.11 this method (and for that matter any second order integration of line transfer) was not stable when strong shocks or contact discontinuities were encountered. This was because interpolation of the source function $S_{\nu} \equiv j_{\nu}/\alpha_{\nu}$ was done. Experimentation showed that interpolation of the emissivity j_{ν} is much more stable. As of version 0.26_27.02.11 this is fixed.

• Version 0.27

- For line transfer: Implemented the possibility to use a Voigt line profile instead of just a Gaussian. This was implemented by Thomas Peters, and slightly modified by CPD. It uses the Voigt approximation by Humlicek JQSRT 27, 437 (1982) as programmed by Schreier, JQSRT 48, 743 (1992). It requires a user-defined subroutine userdef_compute_lorentz_delta() that sets the value of the Lorentz profile delta. This implementation is not yet documented, and may still be subject to modification.
- Implemented the "Large Velocity Gradient" (LVG) method (also called the Sobolev method) of approximate non-LTE line transfer.
- Implemented the optically thin populations method.
- Implemented the possibility of reading linelist molecular data instead of full molecular data. Still needs testing.
- Finally implemented the positive lines_mode modes, i.e. in which the level populations are computed and stored globally before the ray-tracing. This has been latently in the code somewhat, but unfinished. Now it is implemented. The advantage is: it may be under some conditions much faster than the onthe-fly computation of the populations during the ray-tracing (the negative lines_mode modes). Also it allows you to write the populations to file, so that you can examine them. Disadvantage: It is memory hungry.

- The level subset capacilities are now limited to only the storage of the levels in the global arrays (for positive lines_mode modes), and to the lines that will appear in images/spectra. For the rest, the full set of levels are always used from now on.
- Added a directory 'opac/' which contains IDL routines for generating your own dust opacities using optical constants from the web, and for generating your own molecular/atomic input data files using data from several web pages. The data from the web are not included, but there are README files that point you to the web sites.
- Tested the "fisheye" fulldome (OMNIMAX) projection. It seems to work! Thanks to Mario Flock.
- Several small (and bigger) bugfixes
 - * Fixed bug that showed up when no dust is included.
 - * Fixed bug that caused RADMC-3D to crash when using no stars.
 - * Fixed bug that caused RADMC-3D to crash when making images at very short wavelengths with nearly zero thermal emission.
 - * Fixed bug in the AMR module when using second order integration or the doppler catching method with certain kinds of AMR-arrangements of cells.
 - * Fixed many bugs when using a "piece of a cake" model, i.e. using spherical coordinates in 3-D, but having the ϕ -grid going not over the full $0-2\pi$ range but e.g. just from 0 to $\pi/4$. It is rather rare that one really wants to use such grids (certainly not for real physical models, I presume), but for visualization of data it might be useful: for instance for visualizing a 3-D disk MHD model, which is cut open so you can see also to the midplane. Now it works. Thanks to Mario Flock.
 - * Fixed bug with the aperture mode for spectra. Thanks to Daniel Harsono.
 - * Fixed many bugs in linelist mode; now it works. Thanks to Attila Juhasz.
 - * Fixed a bug in LVG mode that caused it to fail when AMR was used. Thanks to Anika Schmiedeke.
 - * Fixed a tiny bug in idl/radmc3dfits.pro: filename was unused. Thanks to Stella Offner.
 - * Retroactive bugfix from version 0.28 (see below): LVG and AMR mode.

For details and for smaller bugfixes, read the src/Radmc_3D_LOG.txt document.

• Version 0.28

- A number of people complained that even without AMR the code requires a huge amount of memory. That is because even if no AMR is used, the cells are connected via the AMR tree. Since the AMR cells contain information about which are the neighboring cells, and each cell has 6 neighbors, and slots for 8 child-cells (which are unused in case of a regular grid) this wastes a lot of memory space. The first big improvement in version 0.28 is that, from now on, the AMR tree is only set up and used if the grid indeed has refinement. If RADMC-3D notices that the grid is regular, it will not allocate space for the AMR tree, and everywhere in the code where the cell-management is done the code will switch to regular grid mode. There is now a flag amr_tree_present that says whether the AMR tree is present or not. Throughout the code there are now if-statements to switch between using or not-using the AMR tree. This may make the code a tiny bit slower, but this is only a minor reduction of speed. But as a result it should now be much easier to load huge regular grid models into memory.
- A small (but potentially nasty) bug was found and fixed for the case when you use LVG mode on a grid with AMR-refinements. For the regular grid case (even in version 0.27, when it still used the AMR tree) this bug should not have caused problems, but perhaps you might want to check nevertheless. Note: This bug is now also retroactively fixed in version 0.27. See, as always, src/Radmc_3D_LOG.txt for details.
- Added the possibility to visualize the location (along the line of sight) of the $\tau=1$ surface (or any $\tau=\tau_s$ surface for that matter). See new Section 9.9. This can be very useful for getting a 3-D feeling for *where* certain emission comes from.

• Version 0.29

The big change in this version is that the whole stuff with the global storage of level populations has been improved. In earlier versions of RADMC-3D, either the populations of *all* levels of a molecule were stored globally (potentially requiring huge amounts of memory), or you would have to select a "subset"

of levels to store globally. This subset selection had to be done by the user ("manually", so to speak). You would have had to think a-priori which lines you wish to model, and which levels they connect, and then, in the lines.inp file you would have to select these levels by hand. That was cumbersome and prone to error. To avoid having to do this you could use "on-the-fly" calculation of populations (by making the lines_mode negative), but that sometimes caused the code to become terribly slow. Now this is dramatically improved: From now on you can forget about the "on-the-fly" calculation of populations. Just use the "normal" way by which RADMC-3D first calculates the populations and then starts the ray-tracing. The subset-selection is now done automatically by RADMC-3D, based on which wavelengths you want to make the image(s) or spectra for (see Section 7.13). Now the on-the-fly methods are no longer default and should not be used, unless absolutely necessary. Also the "manual" subset selection is no longer necessary (though still possible if absolutely desired).

- Added the subbox and sample capabilities to the level populations. See Sections 15.1 and 15.2. Note that, in order to make it easier to identify which levels were written to file, the file formats of ***_subbox.out and ***_sample.out have been slightly modified: A list of identification numbers is added before the main data. For the dust temperature and dust density this list is simply 1 2 3 4 ... (dust species 1, dust species 2, dust species 3 ...), which is trivial. For the level populations (e.g. the file levelpop_co_subbox.out and levelpop_co_sample.out for the CO molecule) this list is, however, essential when not all levels were computed (see Section 7.13). So if only level 4 and level 8 are stored, then the identification list is 4 8.
- Fixed a bug which caused the code to crash when you put a star substantially far outside of the domain and try to make an image or spectrum. Thanks, Erika Hamden, for the bug report.
- Fixed a bug that prevented the lines_mode=50 mode from working. Now it works, and we can ask RADMC-3D to read the level populations from file (rather than calculating them internally). Also a new section was added to this manual describing this option (Section 7.10).
- Added VTK output options (see chapter 16) for allowing 3-D visualization of your model setups using e.g. Paraview, a freely available visualization tool.
- Fixed a bug that occurred sometimes if a spectrum was made at inclination 90 and phi 90. Thanks Stella
 Offner for reporting this bug.

• Version 0.30

- Fixed bugs in the Henyey-Greenstein scattering mode.
- Introduced the new binary I/O feature: No more hassle with f77-unformatted records! The new binary mode is much simpler and more straightforward. This will help reducing the file sizes for large models.
 See Chapter B.

• Version 0.31

- Added the possibility, in cartesian coordinates, to "close the box", in the sense of making the domain boundaries thermal walls. Each of the 6 boundaries can be set separately, so you can also have just one thermall wall. Also the temperatures can be set separately for each of the 6 boundaries. See Section 10.8.
- Added two new coordinate systems:
 - * Cartesian 1-D plane-parallel (the only remaining active coordinate is z). The x and y dimensions are infinitely extended and have translational symmetry. The photons can, however, travel in full 3-D as always. See Section 10.6.
 - * Cartesian 2-D pencil-parallel (the two remaining active coordinate are y and z). The x dimension is infinitely extended and has translational symmetry. The photons can, however, travel in full 3-D as always.
 - * For the 1-D plane-parallel mode it is possible to include parallel beams of radiative flux impinging on the 1-D atmosphere.
 - * Attila Juhasz has improved the VTK output: Now it also supports 3-D spherical coordinates. Thanks, Attila!

• Version 0.32

This is an intermediate version in which some stuff for the near-future modus of polarization is implemented.

• Version 0.33

- Some minor technical changes to the doppler-catching integration of lines (storing the upper and lower level population instead of the inubase and anubase variables).
- Added the classical escape probability to the LVG mode (see Section 7.6 for details).
- Sped up the filling of the matrix of the statistical equilibrium equation.
- Vastly improved the LVG (and esc prob) method: Instead of the simple "lambda iteration style" iteration as it was before, the A_{ik} is now multiplied with β_{ik} (the escape probability of the line i-ik) and the J_{ik} is replaced by $J_{ik}^{\rm background}$. This means that the solution is almost instant, requiring only 2 or 3 iterations.

• Version 0.34

Implemented the Modified Random Walk method, based on Min, Dullemond, Dominik, de Koter & Hovenier (2009) A&A 497, 155, and simplified by Robitaille (2010) A&A 520, 70. But beware: Still in the testing phase! By default it is switched off.

Version 0.35

- Implemented polarized scattering off randomly oriented particles. But beware: Still in the testing phase!
- Fixed a bug in the modified random walk method (thanks to Daniel Harsono for spotting the problem and thanks to Attila Juhasz for finding the fix!)
- Fixed two bugs that made it impossible to use second order integration with axially symmetric spherical coordinates and/or a finite-size star (thanks to Rolf Kuiper for reporting the bug).
- Added the "sloppy" command line option to spectrum and image making in spherical coordinates. This was necessary because RADMC-3D is always trying to make 100% sure that all cells are picked up by the subpixels. In spherical coordinates these cells can be extremely non-cubic (they can be extremely flat or needle-like), which means that under some projections RADMC-3D feels obliged to do extreme subpixeling, which can make image- and spectrum-making extremely slow. By adding the sloppy keyword on the command line, RADMC-3D will limit it's pubpixeling which could speed up the calculation very much (but of course at your own risk!).

• Version 0.38

- Implemented OpenMP parallellization of the thermal Monte Carlo (by Adriana Pohl). Still beta-version.
- Bugfix in the mean intensity computation (mcmono) mode (thanks to Gwendoline Stephan).
- Bugfix in the mean intensity computation (mcmono) mode (thanks to Seokho Lee).
- Major bugfix in aperture mode (thanks to Søren Frimann).
- Unformatted image format is from now on C-style binary instead of F77-style unformatted.
- The viewimage tool is now ported to Qt by Farzin Sereshti, meaning that you can now use viewimage without having an IDL license. Viewimage is a very powerful tool to interactively make and view images of your model at different wavelengths and viewing angles. It can be found in the directory viewimage_QT_GUI/.
- A Python package for RADMC-3D was developed by Attila Juhasz. It is included as of RADMC-3D version 0.38 in the directory python/.

Version 0.39

- Polarization mode is incompatible with mirror mode (in spherical coordinates). An error message is now included to catch this.
- Minor bugfix in pick_randomfreq_db() (thanks to Seokho Lee).
- Optimization of the OpenMP parallellization and extension of the OpenMP parallellization to the Scattering Monte Carlo computation (both by Farzin Sereshti).

- Bugfix in amrray_module.f90: Sometimes one got "Photon outside of cell" error due to a numerical precision round-off error. This bug is now (mostly?) fixed.
- Bugfix in sources_module.f90: When using second order integration (or doppler catching) for line transfer in spherical coordinates, the line doppler shift was not transformed to spherical coordinates. This is now fixed.
- Several bugfixes in the modified random walk method by John Ramsey. The method crashed for extreme optical depth problems due to out-of-cell events. Still not 100% perfect, but better.
- John Ramsey also proposed two small fixes to the Planck function routines so that the events of overflow are caught. Note: This might change the results (in a tiny way: at the machine precision level) to the extent that a model run by an old version might not yield the same values to machine precision, but the differences should not matter in any meaningful way.

Version 0.40

- The RADMC-3D package is now "officially" converting from IDL to Python wrappers. The Python modules were already there since a long time (thanks to Attila Juhasz!). But as of version 0.40 we will no longer update/maintain the IDL scripts (though they remain there and should remain working), and instead use python as the main setup and analysis tools for RADMC-3D. The full conversion will still take some time, but should be finished by the end of version 0.40. Attila Juhasz has made a nice webpage for his python routines:

http://www.ast.cam.ac.uk/~juhasz/radmc3dPyDoc/index.html

- Under some circumstances the simple 2x2 pixel plus sub-pixeling method for making spectra (default method) can be dangerous. For some grid geometries this can lead to under-resolving of the images that are integrated to obtain the flux, leading to a too low flux. So as of now 15.09.2016 the spectra and SEDs are always by default made with 100x100 images (and sub-pixeling of course). One can set the number of pixels with npix. So if you do radmc3d sed nostar npix 2 you get the original behavior again.
- Bugfix in montecarlo_module.f90: The internal heat source method (which is still being tested) had
 a bug. The bug manifested itself for optically thin cells with non-negligible internal heat production.
 The energy was not immediately added to the cell. It only got added upon re-absorption of that photon
 package. Now this is fixed.
- I now added some documentation for the heat source method, which is useful for e.g. disk viscous accretion heating.
- Bugfix in montecarlo_module.f90: When using mirror symmetry in spherical coordinates in the θ -coordinate (i.e. modeling only the upper part of the disk and letting RADMC-3D assume that the lower part is identical), the distributed source luminosity was computed only for the top quadrant, and wasn't multiplied by 2. For most applications this does not cause problems, but for the heat source (see above), for continuous stellar sources and for the thermal origin of the isotropic scattering luminosity (for non-isotropic scattering, mirror symmetry was not allowed anyway), this could lead to a factor of 2 underestimation (only if mirror symmetry was used, i.e. if the θ coordinate was going only up to $\pi/2$). This is now fixed. To test if the fix works one can simply make the same model again, but now without using mirror symmetry (and thus using twice as many cells in θ , to cover both the upper and lower half of the object). This should yield (apart from some Monte Carlo noise) the same results.
- Improved the stability of the Modified Random Walk (MRW) method a bit further.
- Bug fix: scattering mode 3 (tabulated phase function, but not full polarization) had a bug which caused images of scattered light to be multiplied by some arbitrary number. Reason: as a phase function it returned Z_{11} instead of $4\pi Z_{11}/\kappa_{\rm scat}$. Most people use either isotropic scattering (scattering mode 1), or Henyey-Greenstein (scattering mode 2) or full polarization (scattering mode 5), all of which are ok. At any rate: the problem is now fixed, so scattering mode 3 should now also work.

• Version 0.41

 Implemented a first testing version of the aligned grains: only polarized thermal emission so far. Still very much a testing version.

- Implemented a method to also allow full Stokes vector polarized scattering in the 2-D axisymmetric mode in spherical coordinates. Until now the full scattering mode (scattering mode 5) was only possible in full 3-D. Note however that anisotropic scattering in 2-D axisymmetric models requires scattering mode 5, which is the full scattering mode. It is still not possible to use intermediate scattering modes (like henyey-greenstein or any scattering mode between 2 and 4) in 2-D axisymmetry. But those intermediate modes are anyway more for testing than for real models, so that should be ok.
- Bugfixes to the OpenMP stuff. In particular the OpenMP parallellization of the scattering MC crashed.
 This is now fixed. In general the OpenMP stuff was a bit cleaned up.
- Bugfix in thermal Monte Carlo with full polarization mode: needed to reset the photon package after each thermal absorption/re-emission event. Usually the effect is subtle, but had to be fixed.
- Bugfix in reading the scattering_angular_grid.inp: the theta angles should be converted into radian. But this file was not officially offered before anyway.
- Attila Juhasz has made a large improvement of his python package for RADMC-3D. See the python/directory. This is version 0.29 of his package. This package now also supports reading and writing AMR grids.