- Shipment
- Others

Your selection can decide the value help lists of **Event Code**, **IDOC Segment**, and **IDOC Field**.

Application Object Type

This is a mandatory field. Your entry specifies the application object type in the ERP system for IDOC Integration.

Tracked Process / Events table

This includes tracked process event and event types. You are free to input your own value or use value help to define IDOC and ERP Event Code. Event code must be unique in a model.

User Model Fields table

There are **Field** column, **IDOC Segment** column and **IDOC Field** column in the tree table. You are free to input your own values or use value help to define related properties according to your selected **ERP Object Type**.

To Set up IDOC Integration

Context

To set up the IDOC integration, do the following:

Procedure

1. In the **IDOC Integration** tab, select a tracked process.
2. Set the **Integration Switch** to **ON** for IDOC integration.
3. Select an **ERP Object Type**.
4. Fill in the **Application Object Type**.
5. For the **IDOC** column in the **Tracked Process / Events** table:

   If your ERP object type value is:

   - "Others", then use the value help or input a value manually
   - Otherwise, the corresponding is automatically filled in for you.
6. For the **Event Code** column in the **Tracked Process / Events** table, use value help or input a value manually.
7. For the **IDOC Segment** and **IDOC Field** columns in the **User Model Fields** table, use value help or manually enter your own values.

Visibility Provider Integration

Visibility Provider Integration is used for mapping visibility provider generic interface with a tracked process and its actual events. In the **Visibility Provider Integration** tab, you can select a specific tracked process to display or edit related properties.

On the right of the tracked process selection is an **Integration Switch** for this tracked process. The default state of this switch is **OFF**. You can change the state in the edit mode. When the switch state is:

- **OFF**, the related configuration view is not visible. These mapping properties are not checked.
- **ON**, you can see below the **Tracking Indicator**, the **Generate Event for Tracking Request Failure** switch, a **Tracked Process / Events** table, and a **User Model Fields** table.

When saving a draft model, these selected and filled items are checked before saving or deploying it.

Generate Event for Tracking Request Failure switch

This switch allows you to automatically generate an event called “GTT Tracking Request Error Event” when your tracking request is rejected by your business partner. The event contains an error message that your business partner sent to you. You can use the information for troubleshooting.

The event will be displayed in:

- the Check Processes and Events app’s **Other Events** table, which contains a core model field **Error Message** to display the error.
- the fulfillment tracking apps’ **Events** table, which contains a field **Event Reason Text** to display the error. You can also view this error in the **Error Message** field of the **Event Details** page. For more, see *Guide for Transportation Planners*.

Tracked Process / Events table

In this table, there are tracked process events and event types. For event types, you can use value help to define the **LBN Event Type**.

To see the full list of supported LBN event types, see Event Code Descriptions in the *Code Lists* document.

Standard/User Model Fields table

For the tracked process event, the table includes **LBN Tracking Fields** column and the tracked process' **Fields** column. You can select the tracked process field. You cannot input values freely in the edit mode.

For the event type events, the table includes the event's user-defined **Field** column and **LBN Tracking Fields** column. You can select the LBN tracking field. You cannot input values freely in the edit mode.

ℹ Note

In the standard model “gttft1”, you can:

- change the mapping of standard event types with LBN event types. But if you do so, you will no longer benefit from future upgrades of the standard model.
- map user-defined event types with LBN event types. But if you do so, you will no longer benefit from future upgrades of the standard model.
- change the mapping of the tracked process’s standard fields with the LBN tracking fields. But if you do so, you will no longer benefit from future upgrades of the standard field mapping of this tracked process.

If you change the standard field mapping of the “Shipment” and “TrackingUnit” tracked processes, see Reference: Standard Field Mapping of "Shipment" and "TrackingUnit" Tracked Processes for the upgrades, and manually update the field mapping accordingly.

Set up Visibility Provider Integration

Context

To set up the visibility provider integration, do the following:

Procedure

1. In the **Visibility Provider Integration** tab, select a tracked process.
2. Set the **Integration Switch** to **ON** for visibility provider integration.
3. Use value help to fill in the **LBN Event Type** for actual events.
4. Use value help to fill in the **Field** or **LBN Tracking Fields**.

Reference: Standard Field Mapping of "Shipment" and "TrackingUnit" Tracked Processes

"Shipment" Tracked Process

LBN Tracking Fields	Field
Carrier LBN ID	`serviceAgentLbnId`
Ordering Party Name	
Consignee Name	
Quantity of Total Pieces	
Quantity of Total Pieces Unit	
Transportation Mode	`transportationMode`
Transportation Means Standard Code	`transportMeans`
Transportation Means Tracked Objects	`trackedObjects`
• ID	`idType`
• Value	`value`
Dangerous Goods Indicator	`dangerousGoods`
Incoterm	`incoterms`
Incoterm Location	`incotermLocation`
Cargo Gross Weight	
Cargo Gross Weight Unit	
Cargo Gross Volume	

LBN Tracking Fields	Field
Cargo Gross Volume Unit	
Carrier Reference Document	`carrierRefDocuments`
• Document Type	`docType`
• Document	`docId`
Shipping Type	`shippingType`
Document Reference	`shipperRefDocuments`
• Document Type	`docType`
• Document	`docId`
Total Number of Stops	
Total Number of Loading Locations	
Total Number of UnLoading Locations	
Stops	`stops`
• Stop ID	`stopId`
• Ordinal No	`ordinalNo`
• Location Object Type	`locationType`
• Location ID	`locationId`
• Location Alternative Key	`locationAltKey`
Stages	
• Stage ID	
• Loading Stop ID	
• Unloading Stop ID	

"TrackingUnit" Tracked Process

LBN Tracking Fields	Field
Carrier LBN ID	`serviceAgentLbnId`
Ordering Party Name	
Consignee Name	
Quantity of Total Pieces	
Quantity of Total Pieces Unit	
Transportation Mode	`transportationMode`
Transportation Means Standard Code	
Transportation Means Tracked Objects	`trackedObjects`
• ID	`idType`
• Value	`value`
Dangerous Goods Indicator	
Incoterm	
Incoterm Location	
Cargo Gross Weight	
Cargo Gross Weight Unit	
Cargo Gross Volume	
Cargo Gross Volume Unit	
Carrier Reference Document	`carrierRefDocuments`
• Document Type	`docType`
• Document	`docId`
Shipping Type	`shippingType`
Document Reference	
• Document Type	
• Document	
Total Number of Stops	
Total Number of Loading Locations	
Total Number of UnLoading Locations	

LBN Tracking Fields	Field
Stops	`stops`
• Stop ID	`stopId`
• Ordinal No	`ordinalNo`
• Location Object Type	`locationType`
• Location ID	`locationId`
• Location Alternative Key	`locationAltKey`
Stages	
• Stage ID	
• Loading Stop ID	
• Unloading Stop ID	

Planned Event Extension

Planned event extension allows you to define your own planned event extension fields. These fields are applied to all the planned events in the model. You can create/edit/delete user defined planned event extension fields in the **Planned Event Extension** tab. You can have at most 200 planned event extension fields in a model.

Create Planned Event Extension Fields

Context

To create a planned event extension field, do the following:

Procedure

1. Click the **Create** button above the **User Model Fields** table.
2. Fill in the following:
    - Name: should be unique in the planned event extension
    - Label
    - Type: supports **String**, **UUID**, **Boolean**, **Integer**, **Decimal**, **Date**, and **Timestamp**

- Visible
- Readable
- Writable

For more on these attributes, see the relevant information in Create User Model Field.

3. Click **OK** to create this field. The model detail page is changed to the edit mode.
4. Save your model configuration.

Edit Planned Event Extension Fields

Context

You can edit the name, label, type, and readable or writable attributes of a planned event extension field.

Procedure

1. Select the field that needs to be changed in the table.
2. Click the **Edit** button above the table. Or click the pencil icon at the end of the field that needs to be changed in the table.
3. Edit in the pop-up dialog, then click the **OK** button to save changes. And the **Model Details** page is changed to the edit mode.
4. Save your model configuration.

Delete Planned Event Extension Field

Context

To delete one or more planned event extension user model field, do the following:

Procedure

1. Select the fields that you want to delete. Multiple selection is supported.
2. Click the **Delete** button above the **User Model Fields** table.
3. The **To Be Deleted Objects** dialog pops up to ask you if you want to delete the selected fields and all the data in the places where these fields are used.
4. Click **OK**. Fields you selected are removed immediately, and the **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Event to Action (Business Rules)

Under the Event to Action tab, you can add a script incorporating logic (business rules) to your model.

For more information about the script, see Appendix: Event to Action Script.

In the standard model "gttft1", the script is divided into four sections: **Standard Declaration**, **User Script Before Standard Script**, **Standard Script**, and **User Script After Standard Script**. Standard sections are not editable. You can only edit the user script

sections. In the display mode, you can click the eyeglass icon to view the script in a pop-up dialog.

Add a Script to Your Model

Context

To add a script to your model, do the following.

Procedure

1. On the **Model Details** page, click the **Event to Action** tab.
2. You can click **Help** to open the documentation and find information on writing scripts.
3. Click the **Edit** button on the top right. Write or paste your script in the window. You can click the pencil icon to edit the script in a pop-up dialog.
4. Click **Validate Code** to check your script for errors.
    - If there are no errors, you get a success message.
    - If an error is found, click **Open Validation Details** to see the line number and type of error.
    - Once you have corrected the error, click **Validate Code** again.
5. When you have finished your script, you have several options:
    - **Cancel**: you can choose whether to discard all changes and return to the previous script, or not.
    - **Save**: to save your script in the model.

Translation

In the MM app, the following model meta-data fields support multilingual translation:

- Description of the model
- Label of user model field in Planned Event Extension, Tracked Process, Field Type and Event Type
- Description of tracked process
- Description of event type
- Name of code in code list

Supported Language

English (US) is the default language and the default fallback language.

To see the full list of supported languages, see the section Product Availability in the *Administration Guide for Solution Owners*.

Translation Dialog

Context

The translation dialog allows you to manage the translation of different languages.

Procedure

1. On the **Model Details** page, click the **Edit** button on the top right.
2. Click the **Tracked Process** tab.
3. To maintain a translation for a tracked process description:
    a. Select a tracked process from the list.
    b. Click the **Edit** button.
    c. In the pop-up dialog,
        i. If a translation of the description exists in the current logon language, it is displayed in the **Description Input Control**.
        ii. If a translation of description does not exist in the logon language but a fallback language exits, the description in the fallback language is shown as a placeholder in **Description Input Control**.
    d. When editing is complete, click **Save**.
4. To maintain translations for both a tracked process description and fields' label in a tracked process:
    a. Click **Translate** button above the **User Model Fields** table.
    b. In the pop-up dialog, a translation of each field is displayed in one line. The first line is a description of this tracked process. Subsequent lines are user fields' label in this tracked process. In the filter, you can select which language needs to be modified.

       For example, if you select German in the **Language Drop Down List**, a new column is added to the table below.
    c. Add translation in the column of special line.
    d. Click **OK** to save your changes.

Deployed Models

When a model is deployed, two additional views become available:

- **Runtime** View: displays deployment information such as API details and deployment history log.
- **Deployed** View: displays the deployed version of the model details.

Runtime View

When a model is deployed, you can see the runtime information of the deployed model. The **Runtime** view contains the following information:

- Write Service API
- Read Service API

Write Service

In the **Runtime** view, select the **Write Service** tab to see the Write Service API details.

The Write Service section is displayed in the following order:

- Tracked process types appear in alphabetical order. And in each tracked process type, the tracked process event is displayed first and followed by user-defined events in alphabetical order.
- Core events appear at the end in alphabetical order.

The **Write Service** section contains the following information and functions that are offered to consume the Write Service API:

- **API Endpoint**: allows you to test the API against the data available in the tenant account.
- **Resources**: a list of the resources available for the API.
- **API operations**: HTTP POST method can be used to all these resources.
- **Try it out**: consume and test the selected API. You can view the response of the API in JSON format in the Response body section.
- **Schemas**: The schema for the resources.

Trying Out API

Context

To try out an API, do the following:

Procedure

1. In the **Servers** drop-down, you can see the API endpoint for the **Try it out** function.
2. In the API documentation, choose the required resource and its HTTP method. To test the API, click **Try it out**.
3. Enter the request payload in JSON format in the **Request** body text box.
4. Click **Execute** to execute the request.
5. In the server response section, it shows the response with the endpoint.

Read Service

Please see Read Service in *API Documentation*.

Deployed View

After a model has been deployed, you can see its deployed version in the **Deployed** view.

On the **Model Details** page, click the **Deployed** button on the top right.

The **Deployed** view has the same layout and content as the **Draft** view. The difference is the deployed view is read-only because you cannot modify the content of the deployed version of the model.