

Implementation Guide – PUBLIC
Version 2.0 (2026-03-14)

How to Integrate with SAP Business Network Global Track and Trace (ANSI X12)

Implementation guide for B2B EDI ANSI X12 integration

THE BEST RUN SAP

TABLE OF CONTENTS

INTRODUCTION 3
PREREQUISITES 3
PROCESS DESCRIPTION 4
STEP 1: ANSI X12 213 (OUTBOUND) 5
STEP 2: ANSI X12 214/315 (INBOUND) WITH SFTP PULLING 9
OPERATIONAL MONITORING 12

www.sap.com/contactsap

© 2021 SAP SE or an SAP affiliate company. All rights reserved.
No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company.

The information contained herein may be changed without prior notice. Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

In particular, SAP SE or its affiliated companies have no obligation to pursue any course of business outlined in this document or any related presentation, or to develop or release any functionality mentioned therein. This document, or any related presentation, and SAP SE's or its affiliated companies' strategy and possible future developments, products, and/or platform directions and functionality are all subject to change and may be changed by SAP SE or its affiliated companies at any time for any reason without notice. The information in this document is not a commitment, promise, or legal obligation to deliver any material, code, or functionality. All forward-looking statements are subject to various risks and uncertainties that could cause actual results to differ materially from expectations. Readers are cautioned not to place undue reliance on these forward-looking statements, and they should not be relied upon in making purchasing decisions.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies. See www.sap.com/trademark for additional trademark information and notices.

THE BEST RUN SAP®

INTRODUCTION

Note: As of today, SAP Business Network Global Track and Trace (GTT) supports the following B2B standards and corresponding messages:

EDI/B2B Message Standard	Message Type	Version	Description
EDI	ANSI 213	V4010	Motor Carrier Shipment Status Inquiry
EDI	ANSI 214	V4010	Shipment Status
EDI	ANSI 315	V4010	Status Details (Ocean)

To set up ANSI X12 integration, an SFTP connection needs to be configured in the *System Connections* app. This implementation guide describes in detail what you need to do.


Note: All activities mentioned in this guide have to be done in both the test and productive environments.

PREREQUISITES

To set up EDI integration with SAP Business Network Global Track and Trace, you must meet the following requirements:

- Data contributor tenant is available in the test and productive environments. For more information about the process of registering SAP Business Network for Logistics, activating your account, logging on, and adding users, see the Activate Your Account guide.
- In case your SFTP server uses IP filtering, you need to add specific IP ranges to the allow list based on the data center you're onboarded to. Otherwise, the Cloud Integration tenants cannot connect to your SFTP server. For more information, see Regions and Hosts Available for the Connectivity Platform | SAP Help Portal.
- It is expected that data contributors set up an SFTP server on their side for information exchange. Data contributors have to set up the SFTP connection once and solution owners can use the same SFTP connection for communication. Data contributors must enter a base64-encoded string of their SFTP server in the *Known Host Key* field of the *System Connections* app. See also Specifying the Authentication Details and Base URLs for Your System's Endpoints in the guide *Application Help*.


  The following diagram outlines the SFTP communication between the involved parties:



- Ensure that you use different folders for Test and Prod on your SFTP server.


PROCESS DESCRIPTION

The process flow below illustrates a sequence of events for exchanging ANSI messages which are supported by SAP Business Network Global Track and Trace. The supported message types are also listed in the *Introduction* section.




STEP 1: ANSI X12 213 (OUTBOUND)

On the *Manage Network* tab of your SAP Fiori launchpad, select the *System Connections* app.




Choose *Manage Details* in the upper right corner.



Under the *Communication Details* tab, choose *Add* and select the SFTP option from the dropdown menu.



Enter the following data in the *Add EDI Communication* window:



For more information, see Specifying the Authentication Details and Base URLs for Your System's Endpoints.

Note: After fetching the files from the directory configured above, SAP Business Network for Logistics creates by default a ".archive" folder under this directory to which the fetched files will be moved.

Hint: The file name can consist of particular placeholders that you replace when creating the file name and fixed parts. For example, LBN_%DOCUMENT_ID%_%TIMESTAMP%.edi


Available placeholders:

- %DOCUMENT_ID%
- %MESSAGE_TYPE%
- %SHIPPER_LBN_ID%
- %TIMESTAMP%

Under the *Authentication Details* tab, choose *Add* and select the BASIC option from the dropdown menu.



Enter the following data in the *New Basic Authentication Details* window:




Go back to the entry page of the *System Connections* app and create outbound connections for the following services and operations:

Service	Operation	Corresponding ANSI Message
Shipment Tracking All service	Put order for tracking	ANSI 213


This will look as follows:



To do so, create a new service:




Enter the following data for the new service:



Repeat these steps for each of the following operations for all Services mentioned in the table above.

STEP 2: ANSI X12 214/315 (INBOUND) WITH SFTP PULLING


On the *Manage Network* tab of your SAP Fiori launchpad, select the *System Connections* app.




To enable communication from the data contributor to the solution owner for inbound messages (ANSI 214), you must turn on the *Enable Inbound Connections* toggle in Connection Settings.

Proceed as follows:


1. Choose *Connection Settings* in the upper-right corner.
2. Turn on the *Enable Inbound Connections* toggle.
3. Select the *Integration Platform* as *Multi-Cloud.*




Choose *Manage Details* in the upper-right corner.



Under the *Communication Details* tab, choose *Add* and select the SFTP option from the dropdown menu.



Enter the following data in the *Add EDI Communication* window:



For more information, see Specifying the Authentication Details and Base URLs for Your System's Endpoints.

Note:

After fetching the files from the directory configured above, SAP Business Network for Logistics will delete them.