4.6 LX — Assigned Number

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
214 — Transportation Carrier Shipment Status Message	1 .. 1				
┣ **0200** — Loop 0200	1 .. 999999		130		
┃ ┣ **LX** — Assigned Number	1 .. 1		130		
┃ ┃ ┗ **554** — Assigned Number	1 .. 1	Integer	01	1 .. 6	

Documentation

Definition To reference a line number in a transaction set

Properties

Identifier LX

Name Assigned Number

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 130

Level 3

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
554 Assigned Number	Number assigned for differentiation within a transaction set	**Cardinality** min: 1 max: 1 **Primitive Type** Integer **Length** min: 1 max: 6 **Fraction Digits** 0 **Total Digits** 6 **External Category** Simple Data Element **Data Type** N0 **Position** 01

4.7 0205 — Loop 0205

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
214 — Transportation Carrier Shipment Status Message	1 .. 1				
├ **0200** — Loop 0200	1 .. 999999		130		
│ ├ **0205** — Loop 0205	0 .. 10		140		
│ │ └ **AT7** — Shipment Status Details	1 .. 1		140		

Properties

Identifier 0205

Name Loop 0205

Cardinality min: 0 max: 10

Syntax Type Related

External Category Loop

Position 140

Level 3

4.8 AT7 — Shipment Status Details

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
214 — Transportation Carrier Shipment Status Message	1 .. 1				
├ **0200** — Loop 0200	1 .. 999999		130		
│ ├ **0205** — Loop 0205	0 .. 10		140		
│ │ └ **AT7** — Shipment Status Details	1 .. 1		140		
│ │ ├ **1650** — Shipment Status Code	1 .. 1	Token	01	2 .. 2	1650
│ │ ├ **1651** — Shipment Status or Appointment Reason Code	0 .. 1	Token	02	2 .. 2	1651
│ │ ├ **1652** — Shipment Appointment Status Code	0 .. 1	Token	03	2 .. 2	1652
│ │ ├ **373** — Date	1 .. 1	Date	05	8 .. 8	
│ │ ├ **337** — Time	1 .. 1	Time	06	4 .. 8	
│ │ └ **623** — Time Code	1 .. 1	Token	07	2 .. 2	623

Documentation

Definition To specify the status of a shipment, the reason for that status, the date and time of the status and the date and time of any appointments scheduled.

Properties

Identifier AT7

Name Shipment Status Details

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 140

Level 4

Notes

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
1650 Shipment Status Code	Code indicating the status of a shipment **Usage 1** Status Code AG (Estimated Delivery) is used to provide estimated Date/Time for Status X1 (Arrived at Delivery Location). **Usage 2** Status Code SD (Shipment Delayed) is used to report a Delay for Statuses like CP (Completed Loading at Pick-up Location), X1 (Arrived at Delivery Location) and X3 (Arrived at Pick-up Location). If Status Code SD is used, then Field 1652 (AT7-03) is required. For example you can use AT7*SD*BC*X1**Date*Time*TimeCode~ to report a Delay at Arrival due to missing Documents. **Constraint 1** If any not supported code is sent, the whole message will be ignored. **Tech. Info. 1** Please find the mapping from EDI to LBN codelists - Event Status Code Descriptions. AF -> DEPARTURE AG -> GEOLOC D1 -> UNLOAD_END	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Codelist Id** 1650 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

	X1 -> ARRIV_DEST X3 -> ARRIV_DEST X6 -> OUT_FOR_DELIVERY CP -> LOAD_END SD -> DELAYED LBN Event Status Code Descriptions for reference - https://help.sap.com/docs/business-network-freight-collaboration/code-lists/event-code-descriptions **Selected Values** **Code** X1 **Name** Arrived at Delivery Location **Code** X3 **Name** Arrived at Pick-up Location **Code** AF **Name** Carrier Departed Pick-up Location with Shipment **Code** AG **Name** Estimated Delivery **Code** X6 **Name** En Route to Delivery Location **Code** D1 **Name** Completed Unloading at Delivery Location **Code** CP **Name** Completed Loading at Pick-up Location **Code** SD **Name** Shipment Delayed	
1651 Shipment Status or Appointment Reason Code	Code indicating the reason a shipment status or appointment reason was transmitted **Tech. Info. 1** Please find the mapping from EDI to LBN codelists - Event Reason Code Descriptions. BE -> LBN_TRAFFIC AI -> LBN_BRKDWN C1, C6, C7, P2 -> LBN_WTGLOC B8 -> CLEANLINESS_NOT_FIT BC -> DOCUMENTMISSING AF -> ACCIDENT AO -> FORCEOFNATURE A2 -> INCORRECT AQ, C9, D2, T3, T5, T6 -> NOTAVAILABLE AK -> PACKAGINDAMAGED C5 -> STRIKE Others -> LBN_OTHERS LBN Event Reason Code Descriptions for reference - https://help.sap.com/docs/business-network-freight-collaboration/code-lists/event-reason-code-descriptions **Selected Values** **Code** BE **Name** Road Conditions **Code** AI **Name** Mechanical Breakdown **Code** BC **Name** Missing Documents **Code** C1 **Name** Waiting for Customer Pick-up **Code** C6 **Name** Waiting Shipping Instructions **Code** C7 **Name** Waiting for Customer Specified Carrier **Code** P2 **Name** Waiting Inspection **Code** B8 **Name** Improper Unloading Facility or Equipment **Code** AF **Name** Accident **Code** AO **Name** Weather or Natural Disaster Related **Code** A2 **Name** Incorrect Address **Code** AQ **Name** Recipient Unavailable - Delivery Delayed **Code** C9 **Name** Cash Not Available From Consignee **Code** D2 **Name** Driver Not Available **Code** T3 **Name** Trailer not Available **Code** T5 **Name** Trailer Class Not Available **Code** T6 **Name** Trailer Volume Not Available **Code** AK **Name** Damaged, Rewrapped in Hub	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 2 **max:** 2 **External Category** Simple Data Element **Data Type** ID **Position** 02 **Codelist Id** 1651 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

	Code C5 **Name** Customer Strike	
1652 Shipment Appointment Status Code	Code indicating the status of an appointment to pick-up or deliver a shipment **Usage 1** Used as reference if Shipment Status Code (AT7-01) is SD. Please provide one of these statuses X1, X3, AF, X6, D1 or CP. **Selected Values** All Values in Codelist	**Cardinality** min: 0 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 03 **Codelist Id** 1652 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
373 Date	Date expressed as CCYYMMDD	**Cardinality** min: 1 max: 1 **Primitive Type** Date **Length** min: 8 max: 8 **Date Time Format** CCYYMMDD **External Category** Simple Data Element **Data Type** DT **Position** 05
337 Time	Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)	**Cardinality** min: 1 max: 1 **Primitive Type** Time **Length** min: 4 max: 8 **Date Time Format** hhmm[ss[f[f]]] **External Category** Simple Data Element **Data Type** TM **Position** 06
623 Time Code	Code identifying the time. In accordance with International Standards Organization standard 8601, time can be specified by a + or - and an indication in hours in relation to Universal Time Coordinate (UTC) time; since + is a restricted character, + and - are substituted by P and M in the codes that follow **Selected Values** **Code** UT **Name** Universal Time Coordinate **Code** 01 **Name** Equivalent to ISO P01 **Code** 02 **Name** Equivalent to ISO P02 **Code** 03 **Name** Equivalent to ISO P03 **Code** 04 **Name** Equivalent to ISO P04 **Code** 05 **Name** Equivalent to ISO P05 **Code** 06 **Name** Equivalent to ISO P06 **Code** 07 **Name** Equivalent to ISO P07 **Code** 08 **Name** Equivalent to ISO P08 **Code** 09 **Name** Equivalent to ISO P09 **Code** 10 **Name** Equivalent to ISO P10 **Code** 11 **Name** Equivalent to ISO P11 **Code** 12 **Name** Equivalent to ISO P12 **Code** 13 **Name** Equivalent to ISO M12 **Code** 14 **Name** Equivalent to ISO M11 **Code** 15 **Name** Equivalent to ISO M10 **Code** 16 **Name** Equivalent to ISO M09 **Code** 17 **Name** Equivalent to ISO M08 **Code** 18 **Name** Equivalent to ISO M07 **Code** 19 **Name** Equivalent to ISO M06 **Code** 20 **Name** Equivalent to ISO M05 **Code** 21 **Name** Equivalent to ISO M04 **Code** 22 **Name** Equivalent to ISO M03 **Code** 23 **Name** Equivalent to ISO M02 **Code** 24 **Name** Equivalent to ISO M01 **Code** AS **Name** Alaska Standard Time **Code** AD **Name** Alaska Daylight Time **Code** CD **Name** Central Daylight Time **Code** CS **Name** Central Standard Time **Code** ED **Name** Eastern Daylight Time **Code** ES **Name** Eastern Standard Time **Code** MD **Name** Mountain Daylight Time **Code** MS **Name** Mountain Standard Time **Code** PD **Name** Pacific Daylight Time	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 07 **Codelist Id** 623 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

	Code PS **Name** Pacific Standard Time	

4.9 MS1 — Equipment, Shipment, or Real Property Location

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
214 — Transportation Carrier Shipment Status Message	1 .. 1				
├ **0200** — Loop 0200	1 .. 999999		130		
│ ├ **0205** — Loop 0205	0 .. 10		140		
│ │ └ **MS1** — Equipment, Shipment, or Real Property Location	0 .. 1		143		
│ │ ├ **19** — City Name	0 .. 1	String	01	2 .. 30	
│ │ ├ **156** — State or Province Code	0 .. 1	Token	02	2 .. 2	
│ │ ├ **26** — Country Code	0 .. 1	Token	03	2 .. 3	ISO_3166-1
│ │ ├ **1654** — Longitude Code	0 .. 1	Token	04	7 .. 7	
│ │ ├ **1655** — Latitude Code	0 .. 1	Token	05	7 .. 7	
│ │ ├ **1280** — Direction Identifier Code	0 .. 1	Token	06	1 .. 1	1280
│ │ └ **1280** — Direction Identifier Code	0 .. 1	Token	07	1 .. 1	1280

Documentation

Definition To specify the location of a piece of equipment, a shipment, or real property in terms of city and state or longitude and latitude

Properties

Identifier MS1

Name Equipment, Shipment, or Real Property Location

Cardinality min: 0 max: 1

Syntax Type Related

External Category Segment

Position 143

Level 4

Notes

Usage 1 MS101: Free-form text for city name.

Usage 2 MS102: Code (Standard State Province) as defined by appropriate government agency.

Usage 3 MS103: Code identifying the country.

Usage 4 MS104: Code indicating the longitude in decimal degrees.

Usage 5 MS105: Code indicating the latitude in decimal degrees.

Usage 6 MS106: Code identifying longitude direction (only be ‘E’ or ‘W’).

Usage 7 MS107: Code identifying latitude direction (only be ‘N’ or ‘S’).

Constraint 1 If MS101 is present, then at least one of MS102 or MS103 is required.

Constraint 2 Only one of MS101 or MS104 may be present.

Constraint 3 If MS102 is present, then MS101 is required.

Constraint 4 If MS103 is present, then MS101 is required.

Constraint 5 If either MS104 or MS105 is present, then the other is required.

Constraint 6 If MS106 is present, then MS104 is required.

Constraint 7 If MS107 is present, then MS105 is required.

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
19	Free-form text for city name	**Cardinality** **min:** 0 **max:** 1

City Name		**Primitive Type** String **Length** **min:** 2 **max:** 30 **External Category** Simple Data Element **Data Type** AN **Position** 01
156 State or Province Code	Code (Standard State/Province) as defined by appropriate government agency	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 2 **max:** 2 **External Category** Simple Data Element **Data Type** ID **Position** 02
26 Country Code	Code identifying the country **Selected Values** All Values in Codelist	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 2 **max:** 3 **External Category** Simple Data Element **Data Type** ID **Position** 03 **Codelist Id** ISO_3166-1 **Type System** ISO_CodelistsAndSchemes **Version Mode** Latest **Version** 2013
1654 Longitude Code	Code indicating the longitude in decimal degrees. If the longitude length is less than 7, add leading zeros (0) to make it 7 characters long. The first 3 digits represent the integer part, and the next 4 digits represent the fractional part. These are combined with a decimal point to form the final longitude value in decimal degrees.	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 7 **max:** 7 **External Category** Simple Data Element **Data Type** ID **Position** 04
1655 Latitude Code	Code indicating the latitude in decimal degrees. If the latitude length is less than 7, add leading zeros (0) to make it 7 characters long. The first 3 digits represent the integer part, and the next 4 digits represent the fractional part. These are combined with a decimal point to form the final latitude value in decimal degrees.	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 7 **max:** 7 **External Category** Simple Data Element **Data Type** ID **Position** 05
1280 Direction Identifier Code	Code identifying geographic direction **Selected Values** All Values in Codelist	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 1 **max:** 1 **External Category** Simple Data Element **Data Type** ID **Position** 06 **Codelist Id** 1280 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
1280 Direction Identifier Code	Code identifying geographic direction **Selected Values** All Values in Codelist	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** Token **Length** **min:** 1 **max:** 1 **External Category** Simple Data Element **Data Type** ID **Position** 07 **Codelist Id** 1280 **Type System** ASC_X12 **Version Mode** Current **Version** 004010

4.10 L11 — Business Instructions and Reference Number

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
214 — Transportation Carrier Shipment Status Message	1 .. 1				
├ **0200** — Loop 0200	1 .. 999999		130		
│ └ **L11** — Business Instructions and Reference Number	1 .. 10		150		
│ ├ **127** — Reference Identification - Ocean Container Number	0 .. 1	String	01	1 .. 30	
│ ├ **127** — Reference Identification - Location Number	0 .. 1	String	01	1 .. 30	
│ ├ **127** — Reference Identification - Location-specific Services Reference Number	0 .. 1	String	01	1 .. 30	
│ ├ **127** — Reference Identification - Stop Sequence Number	0 .. 1	String	01	1 .. 30	
│ └ **128** — Reference Identification Qualifier	1 .. 1	Token	02	2 .. 3	128

Documentation

Definition To specify instructions in this business relationship or a reference number

Properties

Identifier L11

Name Business Instructions and Reference Number

Cardinality min: 1 max: 10

Syntax Type Related

External Category Segment

Position 150

Level 3

Notes

Constraint 1 R0103 Required - At least one of those noted must be used

Constraint 2 P0102 Paired Multiple - If any are used, all must be used

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
127 [128 = "OC"] Reference Identification - Ocean Container Number	Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier **Usage 1** The container ID.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 30 **External Category** Simple Data Element **Data Type** AN **Position** 01
127 [128 = "LU"] Reference Identification - Location Number	Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier **Usage 1** The location-ID of the stop. **Usage 2** Either location-ID or stop-ID must be provided. In case both are part of the message the stop-ID will be ignored.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 30 **External Category** Simple Data Element **Data Type** AN **Position** 01
127 [128 = "4L"] Reference Identification - Location-specific Services	Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 30

Reference Number	**Usage 1** The location type of the stop. **Comment 1** If location type is not included in the message "LogisticLocation" will be used as default.	**External Category** Simple Data Element **Data Type** AN **Position** 01
127 [128 = "QN"] Reference Identification - Stop Sequence Number	Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier **Usage 1** The stop-ID. **Usage 2** Either location-ID or stop-ID must be provided. In case both are part of the message the stop-ID will be ignored.	**Cardinality** **min:** 0 **max:** 1 **Primitive Type** String **Length** **min:** 1 **max:** 30 **External Category** Simple Data Element **Data Type** AN **Position** 01
128 Reference Identification Qualifier	Code qualifying the Reference Identification **Selected Values** **Code** LU **Name** Location Number **Code** 4L **Name** Location-specific Services Reference Number **Code** QN **Name** Stop Sequence Number **Code** OC **Name** Ocean Container Number	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** Token **Length** **min:** 2 **max:** 3 **External Category** Simple Data Element **Data Type** ID **Position** 02 **Codelist Id** 128 **Type System** ASC_X12 **Version Mode** Current **Version** 004010