		Data Type xsd:string
D_337 Time	Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 6 **max:** 6 **External Category** Element **Data Type** xsd:string
D_28 Group Control Number	Assigned number originated and maintained by the sender	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 9 **max:** 9 **External Category** Element **Data Type** xsd:string
D_455 Responsible Agency Code	Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480 **Selected Values** All Values in Codelist	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 1 **max:** 1 **External Category** Element **Data Type** xsd:string **Codelist Id** D_455 **Type System** Customer_TS **Version Mode** Local **Version** 1.1
D_480 Version / Release / Industry Identifier Code	Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed **Selected Values** All Values in Codelist	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 6 **max:** 6 **External Category** Element **Data Type** xsd:string **Codelist Id** D_480 **Type System** Customer_TS **Version Mode** Local **Version** 1.1

2.5 S_GE — Functional Group Trailer

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **FunctionalGroup** — Functional Group	1 .. 1				
│ └ **S_GE** — Functional Group Trailer	1 .. 1				
│ ├ **D_97** — Number of Transaction Sets Included	1 .. 1	String		1 .. 1	
│ └ **D_28** — Group Control Number	1 .. 1	String		9 .. 9	

Documentation

Definition To indicate the end of a functional group and to provide control information Comments 1. The use of identical data interchange control numbers in the associated functional group header and trailer is designed to maximize functional group integrity. The control number is the same as that used in the corresponding header. Semantic Notes: 1. The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

Properties

Identifier S_GE

Name Functional Group Trailer

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_97 Number of Transaction Sets Included	Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 1 **External Category** Element **Data Type** xsd:string
D_28 Group Control Number	Assigned number originated and maintained by the sender	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 9 max: 9 **External Category** Element **Data Type** xsd:string

2.6 S_IEA — Interchange Control Trailer

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
└ **S_IEA** — Interchange Control Trailer	1 .. 1				
├ **D_I16** — Number of Included Functional Groups	1 .. 1	String		1 .. 1	
└ **D_I12** — Interchange Control Number	1 .. 1	String		9 .. 9	

Documentation

Definition To define the end of an interchange of zero or more functional groups and interchange-related control segments

Properties

Identifier S_IEA

Name Interchange Control Trailer

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_I16 Number of Included Functional Groups	A count of the number of functional groups included in an interchange	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 1 **External Category** Element **Data Type** xsd:string
D_I12 Interchange Control Number	A control number assigned by the interchange sender	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 9 max: 9 **External Category** Element **Data Type** xsd:string

3 OVERVIEW MESSAGE

General Information

Name	SAP_LBN_ANSI_X12_843
Direction	In
Status	Active
Message Type	Response to Request for Quotation
Type System	ASC_X12
Version	004010
External Category	Transaction Set

Documentation

Definition This Draft Standard for Trial Use contains the format and establishes the data contents of the Response to Request for Quotation Transaction Set (843) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used to provide potential buyers with price, delivery schedule, and other terms from potential sellers of goods and services, in response to a request for such information.

Notes

Usage 1 Quotation Identification:

freightQuotationId: Identifier of the freight quotation from carrier's perspective
Path: /BQR/586
freightRequestForQuotationId: Identifier of the freight request for quotation
Path: /REF[128='KT']/127

EDI Example:
BQR*06*QUO0516001~
REF*KT*4500023960~

QUO0516001: Carrier's internal quotation ID
4500023960: Original RFQ ID from shipper

Usage 2 Response Code

Path: /BQR/353
Value:
"06" -- AP, Accept the freight request for quotation
"44" -- RE, Reject the freight request for quotation

EDI Examples:
Accept:
BQR*06*QUO0516001~
REF*KT*4500023960~
Reject:
BQR*44*QUO0516001~
REF*KT*4500023960~

Usage 3 Pricing Information

proposalPrice.value
Path: /CTP/212

proposalPrice.currency
Path: /CUR[98='BY']/100

EDI Example:
CTP***2200.0~
CUR*BY*EUR~

Usage 4 Rejection Reason

When rejecting a quotation, you can optionally provide a reason code.
Path: /REF[128='ZZ']/127
Value list:
LBN_CAPA - No capacity
LBN_OTHERS - Other
LBN_PRICE - Price
LBN_TIME - No time

EDI Example:
REF*ZZ*LBN_PRICE~

Usage 5 Notes

Provide additional information or explanation
Path:/N9[N9/128='L1']/MSG/933

EDI Example:
N9*L1~
MSG*Price exceeds budget~

Usage 6 Transportation Stages

Propose different loading and unloading times for each transportation stage

id: /N9[N9/128='55']/127
proposedLoadingStartDateTime: /N9/DTM[374='080']
proposedLoadingEndDateTime: /N9/DTM[374='083']
proposedUnloadingStartDateTime:/N9/DTM[374='070']
proposedUnloadingEndDateTime: /N9/DTM[374='073']

EDI Example (Multiple Stages):
N9*55*1~
DTM*080*20260320*0800*UT~
DTM*083*20260320*1200*UT~
DTM*070*20260322*0900*UT~
DTM*073*20260322*1500*UT~
N9*55*2~
DTM*080*20260323*0800*UT~
DTM*083*20260323*1200*UT~
DTM*070*20260325*1000*UT~
DTM*073*20260325*1600*UT~

Example 1 Accept Quotation (Full Message)

ISA*00* *00* *02*Carrier LBNID *01*Shipper LBNID *221115*0847*U*00401*000006693*0*P*>~
GS*RR*Carrier LBNID*Shipper LBNID*20251224*075900*000006693*X*004010~
ST*843*0001~
BQR*06*QUO0516001~
CUR*BY*EUR~
REF*KT*4500023960~
REF*06*QW9_170~
CTP***2200.0~
N9*55*1~
DTM*080*20260320*0800*UT~
DTM*083*20260320*1200*UT~
DTM*070*20260322*0900*UT~
DTM*073*20260322*1500*UT~
N9*55*2~
DTM*080*20260323*0800*UT~
DTM*083*20260323*1200*UT~
DTM*070*20260325*1000*UT~
DTM*073*20260325*1600*UT~
N9*L1~
MSG*This is a sample freight quotation response for testing purposes~
SE*19*0001~
GE*1*000006693~
IEA*1*000006693~

Example 2 Reject Quotation with Reason

ISA*00* *00* *02*Carrier LBNID *01*Shipper LBNID *221115*0847*U*00401*000006693*0*P*>~
GS*RR*Carrier LBNID*Shipper LBNID*20251224*075900*000006693*X*004010~
ST*843*0002~
BQR*44*QUOTE031701~
REF*KT*4500023960~
REF*06*QW9_170~
REF*ZZ*LBN_CAPA~
N9*L1~
MSG*No available capacity for the requested dates~
SE*8*0002~
GE*1*000006693~

IEA*1*000006693~

3.1 Structure

The following table shows the complete structure.

Node	Card.	Prim.Type	Pos.	Length	Codelists
843 — Response to Request for Quotation	1 .. 1				
├ **ST** — Transaction Set Header	1 .. 1		010		
│ ├ **143** — Transaction Set Identifier Code	1 .. 1	Token	01	3 .. 3	143
│ └ **329** — Transaction Set Control Number	1 .. 1	String	02	4 .. 9	
├ **BQR** — Beginning Segment for Response to Request for Quotation	1 .. 1		020		
│ ├ **353** — Transaction Set Purpose Code	1 .. 1	Token	01	2 .. 2	353
│ ├ **586** — Request for Quote Reference Number	1 .. 1	String	02	1 .. 45	
│ └ **373** — Date	1 .. 1	Date	03	8 .. 8	
├ **CUR** — Currency	0 .. 1		040		
│ ├ **98** — Entity Identifier Code	1 .. 1	Token	01	2 .. 3	98
│ └ **100** — Currency Code	1 .. 1	Token	02	3 .. 3	ISO_4217
├ **REF** — Reference Identification	0 .. *		050		
│ ├ **128** — Reference Identification Qualifier	1 .. 1	Token	01	2 .. 3	128
│ ├ **127** — Reference Identification	0 .. 1	String	02	1 .. 30	
│ └ **352** — Description	0 .. 1	String	03	1 .. 80	
├ **CTP** — Pricing Information	0 .. *		090		
│ ├ **687** — Class of Trade Code	0 .. 1	Token	01	2 .. 2	687
│ ├ **236** — Price Identifier Code	0 .. 1	Token	02	3 .. 3	236
│ └ **212** — Unit Price	0 .. 1	Decimal	03	1 .. 17	
├ **N9** — Loop N9	0 .. 1000		290		
│ ├ **N9** — Reference Identification	1 .. 1		290		
│ │ ├ **128** — Reference Identification Qualifier	1 .. 1	Token	01	2 .. 3	128
│ │ └ **127** — Reference Identification	0 .. 1	String	02	1 .. 30	
│ ├ **DTM** — Date/Time Reference	0 .. *		295		
│ │ ├ **374** — Date/Time Qualifier	1 .. 1	Token	01	3 .. 3	374
│ │ ├ **373** — Date	0 .. 1	Date	02	8 .. 8	
│ │ ├ **337** — Time	0 .. 1	Time	03	4 .. 8	
│ │ └ **623** — Time Code	0 .. 1	Token	04	2 .. 2	623
│ └ **MSG** — Message Text	0 .. 1000		300		
│ └ **933** — Free-Form Message Text	1 .. 1	String	01	1 .. 264	
└ **SE** — Transaction Set Trailer	1 .. 1		020		
├ **96** — Number of Included Segments	1 .. 1	Integer	01	1 .. 10	
└ **329** — Transaction Set Control Number	1 .. 1	String	02	4 .. 9	

4 DETAILS MESSAGE

4.1 843 — Response to Request for Quotation

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
843 — Response to Request for Quotation	1 .. 1				
├ **ST** — Transaction Set Header	1 .. 1		010		
├ **BQR** — Beginning Segment for Response to Request for Quotation	1 .. 1		020		
├ **CUR** — Currency	0 .. 1		040		
├ **REF** — Reference Identification	0 .. *		050		
├ **CTP** — Pricing Information	0 .. *		090		
├ **N9** — Loop N9	0 .. 1000		290		
└ **SE** — Transaction Set Trailer	1 .. 1		020		

Properties

Identifier 843

Name Response to Request for Quotation

Cardinality min: 1 max: 1

4.2 ST — Transaction Set Header

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
843 — Response to Request for Quotation	1 .. 1				
├ **ST** — Transaction Set Header	1 .. 1		010		
│ ├ **143** — Transaction Set Identifier Code	1 .. 1	Token	01	3 .. 3	143
│ └ **329** — Transaction Set Control Number	1 .. 1	String	02	4 .. 9	

Documentation

Definition To indicate the start of a transaction set and to assign a control number

Properties

Identifier ST

Name Transaction Set Header

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 010

Level 2

Notes

Usage 1 The transaction set identifier (ST01) used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
143 Transaction Set Identifier Code	Code uniquely identifying a Transaction Set **Selected Values** All Values in Codelist	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 3 max: 3 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Codelist Id** 143 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
329 Transaction Set Control Number	Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 4 max: 9 **External Category** Simple Data Element **Data Type** AN **Position** 02

4.3 BQR — Beginning Segment for Response to Request for Quotation

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
843 — Response to Request for Quotation	1 .. 1				
├ **BQR** — Beginning Segment for Response to Request for Quotation	1 .. 1		020		
│ ├ **353** — Transaction Set Purpose Code	1 .. 1	Token	01	2 .. 2	353
│ ├ **586** — Request for Quote Reference Number	1 .. 1	String	02	1 .. 45	
│ └ **373** — Date	1 .. 1	Date	03	8 .. 8	

Documentation

Definition To indicate the beginning of a Response to Request for Quote Transaction Set and transmit identifying numbers and dates

Properties

Identifier BQR

Name Beginning Segment for Response to Request for Quotation

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 020

Level 2

Notes

Usage 1 BQR03 is the date to be used for reference purposes in an RFQ and a response to RFQ.

Constraint 1 P0405 Paired Multiple - If any are used, all must be used

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
353 Transaction Set Purpose Code	Code identifying purpose of transaction set **Selected Values** **Code** 44 **Name** Rejection **Code** 06 **Name** Confirmation	**Cardinality** min: 1 max: 1 **Primitive Type** Token **Length** min: 2 max: 2 **External Category** Simple Data Element **Data Type** ID **Position** 01 **Codelist Id** 353 **Type System** ASC_X12 **Version Mode** Current **Version** 004010
586 Request for Quote Reference Number	Number assigned by the purchaser to identify his request for quote	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 45 **External Category** Simple Data Element **Data Type** AN **Position** 02
373 Date	Date expressed as CCYYMMDD	**Cardinality** min: 1 max: 1 **Primitive Type** Date **Length** min: 8 max: 8 **Date Time Format** CCYYMMDD **External Category** Simple Data Element **Data Type** DT **Position** 03