SAP Schema Documentation

SAP Business Network for Logistics
Message Implementation Guide | Public
EDIFACT_IFTMIN
Message Type: IFTMIN
Document Version: 2.0 – 2026-07-18



Run Simple

TABLE OF CONTENTS

1 OVERVIEW HEADER 3
2 DETAILS HEADER 5
3 OVERVIEW MESSAGE 13
4 DETAILS MESSAGE 17
5 COPYRIGHT STATEMENTS 86

1 OVERVIEW HEADER

General Information

Name	EDIFACT_HEADER
Direction	Both
Status	Active
Message Type	Interchange Structure
External Category	Message

Documentation

Definition

The Interchange Header is the starting control segment of the interchange envelope. After the recipient has received the document, the interchange header is the first data segment encountered in the document. The interchange header contains:
- the sender and receiver information,
- authorization and security information,
- date and time interchange was prepared,
- standard version of interchange structures, and
- the control number that uniquely identifies the interchange.

1.1 Structure

The following table shows the complete structure.

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNA** — S UNA	0 .. 1	String		6 .. 6	
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S001** — C S001	1 .. 1				
│ │ ├ **D_0001** — Syntax identifier	1 .. 1	String		4 .. 4	D_0001
│ │ └ **D_0002** — Syntax version number	1 .. 1	Decimal			D_0002
│ ├ **C_S002** — C S002	1 .. 1				
│ │ ├ **D_0004** — Sender identification	1 .. 1	String		1 .. 35	
│ │ ├ **D_0007** — Partner identification code qualifier	0 .. 1	String		1 .. 4	D_0007
│ │ └ **D_0008** — Address for reverse routing	0 .. 1	String		1 .. 14	
│ ├ **C_S003** — C S003	1 .. 1				
│ │ ├ **D_0010** — Recipient identification	1 .. 1	String		1 .. 35	
│ │ ├ **D_0007** — Partner identification code qualifier	0 .. 1	String		1 .. 4	D_0007
│ │ └ **D_0014** — Routing address	0 .. 1	String		1 .. 14	
│ ├ **C_S004** — C S004	1 .. 1				
│ │ ├ **D_0017** — Date of preparation	1 .. 1	Decimal			
│ │ └ **D_0019** — Time of preparation	1 .. 1	Decimal			
│ ├ **D_0020** — Interchange control reference	1 .. 1	String		1 .. 14	
│ └ **D_0026** — Application reference	0 .. 1	String		1 .. 14	
├ **FunctionalGroup** — Functional Group	1 .. *				
└ **S_UNZ** — S UNZ	1 .. 1				
├ **D_0036** — Interchange control count	1 .. 1	Decimal			
└ **D_0020** — Interchange control reference	1 .. 1	String		1 .. 14	

2 DETAILS HEADER

2.1 Interchange — Interchange Structure

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNA** — S UNA	0 .. 1	String		6 .. 6	
├ **S_UNB** — S UNB	1 .. 1				
├ **FunctionalGroup** — Functional Group	1 .. *				
└ **S_UNZ** — S UNZ	1 .. 1				

Documentation

Definition The Interchange Envelope, often referred to as the “outer envelope,” is the wrapper for all the data to be sent in one transmission. It can contain multiple Functional Groups. This characteristic means that transactions of different types can be included in the Interchange Envelope, with each type of transaction stored in a separate Functional Group. The Interchange Envelope is defined by the header and trailer; the Interchange Control Header (designated ISA) appears at the beginning, and the Interchange Control Trailer (designated IEA) appears at the end. While the typical pattern from Enterprise Systems is to create one Functional Group (GS/GE) within an Interchange Group (ISA/IEA), the X12 enveloping supports one or more Functional Groups (GS/GE) within an Interchange Group (ISA/IEA).

Properties

Namespace Prefix ns1

Identifier Interchange

Name Interchange Structure

Cardinality min: 1 max: 1

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
S_UNA S UNA		**Cardinality** **min:** 0 **max:** 1 **Primitive Type** String **Length** **min:** 6 **max:** 6 **External Category** Element **Data Type** xsd:string **Fixed Value** :+.? ‘

2.2 S_UNB — S UNB

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S001** — C S001	1 .. 1				
│ ├ **C_S002** — C S002	1 .. 1				
│ ├ **C_S003** — C S003	1 .. 1				
│ ├ **C_S004** — C S004	1 .. 1				
│ ├ **D_0020** — Interchange control reference	1 .. 1	String		1 .. 14	
│ └ **D_0026** — Application reference	0 .. 1	String		1 .. 14	

Properties

Identifier S_UNB

Name S UNB

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0020 Interchange control reference	Unique reference assigned by the sender to an interchange. **Usage 1** Shall be identical in UNB and UNZ.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string
D_0026 Application reference	Identification of the application area assigned by the sender, to which the messages in the interchange relate e.g. the message identifier if all the messages in the interchange are of the same type. **Usage 1** Optionally message identification if the message interchange contains only one type of message.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string

2.3 C_S001 — C S001

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S001** — C S001	1 .. 1				
│ │ ├ **D_0001** — Syntax identifier	1 .. 1	String		4 .. 4	D_0001
│ │ └ **D_0002** — Syntax version number	1 .. 1	Decimal			D_0002

Properties

Identifier C_S001

Name C S001

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0001 Syntax identifier	Coded identification of the agency controlling a syntax and syntax level used in an interchange. **Usage 1** a3, upper case, Controlling Agency (e.g. UNO=UN/ECE) and a1 stating level (e.g. A) (which together give UNOA). **Selected Values** **Code** UNOC **Name** UN/ECE level C As defined in ISO/IEC 8859-1 : Information technology - Part 1: Latin alphabet No. 1.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 4 max: 4 **External Category** Element **Data Type** xsd:string **Fixed Value** UNOC **Codelist Id** D_0001 **Type System** Customer_TS **Version Mode** Local **Version** 1.0
D_0002 Syntax version number	Version number of the syntax identified in the syntax identifier (0001) **Usage 1** Increments 1 for each version. **Selected Values** **Code** 3 **Name** Version 3 ISO 9735 Amendment 1:1992.	**Cardinality** min: 1 max: 1 **Primitive Type** Decimal **Length** min: 0 **Total Digits** 1 **External Category** Element **Data Type** xsd:decimal **Fixed Value** 3 **Codelist Id** D_0002 **Type System** Customer_TS **Version Mode** Local **Version** 1.0

2.4 C_S002 — C S002

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S002** — C S002	1 .. 1				
│ │ ├ **D_0004** — Sender identification	1 .. 1	String		1 .. 35	
│ │ ├ **D_0007** — Partner identification code qualifier	0 .. 1	String		1 .. 4	D_0007
│ │ └ **D_0008** — Address for reverse routing	0 .. 1	String		1 .. 14	

Properties

Identifier C_S002

Name C S002

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0004 Sender identification	Name or coded representation of the sender of a data interchange. **Usage 1** Code or name as specified in IA.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 35 **External Category** Element **Data Type** xsd:string
D_0007 Partner identification code qualifier	Qualifier referring to the source of codes for the identifiers of interchanging partners. **Usage 1** Used with sender/recipient identification code. **Selected Values** **Code** 14 **Name** GS1 Partner identification code assigned by GS1, an international organization of GS1 Member Organizations that manages the GS1 System.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 4 **External Category** Element **Data Type** xsd:string **Fixed Value** 14 **Codelist Id** D_0007 **Type System** Customer_TS **Version Mode** Local **Version** 1.0
D_0008 Address for reverse routing	Address specified by the sender of an interchange to be included by the recipient in the response interchanges to facilitate internal routing. **Usage 1** This field contains the shipper LBN ID.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string

2.5 C_S003 — C S003

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S003** — C S003	1 .. 1				
│ │ ├ **D_0010** — Recipient identification	1 .. 1	String		1 .. 35	
│ │ ├ **D_0007** — Partner identification code qualifier	0 .. 1	String		1 .. 4	D_0007
│ │ └ **D_0014** — Routing address	0 .. 1	String		1 .. 14	

Properties

Identifier C_S003

Name C S003

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0010 Recipient identification	Name or coded representation of the recipient of a data interchange. **Usage 1** Code or name as specified in IA.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 35 **External Category** Element **Data Type** xsd:string
D_0007 Partner identification code qualifier	Qualifier referring to the source of codes for the identifiers of interchanging partners. **Usage 1** Used with sender/recipient identification code. **Selected Values** **Code** 14 **Name** GS1 Partner identification code assigned by GS1, an international organization of GS1 Member Organizations that manages the GS1 System.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 4 **External Category** Element **Data Type** xsd:string **Fixed Value** 14 **Codelist Id** D_0007 **Type System** Customer_TS **Version Mode** Local **Version** 1.0
D_0014 Routing address	Address specified by the recipient of an interchange to be included by the sender and used by the recipient for routing of received interchanges inside his organization. **Usage 1** If used, normally coded sub-address for onward routing.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string

2.6 C_S004 — C S004

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **S_UNB** — S UNB	1 .. 1				
│ ├ **C_S004** — C S004	1 .. 1				
│ │ ├ **D_0017** — Date of preparation	1 .. 1	Decimal			
│ │ └ **D_0019** — Time of preparation	1 .. 1	Decimal			

Properties

Identifier C_S004

Name C S004

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0017 Date of preparation	Local date when an interchange or a functional group was prepared. **Usage 1** YYMMDD	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** Decimal **Length** **min:** 0 **Total Digits** 6 **External Category** Element **Data Type** xsd:decimal
D_0019 Time of preparation	Local time of day when an interchange or a functional group was prepared. **Usage 1** HHMM	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** Decimal **Length** **min:** 0 **Total Digits** 4 **External Category** Element **Data Type** xsd:decimal