2.7 FunctionalGroup — Functional Group

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **FunctionalGroup** — Functional Group	1 .. *				

Properties

Identifier FunctionalGroup

Name Functional Group

Cardinality min: 1 max: *

Syntax Type Related

External Category Element

Notes

Tech. Info. 0 Choice : (FunctionalGroup) (maxOccurs : 1) (minOccurs : 1)

2.8 S_UNZ — S UNZ

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
└ **S_UNZ** — S UNZ	1 .. 1				
├ **D_0036** — Interchange control count	1 .. 1	Decimal			
└ **D_0020** — Interchange control reference	1 .. 1	String		1 .. 14	

Properties

Identifier S_UNZ

Name S UNZ

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0036 Interchange control count	The count either of the number of messages or, if used, of the number of functional groups in an interchange. One of these counts shall appear.	**Cardinality** min: 1 max: 1 **Primitive Type** Decimal **Length** min: 0 **Total Digits** 6 **External Category** Element **Data Type** xsd:decimal
D_0020 Interchange control reference	Unique reference assigned by the sender to an interchange. **Usage 1** Shall be identical in UNB and UNZ.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string

3 OVERVIEW MESSAGE

General Information

Name	SAP_LBN_EDIFACT_IFTSTA_GTT
Direction	Both
Status	Active
Message Type	International multimodal status report message
Type System	UNEDIFACT
Version	D.01C S3
External Category	Message Type

Documentation

Definition

Date:
2022-01-27
This specification provides the definition of the International multimodal status report message (IFTSTA) to be used in Electronic Data Interchange (EDI) between trading partners involved in the SAP LBN environment.A message to report the transport status and/or a change in the transport status (i.e. event) between agreed parties.The International multimodal status report message may be used for both national and international applications. It is based on universal practice related to administration, commerce and transport, and is not dependent on the type of business or industry.
This message allows for the exchange of information regarding the status of the physical movement of consignments, goods or equipment at any point (in time or place) within the full transport chain.This message can relate to a status (or statuses) that has or have been reached in a transport chain.
Data requirements for tracking equipment where equipment is not associated with a consignment (such as repair container) are NOT addressed in this message.

Notes

Example 1

```
UNA:+.? ‘
UNB+UNOC:3+GLNID:14+GLNID:14+211214:1442+6743’
UNH+1+IFTSTA:D:01C:UN’
BGM+7+0959186+9’
DTM+137:20250614:102’
CNI+1+04465986868’
STS++21’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ5:ShipperLbnId’
RFF+ZZ8:StopId’
RFF+ZZ9:GTT’
RFF+ZZA:TrackingType’
RFF+ZZB:LocationType’
RFF+ZZC:LocationId’
DTM+9:202506141411:203’
CNI+2+04465986859’
STS++21’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ5:ShipperLbnId’
RFF+ZZ8:StopId’
RFF+ZZ9:GTT’
RFF+ZZA:TrackingType’
DTM+9:202506141411:203’
CNI+3+04465956417’
STS++24’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ5:ShipperLbnId’
RFF+ZZ8:StopId’
RFF+ZZ9:GTT’
RFF+ZZA:TrackingType’
RFF+ZZB:LocationType’
RFF+ZZC:LocationId’
DTM+9:202506141344:203’
CNI+4+04465947892’
STS++21’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ5:ShipperLbnId’
RFF+ZZ8:StopId’
```

RFF+ZZ9:GTT’
RFF+ZZA:TrackingType’
RFF+ZZB:LocationType’
RFF+ZZC:LocationId’
DTM+9:202506141344:203’
UNT+46+1’
UNZ+1+6743’

3.1 Structure

The following table shows only the root element and the group elements.

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **UNH** — Message header	1 .. 99		0010		
│ └ **S009** — Message identifier	1 .. 1		0020		
├ **BGM** — Beginning of message	1 .. 1		0020		
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ ├ **CNI** — Consignment information	1 .. 1		0170		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **STS** — Status	1 .. 1		0210		
│ │ └ **C555** — Status	1 .. 1		0200		
│ ├ **RFF** — Reference - originatorId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - freightOrderId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - orderingPartyLbnId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - unloadingStopId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - lbnSourceSystemId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - trackingType	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - locationType	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - locationId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - ordinalNo	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - latitude	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ ├ **RFF** — Reference - longitude	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		0100		
│ └ **DTM** — Date/time/period	1 .. 1		0230		
│ └ **C507** — Date/time/period	1 .. 1		0100		
└ **UNT** — Message trailer	1 .. 1		0720		

4 DETAILS MESSAGE

4.1 IFTSTA — International multimodal status report message

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **UNH** — Message header	1 .. 99		0010		
├ **BGM** — Beginning of message	1 .. 1		0020		
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
└ **UNT** — Message trailer	1 .. 1		0720		

Properties

Identifier IFTSTA

Name International multimodal status report message

Cardinality min: 1 max: 1

4.2 UNH — Message header

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **UNH** — Message header	1 .. 99		0010		
│ ├ **0062** — Message reference number	1 .. 1	String	010	1 .. 14	
│ └ **S009** — Message identifier	1 .. 1		020		

Documentation

Definition A service segment starting and uniquely identifying a message. The message type code for the International multimodal status report message is IFTSTA. Example: UNH+1+IFTSTA:D:01C:UN'

Properties

Identifier UNH

Name Message header

Cardinality min: 1 max: 99

Syntax Type Related

External Category Segment

Position 0010

Level 2

Notes

Example 1 UNH+1+IFTSTA:D:01C:UN'

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
0062 Message reference number	Unique message reference assigned by the sender. **Usage 1** Shall be identical in UNH and UNT.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Data Element **Data Type** an **Position** 010

4.3 S009 — Message identifier

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **UNH** — Message header	1 .. 99		0010		
│ └ **S009** — Message identifier	1 .. 1		020		
│ ├ **0065** — Message type	1 .. 1	String	010	1 .. 6	0065
│ ├ **0052** — Message version number	1 .. 1	String	020	1 .. 3	0052
│ ├ **0054** — Message release number	1 .. 1	String	030	1 .. 3	0054
│ └ **0051** — Controlling agency	1 .. 1	String	040	1 .. 2	0051

Documentation

Definition Identification of the type, version etc. of the message being interchanged.

Properties

Identifier S009

Name Message identifier

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 020

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
0065 Message type	Code identifying a type of message and assigned by its controlling agency. **Usage 1** Type of message being transmitted. **Selected Values** **Code** IFTSTA	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 6 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 0065 **Type System** UNEDIFACT **Version Mode** Current **Version** D.01C S3
0052 Message version number	Version number of a message type. **Usage 1** If UNG/UNE is used, shall be identical in UNG and UNE. The representation of 0052 was specified as n..3 in version 1 of ISO 9735. **Selected Values** **Code** D	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 020 **Codelist Id** 0052 **Type System** UNEDIFACT **Version Mode** Current **Version** D.01C S3
0054 Message release number	Release number within the current message type version number (0052). **Usage 1** The representation of 0054 was specified as n..3 in version 1 of ISO 9735. **Selected Values** **Code** 01C **Code** 96A	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 030 **Codelist Id** 0054 **Type System** UNEDIFACT **Version Mode** Current

		Version D.01C S3
0051 Controlling agency	Code to identify the agency controlling the specification, maintenance and publication of the message type. **Selected Values** **Code** UN	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 1 **max:** 2 **External Category** Data Element **Data Type** an **Position** 040 **Codelist Id** 0051 **Type System** UNEDIFACT **Version Mode** Current **Version** D.01C S3

4.4 BGM — Beginning of message

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **BGM** — Beginning of message	1 .. 1		0020		

Documentation

Definition A segment indicating the beginning of a message and identifying the consignment for which status is being reported. Remark: None of the information in BGM is used in SAP LBN. Hence there is no validation of codes and identifiers transmitted in this segment

Properties

Identifier BGM

Name Beginning of message

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0020

Level 2

Notes

Comment 1 None of the information in BGM is used in SAP LBN. Hence there is no validation of codes and identifiers transmitted in this segment.

Example 1 BGM+7+7867541+9’