4.15 C506 — Reference

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **RFF** — Reference - freightOrderId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		010		
│ │ ├ **1153** — Reference code qualifier	1 .. 1	String	010	1 .. 3	1
│ │ └ **1154** — Reference identifier	1 .. 1	String	020	1 .. 70	

Documentation

Definition Identification of a reference.

Properties

Identifier C506

Name Reference

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 010

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
1153 Reference code qualifier	Code qualifying a reference. **Tech. Info. 1** Retrieved from headerNotes in the IFTMIN-Message: S_RFF - C_C506 - D_1153 **Selected Values** **Code** ZZ2 **Name** freightOrderId	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 1 **Version Mode** Fixed
1154 Reference identifier	Identifies a reference. **Example 1** 10000290#ALE	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 70 **External Category** Data Element **Data Type** an **Position** 020

4.16 RFF [1153 = “ZZ7”] — Reference - loadingStopId

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **RFF** — Reference - loadingStopId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		010		

Documentation

Definition A segment identifying a reference relating to the status (e.g House Bill of Lading number).

Properties

Identifier RFF

Name Reference - loadingStopId

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0220

Level 4

Notes

Usage 1 RFF+ZZ1, ZZ2 and ZZ8 fields are mandatory. They contain Sendersystem-ID, Freightorder-ID and Unloadingstop-ID. The same fields are provided in IFTMIN message.

Comment 1 A freight order can have multiple shipments in SAP LBN.

Example 1 RFF+ZZ1:QM7_910’ RFF+ZZ2:500167201’ RFF+ZZ8:3’

4.17 C506 — Reference

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **RFF** — Reference - loadingStopId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		010		
│ │ ├ **1153** — Reference code qualifier	1 .. 1	String	010	1 .. 3	1
│ │ └ **1154** — Reference identifier	1 .. 1	String	020	1 .. 70	

Documentation

Definition Identification of a reference.

Properties

Identifier C506

Name Reference

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 010

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
1153 Reference code qualifier	Code qualifying a reference. **Tech. Info. 1** Retrieved from headerNotes in the IFTMIN-Message: S_RFF - C_C506 - D_1153 **Selected Values** **Code** ZZ7 **Name** loadingStopId	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 1 **Version Mode** Fixed
1154 Reference identifier	Identifies a reference. **Example 1** 10000290#ALE	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 70 **External Category** Data Element **Data Type** an **Position** 020

4.18 RFF [1153 = “ZZ8”] — Reference - unloadingStopId

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **RFF** — Reference - unloadingStopId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		010		

Documentation

Definition A segment identifying a reference relating to the status (e.g House Bill of Lading number).

Properties

Identifier RFF

Name Reference - unloadingStopId

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0220

Level 4

Notes

Usage 1 RFF+ZZ1, ZZ2 and ZZ8 fields are mandatory. They contain Sendersystem-ID, Freightorder-ID and Unloadingstop-ID. The same fields are provided in IFTMIN message.

Comment 1 A freight order can have multiple shipments in SAP LBN.

Example 1 RFF+ZZ1:QM7_910’ RFF+ZZ2:500167201’ RFF+ZZ8:3’

4.19 C506 — Reference

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ ├ **RFF** — Reference - unloadingStopId	1 .. 1		0220		
│ │ └ **C506** — Reference	1 .. 1		010		
│ │ ├ **1153** — Reference code qualifier	1 .. 1	String	010	1 .. 3	1
│ │ └ **1154** — Reference identifier	1 .. 1	String	020	1 .. 70	

Documentation

Definition Identification of a reference.

Properties

Identifier C506

Name Reference

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 010

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
1153 Reference code qualifier	Code qualifying a reference. **Tech. Info. 1** Retrieved from headerNotes in the IFTMIN-Message: S_RFF - C_C506 - D_1153 **Selected Values** **Code** ZZ8 **Name** unloadingStopId	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 1 **Version Mode** Fixed
1154 Reference identifier	Identifies a reference. **Example 1** 10000290#ALE	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 70 **External Category** Data Element **Data Type** an **Position** 020

4.20 DTM — Date/time/period

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ └ **DTM** — Date/time/period	1 .. 1		0230		
│ └ **C507** — Date/time/period	1 .. 1		010		

Documentation

Definition A segment indicating the date and time of the status or event.

Properties

Identifier DTM

Name Date/time/period

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0230

Level 4

Notes

Usage 1 As default a UTC timestamp is expected

Example 1 DTM+9:202103111603:203'

4.21 C507 — Date/time/period

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5	0 .. 99999		0160		
│ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14	1 .. 99		0200		
│ └ **DTM** — Date/time/period	1 .. 1		0230		
│ └ **C507** — Date/time/period	1 .. 1		010		
│ ├ **2005** — Date or time or period function code qualifier	1 .. 1	String	010	1 .. 3	2005
│ ├ **2380** — Date or time or period value	1 .. 1	String	020	1 .. 35	
│ └ **2379** — Date or time or period format code	1 .. 1	String	030	1 .. 3	2379

Documentation

Definition Date and/or time, or period relevant to the specified date/time/period type.

Properties

Identifier C507

Name Date/time/period

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 010

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
2005 Date or time or period function code qualifier	Not used. **Tech. Info. 1** If there is more than one DTM field, the field with code qualifier 9 gets prioritized. Other DTM lines will be ignored. **Selected Values** **Code** 9	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 2005 **Type System** UNEDIFACT **Version Mode** Current **Version** D.01C S3
2380 Date or time or period value	The value of a date, a date and time, a time or of a period in a specified representation.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 35 **External Category** Data Element **Data Type** an **Position** 020
2379 Date or time or period format code	Code specifying the representation of a date, time or period. **Selected Values** **Code** 203 **Code** 204 **Code** 102	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 030

		Codelist Id 2379 **Type System** UNEDIFACT **Version Mode** Current **Version** D.01C S3

4.22 UNT — Message trailer

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTSTA — International multimodal status report message	1 .. 1				
└ **UNT** — Message trailer	1 .. 1		0720		
├ **0074** — Number of segments in the message	1 .. 1	Decimal	010	1 .. 6	
└ **0062** — Message reference number	1 .. 1	String	020	1 .. 14	

Documentation

Definition A service segment ending a message, giving the total number of segments in the message (including the UNH & UNT) and the control reference number of the message.

Properties

Identifier UNT

Name Message trailer

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0720

Level 2

Notes

Example 1 UNT+9+1'

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
0074 Number of segments in the message	Control count of number of segments in a message. **Usage 1** Control count including UNH and UNT.	**Cardinality** min: 1 max: 1 **Primitive Type** Decimal **Length** min: 1 max: 6 **Total Digits** 6 **External Category** Data Element **Data Type** n **Position** 010
0062 Message reference number	Unique message reference assigned by the sender. **Usage 1** Shall be identical in UNH and UNT.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Data Element **Data Type** an **Position** 020

5 COPYRIGHT STATEMENTS

5.1 Copyright Statement for MIG

See also: https://www.sap.com/corporate/en/legal/copyright.html

5.2 Copyright Statement for Type System ASC X12

Copyright (c) 2017, Accredited Standards Committee X12 Incorporated, Format (c) 2017 Washington Publishing Company. Exclusively published by the Washington Publishing Company. No part of this publication maybe distributed, posted, reproduced, stored in a retrieval system, or transmitted in any form or by any means without the prior written permission of the copyright owner. See also: http://members.x12.org/policies-procedures/adp06-intellectual-property-rights-policy-statement.pdf

5.3 Copyright Statement for Type System UN/EDIFACT

Copyright (c) United Nations 2000-2008. All rights reserved. None of the materials provided on this web site may be used, reproduced or transmitted, in whole or in part, in any form or by any means, electronic or mechanical, including photocopying, recording or the use of any information storage and retrieval system, except as provided for in the Terms and Conditions of Use of United Nations Web Sites, without permission in writing from the publisher. To request such permission and for further enquiries, contact the Secretary of the Publications Board, United Nations, New York, NY, 10017, USA (pubboard@un.org; Telephone: (+1) 212-963-4664; Facsimile: (+1) 212-963-0077). See also: http://www.unece.org/legal_notice/copyrightnotice.html

5.4 Copyright Statement for Type System ISO Codelists

Copyright (c) 2017, ISO All ISO content is copyright protected. The copyright is owned by ISO. Any use of the content, including copying of it in whole or in part, for example to another Internet site, is prohibited and would require written permission from ISO. All ISO publications are also protected by copyright. The copyright ownership of ISO is clearly indicated on every ISO publication. Any unauthorized use such as copying, scanning or distribution is prohibited. Requests for permission should be addressed to the ISO Central Secretariat or directly through the ISO member in your country. See more: https://www.iso.org/privacy-and-copyright.html

5.5 Copyright Statement for Type System UN/CEFACT

Copyright (c) United Nations 2000-2008. All rights reserved. None of the materials provided on this web site may be used, reproduced or transmitted, in whole or in part, in any form or by any means, electronic or mechanical, including photocopying, recording or the use of any information storage and retrieval system, except as provided for in the Terms and Conditions of Use of United Nations Web Sites, without permission in writing from the publisher. To request such permission and for further enquiries, contact the Secretary of the Publications Board, United Nations, New York, NY, 10017, USA (pubboard@un.org; Telephone: (+1) 212-963-4664; Facsimile: (+1) 212-963-0077). See also: http://www.unece.org/legal_notice/copyrightnotice.html