Field	Explanation
	○ Actual Business Timestamp: the default. ○ Actual Technical Timestamp ○ Inherit from Tracked Process: inheriting the configuration from your tracked process definition. Your selection decides the timestamp that the system uses to process the last reported actual event. In turn, this affects the planned event status.

4. In the Match Actual Event tab, you can define how an actual event matches an admissible planned event when the actual event is sent to SAP Business Network Global Track and Trace.

   - Define the Match Location value by clicking the switch control.
     - On: The location is used as a match key between the planned event and actual event. The check box of `locationAltKey` is then enabled in the Match Planned Event tab.
     - Off: The location is not a match key between the planned event and actual event. The check box of `locationAltKey` is disabled in the Match Planned Event tab.
   - Below the location match condition, you can define match conditions between planned event extension fields and actual event fields. You can add/edit/delete a match condition. The field you added/deleted here will also enable/disable the check box of this field displayed in the Match Planned Event tab.

     > **Note**
     > If a planned event extension field you used here doesn't exist in the event types that inherit `GTTDelayedEvent`, then the system will add this extension field to the event types that inherit `GTTDelayedEvent`.

     To add a match condition, do the following:

     a. Click the Add icon ＋.

     b. On the left, choose a planned event extension field you defined in the Planned Event Extension tab, the match operator is set as equal by default. On the right, choose an actual event field. The two match fields must be of the same type.

     Click the Delete icon on the right to delete a corresponding match condition.

5. In the Match Planned Event tab, you can define how a planned event matches an existing admissible planned event when a planned event update or tracked process update is sent to SAP Business Network Global Track and Trace.

   You can define the match value by using the check box. The check box of `eventType` is enabled by default and cannot be changed. Fields that are not defined in the Match Actual Event tab won't be displayed here.

   If you don't maintain anything here, the system will fall back to the match conditions in the Match Actual Event tab when matching planned events.

   > **Note**
   > In the GTT standard model "gttft1", you cannot change the event type, event match key, and standard fields in the Match Actual Event and Match Planned Event tabs for the events below:
   >
   > - standard admissible planned events
   > - user-defined admissible planned events with a standard event type.

6. Click OK to close the dialog and add a planned event if all checks in the dialog pass.
7. Save your model configuration.

Edit Admissible Planned Event

Context

To edit an admissible planned event, do the following:

Procedure

1. In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Planned Events** view.
2. Click the pencil icon at the end of the planned event that needs to be changed in the table.
3. Edit in the pop-up dialog.
4. Click **OK** to save changes. The **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Delete Admissible Planned Event

Context

To delete an admissible planned event, do the following:

Procedure

1. In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Planned Events** view.
2. Select the planned events that you want to delete. Multiple selection is supported.
3. Click the **Delete** button above the **User Model Planned Event Types** table.
4. Click **OK**. Planned events you selected are removed immediately, and the **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Admissible Unplanned Events

To define unplanned events, you can use admissible unplanned events.

In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Unplanned Events** view. All the admissible unplanned events are listed on the right side of this page.

By default, the content of **Admissible Unplanned Events** is displayed with two tables:

- **User Model Unplanned Event Types**: This table contains the user-defined unplanned events in this tracked process. You can add/edit/delete these unplanned events.
- **Core Model Unplanned Event Types**: This table contains all the unplanned events from the predefined core model's event types. They are: `GTTDelayedEvent`, `GTTOnTimeEvent`, `GTTDeletionEvent`, and `GTTUpdatePlanEvent`. You cannot modify them.

Besides, in a standard tracked process for the standard model "gttft1", you can also see a **Standard Model Unplanned Event Types** table. It contains the standard unplanned events in this tracked process. You cannot modify them.

You can have at most 200 admissible unplanned events in a tracked process.

Create Admissible Unplanned Event

Context

Before doing this task, you must first define one or more event types in the **Event Type Pool** tab.

To create an admissible unplanned event, do the following:

Procedure

1. In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Unplanned Events** view.
2. Click the **Add** button above the **User Model Unplanned Event Types** table. A pop-up dialog appears.
3. In the **Details** tab, select a event type that you defined in the **Event Type Pool** tab.
4. In the **Match Actual Event** tab, you can define how an actual event matches an admissible unplanned event when the actual event is sent to SAP Business Network Global Track and Trace.

   Here, you can add/edit/delete a match condition between:

   - an actual event field and a string field. Only constants, empty and null fields are allowed.
   - an actual event field and a tracked process field. The two match fields should be of the same type. "Attachments", "Composition", "Association to One" and "Association to Many" types are excluded. If the type is "Code List", the two match fields must come from the same code list. For tracked process fields, only standard and user-defined fields are supported.
   - an actual event field and a sub-field in the tracked process composition field. The match condition works when the actual event field matches one of the sub-fields of the composition field. (Composition field means that the field's type is "Association to One" or "Association to Many".)

   Note

   The settings here don't apply to unplanned events whose event type is `GTTUpdatePlanEvent`.

   If there's a referred planned event in the actual event payload, the settings also don't apply to the following actual events:

   - actual events whose event type is `GTTOnTimeEvent` or `GTTDelayedEvent`;
   - actual events that inherit `GTTOnTimeEvent` or `GTTDelayedEvent`.

5. Click **OK** to close the dialog and add a unplanned event if all checks in the dialog pass.
6. Save your model configuration.

Edit Admissible Unplanned Event

Context

To edit an admissible unplanned event, do the following:

Procedure

1. In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Unplanned Events** view.
2. Click the pencil icon at the end of the unplanned event that needs to be changed in the table.
3. Edit in the pop-up dialog.
4. Click **OK** to save changes. The **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Delete Admissible Unplanned Event

Context

To delete an admissible unplanned event, do the following:

Procedure

1. In the **Tracked Process** tab, click the drop-down of the **Content** view on the right and switch to the **Admissible Unplanned Events** view.
2. Select the unplanned events that you want to delete. Multiple selection is supported.
3. Click the **Delete** button above the **User Model Unplanned Event Types** table.
4. Click **OK**. Unplanned events you selected are removed immediately, and the **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Field Type

You can create/edit/delete user-defined field type in the **Field Type Pool** tab. It is used to define the composition of user-defined fields for tracked processes, field types and event types. You can have at most 200 field types in a model.

In the **Field Type Pool** tab, the field types are listed on the left. The **User Fields** table on the right changes according to the field type you select on the left.

Create Field Type

Context

To create a field type, do the following:

Procedure

1. Click the **Create** button above the **Items** List.
2. Select the target **Tracked Process**.
3. Fill in the **Name** of the field type. The name must be unique in the model.
4. Click the **OK** button to close the dialog if all the checks pass.

5. On the right side, the **User Model Fields** table contains user model fields that only belong to this field type. You can have at most 200 user model fields in a field type. You can create/edit/delete user model fields for this field type.

    - To create a user model field, click the **Create** button above the **User Model Fields** list. Fill in the name and label. Select a type and define this field's scope (key, writable, readable and visible) by using the check boxes. For more information on these attributes, see Create User Model Field.

      Note

      - A field type's user model field does not support the "Association to Many" type.
      - If a string field is specified as the primary key (by checking the **Key** box in the creation dialog), only the following types of characters are supported in its value:
        - letters
        - numbers
        - hyphens
        - underscores

        If the value contains characters of other types, an error will appear when the system is trying to read the data.

    - To edit a user model field, refer to Edit User Model Field.
    - To delete a user model field, refer to Delete User Model Field.
    - To add a URL for a user model field, refer to Add URL for User Model Field.
    - To delete a URL for a user model field, refer to Delete URL for User Model Field.

Edit Field Type

Context

You can change the field type's name and the tracked process that it belongs to.

Procedure

1. Click the **Edit** button above the **Items** List.
2. Change the selection of the target **Tracked Process**.
3. Change the **Name** of the field type.
4. Click the **OK** button to close the dialog if all the checks pass.

Delete Field Type

Context

You can delete a field type.

Procedure

1. Select the target field type.
2. Click the **Delete** button above the **Items** List.
3. The selected field type is removed if it is not referred by other objects.
4. Otherwise, before deletion, a **Where Used List** pops up to ask you if you want to delete the field type and all the data in the places where this field type is used.
5. If you click the **OK** button, the deletion takes effect immediately and the model detail page is changed to the edit mode.
6. Save your model configuration.

Event Type

Event type is used in the planned events and unplanned events of a tracked process. There are two types:

- Core model event types: including the `GTTDelayedEvent`, `GTTOnTimeEvent`, `GTTDeletionEvent`, and `GTTUpdatePlanEvent`
- User-defined event type.

Besides, in the standard model "gttft1", you can also see standard event types and the corresponding standard model fields. You cannot modify them.

You can create/edit/delete your own user-defined event type. You can have at most 200 event types in a model.

In the **Event Type Pool** tab, user-defined event types and core model event types are listed on the left. Select an event type in the list. Then on the right side, the field list is displayed in two tables:

- The table at the top contains all user-defined fields used in this event type.
- The table at the bottom contains fields that are inherited from the core model event type.

Create Event Type

Context

You can create an event type in a tracked process, including attributes such as the event type name, description, inherited event, and field list.

Procedure

1. Click the **Create** button above the list on the left.
2. Select a tracked process in the drop-down list.
3. Fill in the event type name and description. The name is mandatory and should be unique in the model. In the **Inherit** drop-down list, the default value **Event** is provided. You can also change it based on your requirement.
4. Click the **OK** button to close dialog if all checks pass.
5. On the right side, two tables appear. The first contains user fields that only belong to this event type. The other contains all fields from the inherited event. You can have at most 200 user model fields in an event type. You can create/edit/delete user fields for this event type.
    - To create a user model field, click the **Create** button above the **User Model Fields** list. Fill in the name and label. Select a type and define this field's scope (writable, readable and visible) by using the check boxes. For more information on these attributes, see Create User Model Field.

Note

a. A field type's user model field does not support the "Association to Many" type.

b. For event types that inherit `GTTDelayedEvent`, if a field has the same name with a planned event extension field, its properties such as type will be copied from the planned event extension field. The properties cannot be changed.

- To edit a user model field, refer to Edit User Model Field.
- To delete a user model field, refer to Delete User Model Field.
- To add a URL for a user model field, refer to Add URL for User Model Field.
- To delete a URL for a user model field, refer to Delete URL for User Model Field.

Edit Event Type

Context

After the event type has been created, you can edit its attributes.

Procedure

1. Click the event type you want to change on the left side.
2. Click the **Edit** button above the list.
3. In the pop-up dialog, you can edit its tracked process, name, description and inherited event.
4. After editing is complete, click the **OK** button and save changes to the model. And the **Model Details** page is changed to edit mode.
5. Save your model configuration.

Delete Event Type

Context

To delete an event type, do the following:

Procedure

1. Select an event type that you want to delete.
2. Click the **Delete** button above the list.
3. If the event type is not used in other places, the deletion takes effect immediately and the model detail page is changed to the edit mode.
4. Otherwise, before deletion, a **Where Used List** dialog pops up to ask you if you want to delete the event type and all the data in the places where this event type is used. If you click the **OK** button, the deletion takes effect immediately and the model detail page is changed to the edit mode.
5. Save your model configuration.

Code List

You can create/edit/delete code list in a tracked process. Each code list is a collection of code with a name. The code list is consumed as the type of a model field for a tracked process, field type, and event type. Code list fields can receive empty value. You can have at most 200 code lists in a model.

In the **Code List** tab, code lists are displayed in alphabetical order. Click a code list, then the table on the right displays the corresponding collection of codes and their names.

Create Code List

Context

To create a code list, do the following:

Procedure

1. In the **Code Lists** tab, click the **Create** button above the list.
2. Fill in the name. The name of code list should be unique in one model.
3. Click **OK**.
4. After the creation is complete, you can create/edit/delete codes for this code list. You can have at most 200 codes in a code list.
    - To create a code in the code list, do the following:
        a. Click the **Add** button above the table.
        b. A new row with two empty inputs will be added on the bottom of the table.
        c. Fill in code and name. The code should be unique in one code list. If the code is left empty, this line will not be saved to model.
        d. Save your model configuration.
    - To edit a code in the code list, do the following:
        a. Click **Edit** on the top right to change the **Model Details** page to the edit mode.
        b. Change the name and code in the table.
        c. Save your model configuration.
    - To delete a code in the code list, do the following:
        a. Click **Edit** on the top right to change the **Model Details** page to the edit mode.
        b. In the **User Model Codes** table, click the Delete icon at the end of the line that you want to delete.
        c. The deletion takes effect immediately.
        d. Save your model configuration.
    - To import codes in a code list, do the following:
        a. Click the **Import** button above the table.

b. A pop-up dialog appears. Select an **LBN Code List** that you want to import. You can preview the codes of the selected LBN code list in the table below.

c. Click **OK** to import the codes.

d. Save your model configuration.

ℹ Note

The following LBN code lists are provided:

- Carrier Reference Document Type
- Event Reason Code Descriptions
- Incoterm Descriptions
- Location Type Descriptions
- Shipper Reference Document Type
- Shipping Type Descriptions
- Traffic Direction Descriptions
- Transportation Means Standard Code Descriptions
- Transportation Modes

For more, see the Code Lists document.

Edit Code List

Context

You can edit a code list's name.

Procedure

1. Select the code list item you want to change.
2. Click the **Edit** button above the list.
3. In the pop-up dialog, you can edit its **Name**.
4. After changes are complete, click **OK** to save changes to model. And the **Model Details** page is changed to the edit mode.
5. Save your model configuration.

Delete Code List

Context

To delete a code list, do the following:

Procedure

1. Select the code list item that you want to delete.
2. Click the **Delete** button above the list.
3. If the code list is not used in other places, the deletion takes effect immediately and the model detail page is changed to the edit mode.
4. Otherwise, before deletion, a **Where Used List** dialog pops up to ask you if you want to delete the code list and all the data in the places where this code list is used. If you click the **OK** button, the deletion takes effect immediately and the model detail page is changed to the edit mode.
5. Save your model configuration.

IDOC Integration

IDOC Integration maintains mapping rules between ERP IDOC and tracked process user-defined fields. It defines:

- ERP Object Type
- Application Object Type
- the mapping of tracked process event and IDOC
- the mapping of tracked process actual event and ERP Event Code
- the mapping of events' IDOC Segment/IDOC Field and tracked process user-defined fields

On the **IDOC Integration** tab, you can select a specific tracked process to display or edit its related properties.

On the right of the tracked process selection, there is an IDOC integration switch for this tracked process. The default state of this switch is **OFF**. You can change the state in the edit mode. When the switch state is:

- **OFF**, the related configuration view is not visible. These mapping properties are not checked.
- **ON**, you can see below the tracked process mapping, a **Tracked Process / Events** table and a **User Model Fields** table.

When saving a draft model, these selected and filled items are checked before saving or deploying it.

In the tracked process mapping part, you can select **ERP Object Type** and fill in **Application Object Type**.

ERP Object Type

You can select:

- Purchase Order Header
- Purchase Order Item
- Inbound Delivery Header
- Inbound Delivery Item
- Sales Order Header
- Sales Order Item
- Outbound Delivery Header
- Outbound Delivery Item
- Freight Unit