2. Overwrite the function "**MapHelper.setMapConfiguration**" with the sample codes attached at the end of this section.

3. Deploy the app. For information on deployment, see 02_Implementation_Guide-TSOF.pdf under the **Documents** folder.

Sample Code

```
MapHelper.setMapConfiguration = function (map, provider) {
      var protocal = "https";
      var hereHost1 = "maps.hereapi.com";
      var appLanguage = sap.ui.getCore().getConfiguration().getLanguageTag().slice(0, 2);
      var servicePattern =
        "{0}://{1}/v3/base/mc/'{LOD}'/'{X}'/'{Y}'/png8?apiKey={2}&lang={3}&lang2=en";

      var configuration = {
        "MapProvider": [{
          "name": "HERE",
          "type": "",
          "description": "",
          "tileX": "256",
          "tileY": "256",
          "minLOD": "3",
          "maxLOD": "22",
          "copyright": "Copyright &copy; HERE",
          "Source": [hereHost1].map(function (hereHost, index) {
            return {
              "id": "server" + index,
              "url": formatMessage(servicePattern, protocal, hereHost, keys.HERE, appLanguage),
            };
          }),
        }, {
          "name": "OpenStreet",
          "type": "",
          "description": "",
          "tileX": "256",
          "tileY": "256",
          "minLOD": "3",
          "maxLOD": "22",
          "copyright": "Copyright &copy; OpenStreet",
          "Source": [{
            "id": "s1",
            "url": formatMessage("{0}://maps.geoapify.com/v1/tile/osm-carto/'{LOD}'/'{X}'/'{Y}'.
          }],
        }],
        "MapLayerStacks": [{
          "name": "DEFAULT",
          "MapLayer": {
            "name": "layer1",
            "refMapProvider": provider || "OpenStreet",
            "opacity": "1.0",
            "colBkgnd": "RGB(255,255,255)",
          },
        }],
      };
      map.setMapConfiguration(configuration);
      map.setRefMapLayerStack("DEFAULT");
      map.setWidth("0%");

      setTimeout(function () {
        map.setWidth("100%");
      }, 0);
    };
```

Track PO Fulfillment App

To migrate to the HERE Raster Tile API v3 service, do the following:

1. Open the file "**MapHelper.mixin.js.**" under **lbn-gtt-template-tpo** > **GTT-V2-Sample-TrackPurchaseOrders-UI** > **ui** > **webapp** > **controller** > **mixins** in the repository.

2. Overwrite the "**setMapConfiguration**" function with the sample codes attached at the end of this section.

3. Deploy the app. For more information on deployment, see 01_Implementation_Guide-TPOF.pdf under the **Documents** folder.

Sample Code

```
setMapConfiguration: function (sProvider) {
      var sProtocol = "https";
      var sHereHost = "maps.hereapi.com";
      var appLanguage = sap.ui.getCore().getConfiguration().getLanguageTag().slice(0, 2);
      var servicePattern =
        "{0}://{1}/v3/base/mc/'{LOD}'/'{X}'/'{Y}'/png8?apiKey={2}&lang={3}&lang2=en";
      var sUrl = formatMessage(servicePattern, sProtocol, sHereHost, this.keys.HERE, appLanguage

      var oConfiguration = {
        "MapProvider": [{
          "name": "HERE",
          "type": "",
          "description": "",
          "tileX": "256",
          "tileY": "256",
          "maxLOD": "22",
          "copyright": "Copyright © HERE",
          "Source": [{
            "id": "s1",
            "url": sUrl,
          }],
        }],
        "MapLayerStacks": [{
          "name": "DEFAULT",
          "MapLayer": {
            "name": "layer1",
            "refMapProvider": sProvider,
            "opacity": "1.0",
            "colBkgnd": Constants.COLORS.DELAYED_OVERDUE,
          },
        }],
      };
      this.oMap.setMapConfiguration(oConfiguration);
      this.oMap.setRefMapLayerStack("DEFAULT");
    },
```

Data Contributor Apps

This chapter provides application help on all the apps used by data contributors as part of SAP Business Network Global Track and Trace.

Overview

Data contributors have access to a SAP Fiori Launchpad that offers various apps including the following:

Manage Network

App	Description
Manage Business Profile	to view and edit your company profile such as contact details and business partner type
User Management	to manage your users such as to add/delete users and assign users to groups

App	Description
Manage Locations	to manage location master data either manually replicated from another system or created from scratch using the app
System Connections	to receive and respond to order and event tracking documents directly from your system by implementing the order and event tracking APIs published by SAP Business Network Global Track and Trace
Manage Invitations	to manage all the invitations you receive from the solution owners to connect with their business network

Settings

App	Description
Define User Settings	to define the default settings in various other apps in SAP Business Network Global Track and Trace

Retention Management

App	Description
Blocking Store	to access restricted data during its blocking period
Retention Management	to define rules that determine the residence and blocking periods of personal data

Business Operations

App	Description
Manage Integration Logs	to view all integration logs for solution owner and data contributor transactions

User Management

ℹ Note

This app is available for data contributors only.

Prerequisite

To access the User Management app, you must be an administrator user of SAP Business Network for Logistics.

If you don't know who is your company's administrator user, create an incident with component SBN-LBN-BP-OB and provide your company's subdomain in the incident. The subdomain can be found in your sign-in URL as follows: https://<subdomain>.lbn.cfapps.eu10.hana.ondemand.com/sites

About the app

The User Management app allows an administrator to perform user management tasks including the following:

- Add or delete users in your company's tenant
- Add users to user groups

The User Management app consists of the following areas:

- Filter bar

  You can filter the users based on one or more of the filter options, such as First Name, Last Name and Email that appear in the header area.

- Worklists

  Include an All Users list and other user lists categorized by user groups.

Note

The user groups are pre-defined and you are not able to modify them.

Worklist (User Management)

There are different ways to work on the users and to set filters. To restrict the number of users displayed, you can use the filter bar in the header and the worklists for different user groups.

Filter Bar

With the filter bar, you can do the following:

- Specify filters to narrow down the worklists and search for users.
- Add or remove the filters displayed on the filter bar by choosing Adapt Filters.
- Save the current filter settings as a view and apply it later.

  After you specified filters (and pressed Enter) and/or adapted filter display, the current view name shown in the upper-left corner displays a * sign, indicating the view has been changed. Save the view by either of the following:

  - Click the view name to open the My Views box and choose Save or Save As.
  - In the Adapt Filters dialog box, choose Save.

  Next time when you want to apply the view, just select the view name in the My Views box.

  Note

  The default Standard view cannot be changed.

Worklists

All Users

The All Users worklist contains all the users in the current tenant.

This worklist displays the following details for each user:

- First name
- Last name
- Email

- User group(s)

  The system displays all the user groups to which the user belongs.

This worklist contains the option to change user information, including first and last names, and the assigned user groups. You can do so by clicking the *Edit* icon in the worklist. You can also add a user by choosing the **Add** button and delete a user by selecting the user and choosing **Delete** > **Delete User**.

User Lists by User Groups

Each worklist displays all the users that belong to a specific user group. These worklists display the same user information as the **All Users** worklist.

The worklists contain the option to change user information, delete a user, and remove a user from the current user group. To edit a user, click the *Edit* icon for the user. To delete a user, select the user in the worklist and choose **Delete** > **Delete User**. To remove a user from the current user group, select the user in the worklist and choose **Delete** > **Delete Mapping**. For example, by choosing **Delete Mapping** in the **ABC** worklist, you remove the user from the **ABC** user group.

Create a User and Assign User Groups

Prerequisites

You are a tenant administrator, that is, you have already been assigned to the admin user group either by the system or by another administrator in your company.

Context

As an administrator, you can create users in your company's tenant and assign users to user groups so that they have access to relevant apps.

Procedure

1. Launch the **User Management** app.
2. In the **All Users** worklist, choose the **Add** button.

   A new empty row is added at the top of the list table.
3. In the new row, enter the user names, user email, and select the user group(s) you want to assign to the user.
   - Users assigned to the "...Admin" user group are administrators. They can perform administrative tasks using the following apps:
     - **Manage Business Profile**
     - **Retention Management**
     - **Blocking Store**
     - **Define User Settings**
     - **Manage Notification Settings**
     - **System Connections**
     - **Manage Invitations**

- User Management
- Manage Integration Logs

- Users assigned to the "...All_Function" user group can access the following apps:
  - Retention Management
  - Blocking Store
  - Define User Settings
  - Manage Notification Settings
  - Manage Invitations
  - Manage Disputes
  - Freight Orders for Confirmation
  - Freight Orders for Reporting
  - Review Freight Documents
  - Invoice Freight Documents
  - Freight Quotations
  - Freight Requests for Quotation
  - Manage Invoices
  - Self-Book Dock Appointments
  - Manage Freight Execution

Note

When assigning user groups, consider the following security considerations:

- Grant the user only the authorization that is necessary.
- Ensure that authorization is removed as soon as it is no longer needed (for example, if an employee leaves the company).

4. Choose the Save button.

Note

If the new user's email domain is different from yours, you'll be prompted to confirm it.

Results

The new user is created and added to the specified user groups in your company's tenant. The system will send an activation email to the user for setting the password.

Note

If the user already exists in SAP Business Network for Logistics, no activation email will be sent because the user was already activated for the network.

Users must sign out and sign in again to see the apps respective to their newly assigned user groups.

You need to send the network URL to the newly added users so they can sign in to the network with their own user credentials (after they've activated their user accounts).

Edit User Information

You, as a tenant administrator, can change the information for existing users in your company's tenant.

Context

The following user information can be changed:

- First and last names
- User group assignments

Procedure

1. Launch the **User Management** app.

   You can view all your users in the current tenant in the **All Users** worklist. To narrow down the list, use the filter bar, search box, or go to the worklist for a specific user group.

2. To edit a user, in any worklist, click the *Edit* icon for the user, make your changes, and choose **Save**.

Results

If the user group assignment for an existing user is changed, the system will send an email to the user to notify the change.

Users must sign out and sign in again to see the apps respective to their newly assigned user groups.

Delete a User

Context

You, as a tenant administrator, can delete a user from the current tenant. The deleted user can no longer access the apps in your company's tenant.

Note

You can't delete your own account.

Procedure

1. Launch the **User Management** app.

   You can view all the users in the **All Users** worklist. To narrow down the list, use the filter bar or search box.

2. To delete a user, in any worklist, select the user and choose **Delete** > **Delete User**.

3. In the confirmation dialog box, click **OK**.

Note

If the user also exists in other tenants of SAP Business Network for Logistics, the deletion only removes the user from the current tenant.

Manage Locations

You can use the Manage Locations app to manage location master data either manually replicated from another system or created from scratch using the app. Location master data can then be consumed by other apps in SAP Business Network Global Track and Trace.

You can set up a location replication using the Data Replication Framework (DRF) in the SAP S4/HANA source system. For more information, see Configurations for Location Replication.

Location master data consists of not only the address information, but also the business purpose of a location. Additionally, the master data of a location can include one or more alternative IDs so that the location becomes cross-platform identifiable.

The main features of this app include:

- View a location
- Create a location
- Upload locations
- Edit a location

ℹ Note

- The Manage Locations app implements all security features and data protection-relevant functions documented in the "Security and Data Protection and Privacy" section of the *Administration Guide*.
- A location master data record enters the blocking period if it has not been accessed for three consecutive years. The blocking period lasts for another three years, during which only audit specialists can access the record. The record will then be automatically deleted when the end of the blocking period is reached.

Viewing a Location

To view a location, proceed as follows:

1. By default, you can use the following fields to filter locations:
    - External ID
    - Source System
    - Object Type
    - Description
    - Country/Region
    - City
    - Data Processing Status

- Additional Information

You can also adjust the filter bar by chooosing **Adapt Filters**.

2. Click the location from the filter results to open the details page.

The detail view of the location consists of a header and other sections.

Header

The Header section displays the address information.

General

This section displays the basic information of a location. This includes the business purposes, the longitude/latitude coordinates, and the revision history.

Geographical Coordinates and Map

This section displays the geographical coordinates of the location. It also identifies the location on the map.

Alternative Location IDs

This section displays a list of type-specific alternative IDs of the location.

Contact Information

This section displays the contact information related to the location.

Additional Information

This section displays the contact information related to the location.

More Information

You can do the following with the filter bar:

- Specify filters to narrow down the worklists and search for locations.
- Add or remove the filters displayed on the filter bar by choosing **Adapt Filters**.
- Save the current filter settings as a view and apply it later.

  After you specified filters (and pressed Enter) and/or adapted filter display, the current view name shown in the upper-left corner displays a * sign, indicating the view has been changed. Save the view by either of the following:

  - Click the view name to open the **My Views** box and choose **Save** or **Save As**.
  - In the **Adapt Filters** dialog box, choose **Save**.

  Next time when you want to apply the view, just select the view name in the **My Views** box.

ℹ Note

The default Standard view cannot be changed.

Creating a Location

To create a location, proceed as follows:

1. Click Create on the upper-right corner of the Locations table. The Create New Location page opens.
2. On the Create New Location page, enter the following details:
    - Source: Source of the location. Valid values are:
        - SAP SCM Logistic Location: Locations from one of the following systems:
            - SAP Extended Warehouse Management
            - SAP Transportation Management
        - SAP ERP Location: Locations from an SAP ERP system
        - Others: Locations from other systems
    - Location Type: Type of the location

      This field is available when Source is set to SAP SCM Logistic Location.
    - Object Type: Business purpose of a location.

      This field is configurable when Source is set to SAP ERP Location or Others. When Source is set to SAP SCM Logistic Location, the system automatically sets Object Type to Logistic Location.

      Valid values for the Object Type field are::
        - Business Partner
        - Customer
        - Plant
        - Shipping Point
        - Supplier

      If none of the values above fits the location's business purpose, you can change Source to SAP SCM Logistic Location as an alternative. This will set Object Type to Logistic Location at the backend and make Location Type configurable. The Location Type field provides you with a broader list of types pertaining to various business purposes, such as port and hub.

      > **Note**
      >
      > You can also maintain the information of an ordering party in this app by setting the Object Type field to Business Partner.

    - Description: Descriptive information about the location
    - Source System/External ID: Source system from which the location master data is copied and the corresponding ID.
        - If you are creating a location from scratch, set the Source System part to LBN, and set the External ID part to the location ID you previously prepared.