### (5 - 1) Object-Oriented Programming (OOP) and C++

Instructor - Andrew S. O'Fallon CptS 122 (February 5, 2018) Washington State University



#### **Key Concepts**

- Object-Oriented Design
- Object-Oriented Programming (OOP)
- Class and Objects
- Data Encapsulation
- Abstraction/Information Hiding
- C++ I/O
- References and Reference Parameters
- Unary Scope Resolution Operator
- Function Overloading



### **Object-Oriented Design (OOD)**

- Model software in ways that are similar to how people view/describe real-world objects
- Descriptions and designs include properties or attributes of the real-world objects
- The Unified Modeling Language (UML) provides a specification for illustrating properties of objects along with interactions between them



# Object-Oriented Programming (OOP) (I)

- Programming language model which institutes mechanisms to support implementing object driven software systems
  - C++, C#, Java
- Procedural programming, such as instituted by C, is action oriented
- In C, the unit of programming is a function
- In C++ the unit is a class



# **Object-Oriented Programming** (OOP) (II)

- We'll explore OOP with classes, encapsulation, objects, operator overloading, inheritance, and polymorphism
- We'll also explore generic programming with function templates and class templates



#### Classes and Objects

- What is a class?
  - A user defined type or data structure
  - Contains data members (attributes) and member functions (operations)
  - A blueprint for an object
- What is an object?
  - An instantiation of a class
  - The class is the type and the object is the variable with allocated memory for that type



### Data Encapsulation (I)

- A way of organizing or wrapping of data/attributes and methods/operations into a structure (or capsule)
  - Demonstrated by objects
- Objects naturally impose encapsulation attributes and operations are closely tied together
- How does making a function or class a friend of another class impact encapsulation?



### **Abstraction/Information Hiding (I)**

- A design principle which states a design decision should be hidden from the rest of the system
- In other words, objects should communicate with each other through well-defined interfaces, but not know how other objects are implemented



### **Abstraction/Information Hiding (II)**

- Prevents access to data aside from the methods specified by the object
- Guarantees integrity of data
- Access specifiers in C++ control the access to information
  - public, protected, and private



### **Programming in C++**

- When programming in an object-oriented language, we'll be exposed to encapsulation, abstraction, and information hiding in action
- We need to start thinking in an objectoriented way so that we can leverage the software design benefits of objects and the richness of C++!
- Always remember, objects contain data and associated operations!



### Basics of C++ and I/O (I)

- In C++, just like in C, every program begins execution with function main ()
- To perform input and output (I/O) we need to include the C++ Standard Library

```
<iostream>
```

- Essentially replaces <stdio.h>, but with even more richness and convenience



#### Basics of C++ and I/O (II)

- In tandem with including <iostream>, we'll need to use the following:
  - A standard output stream object (std::cout) and stream insertion operator (<<) to display information on the screen
    - Replaces the need for printf ()
  - A standard input stream object (std::cin) and the stream extraction operator (>>) to read data from the keyboard
    - Replaces the need for scanf ()



#### Basics of C++ and I/O Example

```
#include <iostream>
using std::cin; // replaces need for std:: in front of cin
using std::cout; // replaces need for std:: in front of cout
using std::endl; // replaces need for std:: in front of endl
int main (void)
         int n1 = 0;
         cout << "Enter a number: ";</pre>
         cin >> n1; // Notice no address of (&) required!
         int n2 = 0, sum = 0; // Can declare variables right
                              // before their use in C++!
         cout << "Enter a second number: ";</pre>
         cin >> n2;
         sum = n1 + n2;
         cout << "The sum is: " << sum << endl; // endl outputs a
                                        // newline, then flushes buffer
         return 0;
```

### References and Reference Parameters (I)

- There are two ways to pass arguments to functions in C++
  - Pass-by-value (PBV) a copy of the contents/value of each argument is made and passed (on the function call stack) to the called function
    - One disadvantage of pass-by-value is copying the contents of a large data item or object introduces longer execution times and memory space
    - In general, should only be used with simple types
    - Passing-by-pointer falls under this category
  - Pass-by-reference (PBR) NO copy of the contents/value of each argument is made
    - The called function can access the caller's data directly, and modify the data

### References and Reference Parameters (II)

- Thoughts: we don't use pass-by-reference strictly so that we can modify the data in an object directly, in many cases we use it so that the overhead of copying data is circumvented
- We use the ampersand (&) to represent pass-byreference
  - i.e. void cube (int &n); // this is a prototype
  - Don't confuse with the address of (&) operator!
     Context determines which one's in play!
- Check out: <a href="http://www.cplusplus.com/articles/z6vU7k9E/">http://www.cplusplus.com/articles/z6vU7k9E/</a>

### References and Reference Parameters (III)

- We can return a reference to a variable as well – however we have to be very careful!
  - i.e. int & someFunction (int &n);
- If we return a reference to an automatic local variable, the variable becomes "undefined" when the function exits; unless the variable is declared as "static" (keyword)
  - References to undefined variables are called dangling references
  - Note: dangling references and dangling pointers are NOT the same!

### References and Reference Parameters Example

```
void cubeByRef (int &n);
void cubeByPtr (int *pN);
int main (void)
           int n = 5:
            cubeByRef (n); // Don't need &, the formal parameter list indicates PBR
            cubeByPtr (&n); // Need address of (&) operator to satisfy pointer; applying PBV
void cubeByRef (int &n)
           n = n * n * n; // We have direct access to n, don't need to dereference;
                         // changes are retained
void cubeByPtr (int *pN)
            *pN = (*pN) * (*pN) * (*pN); // Need to dereference to indirectly change value
   A. O'Fallon, J. Hagemeister
```

#### **Unary Scope Resolution Operator**

- It's possible to declare local and global variables of the same name
  - Unary Scope Resolution Operator (::) allows a global variable to be accessed without confusing it with a local variable

```
int num = 42; // global variable
int main (void)
{
   double num = 100.25; // local variable
   cout << num << endl; // displays 100.25
   cout << ::num << endl; // displays 42</pre>
```



### Function Overloading (I)

- The ability to define multiple functions with the same name
  - Requires that each function has different types of parameters and/or different number of parameters and/or different order of parameters

```
- i.e. int cube (int n);
    double cube (double n);
```

 The C++ compiler selects the appropriate function based on the *number*, *types*, and *order* of arguments in the function *call*



### Function Overloading (II)

- We use function overloading to increase readability and understandability
  - Of course, we only want to overload functions that perform similar tasks



# C++ Standard Template Library (STL) Class Vector

- STL class vector represents a more robust array with many more capabilities
- May operate with different types of data because they're templated!



### **Closing Thoughts**

- OOP and C++ opens us up to an entirely different world!
- We need to start thinking more in terms of data and "capsules" instead of just actions and logic
- Learning C++ is a challenge, but provides features that will increase levels of production!



#### References

 P.J. Deitel & H.M. Deitel, C++: How to Program (9th ed.), Prentice Hall, 2014.



#### **Collaborators**

Jack Hagemeister

