
Chapter 2

Data Representation in Computer Systems



Chapter 2 Objectives (2b)


 Understand the fundamental concepts of floatingpoint representation.

- Floating-point numbers allow an arbitrary number of decimal places to the right of the decimal point.
 - For example: $0.5 \times 0.25 = 0.125$
- They are often expressed in scientific notation.
 - For example:


$$0.125 = 1.25 \times 10^{-1}$$

$$5,000,000 = 5.0 \times 10^6$$

- Computers use a form of scientific notation for floating-point representation
- Numbers written in scientific notation have three components:



 Computer representation of a floating-point number consists of three fixed-size fields:



This is the standard arrangement of these fields.


Note: Although "significand" and "mantissa" do not technically mean the same thing, many people use these terms interchangeably. We use the term "significand" to refer to the fractional part of a floating point number.



- The one-bit sign field is the sign of the stored value.
- The size of the exponent field determines the range of values that can be represented.
- The size of the significand determines the precision of the representation.




- We introduce a hypothetical "Simple Model" to explain the concepts
- In this model:
 - A floating-point number is 14 bits in length
 - The exponent field is 5 bits
 - The significand field is 8 bits





- The significand is always preceded by an implied binary point.
- Thus, the significand always contains a fractional binary value.
- The exponent indicates the power of 2 by which the significand is multiplied.

- Example:
 - Express 32₁₀ in the simplified 14-bit floating-point model.
- We know that 32 is 2^5 . So in (binary) scientific notation $32 = 1.0 \times 2^5 = 0.1 \times 2^6$.
- Using this information, we put 110 (= 6_{10}) in the exponent field and 1 in the significand as shown.



- The illustrations shown at the right are all equivalent representations for 32 using our simplified model.
- Not only do these synonymous representations waste space, but they can also cause confusion.





 Another problem with our system is that we have made no allowances for negative exponents. We have no way to express 0.5 (=2 -1)! (Notice that there is no sign in the exponent field.)

All of these problems can be fixed with no changes to our basic model.

- To resolve the problem of synonymous forms, we establish a rule that the first digit of the significand must be 1, with no ones to the left of the radix point.
- This process, called *normalization*, results in a unique pattern for each floating-point number.
 - In our simple model, all significands must have the form 0.1xxxxxxxxx
 - For example, $4.5 = 100.1 \times 2^0 = 1.001 \times 2^2 = 0.1001 \times 2^3$. The last expression is correctly normalized.

In our simple instructional model, we use no implied bits.

- To provide for negative exponents, we will use a biased exponent.
 - In our case, we have a 5-bit exponent.

$$-2^{5-1}-1=2^4-1=15$$

- Thus will use 15 for our bias: our exponent will use *excess-15* representation.
- In our model, exponent values less than 15 are negative, representing fractional numbers.

Excess-M Representation

- Excess-M representation (also called offset binary representation) is another way for unsigned binary values to represent signed integers.
 - Excess-M representation is intuitive because the binary string with all 0s represents the smallest number, whereas the binary string with all 1s represents the largest value.
- An unsigned binary integer M (called the bias)
 represents the value 0, whereas all zeroes in the bit
 pattern represents the integer 2M.
- The integer is interpreted as positive or negative depending on where it falls in the range.

Excess-M Representation

- If n bits are used for the binary representation, we select the bias in such a manner that we split the range equally.
- Typically we choose a bias of 2ⁿ⁻¹ 1.
 - For example, if we were using 4-bit representation, the bias should be $2^{4-1} 1 = 7$.
- Just as with signed magnitude, one's complement, and two's complement, there is a specific range of values that can be expressed in n bits.

Excess-M Representation

- The unsigned binary value for a signed integer using excess-M representation is determined simply by adding M to that integer.
 - For example, assuming that we are using excess-7 representation, the integer 0_{10} is represented as $0 7 = 7_{10} = 0111_2$.
 - The integer 3_{10} is represented as $3 + 7 = 10_{10} = 1010_{2}$.
 - The integer -7 is represented as $-7 + 7 = 0_{10} = 0000_2$.
 - To find the decimal value of the excess-7 binary number 1111_2 subtract 7: $1111_2 = 15_{10}$ and 15 7 = 8; thus 1111_2 , in excess-7 is $+8_{10}$.


Signed Integer Representation

Lets compare our representations:

Decimal	Binary (for absolute value)	Signed Magnitude	One's Complement
2	00000010	00000010	00000010
-2	00000010	10000010	11111101
100	01100100	01100100	01100100
-100	01100100	11100100	10011011


Decimal	Binary (for absolute value)	Two's Complement	Excess-127
2	00000010	00000010	10000001
-2	00000010	11111110	01111101
100	01100100	01100100	11100011
- 100	01100100	10011100	00011011

- Example:
 - Express 32₁₀ in the revised 14-bit floating-point model.
- We know that $32 = 1.0 \times 2^5 = 0.1 \times 2^6$.
- To use our excess 15 biased exponent, we add 15 to 6, giving 21₁₀ (=10101₂).
- So we have:



Example:

- Express 0.0625₁₀ in the revised 14-bit floating-point model.
- We know that 0.0625 is 2^{-4} . So in (binary) scientific notation $0.0625 = 1.0 \times 2^{-4} = 0.1 \times 2^{-3}$.
- To use our excess 15 biased exponent, we add 15 to -3, giving 12₁₀ (=01100₂).



Example:

- Express -26.625₁₀ in the revised 14-bit floating-point model.
- We find $26.625_{10} = 11010.101_2$. Normalizing, we have: $26.625_{10} = 0.11010101 \times 2^5$.
- To use our excess 15 biased exponent, we add 15 to 5, giving 20₁₀ (=10100₂). We also need a 1 in the sign bit.



- The IEEE has established a standard for floating-point numbers
- The IEEE-754 single precision floating point standard uses an 8-bit exponent (with a bias of 127) and a 23-bit significand.
- The IEEE-754 double precision standard uses an 11-bit exponent (with a bias of 1023) and a 52-bit significand.

- In both the IEEE single-precision and doubleprecision floating-point standard, the significant has an implied 1 to the LEFT of the radix point.
 - The format for a significand using the IEEE format is:
 1.xxx...
 - For example, $4.5 = .1001 \times 2^3$ in IEEE format is $4.5 = 1.001 \times 2^2$. The 1 is implied, which means is does not need to be listed in the significand (the significand would include only 001).

- Example: Express -3.75 as a floating point number using IEEE single precision.
- First, let's normalize according to IEEE rules:
 - $-3.75 = -11.11_2 = -1.111 \times 2^{1}$
 - The bias is 127, so we add 127 + 1 = 128 (this is our exponent)



 Since we have an implied 1 in the significand, this equates to

$$-(1).111_2 \times 2^{(128-127)} = -1.111_2 \times 2^1 = -11.11_2 = -3.75.$$


- Using the IEEE-754 single precision floating point standard:
 - An exponent of 255 indicates a special value.
 - If the significand is zero, the value is \pm infinity.
 - If the significand is nonzero, the value is NaN, "not a number," often used to flag an error condition.
- Using the double precision standard:
 - The "special" exponent value for a double precision number is 2047, instead of the 255 used by the single precision standard.

- Both the 14-bit model that we have presented and the IEEE-754 floating point standard allow two representations for zero.
 - Zero is indicated by all zeros in the exponent and the significand, but the sign bit can be either 0 or 1.
- This is why programmers should avoid testing a floating-point value for equality to zero.
 - Negative zero does not equal positive zero.

- Floating-point addition and subtraction are done using methods analogous to how we perform calculations using pencil and paper.
- The first thing that we do is express both operands in the same exponential power, then add the numbers, preserving the exponent in the sum.
- If the exponent requires adjustment, we do so at the end of the calculation.

Example:

- Find the sum of 12_{10} and 1.25_{10} using the 14-bit "simple" floating-point model.
- We find $12_{10} = 0.1100 \times 2^4$. And $1.25_{10} = 0.101 \times 2^1 = 0.000101 \times 2^4$.
- Thus, our sum is 0.110101 x 2⁴.



- Floating-point multiplication is also carried out in a manner akin to how we perform multiplication using pencil and paper.
- We multiply the two operands and add their exponents.
- If the exponent requires adjustment, we do so at the end of the calculation.

Example:

- Find the product of 12_{10} and 1.25_{10} using the 14-bit floating-point model.
- We find $12_{10} = 0.1100 \times 2^4$. And $1.25_{10} = 0.101 \times 2^1$.
- Thus, our product is $0.0111100 \times 2^{5} = 0.1111 \times 2^{4}$.
- The normalized product requires an exponent of 19₁₀ = 10011₂.

	0	10011	11000000
×	0	10000	10100000
	0	10011	11110000

- No matter how many bits we use in a floating-point representation, our model must be finite.
- The real number system is, of course, infinite, so our models can give nothing more than an approximation of a real value.
- At some point, every model breaks down, introducing errors into our calculations.
- By using a greater number of bits in our model, we can reduce these errors, but we can never totally eliminate them.

- Our job becomes one of reducing error, or at least being aware of the possible magnitude of error in our calculations.
- We must also be aware that errors can compound through repetitive arithmetic operations.
- For example, our 14-bit model cannot exactly represent the decimal value 128.5. In binary, it is 9 bits wide:

 $10000000.1_2 = 128.5_{10}$

 When we try to express 128.5₁₀ in our 14-bit model, we lose the low-order bit, giving a relative error of:

$$\frac{128.5 - 128}{128.5} \approx 0.39\%$$

 If we had a procedure that repetitively added 0.5 to 128.5, we would have an error of nearly 2% after only four iterations.

- Floating-point errors can be reduced when we use operands that are similar in magnitude.
- If we were repetitively adding 0.5 to 128.5, it would have been better to iteratively add 0.5 to itself and then add 128.5 to this sum.
- In this example, the error was caused by loss of the low-order bit.
- Loss of the high-order bit is more problematic.

- Floating-point overflow and underflow can cause programs to crash.
- Overflow occurs when there is no room to store the high-order bits resulting from a calculation.
- Underflow occurs when a value is too small to store, possibly resulting in division by zero.

Experienced programmers know that it's better for a program to crash than to have it produce incorrect, but plausible, results.

- When discussing floating-point numbers, it is important to understand the terms range, precision, and accuracy.
- The range of a numeric integer format is the difference between the largest and smallest values that can be expressed.
- Accuracy refers to how closely a numeric representation approximates a true value.
- The precision of a number indicates how much information we have about a value

- Most of the time, greater precision leads to better accuracy, but this is not always true.
 - For example, 3.1333 is a value of pi that is accurate to two digits, but has 5 digits of precision.
- There are other problems with floating point numbers.
- Because of truncated bits, you cannot always assume that a particular floating point operation is commutative or distributive.

This means that we cannot assume:

$$(a + b) + c = a + (b + c)$$
 or
 $a*(b + c) = ab + ac$

 Moreover, to test a floating point value for equality to some other number, it is best to declare a "nearness to x" epsilon value. For example, instead of checking to see if floating point x is equal to 2 as follows:

if
$$x = 2$$
 then ...

it is better to use:

if
$$(abs(x - 2) < epsilon)$$
 then ...

(assuming we have epsilon defined correctly!)