
Stream Reviews User guide

Collect photos from your community and review them live on stream, safely: room reviews, costume reviews, pet reviews and anything else.



For participants, streamers, moderators and administrators

October 2026

Contents

1	Overview	How it works, roles and pages
2	Finding a streamer and sending photos	For participants
3	Streamers: boards, team and the live deck NEW	For streamers
4	Moderating a board	For Board Admins and team Admins
5	Running boards	For Admins
6	Running the site	For Site Admins and the Owner
7	Privacy and safety checklist	For everyone on the team
8	Troubleshooting	Common questions

Languages and theme

The site is available in English, Spanish, Portuguese, French and Japanese. It follows your browser language, and you can change it at any time with the language menu in the top bar. Next to it you can switch between the light and dark theme; until you choose one, the site uses your device's setting.

What's new in this version

- Streamers sign in with **Twitch**, have their own public page and create their own boards.
- Each streamer can have a **team** of up to two Admins who run and moderate their boards.
- Visitors can **search for a streamer** on the home page. Board addresses are now `/streamer/board`.
- Boards can accept **one short video**, compressed in the browser and sent without sound.
- On the deck, **each review starts blurred** until the streamer reveals it.
- The first account is the **Owner**: two-step verification is required and only they can reset their password.

01 Overview

Stream Reviews hosts any number of **streamers**, and each streamer can run several **boards**. A board is one review event, such as “Room Review” or “Costume Review”, with its own public page and its own team.

1 · Send
A participant finds the streamer and sends up to 5 photos (and, if allowed, one video). No account needed.

2 · Moderate
The streamer’s team or a Board Admin checks each submission for personal details and approves it.

3 · Show live
The streamer opens the deck. Each review starts blurred until they reveal it on stream.

4 · Delete
Everything is deleted after 90 days, or earlier on request.

Roles

Role	How they get in	What they can do
Participant	No account	Search streamers, send a submission to an open board, delete it with its code, report a problem.
Streamer	**Twitch**, approved by a Site Admin the first time	Create and edit **their own** boards and open their **deck**. They don’t see the queue. Choose up to 2 Admins for their team.
Board Admin	The board’s *Board Admin password*	Moderate the **queue** of that board and open its deck.
Deck access	The board’s *streamer password*	Open that board’s deck only (useful for OBS or another computer).
Admin	Personal account	Manage and moderate the boards they create, boards shared with them and **all boards of the streamers whose team they’re in**. They can only create boards for those streamers.
Site Admin	Personal account	Everything on every board, plus approving streamers, accounts, problem reports and the activity log.
Owner	Personal account with **required** two-step verification	Everything a Site Admin can do. The first account of the site; nobody else can demote, delete or reset it.

Staff registration is closed: only a Site Admin (or a streamer, for their own team) can create accounts. Board passwords only open their own board.

Pages

Address	What it is
`/`	Home: search for a streamer, or browse streamers with open boards.
`/pixelwitch`	A streamer's public page, with all their active boards.
`/pixelwitch/room-review`	Public page of a board, with the submission form.
`/pixelwitch/room-review/queue`	Moderation queue (the streamer's team, the board's admins and Board Admins).
`/pixelwitch/room-review/deck`	Live view for the streamer.
`/panel`	Control panel (accounts only).
`/team`	The streamer's team of Admins.
`/streamers` · `/admins`	Streamer requests and staff accounts (Site Admins and the Owner).
`/login`	Sign in: Twitch for streamers, username and password for staff.
`/delete` · `/report`	Delete a submission with its code · Report a problem.
`/privacy` · `/contact`	Privacy and photo terms · Contact details.

Board addresses changed

Boards used to live at `/board-name`. They now live under their streamer: `/streamer/board-name`. Links shared before the update no longer work, so share the new ones from the control panel.


02 Finding a streamer and sending photos

Open the link the streamer shared, or start on the home page and search for them. Nothing is sent until you confirm on the review step.


Find a streamer

The home page lists streamers with open boards. Type part of their name or their Twitch name in the search box: results update as you type.

Open a streamer to see their page: every active board, with **Open** or **Closed** next to it. Choose **Send your photos** on the board you want.



Searching for a streamer on the home page.



A streamer's public page with their boards. "Watch on Twitch" opens their channel.

1. Fill in the form

1. **Username** and **country**: shown on stream if your submission is approved.
2. **Email**: only moderators see it, in case they need to contact you. It's never shown on stream.
3. **Description**: tell the story behind the photos (up to 2,000 characters).
4. **Photos** (and, on some boards, **a video**): click *Choose photos* or drag them in. Up to 5 files in total. Photos are compressed in your browser, and location and camera data (GPS/EXIF) is removed before upload.


Sending a video NEW

If the board allows it, the box says *Photos and video*. You can add **one video** per submission:

- It's compressed in your browser before uploading (720p), which can take a moment: the tile shows the progress.
- It's sent **without sound** and without metadata such as location.
- Only the first **60 seconds** are sent; you'll see a notice if yours is longer.


Check every frame

A video can show much more than a photo. Make sure no faces, names, documents, screens or location clues appear at any moment.



The form with two photos and a video added (the tile with the play icon).

If your browser can't compress videos, use an up-to-date Chrome, Edge, Safari or Firefox.



Form ready to review, with two photos added.


2. Review and confirm

Press **Review and submit**. A window shows your photos, the full privacy checklist, a short summary of how your data is used and four boxes to tick.

Complete the quick verification check and press **Send submission**. You can go *Back to edit* at any time before that.

Before you send: check every photo

- **No people**, unless the board says people are allowed (only you or adults who agreed). **Never children.**
- No names or addresses (letters, parcels, labels), documents or cards, QR codes.
- No screens showing accounts, chats or notifications.
- No location clues: views from windows, street signs, number plates, Wi-Fi stickers.




The review step: four confirmations and the anti-bot check.

3. Save your deletion code


After sending you get a **deletion code** like `RR-XXXXX-XXXXX-XXXXX-XXXXX`. It's the only way to delete your submission yourself, and it can't be shown again. Copy it or save it as a .txt file.

Delete your submission

Go to **Delete my submission** (footer of every page), paste the code and press *Delete permanently*. Your details and photos are erased straight away. Lost the code? Use the contact page from the email you used.



Submission received, with the deletion code.




Deleting a submission with its code.

Report a problem

Anyone can use **Report a problem** in the footer, for example if a photo on stream showed personal details, or something doesn’t work.

The report remembers which page or board it came from. The email field is optional: fill it in only if you’d like a reply. Site Admins read every report.



The problem report form.


03 Streamers: boards, team and the live deck

Streamers have their own account, linked to Twitch. With it you create your boards, choose who moderates them and open the deck on stream.

Sign in with Twitch

1. Open the site and press **Sign in** in the top bar.
2. Press **Continue with Twitch** and accept on Twitch. The site only reads your Twitch name and profile picture; it doesn't ask for any permission or see your password.
3. The first time, your account is a **request**: a Site Admin has to approve it.

Once approved, press **Continue with Twitch** again and you land in your control panel. Your password and two-step verification are the ones you use on Twitch.




Sign-in page: Twitch for streamers, username and password for staff.

Waiting for approval


Until a Site Admin approves your request, signing in shows this message and nothing else. Requests nobody approves are deleted after 30 days.

If your Twitch name is the same as one of the site's pages (for example `login` or `privacy`), it can't be used: contact the administrators.



A new streamer account waiting for approval.

Your control panel



A streamer's panel: one card per board, with its address, counters, switches and access buttons.


- **My public page** opens `/your-twitch-name`, which lists your active boards. Share it with your community.
- Each card shows how many submissions are **pending** and **approved**. You don't see the queue itself: your team moderates it.
- **Deck** opens the live view. **Edit** opens all the settings.
- **Board admin** / **Streamer** rows copy a link or a password to give to someone without an account (a moderator, or OBS on another computer).

Create a board

Press **New board**, give it a title and a description. The address is suggested from the title and always starts with your Twitch name.

Two settings are new:

- **Blur each new review in the deck** (on by default): each submission appears blurred on the deck until you reveal it.
- **Allow a video**: participants can add one short video. It takes more storage than photos, so turn it on only where it makes sense.



New board: the blur and video settings.

Your team NEW


In **Team** you choose up to **two Admins** who help you run your boards. They can create and edit your boards, moderate the queue and copy the board passwords. You keep the deck.

Add someone


- **Someone with an account**: type the username of an Admin who already has an account on the site and press **Add**.
- **Create a new account**: type a username and press **Create**. You get a **one-time password**, shown only once: send it privately with the username. It expires in 72 hours, and they choose their own password the first time they sign in.

Remove someone

Press **×** next to their name. They lose access to your boards at once; their account stays.



Adding a second Admin to the team.




A full team. “Waiting for first sign-in” disappears once they choose their password.

Choose your team carefully

Your team sees every submission, including participants’ emails. Only add people you trust, and remove anyone who leaves.

Showing photos live

Open **Deck** from your panel, or go to `/your-twitch-name/board/deck`. The deck only shows **approved** submissions, oldest first, and never receives emails. Press ⟳ to load new approvals; the page also refreshes itself every 30 minutes.



The deck. The current review is blurred until you press Reveal.

Each review starts blurred NEW

When you move to a new submission, it appears **blurred**. Check it off stream (for example on a second monitor), then click **Reveal** or anywhere on the photo. The **Blur** button (or **B**) blurs it again at any time. Your team can turn this off in the board settings.


Controls

Keys	Action
← →	Previous / next photo of the same submission
↑ ↓	Previous / next submission (it starts blurred again)
+ - 0	Zoom in, zoom out, reset zoom (you can also scroll, pinch or drag)
F	Fullscreen photo (Esc to close)
B	Blur or unblur instantly (works in fullscreen too)

The keys aren't shown on screen, so they don't appear on stream.

Videos

A video appears among the photos with a play icon. Select it to play it with the usual controls; there's no sound. The **Blur** button moves to the top so it doesn't cover the player.



A video in the deck.

The deck on another computer

To open the deck without your Twitch account (for example in OBS on another PC), copy the board's **Streamer** link and password from your panel. The session lasts 12 hours.

Tip

In OBS or a similar app, capture the browser window with the deck. Keep the control panel in a different window that is never captured.

04 Moderating a board

Two kinds of people moderate a board: the **Admins in the streamer's team** (with their own account) and **Board Admins**, who only have that board's queue password.


Opening the queue

- **Team Admins** and the board's admins: sign in and press **Queue** on the board's card.
- **Board Admins**: open the queue link (`/streamer/board/queue`) and enter the Board Admin password. It gives access to that board's queue and deck only, for 12 hours.

Streamers don't open the queue: their team moderates for them, so the streamer only sees approved submissions on the deck.

Before approving


Check every photo and every second of a video for faces, children, names, addresses, documents, screens, reflections and location clues, even if the participant confirmed there are none. When in doubt, don't approve. Never show the queue on stream.



Signing in with the Board Admin password.

The queue

- **Pending** / **Approved** / **All** filter the list; the search box finds a username or country.
- Click a photo to open it large, with zoom. Videos show a play icon and open in a player.
- **Approve** sends the submission to the deck. **Move to pending** takes it back out.
- **Delete**: press and hold the button. The submission and its files are erased permanently.
- If two moderators act on the same submission at the same time, only one action goes through and the other person sees a notice. Nothing is lost.




Pending submissions, oldest first. Emails are masked until you press “Show emails”.


05 Running boards

Admins have a personal account. A Site Admin creates it and sends you your username and a **one-time password**, which expires after 72 hours.

First sign-in



Sign in with your username and the one-time password.




Then choose your own password (12+ characters).

Admins in a streamer’s team NEW

A streamer (or a Site Admin) can add you to a streamer’s **team**. From then on you see **all of that streamer’s boards** in your panel, and you can moderate and edit them. Each streamer has at most two Admins.

You can only create boards **for the streamers whose team you’re in**. If you aren’t in any team yet, **New board** is disabled and the panel tells you why.

The control panel



An Admin in PixelWitch’s team: one card per board, with its streamer, status, links, counters, switches and access buttons.

- Each card shows the **streamer** and labels such as **Videos** or **People allowed**.
- **Active**: when off, the public page shows “not found”. The team can still open it. **Accepting submissions**: when off, the page stays visible but the form is closed.
- **Queue** / **Deck** open the board’s views. **Edit** opens all settings.
- **Board admin** / **Streamer** rows copy the **Link** and the **Password** to send to each person, by a private channel. The full name of each button appears when you hover over it.

Create a board


Press **New board** and choose the **streamer** it belongs to: only the streamers whose team you're in appear (Site Admins see every approved streamer). The board appears on that streamer's page, and its address starts with their Twitch name.

Turn on **People may appear in photos** only for boards like costume reviews. Participants then confirm that everyone shown agreed to appear; children are never allowed.

Blur each new review in the deck and **Allow a video** work as described in section 3.

Both board passwords are generated for you when you create the board.

> **Boards from before the update**
>
> Boards created before streamer accounts existed appear as *No streamer set* and have no public page. Once their streamer has signed in with Twitch and been approved, a Site Admin edits the board and chooses them.




Edit board: streamer, title and address.

Board passwords

In **Edit → Board passwords** you can copy either password, or **Regenerate** it (press and hold).

Regenerating signs out everyone who used the old password at once. Use it whenever someone leaves the team or a password may have leaked.




The new switches, and the streamer and Board Admin passwords.

Share a board

In **Edit → Shared with**, type another admin's username and press **Share**. They can then edit and moderate the board and copy its passwords.

Only the owner or a Site Admin can share, stop sharing or delete a board.

Delete board (press and hold) permanently deletes the board and all its submissions and photos.




Sharing and the danger zone at the end of the edit window.

Your account and two-step verification

In **Account** you can change your password and turn on **two-step verification**.

1. Press *Set up two-step verification*.
2. Scan the QR code with an authenticator app (Google Authenticator, Microsoft Authenticator, 1Password, Aegis, Bitwarden...).
3. Enter the 6-digit code and your password, and press *Turn on*.

From then on, signing in asks for a code from the app.



Setting up two-step verification.

Lost your phone?

Ask a Site Admin to reset your password. That also turns off two-step verification so you can set it up again.

06 Running the site

Site Admins see every board and have four extra tabs: **Streamers**, **Admins**, **Problems** and **Activity**. The **Owner** is a Site Admin with extra protection.

First-time setup: the Owner

On a new installation, nobody has an account yet. Open `/setup`, enter the **setup password** chosen by whoever installed the site, and create the first account. That account is the **Owner**.


Right after, the site asks the Owner to turn on **two-step verification**: the control panel stays locked until it's on, and it can't be turned off later.

1. Press **Set up two-step verification**.
2. Scan the QR code with an authenticator app.
3. Enter the 6-digit code and your password, and press **Turn on**.

The setup page disappears as soon as the Owner exists.

Updating an existing site


When a site from the previous version is updated, its oldest Site Admin becomes the Owner and is asked to turn on two-step verification at the next sign-in.



The Owner must turn on two-step verification before using the panel.


Streamers NEW

When a streamer signs in with Twitch for the first time, a request appears in **Streamers** → **Requests**, and the tab shows how many are waiting.




A request waiting for approval.

- **Approve** lets them in: they can create boards right away. **Reject** (press and hold) deletes the request. Requests nobody approves are deleted after 30 days.
- **Suspend** (press and hold, in **Active**): signs them out at once and hides their page and boards until you **Reactivate** them. Nothing is deleted.
- **Team**: under each active streamer you can add an existing Admin to their team (at most two) or remove one.



Active streamers with their teams.

Accounts



All staff accounts: role, two-step status, last sign-in, number of boards and the streamer teams they're in.


- The **Owner** appears first and has no buttons: no one can reset, demote or delete it from here.
- **Team of @streamer** shows which streamers an Admin helps. Accounts created by a streamer for their team appear here too.
- Making an Admin a Site Admin takes them out of streamer teams (they already see everything).

Owner password reset NEW


The Owner's password can only go back to the **setup password**:

- **Signed in**: **Account → Reset to the setup password**, with a current two-step code.
- **Locked out**: whoever hosts the site runs `npm run reset-owner` (add `-- --clear-2fa` if the phone was lost).


Either way the Owner is signed out everywhere and must sign in within 72 hours with the setup password, then choose a new one.



Resetting the Owner's password from their account.



New admin: username and role.




The one-time password is shown only once.

- **New admin**: choose *Admin* or *Site Admin*. Send the username and one-time password privately; it expires in 72 hours.
- **Reset password** (hold): issues a new one-time password, signs the person out everywhere and turns off their two-step verification.
- **Make / Remove Site Admin**: changes the role and signs them out so the new role applies. The site always keeps at least one Site Admin.
- **Delete account** (hold): their boards are transferred to you.

Problems

Reports sent with the *Report a problem* form arrive here, with the board and page they came from. Mark them resolved when handled; resolved reports are deleted after 30 days. Reports about personal data on stream deserve a quick answer: check the board and delete the submission if needed.




An open problem report.

Activity log

The **Activity** tab records who did what and when: sign-ins (including failed ones), password and two-step changes, accounts, boards, board passwords copied or regenerated, sharing, moderation decisions, deletions requested by participants and automatic clean-ups. Filter by type or board.

- It contains **no participant data**: no emails or usernames, only the submission's ID.
- Connections are pseudonymised: you can tell several attempts came from the same place, not who it was.
- Entries can't be edited or deleted for 365 days, not even directly in the database. Older entries are removed automatically.



The activity log.

07 Privacy and safety checklist

The site handles personal data and shows it to a public audience. These habits keep participants safe and the team compliant.

Every stream

- Capture only the deck window, never the queue or the panel.
- Look at each photo before showing it; press `B` the moment something personal appears.
- Delete any submission that slipped through, even if it was already shown.

Moderation

- Approve only photos with no faces (unless the board allows people), children, names, addresses, documents, screens or location clues.
- On boards with people, be extra careful: anyone who may not have agreed means delete.

Team and access

- Share board passwords only by private message, one person at a time.
- When someone leaves, regenerate the passwords they knew, and delete their account if they had one.
- Site Admins: turn on two-step verification.

Requests from participants

- Answer access or deletion requests sent by email within one month. To delete by hand, use Delete in the queue.
- If a photo was shown, also remove it from recordings and clips you control.

08 Troubleshooting

Problem	What to do
“Incorrect password” on a board	The password may have been regenerated. Ask the board’s admin for the current one. The queue only accepts the Board Admin password, not the streamer’s.
“Too many attempts”	Wait 15 minutes. Counters reset after a successful sign-in.
“This one-time password has expired”	It lasts 72 hours. Ask a Site Admin to press *Reset password*, or, for a team Admin, ask the streamer to remove and create the account again.
Two-step code rejected	Check the time on your phone is set automatically, and wait for the next code: each code works only once.
Signed out unexpectedly	Your password, role or two-step setting changed, a board password was regenerated, your streamer account was suspended or the 12-hour session ended. Sign in again.
Twitch: “waiting for approval” NEW	A Site Admin has to approve the streamer in *Streamers*. Then continue with Twitch again.
Twitch: “suspended” NEW	A Site Admin suspended the account. Contact the administrators.
“New board” is disabled NEW	Admins can only create boards for streamers whose team they’re in. Ask the streamer or a Site Admin to add you.
A board shows “No streamer set” NEW	It’s from before the update. A Site Admin edits it and chooses its streamer.
An old link gives “not found”	Board addresses are now `/streamer/board`. Copy the new link from the panel. Also check the *Active* switch, and whether the streamer is suspended.
“Submissions are closed”	*Accepting submissions* is off for that board.
A photo won’t upload	Use JPEG, PNG or WebP under 40 MB. Very detailed photos are compressed automatically; if it still fails, try a smaller one.
A video won’t add NEW	The board may not accept videos, or there is already one. If it says your browser can’t compress videos, use an up-to-date Chrome, Edge, Safari or Firefox. Very long or heavy videos: try a shorter clip.
The deck shows everything blurred NEW	That’s the new default: press *Reveal*. To show photos straight away, turn off *Blur each new review in the deck* in the board settings.
Photos stop loading in the deck after hours	Photo links are temporary. Press reload (⟳); the deck also refreshes every 30 minutes.
The verification check doesn’t appear	Disable extensions that block scripts for this site, or try another browser.

Can’t find the answer? Use **Report a problem** in the footer.