



4.2. Sensitivities (3)

- Ordinarily, one proceeds from Δ_S to Γ_{SS} , but there is a close relationship between deltas and rhos.
- **Interest rate rho:**

$$\rho = \rho_r \text{ (or } \rho_B) \doteq \frac{\partial \{C, P\}}{\partial r} = \partial_r \left\{ \phi [Se^{-yT}\mathcal{N}(\phi z_+) - Ke^{-rT}\mathcal{N}(\phi z_-)] \right\} = \phi K T e^{-rT} \mathcal{N}(\phi z_-)$$



- **Yield rho** (formerly sometimes nu = ν):

$$\rho_y \text{ (or } \rho_S) \doteq \frac{\partial \{C, P\}}{\partial y} = \partial_y \left\{ \phi [Se^{-yT}\mathcal{N}(\phi z_+) - Ke^{-rT}\mathcal{N}(\phi z_-)] \right\} = -\phi S T e^{-yT} \mathcal{N}(\phi z_+)$$

- Alternatively, if we define rate/yield vector \underline{r} with, e.g., $r_0 = r$ and $r_1 = y$ (corresponding to assets in \underline{S}), then rho vector can be defined as: $\underline{\rho} \doteq \nabla_{\underline{r}} \{C, P\}$ with $\rho_i \doteq \partial \{C, P\} / \partial r_i$
- Some firms use scaled rho, e.g. $0.01 \frac{\partial \{C, P\}}{\partial r}$ or $0.0001 \frac{\partial \{C, P\}}{\partial r}$. Conventions vary...