| EX NO: 7	**Examining Network Address Translation (NAT) using Cisco Packet**
DATE:	**Tracer**

Aim:

To Examine Network Address Translation (NAT) using Cisco Packet Tracer

1. Setting Up the Network Topology

- **Devices Required:**

    1. One or more PCs (for testing connectivity)

    2. One router (to configure NAT)

    3. One switch (to connect the PCs and the router)

    4. One server (to simulate an external network, like the internet)

- **Steps:**

1.Place the Devices: Drag and drop the required devices onto the workspace.

2.Connect the Devices: Use the appropriate cables (copper straight-through for PCs to the switch, copper cross-over for switch to router) to connect the devices.

3.Assign IP Addresses:

- Assign private IP addresses (e.g., 192.168.1.0/24) to the PCs and the router's internal interface.
- Assign a public IP address (e.g., 200.0.0.1/30) to the router's external interface.
- Assign an IP address to the server that simulates an external network (e.g., 200.0.0.2/30).

2. Configuring NAT on the Router

Steps:

1.Access the Router CLI: Click on the router and go to the CLI tab.

2.Enter Global Configuration Mode:

```
Router>enable
Router#config
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line.  End with CNTL/Z.
```

3.Configure Interfaces:

Set up the internal and external interfaces:

```
Router>enable
Router#config
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#ip nat inside
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#interface FastEthernet1/0
Router(config-if)#ip address 200.0.0.1 255.255.255.252
Router(config-if)#ip nat outside
Router(config-if)#no shutdown
```

Configure NAT Overload (PAT):

Define an access list to match the internal IP range:

- Configure NAT to translate the internal addresses to the external address.

- This configures PAT (Port Address Translation), which allows multiple internal IPs to share a single external IP.

```
Router(config)#
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#access-list 1 permit 192.168.1.0 0.0.0.255
Router(config)#ip nat inside source list 1 interface fastethernet 0/1 overload
```

3. Testing NAT

Steps:

1.Ping from a PC to the External Network:

From one of the PCs, open the command prompt and try to ping the external server (e.g., ping 200.0.0.2).

2.Verify NAT Translations:

On the router CLI, check the NAT translation table to see the active translations:

```
Router#show ip nat translations
```

3.Observe the Output:

The NAT translation table should show the mapping of the internal private IP addresses to the external public IP.

4.Advanced NAT Configurations (Optional)

Static NAT: Map a single internal IP to a single public IP:

```
Router#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip nat inside source static 192.168.1.10 200.0.0.10
```

Dynamic NAT: Use a pool of public IPs:

```
Router(config)#ip nat pool MYPOOL 200.0.0.10 200.0.0.20 netmask 255.255.255.0
Router(config)#ip nat inside source list 1 pool MYPOOL
```

5. Observing the Traffic

- Use the simulation mode in Packet Tracer to visually observe the NAT process as packets move from the internal network to the external network.

6. Saving the Configuration

Don't forget to save the configuration on the router to avoid losing the settings:

```
Router#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
```

Result:

Thus,we successfully, we examine network address Translations(NAT) using Cisco Packet Tracer.