```
Confluence Spaces •
                                                                                                                                                                                                                                                               ? Log in Sign up
                                                                                                                                                                                                                             Search
                                             Dashboard / LanguageManual
        Apache Hive
                                             LanguageManual DML
Pages
                                             Created by Confluence Administrator, last modified by Lars Francke on Aug 15, 2018
99 Blog
                                             Hive Data Manipulation Language
SPACE SHORTCUTS

    Hive Data Manipulation Language

How-to articles

    Loading files into tables

                                                            Syntax
CHILD PAGES
                                                            Synopsis
LanguageManual
                                                            Notes

    Inserting data into Hive Tables from queries

   LanguageManual DML
                                                            Syntax
                                                            Synopsis
                                                            Notes

    Dynamic Partition Inserts

                                                                  Example

    Additional Documentation

    Writing data into the filesystem from queries

                                                            Syntax
                                                            Synopsis
                                                            Notes

    Inserting values into tables from SQL

                                                            Syntax
                                                            Synopsis
                                                            Examples
                                                       Update
                                                            Syntax
                                                            Synopsis
                                                            Notes
                                                       Delete
                                                            Syntax
                                                            Synopsis
                                                            Notes
                                                      Merge
                                                            Syntax
                                                            Synopsis

    Performance Note

                                                            Notes
                                                            Examples
                                             There are multiple ways to modify data in Hive:
                                                LOAD

    INSERT

    into Hive tables from queries

    into directories from queries

    into Hive tables from SQL

    UPDATE

                                                DELETE
                                                MERGE
                                             EXPORT and IMPORT commands are also available (as of Hive 0.8).
                                             Loading files into tables
                                             Hive does not do any transformation while loading data into tables. Load operations are currently pure copy/move operations that move datafiles into locations corresponding to Hive tables.
                                             Syntax
                                               LOAD DATA [LOCAL] INPATH 'filepath' [OVERWRITE] INTO TABLE tablename [PARTITION (partcol1=val1, partcol2=val2 ...)]
                                               LOAD DATA [LOCAL] INPATH 'filepath' [OVERWRITE] INTO TABLE tablename [PARTITION (partcol1=val1, partcol2=val2 ...)] [INPUTFORMAT 'inputformat' SERDE 'serde'] (3.0 or later)
                                             Synopsis
                                             Load operations prior to Hive 3.0 are pure copy/move operations that move datafiles into locations corresponding to Hive tables.
                                                • filepath can be:

    a relative path, such as project/data1

    an absolute path, such as /user/hive/project/data1

                                                      • a full URI with scheme and (optionally) an authority, such as hdfs://namenode:9000/user/hive/project/data1
                                                • The target being loaded to can be a table or a partition. If the table is partitioned, then one must specify a specific partition of the table by specifying values for all of the partitioning columns.
                                                • filepath can refer to a file (in which case Hive will move the file into the table) or it can be a directory (in which case Hive will move all the files within that directory into the table). In either case, filepath addresses a set of files.
                                                • If the keyword LOCAL is specified, then:
                                                      • the load command will look for filepath in the local file system. If a relative path is specified, it will be interpreted relative to the user's current working directory. The user can specify a full URI for local files as well - for
                                                         example: file:///user/hive/project/data1
                                                      • the load command will try to copy all the files addressed by filepath to the target filesystem. The target file system is inferred by looking at the location attribute of the table. The copied data files will then be moved to the
                                                       • Note: If you run this command against a HiveServer2 instance then the local path refers to a path on the HiveServer2 instance. HiveServer2 must have the proper permissions to access that file.
                                                • If the keyword LOCAL is not specified, then Hive will either use the full URI of filepath, if one is specified, or will apply the following rules:
                                                       • If scheme or authority are not specified, Hive will use the scheme and authority from the hadoop configuration variable fs.default.name that specifies the Namenode URI.

    If the path is not absolute, then Hive will interpret it relative to /user/<username>

                                                      • Hive will move the files addressed by filepath into the table (or partition)
                                                • If the OVERWRITE keyword is used then the contents of the target table (or partition) will be deleted and replaced by the files referred to by filepath; otherwise the files referred by filepath will be added to the table.
                                             Additional load operations are supported by Hive 3.0 onwards as Hive internally rewrites the load into an INSERT AS SELECT.
                                                • If table has partitions, however, the load command does not have them, the load would be converted into INSERT AS SELECT and assume that the last set of columns are partition columns. It will throw an error if the file does not
                                                   conform to the expected schema.

    If table is bucketed then the following rules apply:

    In strict mode: launches an INSERT AS SELECT job.

                                                      • In non-strict mode: if the file names conform to the naming convention (if the file belongs to bucket 0, it should be named 000000_0 or 000000_0_copy_1, or if it belongs to bucket 2 the names should be like 000002_0 or 000000_0.
                                                         000002_0_copy_3, etc.) then it will be a pure copy/move operation, else it will launch an INSERT AS SELECT job.

    filepath can contain subdirectories, provided each file conforms to the schema.

    inputformat can be any Hive input format such as text, ORC, etc.

                                                • serde can be the associated Hive SERDE.
                                                • Both inputformat and serde are case sensitive.
                                             Example of such a schema:
                                               CREATE TABLE tab1 (col1 int, col2 int) PARTITIONED BY (col3 int) STORED AS ORC;
                                               LOAD DATA LOCAL INPATH 'filepath' INTO TABLE tab1;
                                             Here, partition information is missing which would otherwise give an error, however, if the file(s) located at filepath conform to the table schema such that each row ends with partition column(s) then the load will rewrite into an INSERT
                                             AS SELECT job.
                                             The uncompressed data should look like this:
                                             (1,2,3), (2,3,4), (4,5,3) etc.
                                             Notes

    filepath cannot contain subdirectories (except for Hive 3.0 or later, as described above).

                                                • If the keyword LOCAL is not given, filepath must refer to files within the same filesystem as the table's (or partition's) location.
                                                • Hive does some minimal checks to make sure that the files being loaded match the target table. Currently it checks that if the table is stored in sequencefile format, the files being loaded are also sequencefiles, and vice versa.

    A bug that prevented loading a file when its name includes the "+" character is fixed in release 0.13.0 (HIVE-6048).

    Please read CompressedStorage if your datafile is compressed.

                                             Inserting data into Hive Tables from queries
                                             Query Results can be inserted into tables by using the insert clause.
                                             Syntax
                                             Standard syntax:
                                             INSERT OVERWRITE TABLE tablename1 [PARTITION (partcol1=val1, partcol2=val2 ...) [IF NOT EXISTS]] select_statement1 FROM from_statement;
                                             INSERT INTO TABLE tablename1 [PARTITION (partcol1=val1, partcol2=val2 ...)] select_statement1 FROM from_statement;
                                             Hive extension (multiple inserts):
                                             FROM from_statement
                                             INSERT OVERWRITE TABLE tablename1 [PARTITION (partcol1=val1, partcol2=val2 ...) [IF NOT EXISTS]] select_statement1
                                             [INSERT OVERWRITE TABLE tablename2 [PARTITION ... [IF NOT EXISTS]] select_statement2]
                                             [INSERT INTO TABLE tablename2 [PARTITION ...] select_statement2] ...;
                                             FROM from_statement
                                             INSERT INTO TABLE tablename1 [PARTITION (partcol1=val1, partcol2=val2 ...)] select_statement1
                                             [INSERT INTO TABLE tablename2 [PARTITION ...] select_statement2]
                                             [INSERT OVERWRITE TABLE tablename2 [PARTITION ... [IF NOT EXISTS]] select_statement2] ...;
                                             Hive extension (dynamic partition inserts):
                                             INSERT OVERWRITE TABLE tablename PARTITION (partcol1[=val1], partcol2[=val2] ...) select_statement FROM from_statement;
                                             INSERT INTO TABLE tablename PARTITION (partcol1[=val1], partcol2[=val2] ...) select_statement FROM from_statement;
                                             Synopsis

    INSERT OVERWRITE will overwrite any existing data in the table or partition

                                                      • unless IF NOT EXISTS is provided for a partition (as of Hive 0.9.0).
                                                      • As of Hive 2.3.0 (HIVE-15880), if the table has TBLPROPERTIES ("auto.purge"="true") the previous data of the table is not moved to Trash when INSERT OVERWRITE query is run against the table. This functionality is
                                                         applicable only for managed tables (see managed tables) and is turned off when "auto.purge" property is unset or set to false.
                                                • INSERT INTO will append to the table or partition, keeping the existing data intact. (Note: INSERT INTO syntax is only available starting in version 0.8.)
                                                       • As of Hive 0.13.0, a table can be made immutable by creating it with TBLPROPERTIES ("immutable"="true"). The default is "immutable"="false".
                                                         INSERT INTO behavior into an immutable table is disallowed if any data is already present, although INSERT INTO still works if the immutable table is empty. The behavior of INSERT OVERWRITE is not affected by the
                                                         "immutable" table property.
                                                         An immutable table is protected against accidental updates due to a script loading data into it being run multiple times by mistake. The first insert into an immutable table succeeds and successive inserts fail, resulting in
                                                         only one set of data in the table, instead of silently succeeding with multiple copies of the data in the table.
                                                • Inserts can be done to a table or a partition. If the table is partitioned, then one must specify a specific partition of the table by specifying values for all of the partitioning columns. If hive.typecheck.on.insert is set to true, these
                                                   values are validated, converted and normalized to conform to their column types (Hive 0.12.0 onward).

    Multiple insert clauses (also known as Multi Table Insert) can be specified in the same query.

                                                • The output of each of the select statements is written to the chosen table (or partition). Currently the OVERWRITE keyword is mandatory and implies that the contents of the chosen table or partition are replaced with the output of
                                                   corresponding select statement.
                                                • The output format and serialization class is determined by the table's metadata (as specified via DDL commands on the table).
                                                • As of Hive 0.14, if a table has an OutputFormat that implements AcidOutputFormat and the system is configured to use a transaction manager that implements ACID, then INSERT OVERWRITE will be disabled for that table. This is
                                                   to avoid users unintentionally overwriting transaction history. The same functionality can be achieved by using TRUNCATE TABLE (for non-partitioned tables) or DROP PARTITION followed by INSERT INTO.

    As of Hive 1.1.0 the TABLE keyword is optional.

                                                • As of Hive 1.2.0 each INSERT INTO T can take a column list like INSERT INTO T (z, x, c1). See Description of HIVE-9481 for examples.
                                             Notes
                                                • Multi Table Inserts minimize the number of data scans required. Hive can insert data into multiple tables by scanning the input data just once (and applying different query operators) to the input data.
                                                • Starting with Hive 0.13.0, the select statement can include one or more common table expressions (CTEs) as shown in the SELECT syntax. For an example, see Common Table Expression.
                                             Dynamic Partition Inserts
                                               Version information
                                                   This information reflects the situation in Hive 0.12; dynamic partition inserts were added in Hive 0.6.
                                             In the dynamic partition inserts, users can give partial partition specifications, which means just specifying the list of partition column names in the PARTITION clause. The column values are optional. If a partition column value is given,
                                             we call this a static partition, otherwise it is a dynamic partition. Each dynamic partition column has a corresponding input column from the select statement. This means that the dynamic partition creation is determined by the value of
                                             the input column. The dynamic partition columns must be specified last among the columns in the SELECT statement and in the same order in which they appear in the PARTITION() clause. As of Hive 3.0.0 (HIVE-19083) there is no
                                             need to specify dynamic partition columns. Hive will automatically generate partition specification if it is not specified.
                                             Dynamic partition inserts are disabled by default prior to Hive 0.9.0 and enabled by default in Hive 0.9.0 and later. These are the relevant configuration properties for dynamic partition inserts:
                                               Configuration property
                                                                                                               Note
                                                                                                    Default
                                                                                                               Needs to be set to true to enable dynamic partition inserts
                                               hive.exec.dynamic.partition
                                                                                                    true
                                                                                                               In strict mode, the user must specify at least one static partition in case the user accidentally overwrites all partitions, in nonstrict mode all partitions are
                                               hive.exec.dynamic.partition.mode
                                                                                                    strict
                                                                                                               allowed to be dynamic
                                                                                                    100
                                               hive.exec.max.dynamic.partitions.pernode
                                                                                                               Maximum number of dynamic partitions allowed to be created in each mapper/reducer node
                                                                                                               Maximum number of dynamic partitions allowed to be created in total
                                               hive.exec.max.dynamic.partitions
                                                                                                    1000
                                               hive.exec.max.created.files
                                                                                                    100000
                                                                                                               Maximum number of HDFS files created by all mappers/reducers in a MapReduce job
                                               hive.error.on.empty.partition
                                                                                                    false
                                                                                                               Whether to throw an exception if dynamic partition insert generates empty results
                                             Example
                                               FROM page_view_stg pvs
                                               INSERT OVERWRITE TABLE page_view PARTITION(dt='2008-06-08', country)
                                                        SELECT pvs.viewTime, pvs.userid, pvs.page_url, pvs.referrer_url, null, null, pvs.ip, pvs.cnt
                                             Here the country partition will be dynamically created by the last column from the SELECT clause (i.e. pvs.cnt). Note that the name is not used. In nonstrict mode the dt partition could also be dynamically created.
                                             Additional Documentation

    Design Document

    Original design doc

                                                      • HIVE-936
                                                • Tutorial: Dynamic-Partition Insert

    HCatalog Dynamic Partitioning

    Usage with Pig

                                                      • Usage from MapReduce
                                             Writing data into the filesystem from queries
                                             Query results can be inserted into filesystem directories by using a slight variation of the syntax above:
                                             Syntax
                                               Standard syntax:
                                                INSERT OVERWRITE [LOCAL] DIRECTORY directory1
                                                  [ROW FORMAT row_format] [STORED AS file_format] (Note: Only available starting with Hive 0.11.0)
                                                  SELECT ... FROM ...
                                               Hive extension (multiple inserts):
                                               FROM from_statement
                                               INSERT OVERWRITE [LOCAL] DIRECTORY directory1 select_statement1
                                                [INSERT OVERWRITE [LOCAL] DIRECTORY directory2 select_statement2] ...
                                                row_format
                                                  : DELIMITED [FIELDS TERMINATED BY char [ESCAPED BY char]] [COLLECTION ITEMS TERMINATED BY char]
                                                         [MAP KEYS TERMINATED BY char] [LINES TERMINATED BY char]
                                                        [NULL DEFINED AS char] (Note: Only available starting with Hive 0.13)
                                             Synopsis
                                                • Directory can be a full URI. If scheme or authority are not specified, Hive will use the scheme and authority from the hadoop configuration variable fs.default.name that specifies the Namenode URI.

    If LOCAL keyword is used, Hive will write data to the directory on the local file system.

                                                • Data written to the filesystem is serialized as text with columns separated by 'A and rows separated by newlines. If any of the columns are not of primitive type, then those columns are serialized to JSON format.
                                             Notes
                                                • INSERT OVERWRITE statements to directories, local directories, and tables (or partitions) can all be used together within the same query.
                                                • INSERT OVERWRITE statements to HDFS filesystem directories are the best way to extract large amounts of data from Hive. Hive can write to HDFS directories in parallel from within a map-reduce job.
                                                • The directory is, as you would expect, OVERWRITten; in other words, if the specified path exists, it is clobbered and replaced with the output.
                                                • As of Hive 0.11.0 the separator used can be specified; in earlier versions it was always the 'A character (\001). However, custom separators are only supported for LOCAL writes in Hive versions 0.11.0 to 1.1.0 – this bug is fixed in
                                                   version 1.2.0 (see HIVE-5672).
                                                 • In Hive 0.14, inserts into ACID compliant tables will deactivate vectorization for the duration of the select and insert. This will be done automatically. ACID tables that have data inserted into them can still be queried using
                                                   vectorization.
                                             Inserting values into tables from SQL
                                             The INSERT...VALUES statement can be used to insert data into tables directly from SQL.
                                               Version Information
                                                  INSERT...VALUES is available starting in Hive 0.14.
                                             Syntax
                                             ndard Syntax:
                                             ERT INTO TABLE tablename [PARTITION (partcol1[=val1], partcol2[=val2] ...)] VALUES values_row [, values_row ...]
                                             re values row is:
                                             alue [, value ...] )
                                             re a value is either null or any valid SQL literal
                                             Synopsis

    Each row listed in the VALUES clause is inserted into table tablename.

                                                • Values must be provided for every column in the table. The standard SQL syntax that allows the user to insert values into only some columns is not yet supported. To mimic the standard SQL, nulls can be provided for columns the
                                                   user does not wish to assign a value to.

    Dynamic partitioning is supported in the same way as for INSERT...SELECT.

                                                • If the table being inserted into supports ACID and a transaction manager that supports ACID is in use, this operation will be auto-committed upon successful completion.
                                                • Hive does not support literals for complex types (array, map, struct, union), so it is not possible to use them in INSERT INTO...VALUES clauses. This means that the user cannot insert data into a complex datatype column using the
                                                   INSERT INTO...VALUES clause.
                                             Examples
                                               CREATE TABLE students (name VARCHAR(64), age INT, gpa DECIMAL(3, 2))
                                                 CLUSTERED BY (age) INTO 2 BUCKETS STORED AS ORC;
                                                INSERT INTO TABLE students
                                                  VALUES ('fred flintstone', 35, 1.28), ('barney rubble', 32, 2.32);
                                               CREATE TABLE pageviews (userid VARCHAR(64), link STRING, came_from STRING)
                                                  PARTITIONED BY (datestamp STRING) CLUSTERED BY (userid) INTO 256 BUCKETS STORED AS ORC;
                                               INSERT INTO TABLE pageviews PARTITION (datestamp = '2014-09-23')
                                                 VALUES ('jsmith', 'mail.com', 'sports.com'), ('jdoe', 'mail.com', null);
                                               INSERT INTO TABLE pageviews PARTITION (datestamp)
                                                 VALUES ('tjohnson', 'sports.com', 'finance.com', '2014-09-23'), ('tlee', 'finance.com', null, '2014-09-21');
                                               INSERT INTO TABLE pageviews
                                                  VALUES ('tjohnson', 'sports.com', 'finance.com', '2014-09-23'), ('tlee', 'finance.com', null, '2014-09-21');
                                             Update
                                               Version Information
                                                  UPDATE is available starting in Hive 0.14.
                                                  Updates can only be performed on tables that support ACID. See Hive Transactions for details.
                                             Syntax
                                               Standard Syntax:
                                               UPDATE tablename SET column = value [, column = value ...] [WHERE expression]
                                             Synopsis

    The referenced column must be a column of the table being updated.

                                                • The value assigned must be an expression that Hive supports in the select clause. Thus arithmetic operators, UDFs, casts, literals, etc. are supported. Subqueries are not supported.

    Only rows that match the WHERE clause will be updated.

    Partitioning columns cannot be updated.

    Bucketing columns cannot be updated.

                                                • In Hive 0.14, upon successful completion of this operation the changes will be auto-committed.
                                             Notes
                                                • Vectorization will be turned off for update operations. This is automatic and requires no action on the part of the user. Non-update operations are not affected. Updated tables can still be queried using vectorization.
                                                • In version 0.14 it is recommended that you set hive.optimize.sort.dynamic.partition=false when doing updates, as this produces more efficient execution plans.
                                             Delete
                                               Version Information
                                                  DELETE is available starting in Hive 0.14.
                                                  Deletes can only be performed on tables that support ACID. See Hive Transactions for details.
                                             Syntax
                                               Standard Syntax:
                                               DELETE FROM tablename [WHERE expression]
                                             Synopsis

    Only rows that match the WHERE clause will be deleted.

                                                • In Hive 0.14, upon successful completion of this operation the changes will be auto-committed.
                                             Notes
                                                • Vectorization will be turned off for delete operations. This is automatic and requires no action on the part of the user. Non-delete operations are not affected. Tables with deleted data can still be queried using vectorization.
                                                • In version 0.14 it is recommended that you set hive optimize sort dynamic partition = false when doing deletes, as this produces more efficient execution plans.
                                             Merge
                                               ⚠ Version Information
                                                   MERGE is available starting in Hive 2.2.
                                                   Merge can only be performed on tables that support ACID. See Hive Transactions for details.
                                             Syntax
                                               Standard Syntax:
                                               MERGE INTO <target table> AS T USING <source expression/table> AS S
                                               ON <boolean expression1>
                                               WHEN MATCHED [AND <boolean expression2>] THEN UPDATE SET <set clause list>
                                               WHEN MATCHED [AND <boolean expression3>] THEN DELETE
                                               WHEN NOT MATCHED [AND <boolean expression4>] THEN INSERT VALUES<value list>
                                             Synopsis
                                                • Merge allows actions to be performed on a target table based on the results of a join with a source table.
                                                • In Hive 2.2, upon successful completion of this operation the changes will be auto-committed.
                                             Performance Note
                                             SQL Standard requires that an error is raised if the ON clause is such that more than 1 row in source matches a row in target. This check is computationally expensive and may affect the overall runtime of a MERGE statement
                                             significantly. hive.merge.cardinality.check=false may be used to disable the check at your own risk. If the check is disabled, but the statement has such a cross join effect, it may lead to data corruption.
                                             Notes
                                                • 1, 2, or 3 WHEN clauses may be present; at most 1 of each type: UPDATE/DELETE/INSERT.

    WHEN NOT MATCHED must be the last WHEN clause.

                                                • If both UPDATE and DELETE clauses are present, the first one in the statement must include [AND <boolean expression>].
                                                • Vectorization will be turned off for merge operations. This is automatic and requires no action on the part of the user. Non-delete operations are not affected. Tables with deleted data can still be queried using vectorization.
                                             Examples

    See here.

                                             7 people like this
                                                                                                                                                                                                                                                                       No labels
                                                                                                    Powered by a free Atlassian Confluence Open Source Project License granted to Apache Software Foundation. Evaluate Confluence today.
                                                                                                                   This Confluence installation runs a Free Gliffy License - Evaluate the Gliffy Confluence Plugin for your Wiki!
                                                                                                                                Powered by Atlassian Confluence 7.5.0 · Report a bug · Atlassian News
```