# Locking

Mythili Vutukuru CSE, IIT Bombay

#### Recap: Shared data access in threads

```
load counter → reg
reg = reg + 1
store reg → counter
```

- The C code "counter = counter + 1" is compiled into multiple instructions
  - Load counter variable from memory into register
  - Increment register
  - Store register back into memory of counter variable
- What happens when two threads run this line of code concurrently?
  - Counter is 0 initially
  - T1 loads counter into register, increment reg
  - Context switch, register (value 1) saved
  - T2 runs, loads counter 0 from memory
  - T2 increments register, stores to memory
  - T1 resumes, stores register value to counter
  - Counter value rewritten to 1 again
  - Final counter value is 1, expected value is 2

Both threads updated the value, not consecutively but concurrently leading to unexpected result.

```
T1
load counter → reg
reg = reg + 1
(context switch, save reg)

load counter → reg
reg = reg + 1
store reg → counter

(resume, restore reg)
store reg → counter
```

#### Recap: Race conditions, critical sections

- Incorrect execution of code due to concurrency is called race condition
  - Due to unfortunate timing of context switches, atomicity of data update violated
- Race conditions happen when we have concurrent execution on shared data
  - Threads sharing common data in memory image of user processes
  - Processes in kernel mode sharing OS data structures
- We require mutual exclusion on some parts of user or OS code
  - Concurrent execution by multiple threads/processes should not be permitted
- Parts of program that need to be executed with mutual exclusion for correct operation are called critical sections
  - Present in multi-threaded programs, OS code
- How to access critical sections with mutual exclusion? Using locks

#### Using locks

- Locks are special variables that provide mutual exclusion
  - Provided by threading libraries
  - Can call lock/acquire and unlock/release functions on a lock
- When a thread T1 acquires a lock, another thread T2 cannot acquire same lock
  - Execution of T2 stops at the lock statement
  - T2 can proceed only after T1 releases the lock
- Acquire lock → critical section → release lock ensures mutual exclusion in critical section

```
int counter;
pthread mutex t m;
void start fn() {
  for(int i=0; i < 1000; i++) {
    pthread mutex lock(&m)
    counter = counter + 1
    pthread mutex unlock(&m)
main() {
  counter = 0
  pthread tt1, t2
  pthread create(&t1,.., start fn, ..)
  pthread_create(&t2, .., start fn,..)
  pthread join(t1, ..)
  pthread join(t2, ..)
  print counter
```

#### How to implement a lock?

- Goals of a lock implementation
  - Mutual exclusion (obviously!)
  - Fairness: all threads should eventually get the lock, and no thread should starve
  - Low overhead: acquiring, releasing, and waiting for lock should not consume too many resources
- Implementation of locks are needed for both userspace programs (e.g., pthreads library) and kernel code
  - Separate implementations in user libraries and OS

#### Incorrect lock implementation

- Example of incorrect lock implementation
  - Use variable isLocked to indicate lock status (0 means lock is free, 1 indicates it is acquired)
  - To acquire lock, a thread waits as long as lock is busy, and then sets it to 1 (acquired)
  - One interleaving of executions (left) works while another (right) may not work

```
int isLocked = 0

void acquire_lock() {
   while(isLocked == 1); //wait
   isLocked = 1
}

void release_lock() {
   isLocked = 0
}
```

```
while(isLocked==1);
isLocked = 1

CRITICAL SECTION

while(isLocked==1);
while(isLocked==1);
while(isLocked==1);
while(isLocked==1);
isLocked = 0

CRITICAL SECTION
```

```
while(isLocked==1);
(context switch, PC saved)

while(isLocked==1);
isLocked = 1
CRITICAL SECTION

T2

While(isLocked==1);
isLocked = 1
CRITICAL SECTION
```

#### Hardware atomic instructions

- Need a way to check a variable and set its value atomically
  - No context switch between checking lock variable and setting it
  - But user programs have no control over context switches
- Solution: use hardware atomic instructions
- Example: test-and-set hardware atomic instruction
  - Two arguments: address of variable and new value to set
  - Writes new value into a variable and returns old value in one single step
  - Entire logic implemented in hardware, runs in one single step

```
int TestAndSet(int *old_ptr, int new) {
    int old = *old_ptr; // fetch old value at old_ptr
    *old_ptr = new; // store 'new' into old_ptr
    return old; // return the old value
}
```

#### Lock implementation using test-and-set

- Simple lock can be implemented using test-and-set instruction
  - isLocked variable indicates lock status (0=free, 1=acquired)
  - If test-and-set(&isLocked, 1) returns 1, it means lock is not free, wait
  - If test-and-set(&isLocked, 1) returns 0, lock was free and was acquired, done!
- No further race conditions possible with this lock implementation
  - All modern lock implementations based on such hardware instructions
  - Software based locking algorithms do not work well in modern systems

```
int isLocked = 0

void acquire_lock() {
   while(test-and-set(&isLocked, 1) == 1); //wait
   //return, lock is acquired
}
```

```
typedef struct __lock_t {
1
        int flag;
    } lock_t;
3
4
    void init(lock_t *lock) {
5
        // 0 indicates that lock is available, 1 that it is held
6
        lock -> flag = 0;
8
9
    void lock(lock_t *lock) {
10
        while (TestAndSet(&lock->flag, 1) == 1)
11
             ; // spin-wait (do nothing)
12
13
14
    void unlock(lock_t *lock) {
15
        lock -> flag = 0;
16
17
```

Figure 28.3: A Simple Spin Lock Using Test-and-set

Image credit: OSTEP

#### Another instruction: compare-and-swap

- Another example: compare-and-swap (CAS) hardware atomic instruction
  - Three arguments: address of variable, expected old value, new value
  - If variable has expected old value, then write new value and return true; else do not change variable and return false

```
int CompareAndSwap(int *ptr, int expected, int new) {
    int actual = *ptr;
    if (actual == expected)
        *ptr = new;
    return actual;
}
```

Figure 28.4: Compare-and-swap

Image credit: OSTEP

#### Lock using CAS

- Lock implementation using compare-and-swap
  - If compare-and-swap(&isLocked, 0, 1) returns false, it means lock is busy, wait
  - If compare-and-swap(&isLocked, 0, 1) returns true, it means old value of lock was 0 and was changed to 1, so lock has been acquired, done!

```
int isLocked = 0

void acquire_lock() {
   while(compare-and-swap(&isLocked, 0, 1) == false); //wait
}
```

### Evaluating spinlock implementations

- Correctness: does it lead to mutual exclusion correctly?
- Fairness: are all waiting threads treated fairly? Can we guarantee that every waiting thread will get its turn?
  - The implementations we saw here do not guarantee it
- Performance: overheads of having threads spin for lock
  - Single core system: what happens when thread holding lock is context switched out and other threads that are scheduled continue to spin for lock?
  - Problem less severe in multicore system. Why? (Thread holding lock can finish while other threads are spinning)

#### Spinlock vs. sleeping mutex

- Simple lock implementation seen here is a spinlock
  - If thread T1 has acquired lock, and thread T2 also wants lock, then T2 will keep spinning in a while loop till lock is free
- Another implementation option: thread can go to sleep (be blocked) while waiting for lock, saving CPU cycles
  - OS blocks waiting thread, context switch to another thread/process
  - Such locks are called (sleeping) mutex
- Threading libraries provide APIs for both spinlocks and sleeping mutex
  - Better to use spinlock if locks are expected to be held for short time, avoid context switch overhead
  - Better to use sleeping mutex if critical sections are long

#### Guidelines for using locks

- When writing multithreaded programs, careful locking discipline
  - Protect each shared data structure with one lock
  - Locks can be coarse-grained (one big fat lock) or fine-grained (many smaller locks)
  - Any thread wanting to access shared data must acquire corresponding lock before access, release lock after access
- If using third-party libraries in multi-threaded programs, check the documentation to see if if the library is thread-safe
  - Thread-safe implementations work correctly with concurrent access

#### Guidelines for using locks

- Good practice to acquire locks for both reading and writing data
  - Why locks for reading? We do not want to read incorrect data while another thread is concurrently updating the data
  - Some libraries provide separate locks for reading and writing, allowing multiple threads to concurrently read data if no other thread is writing
- Good practice to minimize use of locks, use only when needed
  - Why? Use of locks serializes thread access, removes gains due to parallelism
  - Example of minimizing lock usage: instead of each thread updating shared global counter, let each thread update a local counter, and periodically update global counter

```
typedef struct __counter_t {
1
        int
2
                         value;
        pthread_mutex_t lock;
3
    } counter_t;
4
5
   void init(counter_t *c) {
6
        c->value = 0;
7
        Pthread_mutex_init(&c->lock, NULL);
8
9
10
    void increment(counter_t *c) {
11
        Pthread_mutex_lock(&c->lock);
12
13
        c->value++;
        Pthread_mutex_unlock(&c->lock);
14
15
16
    void decrement(counter_t *c) {
17
        Pthread mutex lock (&c->lock);
18
19
        c->value--;
        Pthread_mutex_unlock(&c->lock);
20
21
22
    int get(counter_t *c) {
23
        Pthread_mutex_lock(&c->lock);
24
25
        int rc = c->value;
        Pthread_mutex_unlock(&c->lock);
26
        return rc;
27
28
```

Figure 29.2: A Counter With Locks

Image credit: OSTEP

#### Locking in xv6

- No threads in xv6, no two user programs can access same memory image
  - No need for userspace locks like pthreads mutex
- However, scope for concurrency in xv6 kernel
  - Two processes in kernel mode in different CPUs can access same kernel data structures like ptable
  - Even in single core, when a process is running in kernel mode, another trap occurs, trap handler can access data that was being accessed by previous kernel code
- Solution: spinlocks used to protect critical sections
  - Limit concurrent access to kernel data structures that can result in race conditions
- xv6 also has a sleeping lock (built on spinlock, not discussed)

#### Spinlocks in xv6

- Acquiring lock: uses xchg x86 atomic instruction (test and set)
  - Atomically set lock variable to new value and returns previous value
  - If previous value is 0, it means free lock has been acquired, success!

1573 void

• If previous value is 1, it means lock is held by someone, continue to spin in a busy

1574 acquire(struct spinlock \*lk)

while loop till success

```
1575 {
                                                                       pushcli(); // disable interrupts to avoid deadlock.
                                                                1576
                                                                1577
                                                                       if(holding(lk))
                                                                         panic("acquire");
                                                                1578
1500 // Mutual exclusion lock.
                                                               1579
1501 struct spinlock {
                                                                1580
                                                                       // The xchg is atomic.
1502
      uint locked;
                          // Is the lock held?
                                                                       while(xchg(\&lk \rightarrow locked, 1) != 0)
                                                                1581
1503
                                                                1582
1504
      // For debugging:
                                                                1583
                          // Name of lock.
1505
       char *name:
                                                                1584
                                                                       // Tell the C compiler and the processor to not move loads or stores
1506
       struct cpu *cpu:
                         // The cpu holding the lock.
                         // The call stack (an array of program 1585
                                                                       // past this point, to ensure that the critical section's memory
1507
       uint pcs[10];
                                                                1586
                                                                       // references happen after the lock is acquired.
1508
                          // that locked the lock.
                                                                1587
                                                                       __sync_synchronize();
1509 };
                                                                1588
                                                                       // Record info about lock acquisition for debugging.
                                                                1589
                                                                1590
                                                                       1k \rightarrow cpu = mycpu();
                                                                1591
                                                                       getcallerpcs(&lk, lk->pcs);
                                                                1592 }
```

## Disabling interrupts for kernel spinlocks (1)

- When acquiring kernel spinlock, disables interrupts on CPU core: why?
  - What if interrupt and handler requests same lock: deadlock
  - Interrupts disabled only on local core, OK to spin for lock on another core
  - Why disable interrupts before even acquiring lock? (otherwise, vulnerable window after lock acquired and before interrupts disabled)
- Disabling interrupts not needed for userspace locks like pthread mutex
  - Kernel interrupt handlers will not deadlock for userspace locks

The kernel cannot release the lock until it resumes execution, but the interrupt handler is spinning on the same lock, preventing the kernel from resuming.

#### Process in kernel mode

Kernel spinlock L acquired Interrupt, switch to trap handler

Interrupt handler

Spin to acquire L DEADLOCK

#### Process in kernel mode

## Disabling interrupts for kernel spinlocks (2)

- Function pushcli: disables interrupts on CPU core before spinning for lock
  - Interrupts stay disabled until lock is released
- What if multiple spinlocks are acquired?
  - Interrupts must stay disabled until all locks are released
- Disabling/enabling interrupts:
  - pushcli disables interrupts on first lock acquire, increments count for future locks
  - popcli decrements count, renables interrupts only when all locks released

```
1662 // Pushcli/popcli are like cli/sti except that they are matched:
1663 // it takes two popcli to undo two pushcli. Also, if interrupts
1664 // are off, then pushcli, popcli leaves them off.
1665
1666 void
1667 pushcli(void)
1668 {
1669
       int eflags:
1670
1671
       eflags = readeflags();
1672
       cli();
       if(mycpu()->ncli == 0)
1673
1674
         mycpu()->intena = eflags & FL_IF;
1675
       mycpu()->ncli += 1;
1676
1677
1678 void
1679 popcli(void)
1680 {
1681
       if(readeflags()&FL_IF)
1682
         panic("popcli - interruptible");
1683
      if(--mycpu()->ncli < 0)</pre>
1684
         panic("popcli");
       if(mycpu()->ncli == 0 && mycpu()->intena)
sti(); enable interrupts only when all locks released
1685
1686
1687 }
                                                                20
         cli: removes the interrupt flag
```

cli : removes the interrupt flag sti : sets the interrupt flag.

#### Recap: Context switching in xv6 (1)

- Every CPU has a scheduler thread (special process that runs scheduler code)
- Scheduler goes over list of processes and switches to one of the runnable ones
- The special function "swtch" performs the actual context switch
  - Save context on kernel stack of old process
  - Restore context from kernel stack of new process

save restore kernel context from the kernel stack.

```
2757 void
2758 scheduler(void)
       struct proc *p:
       struct cpu *c = mycpu();
2762
       c \rightarrow proc = 0;
2763
2764
       for(;;){
2765
         // Enable interrupts on this processor.
2766
2767
2768
         // Loop over process table looking for process to run.
2769
         acquire(&ptable.lock);
2770
        for(p = ptable.proc; p < &ptable.proc[NPROC]; p++){</pre>
2771
           if(p->state != RUNNABLE)
2772
             continue:
2773
2774
           // Switch to chosen process. It is the process's job
2775
           // to release ptable.lock and then reacquire it
2776
           // before jumping back to us.
2777
           c->proc = p;
2778
           switchuvm(p);
2779
           p->state = RUNNING;
2780
2781
           swtch(&(c->scheduler), p->context);
2782
           switchkvm():
2783
2784
           // Process is done running for now.
2785
           // It should have changed its p->state before coming back.
2786
           c \rightarrow proc = 0;
2787
2788
         release(&ptable.lock);
2789
2790
2791 }
```

### Recap: Context switching in xv6 (2)

- After running for some time, the process switches back to the scheduler thread, when:
  - Process has terminated (exit system call)
  - Process needs to sleep (e.g., blocking read system call)
  - Process yields after running for long (timer interrupt)
- Process calls "sched" which calls "swtch" to switch to scheduler thread again
- Scheduler thread runs its loop and picks next process to run, and the story repeats

```
// Jump into the scheduler, never to return.
2662
2663
       curproc->state = ZOMBIE;
2664
       sched();
2665
       panic("zombie exit");
2666 }
                            // Go to sleep.
                    2894
                    2895
                            p->chan = chan;
                    2896
                            p->state = SLEEPING;
                    2897
                    2898
                            sched();
                    2899
  2826 // Give up the CPU for one scheduling round.
 2827 void
  2828 yield(void)
  2829 {
 2830
        acquire(&ptable.lock);
        myproc()->state = RUNNABLE;
 2831
 2832
        sched();
```

release(&ptable.lock);


2833

2834 }

## ptable.lock (1)

```
2409 struct {
2410    struct spinlock lock;
2411    struct proc proc[NPROC];
2412 } ptable;
```

- The process table protected by a lock, any access to ptable must be done with ptable.lock held
- Normally, a process in kernel mode acquires ptable.lock, changes ptable in some way, releases lock
  - Example: when allocproc allocates new struct proc
- But during context switch from process P1 to P2, ptable structure is being changed all through context switch, so when to release lock?
  - P1 acquires lock, switches to scheduler, switches to P2, P2 releases lock



### ptable.lock (2)

- Every function that calls sched() to give up CPU will do so with ptable.lock held
- Which functions invoke sched() to give up CPU?
  - Yield: process gives up CPU due to timer interrupt
  - Sleep: when process wishes to block
  - Exit: when process terminates
- Every function where a process resumes after being scheduled release ptable.lock
- What functions does a process resume after swtch?
  - Yield: resuming process after yield is done
  - Sleep: resuming process that is waking up after sleep
  - Forkret: for newly created processes
- Purpose of forkret: to release ptable.lock
  - New process then returns from trap like its parent

```
2826 // Give up the CPU for one scheduling round.
2827 void
2828 yield(void)
2829 {
2830          acquire(&ptable.lock);
2831          myproc()->state = RUNNABLE;
2832          sched();
2833          release(&ptable.lock);
2834 }
```

```
2852 void
2853 forkret(void)
2854 {
2855
       static int first = 1;
2856
       // Still holding ptable.lock from scheduler.
2857
      release(&ptable.lock);
2858
2859
      if (first) {
2860
         // Some initialization functions must be run i
         // of a regular process (e.g., they call sleep
2861
2862
         // be run from main().
2863
         first = 0:
2864
         iinit(ROOTDEV);
2865
         initlog(ROOTDEV);
2866
```

That's why we return to the forkret instead of directly to the trapret so as to release the lock before going to user space.

#### ptable.lock (3)

# P1 — scheduler – Acquire ptable.lock

Release ptable.lock

- Scheduler goes into loop with lock held
- Acquire ptable.lock in P1 →
   scheduler picks P2 → release in P2
- Later, acquire ptable.lock in P2 → scheduler picks P3 → release in P3
- Periodically, end of looping over all processes, releases lock temporarily
  - What if no runnable process found due to interrupts being disabled?
     Release lock, enable interrupts, allow processes to become runnable.

Damn smart coding practice.

```
2757 void
2758 scheduler(void)
2759 {
       struct proc *p;
2761
       struct cpu *c = mycpu();
2762
       c \rightarrow proc = 0;
2763
2764
       for(;;){
2765
         // Enable interrupts on this processor.
2766
2767
2768
         // Loop over process table looking for process to run.
         acquire(&ptable.lock); It'll anyway disable the interrupt
2769
         for(p = ptable.proc; p < &ptable.proc[NPROC]; p++){</pre>
2770
2771
           if(p->state != RUNNABLE)
2772
             continue:
2773
2774
           // Switch to chosen process. It is the process's job
2775
           // to release ptable.lock and then reacquire it
2776
           // before jumping back to us.
2777
           c \rightarrow proc = p;
2778
           switchuvm(p);
2779
           p->state = RUNNING;
2780
2781
           swtch(&(c->scheduler), p->context);
2782
           switchkvm():
2783
2784
           // Process is done running for now.
2785
           // It should have changed its p->state before coming back.
2786
           c \rightarrow proc = 0;
2787
2788
         release(&ptable.lock);
2789
2790
2791 }
```