


MONICALIAN SILVERSILY

Concurrency In C

•••

Doing Things... At The Same Time


- Concurrency is the term we use for when logical operations overlap in time
- Concurrency is found at many layers in the computer




- The most obvious instance of concurrency on computers is application concurrency
- We all run multiple
 applications at the same time
 on our computers, phones,
 etc.

Processes Reso	urces	File S	ystems	Q	≡] -	+)	8
Process Name	Usei		% CPU →	ID	1	Memory	Disk	read
⊒gnome-shell	cars	on	3	217400) 2	246.4 MiB		
	cars	on	1	243006	5	15.8 MiB		9.0
. ■Xorg	cars	on	1	2893	3	92.4 MiB		11.8
MainThread	carse	on	1	581	2 3	86.0 MiB	38	87.6
☑ Discord	cars	on	1	7533	3 :	307.8 MiB	8	76.0
o chromium	cars	on	0	241816	5 2	204.2 MiB		
systemd	cars	on	0	2782	2	2.5 MiB	4	40.8
(sd-pam)	cars	on	0	2783	3	4.0 MiB		
🔛 pulseaudio	cars		0	2794	+	5.7 MiB	6	04.0
tracker-miner-fs	cars	on	0	2796	5	45.3 MiB	12	24.6
dbus-daemon	cars	on	0	2804	+	4.0 MiB		1.7
gnome-keyring-daemon	carso	on	0	280	7	1.2 MiB		

- Even on a single CPU, multiple programs can be run concurrently
- When one program blocks on an I/O operation, another can be run



- There are three main mechanism for building concurrent programs on modern CPUs:
 - Processes
 - Threads
 - I/O Multiplexing



- The simplest way to create concurrent programs is via processes
- Use the venerable fork()
 function to create a new
 process
- __pid_t is an integer value

```
int main() {
   __pid_t pid = fork();
```

- __pid_t value
 - Negative Value: unable to create a child process (Out of Memory, etc.)
 - Zero: the newly created process
 - Positive: the original process gets this as the Process ID (PID) of the child process

```
int main() {
   __pid_t pid = fork();
```

- Both processes have a complete copy of memory
- This includes any files, sockets, etc. that are open
- The parent process must close any resources (e.g. open files) shared with the child or risk leaking them

```
int main() {
   __pid_t pid = fork();
```

- The memory spaces, however, are separate
- No shared memory between the processes, so no chance of corrupting one another's memory
- But also no way to communicate with other process

```
int main() {
   __pid_t pid = fork();
```

- Process Pros
 - Simple
 - Time Tested
- Process Cons
 - Heavyweight
 - Awkward to communicate between processes

```
int main() {
   __pid_t pid = fork();
```

- A more advanced technique is to use *threads*
- Threads are a lightweight alternative to processes
- Threads share the same memory space

```
pthread_t tid1, tid2;
pthread_create(&tid1, attr: NULL, run_thread, arg: 1);
```

- The standard threading library in unix is *pthreads*
- Provides 60+ functions and for working with threads
- The core function is pthread_create() which creates a new thread

```
pthread_t tid1, tid2;
pthread_create(&tid1, attr: NULL, run_thread, arg: 1);
```

- The arguments are
 - A pointer to a thread id (unsigned long)
 - An options argument
 - A pointer to the function to call as the root of the thread
 - An optional argument to pass to that function

```
pthread_t tid1, tid2;
pthread_create(&tid1, attr: NULL, run_thread, arg: 1);
```

- Thread termination
 - A thread can terminate implicitly by simply completing
 - It can terminate explicitly by calling the pthread_exit() function
 - It can be terminated by another thread with the pthread_cancel() function
 - Or the entire process can exit, killing all threads within it.

```
pthread_t tid1, tid2;
pthread_create(&tid1, attr: NULL, run_thread, arg: 1);
```

- Waiting on threads
- It is common to spawn threads and then wait for them to complete
- To do so, you can use the pthread_join() function
- A thread that joins another thread will wait until it completes before proceeding

```
pthread_create(&tid2, attr: NULL, run_thread, arg: 2);
pthread_join(tid2, thread_return: NULL);
```

- Threads Pros
 - Relatively fast and lightweight
 - Shared memory: easy thread communication!
- Threads Cons
 - More complex API
 - Shared memory: easy thread communication!

```
int main() {
   __pid_t pid = fork();
```


I/O Multiplexing

- The most complex way to achieve parallelism
- Uses the select() function
- Waits until one or more of a set of input sources is ready, or a timeout occurs
- Can be very efficient
- Very complex to deal with
 - We will not be using it in this class

```
fd_set rfds;
struct timeval tv;
int retval;
/* Watch stdin (fd 0) to see when it has input. */
FD_ZERO(fdsetp: &rfds);
FD_SET(fd: 0, fdsetp: &rfds);
/* Wait up to five seconds. */
tv.tv_sec = 5;
tv.tv_usec = 0;
retval = select( nfds: 1, &rfds, writefds: NULL, exceptfds: NULL, &tv);
/* Don't rely on the value of tv now! */
if (retval == -1)
    perror(s: "select()");
else if (retval)
    printf(format: "Data is available now.\n");
    /* FD_ISSET(0, &rfds) will be true. */
else
    printf( format: "No data within five seconds.\n");
```


Concurrency vs Parallelism

- We have been talking about concurrency
- But you are probably thinking about parallelism
- They are not the same thing
- It is possible to be concurrent and not parallel
 - e.g. a single threaded core



Concurrency vs Parallelism

 On modern computer systems, concurrency almost always implies parallelism




Synchronization


•••

Doing Things... At The Same Time. Safely.


- If there is concurrent activity on a shared resource, you need to coordinate activities to avoid issues
- A traffic light coordinates access to a shared intersection



- The same logic applies to concurrency in computing systems
- Processes, since they do not share memory space, are less concerned with this issue
- Threads, however, since they share memory, must be very careful



- We will discuss two different tools for dealing with concurrency
- Mutexes A lock to isolate critical parts of the code to a single thread
- Semaphores A way to coordinate cooperation between threads



- A mutex is a simple lock with two primary operations
- lock() (sometimes wait())
 - Acquires the lock. If the lock is already held by someone else, the thread halts until it is released.
- unlock() (sometimes signal())
 - Releases the lock. If a thread is waiting on the lock, it is activated.




- In pthreads these functions are
 - pthread_mutex_lock()
 - pthread_mutex_unlock()
- The mutex is a struct which must be initialized and cleaned up
 - pthread_mutex_init()
 - pthread_mutex_destory()

```
pthread_mutex_t lock;
pthread_mutex_init(&lock, mutexattr: NULL);
pthread_mutex_lock(&lock);
pthread_mutex_unlock(&lock);
pthread_mutex_destroy(&lock);
```


- With a mutex, you want place the locking and unlocking around the *critical section* of your code
- The critical section is where shared data is being accessed or updated by multiple threads
- Demo...

- So you can see how to use mutexes to ensure that only one thread at a time is updating shared data
- This will be required in your project as you take network input from two users concurrently


- What if
 - Thread 1 acquires lock 1
 - Thread 2 acquires lock 2
 - Thread 1 attempts to acquire lock 2
 - Thread 2 attempts to acquire lock 1
- Deadlock!



- To avoid deadlock you have a few options
 - Option 1: only one lock!
 - The Python GIL (Global Interpreter Lock)
 - Simple!
 - Destroys parallelism
 - Option 2: locks must be acquired in specific order
 - Better parallelism
 - Hard to enforce




- To avoid deadlock you have a few options
 - Option 3: All locks must be acquired up front, in a single atomic action
 - Better parallelism
 - Hard to know in advance what locks an operation might need



- For the project, I recommend option 1: a single lock
- If it's good enough for python,
 it's good enough for us



- Mutexes are about a single thread claiming and releasing sole ownership of a critical section
- Semaphores, on the other hand, are about multiple threads coordinating with one another




- Semaphores have a counter associated with them
- The core operations with a semaphore are
 - wait() waits for the semaphore to be a non-0 value, then decrements it
 - post() increments the semaphore counter

```
sem_t s;
sem_init(&s, pshared: 0, value: 1);
sem_wait(&s);
sem_post(&s);
sem_destroy(&s);
```


- A Semaphore with a limit of 1 is a binary semaphore
- Note that semaphores do not make any guarantees around shared data
- You may still need to do locking if there is shared data being access concurrently
- Demo...

```
sem_t s;
sem_init(&s, pshared: 0, value: 1);
sem_wait(&s);
sem_post(&s);
sem_destroy(&s);
```


- Semaphores are useful for implementing things like worker queues
- Producer threads contribute work to a queue and signal
- Consumer threads wait for work to arrive
- Note that access to the shared Work Queue may still require locking!



- Again, Semaphores are about thread coordination
- The thread signaling a semaphor is not a thread waiting on it
 - Compare w/ a mutex, where the thread unlocking the mutex better darn well be the thread that locked it!



- You can implement a lock with a binary semaphore by using conventions
 - Wait -> lock()
 - Signal -> unlock()
- But there is nothing enforcing the lock/unlock pairing as with a mutex



Review

- Concurrency is when two logical operations can overlap
- Concurrency and Parallelism are not the same thing
- The two major concurrency tools in C are
 - Processes Heavy, Simple
 - o Threads Lightweight, Complex
- Concurrency with shared data requires coordination
- Mutexes (Locks) can be used to protect critical shared data
- Semaphores can be used to coordinate activities between threads but are not typically used for protecting critical shared data



MONICALIAN SHARE WINDOWS HIS TO THE WATER SHARE TO THE WATER SHARE TO THE SHARE THE SH