Hammer Satellite 6.2 Command Help

Table of Contents

hammer activation-key hammer activation-key add-host-collection hammer activation-key add-subscription hammer activation-key content-override hammer activation-key copy hammer activation-key create hammer activation-key delete hammer activation-key host-collections hammer activation-key info hammer activation-key list hammer activation-key product-content hammer activation-key remove-host-collection hammer activation-key remove-subscription hammer activation-key subscriptions hammer activation-key update hammer admin hammer admin logging hammer architecture hammer architecture add-operatingsystem hammer architecture create hammer architecture delete hammer architecture info hammer architecture list hammer architecture update hammer auth hammer auth login hammer auth logout hammer auth status hammer auth-source hammer auth-source Idap hammer bootdisk hammer bootdisk generic hammer bootdisk host hammer bootdisk subnet hammer capsule hammer capsule content hammer capsule create hammer capsule delete hammer capsule import-classes hammer capsule info

hammer capsule list

hammer capsule refresh-features

hammer capsule update

hammer compute-resource

<u>hammer compute-resource create</u>

hammer compute-resource delete

<u>hammer compute-resource image</u>

<u>hammer compute-resource info</u>

hammer compute-resource list

hammer compute-resource update

hammer content-host

hammer content-host info

hammer content-host list

<u>hammer content-host update</u>

hammer content-view

hammer content-view add-repository

hammer content-view copy

hammer content-view create

hammer content-view delete

hammer content-view filter

hammer content-view info

hammer content-view list

hammer content-view publish

hammer content-view puppet-module

hammer content-view remove

hammer content-view remove-from-environment

hammer content-view remove-version

hammer content-view update

hammer content-view version

hammer csv

hammer csv export

hammer csv import

hammer csv settings

hammer defaults

hammer defaults add

hammer defaults delete

hammer defaults list

hammer defaults providers

hammer discovery

hammer discovery auto-provision

hammer discovery delete

hammer discovery facts

hammer discovery info

hammer discovery list hammer discovery provision

hammer discovery reboot

hammer discovery refresh-facts

hammer discovery_rule

hammer discovery_rule create

hammer discovery_rule delete

hammer discovery_rule info

hammer discovery rule list

hammer discovery_rule update

hammer docker

hammer docker container

hammer docker manifest

hammer docker registry

hammer docker tag

hammer domain

hammer domain create

hammer domain delete

hammer domain delete-parameter

hammer domain info

hammer domain list

hammer domain set-parameter

hammer domain update

hammer environment

hammer environment create

hammer environment delete

hammer environment info

hammer environment list

<u>hammer environment sc-params</u>

<u>hammer environment update</u>

hammer erratum

hammer erratum info

hammer erratum list

hammer fact

hammer fact list

hammer filter

hammer filter available-permissions

hammer filter available-resources

hammer filter create

hammer filter delete

hammer filter info

hammer filter list

hammer filter update

hammer foreign-input-set hammer foreign-input-set create hammer foreign-input-set delete hammer foreign-input-set info hammer foreign-input-set list hammer foreign-input-set update <u>hammer global-parameter</u> hammer global-parameter delete hammer global-parameter list hammer global-parameter set hammer gpg hammer gpg create hammer gpg delete hammer gpg info hammer gpg list hammer gpg update hammer host hammer host create hammer host delete hammer host delete-parameter hammer host errata hammer host facts hammer host info hammer host interface hammer host list hammer host package hammer host package-group hammer host puppet-classes hammer host puppetrun hammer host reboot hammer host reports hammer host sc-params hammer host set-parameter hammer host smart-variables hammer host start hammer host status hammer host stop hammer host subscription hammer host update hammer host-collection hammer host-collection add-host hammer host-collection copy hammer host-collection create

hammer host-collection delete

hammer host-collection erratum

hammer host-collection hosts

hammer host-collection info

hammer host-collection list

hammer host-collection package

hammer host-collection package-group

hammer host-collection remove-host

hammer host-collection update

hammer hostgroup

hammer hostgroup create

hammer hostgroup delete

hammer hostgroup delete-parameter

hammer hostgroup info

hammer hostgroup list

hammer hostgroup puppet-classes

hammer hostgroup sc-params

<u>hammer hostgroup set-parameter</u>

hammer hostgroup smart-variables

hammer hostgroup update

hammer import

hammer import activation-key

hammer import all

hammer import config-file

hammer import content-host

hammer import content-view

hammer import host-collection

hammer import organization

hammer import repository

hammer import repository-enable

hammer import template-snippet

hammer import user

hammer job-invocation

hammer job-invocation create

hammer job-invocation info

hammer job-invocation list

hammer job-invocation output

hammer job-template

hammer job-template delete

hammer job-template dump

hammer job-template info

hammer job-template list

hammer job-template update

hammer lifecycle-environment

hammer lifecycle-environment create

hammer lifecycle-environment delete

hammer lifecycle-environment info

hammer lifecycle-environment list

hammer lifecycle-environment paths

hammer lifecycle-environment update

hammer location

hammer location add-compute-resource

hammer location add-config-template

hammer location add-domain

hammer location add-environment

hammer location add-hostgroup

hammer location add-medium

hammer location add-organization

hammer location add-smart-proxy

hammer location add-subnet

hammer location add-user

hammer location create

hammer location delete

hammer location delete-parameter

hammer location info

hammer location list

hammer location remove-compute-resource

hammer location remove-config-template

hammer location remove-environment

hammer location remove-hostgroup

hammer location remove-medium

hammer location remove-organization

hammer location remove-smart-proxy

hammer location remove-subnet

hammer location remove-user

hammer location set-parameter

hammer location update

hammer medium

hammer medium add-operatingsystem

hammer medium create

hammer medium delete

hammer medium info

hammer medium list

hammer medium remove-operatingsystem

hammer medium update

hammer model

hammer model create

hammer model delete

hammer model info

hammer model list

hammer model update

hammer organization

hammer organization add-compute-resource

hammer organization add-config-template

hammer organization add-domain

hammer organization add-environment

hammer organization add-hostgroup

hammer organization add-medium

hammer organization add-smart-proxy

hammer organization add-subnet

hammer organization add-user

hammer organization create

hammer organization delete

<u>hammer organization delete-parameter</u>

hammer organization info

hammer organization list

hammer organization remove-compute-resource

hammer organization remove-config-template

hammer organization remove-domain

hammer organization remove-environment

hammer organization remove-hostgroup

hammer organization remove-medium

hammer organization remove-smart-proxy

hammer organization remove-subnet

hammer organization remove-user

<u>hammer organization set-parameter</u>

hammer organization update

hammer os

hammer os add-architecture

hammer os add-config-template

hammer os add-ptable

hammer os create

hammer os delete

hammer os delete-default-template

hammer os delete-parameter

hammer os info

hammer os list

hammer os remove-architecture

hammer os remove-config-template

```
hammer os remove-ptable
   hammer os set-default-template
   hammer os set-parameter
   hammer os update
hammer ostree-branch
   hammer ostree-branch info
   hammer ostree-branch list
hammer package
hammer package-group
   hammer package-group info
   hammer package-group list
hammer partition-table
   hammer partition-table add-operatingsystem
   hammer partition-table create
   hammer partition-table delete
   hammer partition-table dump
   hammer partition-table info
   hammer partition-table list
   hammer partition-table remove-operatingsystem
   hammer partition-table update
hammer ping
hammer product
   hammer product create
   hammer product delete
   hammer product info
   hammer product list
   hammer product remove-sync-plan
   hammer product set-sync-plan
   hammer product synchronize
   hammer product update
hammer proxy
   hammer proxy content
   hammer proxy create
   hammer proxy delete
   hammer proxy import-classes
   hammer proxy info
   hammer proxy list
   hammer proxy refresh-features
   hammer proxy update
hammer puppet-class
   hammer puppet-class info
   hammer puppet-class list
   hammer puppet-class sc-params
```

hammer puppet-class smart-variables
hammer puppet-module
hammer puppet-module info
hammer puppet-module list
hammer recurring-logic
hammer recurring-logic cancel
hammer recurring-logic info
hammer recurring-logic list
hammer remote-execution-feature
hammer remote-execution-feature info
hammer remote-execution-feature list
hammer remote-execution-feature update
hammer report
hammer report delete
hammer report info
hammer report list
hammer repository
hammer repository create
hammer repository delete
hammer repository export
hammer repository info
hammer repository list
hammer repository remove-content
hammer repository synchronize
hammer repository update
hammer repository upload-content
hammer repository-set
hammer repository-set available-repositories
hammer repository-set disable
hammer repository-set enable
hammer repository-set info
hammer repository-set list
hammer role
hammer role create
hammer role delete
hammer role filters
hammer role info
hammer role list
<u>hammer role update</u>
hammer sc-param
hammer sc-param add-override-value
hammer sc-param info
hammer sc-param list

```
hammer sc-param remove-override-value
   hammer sc-param update
hammer settings
   hammer settings list
   hammer settings set
hammer shell
   hammer smart-variable
   hammer smart-variable add-override-value
   hammer smart-variable create
   hammer smart-variable delete
   hammer smart-variable info
   hammer smart-variable list
   hammer smart-variable remove-override-value
   hammer smart-variable update
hammer subnet
   hammer subnet create
   hammer subnet delete
   hammer subnet info
   hammer subnet list
   hammer subnet update
hammer subscription
   hammer subscription delete-manifest
   hammer subscription list
   hammer subscription manifest-history
   hammer subscription refresh-manifest
   hammer subscription upload
hammer sync-plan
   hammer sync-plan create
   <u>hammer sync-plan delete</u>
   hammer sync-plan info
   hammer sync-plan list
   hammer sync-plan update
hammer task
   hammer task list
   hammer task progress
   hammer task resume
hammer template
   hammer template add-operatingsystem
   hammer template build-pxe-default
   hammer template clone
   hammer template create
   hammer template delete
```

hammer template dump

hammer template info

hammer template kinds

hammer template list

hammer template remove-operatingsystem

hammer template update

hammer template-input

hammer template-input create

hammer template-input delete

hammer template-input info

hammer template-input list

hammer user

hammer user add-role

hammer user create

hammer user delete

hammer user info

hammer user list

hammer user remove-role

hammer user update

hammer user-group

hammer user-group add-role

hammer user-group add-user

hammer user-group add-user-group

hammer user-group create

hammer user-group delete

hammer user-group external

hammer user-group info

hammer user-group list

hammer user-group remove-role

hammer user-group remove-user

hammer user-group remove-user-group

hammer user-group update

hammer activation-key

Usage:

hammer activation-key [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-host-collection Associate a resource add-subscription Add subscription

content-override Override product content defaults

copy Copy an activation key
create Create an activation key
delete Destroy an activation key

host-collections List associated host collections

info Show an activation key list List activation keys

product-content List associated products remove-host-collection remove-subscription Subscriptions update List associated products

Disassociate a resource Remove subscription

List associated subscriptions Update an activation key

Options:

-h, --help print help

hammer activation-key add-host-collection

Usage:

hammer activation-key add-host-collection [OPTIONS]

Options:

--host-collection HOST_COLLECTION_NAME

Host collection name to search

by

--host-collection-id HOST_COLLECTION_ID Id of the host collection

--host-collection-organization-id HOST_COLLECTION_ORGANIZATION_ID Organization ID to search by

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key add-subscription

Usage:

hammer activation-key add-subscription [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--quantity QUANTITY Quantity of this subscription to add

-h, --help print help

hammer activation-key content-override

Usage:

hammer activation-key content-override [OPTIONS]

Options:

--content-label CONTENT_LABEL Label of the content

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--value VALUE Override to 0/1, or 'default'

Possible value(s): '0', '1', 'default'

-h, --help print help

hammer activation-key copy

Usage:

hammer activation-key copy [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by --new-name NEW NAME Name of new activation key

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key create

Usage:

hammer activation-key create [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID content view numeric identifier

--description DESCRIPTION description

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--max-hosts MAX_HOSTS maximum number of registered content hosts

--name NAME name

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--unlimited-hosts Set hosts max to unlimited

-h, --help print help

hammer activation-key delete

Usage:

hammer activation-key delete [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key host-collections

Usage:

hammer activation-key host-collections [OPTIONS]

Options:

--available-for AVAILABLE_FOR Interpret specified object to return only Host Collections

that can be

associated with specified object. The value 'host' is supported.

--host-id HOST_ID Filter products by host id

--id ID ID of activation key

--name NAME Name of activation key

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key info

Usage:

hammer activation-key info [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help print help

hammer activation-key list

Usage:

hammer activation-key list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME
--content-view-id CONTENT_VIEW_ID
--full-results FULL_RESULTS

Content view name to search by content view numeric identifier
Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME activation key name to filter by

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER PAGE Number of results per page to return

--search SEARCH Search string

-h, --help print help

hammer activation-key product-content

Usage:

hammer activation-key product-content [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key remove-host-collection

Usage:

hammer activation-key remove-host-collection [OPTIONS]

Options:

--host-collection HOST_COLLECTION_NAME Host collection name to search

by

--host-collection-id HOST COLLECTION ID Id of the host collection

--host-collection-organization-id HOST_COLLECTION_ORGANIZATION_ID Organization ID to search by

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer activation-key remove-subscription

Usage:

hammer activation-key remove-subscription [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--subscription-id SUBSCRIPTION ID ID of subscription

-h, --help print help

hammer activation-key subscriptions

Usage:

hammer activation-key subscriptions [OPTIONS]

Options:

--activation-key-id ACTIVATION_KEY_ID ID of the activation key

--available-for AVAILABLE_FOR Object to show subscriptions available for, either 'host' or

'activation_key'

--by BY Field to sort the results on

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Name to search by

--host-id HOST_ID

--id ACTIVATION_KEY_ID ID of the activation key

--match-host MATCH HOST Ignore subscriptions that are unavailable to the

specified host

One of true/false, yes/no, 1/0.

--match-installed MATCH_INSTALLED Return subscriptions that match installed products

of the specified host

One of true/false, yes/no, 1/0.

--name ACTIVATION_KEY_NAME Activation key name to search by

--no-overlap NO_OVERLAP Return subscriptions which do not overlap with a

currently-attached

subscription

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'name DESC'

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help print help

hammer activation-key update

Usage:

hammer activation-key update [OPTIONS]

Options:

--auto-attach AUTO_ATTACH auto attach subscriptions upon registration

One of true/false, yes/no, 1/0.

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--description DESCRIPTION description

--id ID ID of the activation key

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE ENVIRONMENT ID

--max-hosts MAX_HOSTS maximum number of registered content hosts

--name NAME Activation key name to search by

--new-name NEW NAME name

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--release-version RELEASE_VERSION content release version

--service-level SERVICE_LEVEL service level

--unlimited-hosts set hosts max to unlimited

-h, --help print help

hammer admin

Usage:

hammer admin [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

logging Logging verbosity level setup

Options:

-h, --help print help

hammer admin logging

Usage:

hammer admin logging [OPTIONS]

Options:

--no-backup Skip configuration backups creation.

--prefix PATH Operate on prefixed environment (e.g. chroot).

-a, --all Apply to all components.

-c, --components COMPONENTS Components to apply, use --list to get them.

Comma separated list of values.

-d, --level-debug Increase verbosity level to debug.

-h, --help print help

-l, --list List available components.

-n, --dry-run Do not apply specified changes.

-p, --level-production Decrease verbosity level to standard.

hammer architecture

Usage:

hammer architecture [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

create Create an architecture delete Delete an architecture info Show an architecture list List all architectures

remove-operating system Disassociate an operating system

update Update an architecture

Options:

-h, --help print help

hammer architecture add-operatingsystem

Usage:

hammer architecture add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Architecture name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer architecture create

Usage:

hammer architecture create [OPTIONS]

Options:

- --name NAME
- --operatingsystem-ids OPERATINGSYSTEM_IDS Operating system IDs

Comma separated list of values.

- --operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.
- -h, --help print help

hammer architecture delete

Usage:

hammer architecture delete [OPTIONS]

Options:

--id ID

--name NAME Architecture name

-h, --help print help

hammer architecture info

Usage:

hammer architecture info [OPTIONS]

Options:

--id ID

--name NAME Architecture name

-h, --help print help

hammer architecture list

Usage:

hammer architecture list [OPTIONS]

Options:

- --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
- --operatingsystem-id OPERATINGSYSTEM_ID
- --order ORDER sort results
- --page PAGE paginate results
- --per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer architecture remove-operatingsystem

Usage:

hammer architecture remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Architecture name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer architecture update

Usage:

hammer architecture update [OPTIONS]

Options:

--id ID

--name NAME Architecture name

--new-name NEW_NAME

--operatingsystem-ids OPERATINGSYSTEM_IDS Operating system IDs

Comma separated list of values.

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.

-h, --help print help

hammer auth

Usage:

hammer auth [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

login Set credentials

logout Wipe your credentials

status Information about current connections

Options:

-h, --help print help

hammer auth login

Usage:

hammer auth login [OPTIONS]

Options:

-h, --help print help

hammer auth logout

Usage:

hammer auth logout [OPTIONS]

Options:

-h, --help print help

hammer auth status

Usage:

hammer auth status [OPTIONS]

Options:

-h, --help print help

hammer auth-source

Usage:

hammer auth-source [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand

[ARG] ... subcommand arguments

Subcommands:

Idap Manage LDAP auth sources.

Options:

-h, --help print help

hammer auth-source Idap

Usage:

hammer auth-source Idap [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create an LDAP authentication source delete Delete an LDAP authentication source info Show an LDAP authentication source list List all LDAP authentication sources

update Update an LDAP authentication source

Options:

-h, --help print help

hammer bootdisk

Usage:

hammer bootdisk [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

generic Download generic image host Download host image

subnet Download subnet generic image

Options:

-h, --help print help

hammer bootdisk generic

Usage:

hammer bootdisk generic [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)

--sudo Use sudo to write to device

-h, --help print help

hammer bootdisk host

Usage:

hammer bootdisk host [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)
--full FULL True for full, false for basic reusable image

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST ID

--sudo Use sudo to write to device

-h, --help print help

hammer bootdisk subnet

Usage:

hammer bootdisk subnet [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

--sudo Use sudo to write to device

-h, --help print help

hammer capsule

Usage:

hammer capsule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

content Manage the capsule content

create Create a capsule delete Delete a capsule

import-classes Import puppet classes from puppet Capsule.

info Show a capsule list List all capsules

refresh-features Refresh capsule features

update Update a capsule

Options:

-h, --help print help

hammer capsule content

Usage:

hammer capsule content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-lifecycle-environment Add lifecycle environments to the capsule available-lifecycle-environments List the lifecycle environments not attached to the capsule

cancel-synchronization Cancel running capsule synchronization.

info Get current capsule synchronization status

lifecycle-environments List the lifecycle environments attached to the capsule remove-lifecycle-environment Remove lifecycle environments from the capsule

synchronization-status Get current capsule synchronization status

synchronize Synchronize the content to the capsule

Options:

-h, --help print help

hammer capsule create

Usage:

hammer capsule create [OPTIONS]

Options:

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--url URL

-h, --help print help

hammer capsule delete

Usage:

hammer capsule delete [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer capsule import-classes

Usage:

hammer capsule import-classes [OPTIONS]

Options:

--dryrun Do not run the import

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--except EXCEPT Optional comma-delimited string containing either 'new',

'updated', or 'obsolete' that is used to limit the imported

Puppet classes

--id ID

--name NAME Name to search by

-h, --help print help

hammer capsule info

Usage:

hammer capsule info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer capsule list

Usage:

hammer capsule list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer capsule refresh-features

Usage:

hammer capsule refresh-features [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer capsule update

Usage:

hammer capsule update [OPTIONS]

Options:

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Name to search by

--new-name NEW_NAME

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--url URL

-h, --help print help

hammer compute-resource

Usage:

hammer compute-resource [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a compute resource delete Delete a compute resource

image View and manage compute resource's images

info Show a compute resource
list List all compute resources
update Update a compute resource

Options:

-h, --help print help

hammer compute-resource create

Usage:

hammer compute-resource create [OPTIONS]

Options:

--description DESCRIPTION

--display-type DISPLAY_TYPE for Libvirt only

Possible value(s): 'VNC', 'SPICE'

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION NAMES Comma separated list of values.

--password PASSWORD Password for RHEV, EC2, VMware, RHEL RHEL

OpenStack Platform Platform.

Secret key for EC2

--provider PROVIDER Providers include Libvirt, Ovirt, EC2, Vmware,

Openstack, Rackspace, GCE

--region REGION for EC2 only --server SERVER for VMware

--set-console-password SET_CONSOLE_PASSWORD for Libvirt and VMware only

One of true/false, yes/no, 1/0.

--tenant TENANT for RHEL RHEL OpenStack Platform Platform only

--url URL URL for Libvirt, RHEV, and RHEL RHEL OpenStack Platform

Platform

--user USER Username for RHEV, EC2, VMware, RHEL RHEL OpenStack

Platform Platform.

Access Key for EC2.

--uuid UUID for RHEV, VMware Datacenter

hammer compute-resource delete

Usage:

hammer compute-resource delete [OPTIONS]

Options:

--id ID

--name NAME Compute resource name

-h, --help print help

hammer compute-resource image

Usage:

hammer compute-resource image [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

available Show images available for addition

create Create an image delete Delete an image info Show an image

list List all images for a compute resource

update Update an image

Options:

-h, --help print help

hammer compute-resource info

Usage:

hammer compute-resource info [OPTIONS]

Options:

--id ID

--name NAME Compute resource name

-h, --help print help

hammer compute-resource list

Usage:

hammer compute-resource list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer compute-resource update

Usage:

hammer compute-resource update [OPTIONS]

Options:

--description DESCRIPTION

--display-type DISPLAY_TYPE for Libvirt only

Possible value(s): 'VNC', 'SPICE'

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Compute resource name

--new-name NEW_NAME

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--password PASSWORD Password for RHEV, EC2, VMware, RHEL RHEL

OpenStack Platform Platform.

Secret key for EC2

--provider PROVIDER Providers include Libvirt, Ovirt, EC2, Vmware,

Openstack, Rackspace, GCE

--region REGION for EC2 only --server SERVER for VMware

--set-console-password SET_CONSOLE_PASSWORD for Libvirt and VMware only

One of true/false, yes/no, 1/0.

--tenant TENANT for RHEL RHEL OpenStack Platform Platform only

--url URL URL for Libvirt, RHEV, and RHEL RHEL OpenStack Platform

Platform

--user USER Username for RHEV, EC2, VMware, RHEL RHEL OpenStack

Platform Platform.

Access Key for EC2.

--uuid UUID for RHEV, VMware Datacenter

-h, --help print help

hammer content-host

Usage:

hammer content-host [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

available-incremental-updates

info Show a content host list List content hosts

update Update content host information

Options:

-h, --help print help

hammer content-host available-incremental-updates

Usage:

hammer content-host available-incremental-updates [OPTIONS]

Options:

--id ID ID of a content host

-h, --help print help

hammer content-host info

Usage:

hammer content-host info [OPTIONS]

Options:

--id ID ID of the content host --name NAME Name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-host list

Usage:

hammer content-host list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID content view numeric identifier --full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Filter content host by name

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return
--pool-id POOL_ID Filter content host by subscribed pool

--search SEARCH Search string

--uuid UUID Filter content host by uuid

-h, --help print help

hammer content-host update

Usage:

hammer content-host update [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID content view numeric identifier --host-collection-ids HOST_COLLECTION_IDS Specify the host collections as

an array

Comma separated list of values.

A service level for auto-healing

--host-collection-organization-ids HOST_COLLECTION_ORGANIZATION_IDS Comma separated list of values.

--host-collections HOST_COLLECTION_NAMES Comma separated list of values.

--id ID ID of the content host

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Name to search by

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--release-ver RELEASE_VER Release version of the content host

--service-level SERVICE_LEVEL process, e.g. SELF-SUPPORT

-h, --help print help

hammer content-view

Usage:

hammer content-view [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-repository Associate a resource

add-version Add a content view version to a composite view

copy Copy a content view
create Create a content view
delete Delete a content view
filter View and manage filters
info Show a content view
list List content views

publish Publish a content view

puppet-module View and manage puppet modules

remove Remove versions and/or environments from a content view and reassign

systems and keys

remove-from-environment Remove a content view from an environment

remove-repository Disassociate a resource

remove-version Remove a content view version from a composite view

update Update a content view

version View and manage content view versions

Options:

-h, --help print help

hammer content-view add-repository

Usage:

hammer content-view add-repository [OPTIONS]

Options:

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID repository ID

-h, --help print help

hammer content-view add-version

Usage:

hammer content-view add-version [OPTIONS]

Options:

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-view copy

Usage:

hammer content-view copy [OPTIONS]

Options:

--id ID Content view numeric identifier
--name NAME New content view name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-view create

Usage:

hammer content-view create [OPTIONS]

Options:

--component-ids COMPONENT_IDS List of component content view version ids for composite views

Comma separated list of values.

--composite Create a composite content view

--description DESCRIPTION Description for the content view

--label LABEL Content view label

--name NAME Name of the content view

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier

--repositories REPOSITORY_NAMES Comma separated list of values.

--repository-ids REPOSITORY_IDS List of repository ids

Comma separated list of values.

-h, --help print help

hammer content-view delete

Usage:

hammer content-view delete [OPTIONS]

Options:

--async Do not wait for the task

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-view filter

Usage:

hammer content-view filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-repository Associate a resource

create create a filter for a content view

delete delete a filter info show filter info

list list filters

remove-repository Disassociate a resource rule View and manage filter rules

update update a filter

Options:

hammer content-view info

Usage:

hammer content-view info [OPTIONS]

Options:

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-view list

Usage:

hammer content-view list [OPTIONS]

Options:

--by BY Field to sort the results on

--composite COMPOSITE Filter only composite content views

One of true/false, yes/no, 1/0.

--full-results FULL RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Name of the content view

--noncomposite NONCOMPOSITE Filter out composite content views

One of true/false, yes/no, 1/0.

--nondefault NONDEFAULT Filter out default content views

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--without WITHOUT Do not include this array of content views

Comma separated list of values.

hammer content-view publish

Usage:

hammer content-view publish [OPTIONS]

Options:

--async Do not wait for the task

--description DESCRIPTION Description for the new published content view version

--id ID Content view identifier

--name NAME Content view name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer content-view puppet-module

Usage:

hammer content-view puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add Add a puppet module to the content view

list List content view puppet modules

remove Remove a puppet module from the content view

Options:

-h, --help print help

hammer content-view remove

Usage:

hammer content-view remove [OPTIONS]

Options:

--async Do not wait for the task

--content-view-version-ids VERSION_IDS Comma separated list of version ids to

remove

--content-view-versions CONTENT_VIEW_VERSION_VERSIONS Comma separated list of values.

--environment-ids ENVIRONMENT_IDS Comma separated list of environment ids

to remove

--environments ENVIRONMENT_NAMES Comma separated list of values.

--id ID content view numeric identifier

--key-content-view-id KEY_CONTENT_VIEW_ID content view to reassign orphaned

activation keys to

--key-environment-id KEY_ENVIRONMENT_ID environment to reassign orphaned

activation keys to

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by --system-content-view-id SYSTEM_CONTENT_VIEW_ID content view to reassign

orphaned systems to

--system-environment-id SYSTEM ENVIRONMENT ID environment to reassign

orphaned systems to

-h, --help print help

hammer content-view remove-from-environment

Usage:

hammer content-view remove-from-environment [OPTIONS]

Options:

--async Do not wait for the task

--id ID content view numeric identifier

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Content view name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

-h, --help print help

hammer content-view remove-repository

Usage:

hammer content-view remove-repository [OPTIONS]

Options:

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID repository ID

-h, --help print help

hammer content-view remove-version

Usage:

hammer content-view remove-version [OPTIONS]

Options:

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--id ID content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

-h, --help print help

hammer content-view update

Usage:

hammer content-view update [OPTIONS]

Options:

--component-ids COMPONENT_IDS List of component content view version ids for

composite views

Comma separated list of values.

--description DESCRIPTION Description for the content view

--id ID Content view identifier

--name NAME Content view name to search by
--new-name NEW_NAME New name for the content view

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--repositories REPOSITORY_NAMES Comma separated list of values.

--repository-ids REPOSITORY_IDS List of repository ids

Comma separated list of values.

-h, --help print help

hammer content-view version

Usage:

hammer content-view version [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

delete Remove content view version export Export a content view version

incremental-update Perform an Incremental Update on one or more Content View

Versions

info Show content view version list List content view versions

promote Promote a content view version

Options:

-h, --help print help

hammer csv

Usage:

hammer csv [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

export export into directory import import by directory

settings import or export settings

Options:

-h, --help print help

hammer csv export

Usage:

hammer csv export [OPTIONS]

Options:

--dir DIRECTORY directory to export to

--organization ORGANIZATION Only process organization matching this name

--settings FILE csv file for settings

-h, --help print help -v, --verbose be verbose

hammer csv import

Usage:

hammer csv import [OPTIONS]

Options:

--dir DIRECTORY directory to import from

--organization ORGANIZATION Only process organization matching this name

--settings FILE csv file for settings

-h, --help print help -v, --verbose be verbose

hammer csv settings

Usage:

hammer csv settings [OPTIONS]

Options:

--export Export current data instead of importing

--file FILE_NAME CSV file (default to /dev/stdout with --csv-export, otherwise required)

--organization ORGANIZATION Only process organization matching this name

-h, --help print help -v, --verbose be verbose

hammer defaults

Usage:

hammer defaults [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add Add a default parameter to config

delete Delete a default param list List all the default parameters

providers List all the providers

Options:

-h, --help print help

hammer defaults add

Usage:

hammer defaults add [OPTIONS]

Options:

--param-name OPTION_NAME The name of the default option (e.g. organization_id).

--param-value OPTION_VALUE The value for the default option

--provider OPTION_PROVIDER The name of the provider providing the value. For list available providers see `hammer defaults providers`.

-h, --help print help

hammer defaults delete

Usage:

hammer defaults delete [OPTIONS]

Options:

--param-name OPTION_NAME T

The name of the default option

-h, --help

print help

hammer defaults list

Usage:

hammer defaults list [OPTIONS]

Options:

-h, --help print help

hammer defaults providers

Usage:

hammer defaults providers [OPTIONS]

Options:

-h, --help print help

hammer discovery

Usage:

hammer discovery [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

auto-provision Auto provision a host delete Delete a discovered host facts Show a discovered host info Show a discovered host list List all discovered hosts

provision Provision a discovered host

reboot Reboot a host

refresh-facts Refresh the facts of a host

Options:

-h, --help print help

hammer discovery auto-provision

Usage:

hammer discovery auto-provision [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery delete

Usage:

hammer discovery delete [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery facts

Usage:

hammer discovery facts [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery info

Usage:

hammer discovery info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery list

Usage:

hammer discovery list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer discovery provision

Usage:

hammer discovery provision [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-password ASK_ROOT_PW One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

--capabilities CAPABILITIES

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID
--enabled ENABLED
--environment ENVIRONMENT_NAME
Numerical ID or domain name
One of true/false, yes/no, 1/0.
Environment name

--environment-id ENVIRONMENT ID

--host-parameters-attributes HOST_PARAMETERS_ATTRIBUTES Comma separated list of values.

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--image IMAGE_NAME Name to search by

--image-id IMAGE_ID

--interface INTERFACE Interface parameters

Comma-separated list of key=value. Can be specified multiple times.

--ip IP not required if using a subnet with DHCP Capsule

--mac MAC not required if it's a virtual machine --managed MANAGED One of true/false, yes/no, 1/0.

--medium MEDIUM NAME Medium name

--medium-id MEDIUM_ID

--model MODEL_NAME Model name

--model-id MODEL_ID

--name NAME Name to search by

--new-name NEW_NAME

--operatingsystem-id OPERATINGSYSTEM_ID

--owner-id OWNER_ID

--parameters PARAMS Host parameters

Comma-separated list of key=value.

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

status, GET

/api/orchestration/:UUID/tasks

--provision-method METHOD Possible value(s): 'build', 'image'

--puppet-ca-proxy-id PUPPET_CA_PROXY_ID

--puppet-proxy-id PUPPET_PROXY_ID

--puppetclass-ids PUPPETCLASS_IDS Comma separated list of values.

--root-password ROOT_PW
--sp-subnet-id SP_SUBNET_ID

--subnet SUBNET NAME Subnet name

--subnet-id SUBNET_ID

-h, --help print help

hammer discovery reboot

Usage:

hammer discovery reboot [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery refresh-facts

Usage:

hammer discovery refresh-facts [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery_rule

Usage:

hammer discovery_rule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a discovery rule

delete Delete a rule

info Show a discovery rule list List all discovery rules update Update a rule

Options:

-h, --help print help

hammer discovery_rule create

Usage:

hammer discovery_rule create [OPTIONS]

Options:

--enabled ENABLED flag is used for temporary shutdown of rules

One of true/false, yes/no, 1/0.

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--hostname HOSTNAME defines a pattern to assign human-readable hostnames to

the matching hosts

--hosts-limit HOSTS_LIMIT

--max-count MAX_COUNT enables to limit maximum amount of provisioned hosts per

rule

--name NAME represents rule name shown to the users

--priority PRIORITY puts the rules in order, low numbers go first. Must be greater then

zero

--search SEARCH query to match discovered hosts for the particular rule

-h, --help print help

hammer discovery_rule delete

Usage:

hammer discovery_rule delete [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery_rule info

Usage:

hammer discovery_rule info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer discovery_rule list

Usage:

hammer discovery rule list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer discovery_rule update

Usage:

hammer discovery rule update [OPTIONS]

Options:

--enabled ENABLED flag is used for temporary shutdown of rules

One of true/false, yes/no, 1/0.

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--hostname HOSTNAME defines a pattern to assign human-readable hostnames to

the matching hosts

--hosts-limit HOSTS_LIMIT

--id ID

--max-count MAX_COUNT enables to limit maximum amount of provisioned hosts per

rule

--name NAME Name to search by

--new-name NEW_NAME represents rule name shown to the users

--priority PRIORITY puts the rules in order, low numbers go first. Must be greater then

zero

--search SEARCH query to match discovered hosts for the particular rule

-h, --help print help

hammer docker

Usage:

hammer docker [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand

[ARG] ... subcommand arguments

Subcommands:

container Manage docker containers manifest Manage docker manifests registry Manage docker registries

tag Manage docker tags

Options:

-h, --help print help

hammer docker container

Usage:

hammer docker container [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a container
delete Delete a container
info Show a container
list List all containers
logs Show container logs
start Power a container on

status Run power operation on a container

stop Power a container off

Options:

-h, --help print help

hammer docker manifest

Usage:

hammer docker manifest [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a docker manifest list List docker_manifests

Options:

-h, --help print help

hammer docker registry

Usage:

hammer docker registry [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a docker registry
delete Delete a docker registry
info Show a docker registry
list List all docker registries
update Update a docker registry

Options:

-h, --help print help

hammer docker tag

Usage:

hammer docker tag [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a docker tag list List docker_tags

Options:

hammer domain

Usage:

hammer domain [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a domain delete Delete a domain

delete-parameter Delete parameter for a domain.

info Show a domain list List of domains

set-parameter Create or update parameter for a domain.

update Update a domain

Options:

-h, --help print help

hammer domain create

Usage:

hammer domain create [OPTIONS]

Options:

--description DESC Full name describing the domain

--dns DNS_NAME Name of DNS proxy to use within this domain
--dns-id DNS_ID ID of DNS proxy to use within this domain
--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME The full DNS domain name

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

hammer domain delete

Usage:

hammer domain delete [OPTIONS]

Options:

--id ID

--name NAME Domain name

-h, --help print help

hammer domain delete-parameter

Usage:

hammer domain delete-parameter [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN ID
Numerical ID or domain name

--name NAME parameter name

-h, --help print help

hammer domain info

Usage:

hammer domain info [OPTIONS]

Options:

--id ID Numerical ID or domain name

--name NAME Domain name

-h, --help print help

hammer domain list

Usage:

hammer domain list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

-h, --help print help

hammer domain set-parameter

Usage:

hammer domain set-parameter [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--name NAME parameter name
--value VALUE parameter value

-h, --help print help

hammer domain update

Usage:

hammer domain update [OPTIONS]

Options:

--description DESC Full name describing the domain

--dns DNS_NAME Name of DNS proxy to use within this domain
--dns-id DNS_ID ID of DNS proxy to use within this domain

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Domain name

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

-h, --help print help

hammer environment

Usage:

hammer environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create an environment delete Delete an environment info Show an environment list List all environments

sc-params List all smart class parameters

update Update an environment

Options:

-h, --help print help

hammer environment create

Usage:

hammer environment create [OPTIONS]

Options:

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

hammer environment delete

Usage:

hammer environment delete [OPTIONS]

Options:

--id ID

--name NAME Environment name

-h, --help print help

hammer environment info

Usage:

hammer environment info [OPTIONS]

Options:

--id ID

--name NAME Environment name

-h, --help print help

hammer environment list

Usage:

hammer environment list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--puppet-class PUPPET_CLASS_NAME Puppet class name

--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

hammer environment sc-params

Usage:

hammer environment sc-params [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID
--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer environment update

Usage:

hammer environment update [OPTIONS]

Options:

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION NAMES Comma separated list of values.

--name NAME Environment name

--new-name NEW_NAME

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

-h, --help print help

hammer erratum

Usage:

hammer erratum [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand

[ARG] ... subcommand arguments

Subcommands:

info Show an erratum

list List errata

Options:

-h, --help print help

hammer erratum info

Usage:

hammer erratum info [OPTIONS]

Options:

--id ID an erratum identifier

--name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

-h, --help print help

hammer erratum list

Usage:

hammer erratum list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID filter identifier

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version

number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--cve CVE CVE identifier

--environment ENVIRONMENT_NAME Name to search by

--environment-id ENVIRONMENT ID

--errata-restrict-applicable ERRATA_RESTRICT_APPLICABLE show only errata with one or more applicable hosts

One of true/false, yes/no, 1/0.

--errata-restrict-installable ERRATA_RESTRICT_INSTALLABLE show only errata with one or more installable hosts

One of true/false, yes/no, 1/0.

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID
--search SEARCH Search string

-h, --help print help

hammer fact

Usage:

hammer fact [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

list List all fact values

Options:

-h, --help print help

hammer fact list

Usage:

hammer fact list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer filter

Usage:

hammer filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

available-permissions List all permissions

available-resources List available resource types.

create Create a filter
delete Delete a filter
info Show a filter
list List all filters
update Update a filter

Options:

-h, --help print help

hammer filter available-permissions

Usage:

hammer filter available-permissions [OPTIONS]

Options:

--name NAME

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--resource-type RESOURCE_TYPE
--search SEARCH filter results

hammer filter available-resources

Usage:

hammer filter available-resources [OPTIONS]

Options:

-h, --help print help

hammer filter create

Usage:

hammer filter create [OPTIONS]

Options:

--location-ids LOCATION_IDS Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--organization-ids ORGANIZATION_IDS Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--permission-ids PERMISSION_IDS Comma separated list of values.

--role-id ROLE_ID

--search SEARCH

-h, --help print help

hammer filter delete

Usage:

hammer filter delete [OPTIONS]

Options:

--id ID

hammer filter info

Usage:

hammer filter info [OPTIONS]

Options:

--id ID

-h, --help print help

hammer filter list

Usage:

hammer filter list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer filter update

Usage:

hammer filter update [OPTIONS]

Options:

--id ID

--location-ids LOCATION_IDS Comma separated list of values.
--locations LOCATION_NAMES Comma separated list of values.

--organization-ids ORGANIZATION_IDS Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--permission-ids PERMISSION_IDS Comma separated list of values.

--role ROLE_NAME User role name

--role-id ROLE_ID --search SEARCH

hammer foreign-input-set

Usage:

hammer foreign-input-set [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create delete info list update

Options:

-h, --help print help

hammer foreign-input-set create

Usage:

hammer foreign-input-set create [OPTIONS]

Options:

-h, --help print help

hammer foreign-input-set delete

Usage:

hammer foreign-input-set delete [OPTIONS]

Options:

hammer foreign-input-set info

Usage:

hammer foreign-input-set info [OPTIONS]

Options:

-h, --help print help

hammer foreign-input-set list

Usage:

hammer foreign-input-set list [OPTIONS]

Options:

-h, --help print help

hammer foreign-input-set update

Usage:

hammer foreign-input-set update [OPTIONS]

Options:

-h, --help print help

hammer global-parameter

Usage:

hammer global-parameter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

delete Delete a global parameter list List all global parameters. set Set a global parameter.

Options:

-h, --help print help

hammer global-parameter delete

Usage:

hammer global-parameter delete [OPTIONS]

Options:

--name NAME Common parameter name

-h, --help print help

hammer global-parameter list

Usage:

hammer global-parameter list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer global-parameter set

Usage:

hammer global-parameter set [OPTIONS]

Options:

--name NAME parameter name --value VALUE parameter value

hammer gpg

Usage:

hammer gpg [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a gpg key
delete Destroy a gpg key
info Show a gpg key
list List gpg keys

update Update a repository

Options:

-h, --help print help

hammer gpg create

Usage:

hammer gpg create [OPTIONS]

Options:

--key GPG_KEY_FILE GPG Key file

--name NAME identifier of the gpg key

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer gpg delete

Usage:

hammer gpg delete [OPTIONS]

Options:

--id ID gpg key numeric identifier --name NAME Name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer gpg info

Usage:

hammer gpg info [OPTIONS]

Options:

--id ID gpg key numeric identifier --name NAME Name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer gpg list

Usage:

hammer gpg list [OPTIONS]

Options:

--by BY Field to sort the results on

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME name of the GPG key

--order ORDER Sort field and order, eg. 'name DESC'

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

hammer gpg update

Usage:

hammer gpg update [OPTIONS]

Options:

--id ID gpg key numeric identifier--key GPG_KEY_FILE GPG Key file--name NAME Name to search by

--new-name NEW_NAME identifier of the gpg key

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer host

Usage:

hammer host [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a host delete Delete a host

delete-parameter Delete parameter for a host. errata Manage errata on your hosts

facts List all fact values

info Show a host

interface View and manage host's network interfaces

list List all hosts

package Manage packages on your hosts

package-group Manage package-groups on your hosts

puppet-classes List all Puppet classes

puppetrun Force a Puppet agent run on the host

reboot Reboot a host reports List all reports

sc-params List all smart class parameters

set-parameter Create or update parameter for a host.

smart-variables List all smart variables

start Power a host on

status Get configuration status of host

stop Power a host off

subscription Manage subscription information on your hosts

update Update a host

Options:

-h, --help print help

hammer host create

Usage:

hammer host create [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-password ASK_ROOT_PW One of true/false, yes/no, 1/0.

--autoheal AUTOHEAL Sets whether the Host will autoheal subscriptions

upon checkin

One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

Default: "true"

--comment COMMENT Additional information about this host

Comma-separated list of key=value.

--compute-profile-id COMPUTE PROFILE ID

--compute-resource-id COMPUTE_RESOURCE_ID

--content-view CONTENT_VIEW_NAME Name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID

--enabled ENABLED

Numerical ID or domain name
One of true/false, yes/no, 1/0.

Default: "true"

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID --hostgroup-title HOSTGROUP TITLE Hostgroup title --hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS List of hypervisor guest uuids Comma separated list of values. --image IMAGE NAME Name to search by --image-id IMAGE ID --interface INTERFACE Interface parameters. Comma-separated list of key=value. Can be specified multiple times. --ip IP not required if using a subnet with DHCP Capsule --kickstart-repository-id KICKSTART REPOSITORY ID Repository Id associated with the kickstart repo used for provisioning --lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment Location name --location LOCATION NAME --location-id LOCATION ID --mac MAC required for managed host that is bare metal, not required if it's a virtual machine --managed MANAGED One of true/false, yes/no, 1/0. Default: "true" --medium MEDIUM_NAME Medium name --medium-id MEDIUM ID --model MODEL NAME Model name --model-id MODEL ID --name NAME --operatingsystem OPERATINGSYSTEM TITLE Operating system title --operatingsystem-id OPERATINGSYSTEM ID --organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION ID organization ID --overwrite OVERWRITE One of true/false, yes/no, 1/0. Default: "true" --owner OWNER_LOGIN Login of the owner --owner-id OWNER ID ID of the owner --owner-type OWNER TYPE Host's owner type Possible value(s): 'User', 'Usergroup' Host parameters. --parameters PARAMS Comma-separated list of key=value. --partition-table PARTITION TABLE NAME Partition table name

/api/orchestration/:UUID/tasks

UUID to track orchestration tasks

--partition-table-id PARTITION_TABLE_ID
--progress-report-id PROGRESS_REPORT_ID

status. GET

--provision-method METHOD Possible value(s): 'build', 'image'

--puppet-ca-proxy PUPPET_CA_PROXY_NAME

--puppet-ca-proxy-id PUPPET_CA_PROXY_ID

--puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values.
--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values.

--puppet-proxy PUPPET_PROXY_NAME
--puppet-proxy-id PUPPET_PROXY_ID

--realm REALM_NAME Name to search by

--realm-id REALM ID Numerical ID or realm name

--release-version RELEASE_VERSION Release version for this Host to use

(7Server, 7.1, etc)

--root-pass ROOT_PASS required if host is managed and value is not

inherited from host group or

default password in settings

--root-password ROOT_PW

--service-level SERVICE_LEVEL Service level to be used for autoheal.

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

--volume VOLUME Volume parameters

Comma-separated list of key=value. Can be specified multiple times.

-h, --help print help

hammer host delete

Usage:

hammer host delete [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host delete-parameter

Usage:

hammer host delete-parameter [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--name NAME parameter name

-h, --help print help

hammer host errata

Usage:

hammer host errata [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

apply Schedule errata for installation
info Retrieve a single errata for a host
list List errata available for the content host

Options:

-h, --help print help

hammer host facts

Usage:

hammer host facts [OPTIONS]

Options:

--id ID

--name NAME--order ORDER--page PAGEHost namesort resultspaginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host info

Usage:

hammer host info [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host interface

Usage:

hammer host interface [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create an interface on a host

delete Delete a host's interface info Show an interface for host list List all interfaces for host update Update a host's interface

Options:

-h, --help print help

hammer host list

Usage:

hammer host list [OPTIONS]

Options:

- --environment-id ENVIRONMENT_ID
- --hostgroup HOSTGROUP_NAME Hostgroup name
- --hostgroup-id HOSTGROUP_ID
- --hostgroup-title HOSTGROUP_TITLE Hostgroup title
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --order ORDER sort results
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION_ID organization ID
- --page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host package

Usage:

hammer host package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

install Install packages remotely

list List packages installed on the host remove Uninstall packages remotely upgrade Update packages remotely upgrade-all Update packages remotely

Options:

-h, --help print help

hammer host package-group

Usage:

hammer host package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

install Install packages remotely remove Uninstall packages remotely

Options:

-h, --help print help

hammer host puppet-classes

Usage:

hammer host puppet-classes [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host puppetrun

Usage:

hammer host puppetrun [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host reboot

Usage:

hammer host reboot [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host reports

Usage:

hammer host reports [OPTIONS]

Options:

--id ID

--name NAME--order ORDER--page PAGEHost namesort resultspaginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host sc-params

Usage:

hammer host sc-params [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host set-parameter

Usage:

hammer host set-parameter [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--name NAME parameter name
--value VALUE parameter value

-h, --help print help

hammer host smart-variables

Usage:

hammer host smart-variables [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host start

Usage:

hammer host start [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host status

Usage:

hammer host status [OPTIONS]

Options:

--id ID

--name NAME Host name

-h, --help print help

hammer host stop

Usage:

hammer host stop [OPTIONS]

Options:

--force Force turning off a host

--id ID

--name NAME Host name

-h, --help print help

hammer host subscription

Usage:

hammer host subscription [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

register Register a host with subscription and information.
unregister Unregister the host as a subscription consumer

Options:

-h, --help print help

hammer host update

Usage:

hammer host update [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-password ASK ROOT PW One of true/false, yes/no, 1/0.

--autoheal AUTOHEAL Sets whether the Host will autoheal subscriptions

upon checkin

One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

--comment COMMENT Additional information about this host

--compute-attributes COMPUTE_ATTRS Compute resource attributes.

Comma-separated list of key=value.

--compute-profile-id COMPUTE_PROFILE_ID

--compute-resource-id COMPUTE_RESOURCE_ID

--content-view CONTENT_VIEW_NAME Name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID

--enabled ENABLED

--environment ENVIRONMENT NAME

Numerical ID or domain name
One of true/false, yes/no, 1/0.

Environment name

--environment-id ENVIRONMENT_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS List of hypervisor guest uuids

Comma separated list of values.

--id ID

--image IMAGE_NAME Name to search by

--image-id IMAGE_ID

--interface INTERFACE Interface parameters.

Comma-separated list of key=value.
Can be specified multiple times.

--ip IP not required if using a subnet with DHCP Capsule

--kickstart-repository-id KICKSTART_REPOSITORY_ID Repository Id associated with the kickstart repo used for provisioning

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--mac MAC required for managed host that is bare metal, not

required if it's a

virtual machine

--managed MANAGED One of true/false, yes/no, 1/0.

--medium MEDIUM_NAME Medium name

--medium-id MEDIUM_ID

--model MODEL NAME Model name

--model-id MODEL ID

--name NAME Host name

--new-name NEW_NAME

--operatingsystem OPERATINGSYSTEM TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID organization ID

--overwrite OVERWRITE One of true/false, yes/no, 1/0.

--owner OWNER_LOGIN Login of the owner

--owner-id OWNER ID ID of the owner

--owner-type OWNER_TYPE Host's owner type

Possible value(s): 'User', 'Usergroup'

--parameters PARAMS Host parameters.

Comma-separated list of key=value.

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

status, GET

/api/orchestration/:UUID/tasks

--provision-method METHOD Possible value(s): 'build', 'image'

--puppet-ca-proxy PUPPET_CA_PROXY_NAME --puppet-ca-proxy-id PUPPET_CA_PROXY_ID

--puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values.
--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values.

--puppet-proxy PUPPET_PROXY_NAME
--puppet-proxy-id PUPPET_PROXY_ID

--realm REALM_NAME Name to search by

--realm-id REALM ID Numerical ID or realm name

--release-version RELEASE_VERSION Release version for this Host to use

(7Server, 7.1, etc)

--root-pass ROOT_PASS required if host is managed and value is not

inherited from host group or

default password in settings

--root-password ROOT_PW

--service-level SERVICE LEVEL Service level to be used for autoheal.

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET ID

--volume VOLUME Volume parameters

Comma-separated list of key=value. Can be specified multiple times.

-h, --help print help

hammer host-collection

Usage:

hammer host-collection [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-host Add host to the host collection

copy Copy a host collection

create Create a host collection delete Destroy a host collection

erratum Manipulate errata for a host collection

hosts List all hosts

info Show a host collection list List host collections

package Manipulate packages for a host collection

package-group Manipulate package-groups for a host collection

remove-host Remove hosts from the host collection

update Update a host collection

Options:

-h, --help print help

hammer host-collection add-host

Usage:

hammer host-collection add-host [OPTIONS]

Options:

--host-ids HOST_IDS Array of host ids

Comma separated list of values.

--hosts HOST_NAMES Comma separated list of values.

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help print help

hammer host-collection copy

Usage:

hammer host-collection copy [OPTIONS]

Options:

--id ID ID of the host collection

--name NAME Host collection name to search by --new-name NEW NAME New host collection name

 --organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer host-collection create

Usage:

hammer host-collection create [OPTIONS]

Options:

--description DESCRIPTION

--host-ids HOST_IDS List of host ids to replace the hosts in host collection

Comma separated list of values.

--hosts HOST_NAMES Comma separated list of values.

--max-hosts MAX_HOSTS Maximum number of hosts in the host collection

--name NAME Host Collection name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have

unlimited hosts

One of true/false, yes/no, 1/0.

-h, --help print help

hammer host-collection delete

Usage:

hammer host-collection delete [OPTIONS]

Options:

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer host-collection erratum

Usage:

hammer host-collection erratum [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

install Install errata on content hosts contained within a host collection

Options:

-h, --help print help

hammer host-collection hosts

Usage:

hammer host-collection hosts [OPTIONS]

Options:

--environment-id ENVIRONMENT_ID

--hostgroup-id HOSTGROUP_ID

--id HOST_COLLECTION_ID Host Collection ID
--location LOCATION_NAME Name to search by

--location-id LOCATION_ID

--name HOST_COLLECTION_NAME Host Collection Name

--order ORDER sort results

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer host-collection info

Usage:

hammer host-collection info [OPTIONS]

Options:

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help print help

hammer host-collection list

Usage:

hammer host-collection list [OPTIONS]

Options:

--activation-key-id ACTIVATION_KEY_ID ID of the activation key

--available-for AVAILABLE_FOR Interpret specified object to return only Host Collections

that can be

associated with specified object. The value 'host' is supported.

--by BY Field to sort the results on

--full-results FULL RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Name to search by

--host-id HOST_ID

--name NAME host collection name to filter by

--order ORDER Sort field and order, eg. 'name DESC'

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help print help

hammer host-collection package

Usage:

hammer host-collection package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

install Install packages on content hosts contained within a host collection remove Packages on content hosts contained within a host collection update Update packages on content hosts contained within a host collection

Options:

-h, --help print help

hammer host-collection package-group

Usage:

hammer host-collection package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

install Install package-groups on content hosts contained within a host collection remove Remove package-groups on content hosts contained within a host

collection

update Update package-groups on content hosts contained within a host

collection

Options:

-h, --help print help

hammer host-collection remove-host

Usage:

hammer host-collection remove-host [OPTIONS]

Options:

--host-ids HOST IDS Array of host ids

Comma separated list of values.

--hosts HOST_NAMES Comma separated list of values.

--id ID Id of the host collection

--name NAME Host collection name to search by

 --organization-label ORGANIZATION_LABEL Organization label to search by -h, --help print help

hammer host-collection update

Usage:

hammer host-collection update [OPTIONS]

Options:

--description DESCRIPTION

--host-ids HOST_IDS List of host ids to replace the hosts in host collection

Comma separated list of values.

--hosts HOST_NAMES Comma separated list of values.

--id ID Id of the host collection

--max-hosts MAX_HOSTS Maximum number of hosts in the host collection

--name NAME Host collection name to search by

--new-name NEW NAME Host Collection name

--new-organization-id NEW_ORGANIZATION_ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have

unlimited hosts

One of true/false, yes/no, 1/0.

-h, --help print help

hammer hostgroup

Usage:

hammer hostgroup [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a host group delete Delete a host group

delete-parameter Delete parameter for a hostgroup.

info Show a host group list List all host groups

puppet-classes List all Puppet classes

sc-params List all smart class parameters

set-parameter Create or update parameter for a hostgroup.

smart-variables List all smart variables update Update a host group

Options:

-h, --help print help

hammer hostgroup create

Usage:

hammer hostgroup create [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE ID

--ask-root-pass ASK_ROOT_PW One of true/false, yes/no, 1/0.

--content-source-id CONTENT_SOURCE_ID

--content-view CONTENT_VIEW_NAME Name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID Numerical ID or domain name
--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--medium MEDIUM_NAME Medium name

--medium-id MEDIUM_ID

--name NAME

--operatingsystem-id OPERATINGSYSTEM_ID

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION ID Organization ID to search by

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION NAMES Comma separated list of values.

--parent PARENT_NAME Name of parent hostgroup

--parent-id PARENT_ID

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--puppet-ca-proxy-id PUPPET_CA_PROXY_ID

--puppet-class-ids PUPPETCLASS_IDS List of puppetclass ids

Comma separated list of values.

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values.

--puppet-proxy-id PUPPET_PROXY_ID

--realm REALM NAME Name to search by

--realm-id REALM_ID Numerical ID or realm name

--root-pass ROOT_PASSWORD Root password

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

-h, --help print help

hammer hostgroup delete

Usage:

hammer hostgroup delete [OPTIONS]

Options:

--id ID

--name NAME Hostgroup name

--title TITLE Hostgroup title

-h, --help print help

hammer hostgroup delete-parameter

Usage:

hammer hostgroup delete-parameter [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--name NAME parameter name

-h, --help print help

hammer hostgroup info

Usage:

hammer hostgroup info [OPTIONS]

Options:

--id ID

--name NAME Hostgroup name

--title TITLE Hostgroup title

-h, --help print help

hammer hostgroup list

Usage:

hammer hostgroup list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--puppet-class PUPPET_CLASS_NAME Puppet class name

--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

-h, --help print help

hammer hostgroup puppet-classes

Usage:

hammer hostgroup puppet-classes [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer hostgroup sc-params

Usage:

hammer hostgroup sc-params [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer hostgroup set-parameter

Usage:

hammer hostgroup set-parameter [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--name NAME parameter name
--value VALUE parameter value

-h, --help print help

hammer hostgroup smart-variables

Usage:

hammer hostgroup smart-variables [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer hostgroup update

Usage:

hammer hostgroup update [OPTIONS]

Options:

--architecture ARCHITECTURE NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-pass ASK_ROOT_PW One of true/false, yes/no, 1/0.

--content-source-id CONTENT SOURCE ID

--content-view CONTENT VIEW NAME Name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID Numerical ID or domain name --environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--id ID

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by

--lifecycle-environment-id LIFECYCLE ENVIRONMENT ID ID of the environment

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION NAMES Comma separated list of values.

--medium MEDIUM_NAME Medium name

--medium-id MEDIUM ID

--name NAME Hostgroup name

--new-name NEW NAME

--operatingsystem-id OPERATINGSYSTEM_ID

--organization ORGANIZATION_NAME Organization name to search by

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION NAMES Comma separated list of values.

--parent PARENT_NAME Name of parent hostgroup

--parent-id PARENT_ID

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--puppet-ca-proxy-id PUPPET_CA_PROXY_ID

--puppet-class-ids PUPPETCLASS_IDS List of puppetclass ids

Comma separated list of values.

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values.

--puppet-proxy-id PUPPET_PROXY_ID

--realm REALM NAME Name to search by

--realm-id REALM_ID Numerical ID or realm name

--root-pass ROOT_PASSWORD Root password

--subnet SUBNET NAME Subnet name

--subnet-id SUBNET_ID

--title TITLE Hostgroup title

-h, --help print help

hammer import

Usage:

hammer import [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

activation-key Import Activation Keys (from spacewalk-report activation-keys).

all Load ALL data from a specified directory that is in spacewalk-export format.

config-file Create puppet-modules from Configuration Channel content (from

spacewalk-report config-files-latest).

content-host Import Content Hosts (from spacewalk-report system-profiles). Create Content Views based on local/cloned Channels (from

spacewalk-export-channels).

host-collection Import Host Collections (from spacewalk-report system-groups).

organization Import Organizations (from spacewalk-report users).
repository Import repositories (from spacewalk-report repositories).

repository-enable Enable any Red Hat repositories accessible to any Organization (from

spacewalk-report channels).

template-snippet Import template snippets (from spacewalk-report kickstart-scripts).

user Import Users (from spacewalk-report users).

Options:

-h, --help print help

hammer import activation-key

Usage:

hammer import activation-key [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer import all

Usage:

hammer import all [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities instead of importing them

Default: false

--directory DIR_PATH The directory where the export file was extracted

Default: "/tmp/exports"

--dry-run Show what we would have done, if we'd been allowed

Default: false

--entities entity[,entity...] Import specific entities

Default: "all"

--into-org-id ORG_ID Import all organizations into one specified by id

--list-entities List entities we understand

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--macro_mapping FILE Mapping of Satellite-5 config-file-macros to puppet facts

--manifest-directory DIR PATH Directory holding manifests

--merge-users Merge pre-created users (except admin)

Default: false

--no-async Wait for async tasks in foreground

Default: false

--quiet Be silent - no output to STDOUT

Default: false

--synchronize Synchronize imported repositories

Default: false

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

--wait Wait for repository synchronization to finish

Default: false

-h, --help print help

hammer import config-file

Usage:

hammer import config-file [OPTIONS]

Options:

--answers-file FILE_NAME Answers to the puppet-generate-module interview questions

Default: "/etc/hammer/cli.modules.d/import/interview_answers.yml"

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--generate-only Create and fill puppet-modules, but DO NOT upload anything

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--macro-mapping FILE NAME Mapping of Satellite-5 config-file-macros to puppet facts

Default: "/etc/hammer/cli.modules.d/import/config macros.yml"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

--working-directory FILE_NAME Location for building puppet modules (will be created if it

doesn't exist

Default: "/root/puppet work dir"

-h, --help print help

hammer import content-host

Usage:

hammer import content-host [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--export-directory DIR_PATH Directory to export rpmbuild structure

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer import content-view

Usage:

hammer import content-view [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--dir DIR Export directory

--filter Filter content-views for package names present in Sat5 channel

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--no-async Wait for async tasks in foreground

Default: false

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--synchronize Synchronize imported repositories

Default: false

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

--wait Wait for repository synchronization to finish

Default: false

-h, --help print help

hammer import host-collection

Usage:

hammer import host-collection [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer import organization

Usage:

hammer import organization [OPTIONS]

Options:

--csv-file FILE_NAME CSV file with data to be imported

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--into-org-id ORG_ID Import all organizations into one specified by id

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--upload-manifests-from MANIFEST_DIR Upload manifests found at MANIFEST_DIR.

Assumes manifest for "ORG NAME" will be of the form ORG_NAME.zip

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer import repository

Usage:

hammer import repository [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--no-async Wait for async tasks in foreground

Default: false

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--synchronize Synchronize imported repositories

Default: false

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

--wait Wait for repository synchronization to finish

Default: false

-h, --help print help

hammer import repository-enable

Usage:

hammer import repository-enable [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--dry-run Only show the repositories that would be enabled

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--no-async Wait for async tasks in foreground

Default: false

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

Default:

"/opt/theforeman/tfm/root/usr/share/gems/gems/hammer_cli_import-0.11.2/channel_data_pretty.

json"

--synchronize Synchronize imported repositories

Default: false

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

--wait Wait for repository synchronization to finish

Default: false

hammer import template-snippet

Usage:

hammer import template-snippet [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer import user

Usage:

hammer import user [OPTIONS]

Options:

--debug Turn on debugging-information

Default: false

--delete Delete entities from CSV file

Default: false

--logfile LOGFILE Where output is logged to

Default: "/root/import.log"

--merge-users Merge pre-created users (except admin)

Default: false

--new-passwords FILE NAME Output for new passwords

--quiet Be silent - no output to STDOUT

Default: false

--recover RECOVER Recover strategy, can be: rename (default), map, none

Default: :rename

--role-mapping FILE_NAME Mapping of Satellite-5 role names to Satellite-6 defined roles

Default: "/etc/hammer/cli.modules.d/import/role_map.yml"

--verbose Be noisy - everything goes to STDOUT and to a logfile

Default: false

-h, --help print help

hammer job-invocation

Usage:

hammer job-invocation [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create info list

output View the output for a host

Options:

-h, --help print help

hammer job-invocation create

Usage:

hammer job-invocation create [OPTIONS]

Options:

--async Do not wait for the task

--cron-line CRONLINE Create a recurring execution

Cron line format 'a b c d e', where:

a. is minute (range: 0-59)b. is hour (range: 0-23)

c. is day of month (range: 1-31)

d. is month (range: 1-12)

e. is day of week (range: 0-6)

--dynamic Dynamic search queries are evaluated at run time

--end-time DATETIME Perform no more executions after this time, used with --cron-line

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

--input-files INPUT FILES Read input values from files

Comma-separated list of key=file, where file is a path to a text file to be read

--inputs INPUTS Specify inputs from command line

Comma-separated list of key=value.

--start-at DATETIME Schedule the execution for a later time

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

--start-before DATETIME Execution should be cancelled if it cannot be started before

--start-at

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

-h, --help print help

hammer job-invocation info

Usage:

hammer job-invocation info [OPTIONS]

Options:

-h, --help print help

hammer job-invocation list

Usage:

hammer job-invocation list [OPTIONS]

Options:

-h, --help print help

hammer job-invocation output

Usage:

hammer job-invocation output [OPTIONS]

Options:

--async Do not wait for job to complete, shows current output only

-h, --help print help

hammer job-template

Usage:

hammer job-template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create delete

dump View job template content

info list update

Options:

-h, --help print help

hammer job-template create

Usage:

hammer job-template create [OPTIONS]

Options:

--file TEMPLATE Path to a file that contains the template

-h, --help print help

hammer job-template delete

Usage:

hammer job-template delete [OPTIONS]

Options:

-h, --help print help

hammer job-template dump

Usage:

hammer job-template dump [OPTIONS]

Options:

-h, --help print help

hammer job-template info

Usage:

hammer job-template info [OPTIONS]

Options:

-h, --help print help

hammer job-template list

Usage:

hammer job-template list [OPTIONS]

Options:

-h, --help print help

hammer job-template update

Usage:

hammer job-template update [OPTIONS]

Options:

--file TEMPLATE Path to a file that contains the template

-h, --help print help

hammer lifecycle-environment

Usage:

hammer lifecycle-environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create an environment delete Destroy an environment info Show an environment

list List environments in an organization

paths List environment paths update Update an environment

Options:

-h, --help print help

hammer lifecycle-environment create

Usage:

hammer lifecycle-environment create [OPTIONS]

Options:

--description DESCRIPTION description of the environment

--label LABEL label of the environment --name NAME name of the environment

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--prior PRIOR Name of the prior environment

--prior-id PRIOR_ID ID of an environment that is prior to the new environment in

the chain. It

has to be either the ID of Library or the ID of an environment at the

end

of a chain.

-h, --help print help

hammer lifecycle-environment delete

Usage:

hammer lifecycle-environment delete [OPTIONS]

Options:

--id ID ID of the environment

--name NAME Lifecycle environment name to search by --organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer lifecycle-environment info

Usage:

hammer lifecycle-environment info [OPTIONS]

Options:

--id ID ID of the environment

--name NAME Lifecycle environment name to search by --organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer lifecycle-environment list

Usage:

hammer lifecycle-environment list [OPTIONS]

Options:

--library LIBRARY set true if you want to see only library environments

Possible value(s): 'true', 'false'

--name NAME filter only environments containing this name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer lifecycle-environment paths

Usage:

hammer lifecycle-environment paths [OPTIONS]

Options:

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

promotable) Default:

readable

-h, --help print help

hammer lifecycle-environment update

Usage:

hammer lifecycle-environment update [OPTIONS]

Options:

--description DESCRIPTION description of the environment

--id ID ID of the environment

--name NAME Lifecycle environment name to search by

--new-name NEW_NAME new name to be given to the environment

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer location

Usage:

hammer location [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-compute-resource Associate a compute resource add-config-template Associate a configuration template

add-domain Associate a domain

add-environment Associate an environment

add-hostgroup Associate a hostgroup add-medium Associate a medium

add-organization Associate an organization add-smart-proxy Associate a smart proxy

add-subnet Associate a subnet add-user Associate an user create Create a location delete Delete a location

delete-parameter Delete parameter for a location.

info Show a location list List all locations

remove-compute-resource Disassociate a compute resource remove-config-template Disassociate a configuration template

remove-domain Disassociate a domain

remove-environment Disassociate an environment remove-hostgroup Disassociate a hostgroup Disassociate a medium

remove-organization Disassociate an organization remove-smart-proxy Disassociate a smart proxy

remove-subnet Disassociate a subnet Pisassociate an user

set-parameter Create or update parameter for a location.

update Update a location

Options:

-h, --help print help

hammer location add-compute-resource

Usage:

hammer location add-compute-resource [OPTIONS]

Options:

--compute-resource-id COMPUTE_RESOURCE_ID

--id ID

--name NAME Location name

hammer location add-config-template

Usage:

hammer location add-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID

--id ID

--name NAME Location name

-h, --help print help

hammer location add-domain

Usage:

hammer location add-domain [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID

--name NAME Location name

-h, --help print help

hammer location add-environment

Usage:

hammer location add-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--id ID

--name NAME Location name

hammer location add-hostgroup

Usage:

hammer location add-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--name NAME Location name

-h, --help print help

hammer location add-medium

Usage:

hammer location add-medium [OPTIONS]

Options:

--id ID

--medium-id MEDIUM ID

--name NAME Location name

-h, --help print help

hammer location add-organization

Usage:

hammer location add-organization [OPTIONS]

Options:

--id ID

--name NAME Location name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

hammer location add-smart-proxy

Usage:

hammer location add-smart-proxy [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --smart-proxy SMART_PROXY_NAME Name to search by
- --smart-proxy-id SMART_PROXY_ID
- -h, --help print help

hammer location add-subnet

Usage:

hammer location add-subnet [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --subnet SUBNET_NAME Subnet name
- --subnet-id SUBNET_ID
- -h, --help print help

hammer location add-user

Usage:

hammer location add-user [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --user-id USER_ID
- -h, --help print help

hammer location create

Usage	
-------	--

hammer location create [OPTIONS]

Options:

--compute-resource-ids COMPUTE_RESOURCE_IDS Compute resource IDs

Comma separated list of values.

--compute-resources COMPUTE RESOURCE NAMES Comma separated list of values.

--config-template-ids CONFIG TEMPLATE IDS

Provisioning template IDs

Comma separated list of values.

--config-templates CONFIG TEMPLATE NAMES

Comma separated list of values.

--description DESCRIPTION

--domain-ids DOMAIN IDS

Domain IDs

Comma separated list of values.

--domains DOMAIN NAMES --environment-ids ENVIRONMENT IDS

Comma separated list of values. **Environment IDs**

Comma separated list of values.

--environments ENVIRONMENT NAMES

Comma separated list of values.

--hostgroup-ids HOSTGROUP_IDS

Host group IDs Comma separated list of values.

--hostgroup-titles HOSTGROUP TITLES

Comma separated list of values.

--hostgroups HOSTGROUP NAMES

Comma separated list of values.

--media MEDIUM NAMES

Comma separated list of values.

--media-ids MEDIA IDS

Media IDs

Comma separated list of values.

--name NAME

--parent-id PARENT ID

Parent ID

--partition-table-ids PARTITION TABLE IDS

Partition template IDs

Comma separated list of values.

--partition-tables PARTITION_TABLE_NAMES

Comma separated list of values.

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values.

--provisioning-templates PROVISIONING TEMPLATE NAMES Comma separated list of values.

--realm-ids REALM IDS

Realm IDs

Comma separated list of values.

--realms REALM NAMES

Comma separated list of values.

--smart-proxies SMART_PROXY_NAMES

Comma separated list of values.

--smart-proxy-ids SMART PROXY IDS

Capsule IDs

Comma separated list of values.

--subnet-ids SUBNET_IDS Subnet IDs

Comma separated list of values.

--subnets SUBNET_NAMES

Comma separated list of values.

--user-ids USER_IDS

User IDs

Comma separated list of values.

--users USER_LOGINS Comma separated list of values.

-h, --help print help

hammer location delete

Usage:

hammer location delete [OPTIONS]

Options:

--id ID Location numeric id to search by

--name NAME Organization name

-h, --help print help

hammer location delete-parameter

Usage:

hammer location delete-parameter [OPTIONS]

Options:

--location-id LOCATION_ID

--name NAME parameter name

-h, --help print help

hammer location info

Usage:

hammer location info [OPTIONS]

Options:

--id ID Location numeric id to search by

--name NAME Organization name

hammer location list

Usage:

hammer location list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer location remove-compute-resource

Usage:

hammer location remove-compute-resource [OPTIONS]

Options:

--compute-resource-id COMPUTE RESOURCE ID

--id ID

--name NAME Location name

-h, --help print help

hammer location remove-config-template

Usage:

hammer location remove-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID

--id ID

--name NAME Location name

-h, --help print help

hammer location remove-domain

Usage:

hammer location remove-domain [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID

--name NAME Location name

-h, --help print help

hammer location remove-environment

Usage:

hammer location remove-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--id ID

--name NAME Location name

-h, --help print help

hammer location remove-hostgroup

Usage:

hammer location remove-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--name NAME Location name

-h, --help print help

hammer location remove-medium

Usage:

hammer location remove-medium [OPTIONS]

Options:

- --id ID
- --medium MEDIUM NAME

Medium name

- --medium-id MEDIUM_ID
- --name NAME Location name
- -h, --help print help

hammer location remove-organization

Usage:

hammer location remove-organization [OPTIONS]

Options:

- --id ID
- --name NAME

Location name

- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID organization ID
- -h, --help print help

hammer location remove-smart-proxy

Usage:

hammer location remove-smart-proxy [OPTIONS]

Options:

- --id ID
- --name NAME

Location name

- --smart-proxy SMART_PROXY_NAME Name to search by
- $\hbox{\it --smart-proxy-id SMART_PROXY_ID}$
- -h, --help print help

hammer location remove-subnet

Usage:

hammer location remove-subnet [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --subnet SUBNET_NAME Subnet name

```
--subnet-id SUBNET_ID
-h, --help print help
```

hammer location remove-user

Usage:

hammer location remove-user [OPTIONS]

Options:

--id ID

--name NAME Location name

--user-id USER_ID

-h, --help print help

hammer location set-parameter

Usage:

hammer location set-parameter [OPTIONS]

Options:

--location-id LOCATION_ID

--name NAME parameter name
--value VALUE parameter value

-h, --help print help

hammer location update

Usage:

hammer location update [OPTIONS]

Options:

--compute-resource-ids COMPUTE_RESOURCE_IDS Compute resource IDs Comma separated list of values.

--compute-resources COMPUTE_RESOURCE_NAMES Comma separated list of values.

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs Comma separated list of values.

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. --description DESCRIPTION --domain-ids DOMAIN_IDS Domain IDs Comma separated list of values. --domains DOMAIN_NAMES Comma separated list of values. --environment-ids ENVIRONMENT IDS **Environment IDs** Comma separated list of values. --environments ENVIRONMENT NAMES Comma separated list of values. --hostgroup-ids HOSTGROUP IDS Host group IDs Comma separated list of values. Comma separated list of values. --hostgroup-titles HOSTGROUP_TITLES --hostgroups HOSTGROUP NAMES Comma separated list of values. --id ID Location numeric id to search by --media MEDIUM_NAMES Comma separated list of values. --media-ids MEDIA_IDS Media IDs Comma separated list of values. --name NAME --new-name NEW_NAME --parent-id PARENT_ID Parent ID --partition-table-ids PARTITION_TABLE_IDS Partition template IDs Comma separated list of values. --partition-tables PARTITION_TABLE_NAMES Comma separated list of values. --provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs Comma separated list of values. --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. --realm-ids REALM IDS Realm IDs Comma separated list of values. Comma separated list of values. --realms REALM_NAMES --smart-proxies SMART PROXY NAMES Comma separated list of values. --smart-proxy-ids SMART PROXY IDS Capsule IDs Comma separated list of values. --subnet-ids SUBNET_IDS Subnet IDs Comma separated list of values. --subnets SUBNET NAMES Comma separated list of values. --user-ids USER_IDS User IDs Comma separated list of values. Comma separated list of values. --users USER_LOGINS

print help

-h, --help

hammer medium

Usage:

hammer medium [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

create Create a medium delete Delete a medium info Show a medium

list List all installation media

remove-operatingsystem Disassociate an operating system

update Update a medium

Options:

-h, --help print help

hammer medium add-operatingsystem

Usage:

hammer medium add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Medium name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer medium create

Usage:

hammer medium create [OPTIONS]

Options:

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Name of media

- --operatingsystem-ids OPERATINGSYSTEM IDS Comma separated list of values.
- --operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--os-family OS_FAMILY Operating system family, available values: AIX, Altlinux,

Archlinux,

Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Redhat, Solaris,

Suse,

Windows

--path PATH The path to the medium, can be a URL or a valid NFS server

(exclusive of

the architecture).

for example mirror.centos.org/centos/\$version/os/\$arch

where \$arch will be substituted for the host's actual OS architecture and \$version, \$major and \$minor will be substituted for the version of

the

operating system.

Solaris and Debian media may also use \$release.

-h, --help print help

hammer medium delete

Usage:

hammer medium delete [OPTIONS]

Options:

--id ID

--name NAME Medium name

-h, --help print help

hammer medium info

Usage:

hammer medium info [OPTIONS]

Options:

--id ID

--name NAME Medium name

-h, --help print help

hammer medium list

Usage:

hammer medium list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

 $\hbox{\it --} operating system-id\ OPERATING SYSTEM_ID$

--order ORDER sort results
--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer medium remove-operatingsystem

Usage:

hammer medium remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Medium name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

hammer medium update

Usage:

hammer medium update [OPTIONS]

Options:

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Medium name

--new-name NEW_NAME Name of media

--operatingsystem-ids OPERATINGSYSTEM IDS Comma separated list of values.

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION NAMES Comma separated list of values.

--os-family OS_FAMILY Operating system family, available values: AIX, Altlinux,

Archlinux.

Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Redhat, Solaris,

Suse,

Windows

--path PATH The path to the medium, can be a URL or a valid NFS server

(exclusive of

the architecture).

for example mirror.centos.org/centos/\$version/os/\$arch

where \$arch will be substituted for the host's actual OS architecture and \$version, \$major and \$minor will be substituted for the version of

the

operating system.

Solaris and Debian media may also use \$release.

-h, --help print help

hammer model

Usage:

hammer model [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a hardware model
delete Delete a hardware model
info Show a hardware model
list List all hardware models
update Update a hardware model

Options:

-h, --help print help

hammer model create

Usage:

hammer model create [OPTIONS]

Options:

- --hardware-model HARDWARE_MODEL
- --info INFO
- --name NAME
- --vendor-class VENDOR_CLASS -h, --help print help

hammer model delete

Usage:

hammer model delete [OPTIONS]

Options:

--id ID

--name NAME Model name

hammer model info

Usage:

hammer model info [OPTIONS]

Options:

--id ID

--name NAME Model name

-h, --help print help

hammer model list

Usage:

hammer model list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer model update

Usage:

hammer model update [OPTIONS]

Options:

--hardware-model HARDWARE_MODEL

--id ID

--info INFO

--name NAME Model name

--new-name NEW_NAME

--vendor-class VENDOR_CLASS

hammer organization

Usage:

hammer organization [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-compute-resource Associate a compute resource add-config-template Associate a configuration template

add-domain Associate a domain

add-environment Associate an environment add-hostgroup Associate a hostgroup

add-medium Associate a medium

add-smart-proxy Associate a smart proxy add-subnet Associate a subnet

add-subnet Associate a subnet add-user Associate an user create Create organization delete Delete an organization

delete-parameter Delete parameter for an organization.

info Show organization list List all organizations

remove-compute-resource Disassociate a compute resource remove-config-template Disassociate a configuration template

remove-domain Disassociate a domain

remove-environment Disassociate an environment

remove-hostgroup

remove-medium

Disassociate a hostgroup

Disassociate a medium

Disassociate a smart proxy

remove-subnet Disassociate a subnet Pisassociate an user

set-parameter Create or update parameter for an organization.

update Update organization

Options:

hammer organization add-compute-resource

Usage:

hammer organization add-compute-resource [OPTIONS]

Options:

--compute-resource-id COMPUTE_RESOURCE_ID

--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization add-config-template

Usage:

hammer organization add-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID
--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization add-domain

Usage:

hammer organization add-domain [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID organization ID

--name NAME Organization name

hammer organization add-environment

Usage:

hammer organization add-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID
--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization add-hostgroup

Usage:

hammer organization add-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization add-medium

Usage:

hammer organization add-medium [OPTIONS]

Options:

--id ID organization ID

--medium-id MEDIUM ID

--name NAME Organization name

hammer organization add-smart-proxy

Usage:

hammer organization add-smart-proxy [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name

--smart-proxy SMART_PROXY_NAME Name to search by

--smart-proxy-id SMART_PROXY_ID

-h, --help print help

hammer organization add-subnet

Usage:

hammer organization add-subnet [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

-h, --help print help

hammer organization add-user

Usage:

hammer organization add-user [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name

--user-id USER_ID

hammer organization create

U	sa	ıa	е	

hammer organization create [OPTIONS]

Options:

Comma separated list of values.

values.

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values.

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values.

--description DESCRIPTION description
--domain-ids DOMAIN IDS Domain IDs

Comma separated list of values.

--domains DOMAIN_NAMES Comma separated list of values.

--environment-ids ENVIRONMENT_IDS Environment IDs

Comma separated list of values.

--environments ENVIRONMENT NAMES Comma separated list of values.

--hostgroup-ids HOSTGROUP_IDS Host group IDs Comma separated list of values.

--hostgroups HOSTGROUP_NAMES Comma separated list of values.

--label LABEL unique label

--media MEDIUM_NAMES Comma separated list of values.

--media-ids MEDIA IDS Media IDs

Comma separated list of values.

--name NAME name

 $\hbox{\it --provisioning-template-ids PROVISIONING_TEMPLATE_IDS\ Provisioning\ template\ IDs}$

Comma separated list of values.

 $\hbox{--provisioning-templates PROVISIONING_TEMPLATE_NAMES} \ \ Comma \ separated \ list \ of$

values.

--ptable-ids PTABLE_IDS Partition template IDs

Comma separated list of values.

--ptables PTABLE NAMES Comma separated list of values.

--realm-ids REALM_IDS Realm IDs

Comma separated list of values.

--realms REALM NAMES Comma separated list of values.

--smart-proxies SMART PROXY NAMES Comma separated list of values.

--smart-proxy-ids SMART_PROXY_IDS Capsule IDs

Comma separated list of values.

--subnet-ids SUBNET_IDS Subnet IDs

Comma separated list of values.

--subnets SUBNET_NAMES Comma separated list of values.

--user-ids USER_IDS User IDs

Comma separated list of values.

--users USER_NAMES Comma separated list of values.

-h, --help print help

hammer organization delete

Usage:

hammer organization delete [OPTIONS]

Options:

--async Do not wait for the task

--id ID

--label LABEL Organization label to search by

--name NAME Organization name

-h, --help print help

hammer organization delete-parameter

Usage:

hammer organization delete-parameter [OPTIONS]

Options:

--name NAME parameter name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

-h, --help print help

hammer organization info

Usage:

hammer organization info [OPTIONS]

Options:

--id ID

--label LABEL Organization label to search by

--name NAME Organization name

-h, --help print help

hammer organization list

Usage:

hammer organization list [OPTIONS]

Options:

--by BY Field to sort the results on

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'name DESC'

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help print help

hammer organization remove-compute-resource

Usage:

hammer organization remove-compute-resource [OPTIONS]

Options:

--compute-resource-id COMPUTE_RESOURCE_ID

--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization remove-config-template

Usage:

hammer organization remove-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID
--id ID organization ID

--name NAME Organization name

hammer organization remove-domain

Usage:

hammer organization remove-domain [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization remove-environment

Usage:

hammer organization remove-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID
--id ID organization ID

--name NAME Organization name

-h, --help print help

hammer organization remove-hostgroup

Usage:

hammer organization remove-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID organization ID

--name NAME Organization name

hammer organization remove-medium

Usage:

hammer organization remove-medium [OPTIONS]

Options:

--id ID organization ID

--medium MEDIUM NAME Medium name

--medium-id MEDIUM ID

--name NAME Organization name

-h, --help print help

hammer organization remove-smart-proxy

Usage:

hammer organization remove-smart-proxy [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name

--smart-proxy SMART_PROXY_NAME Name to search by

--smart-proxy-id SMART_PROXY_ID
-h, --help print help

hammer organization remove-subnet

Usage:

hammer organization remove-subnet [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name
--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

hammer organization remove-user

Usage:

hammer organization remove-user [OPTIONS]

Options:

--id ID organization ID

--name NAME Organization name

--user-id USER_ID

-h, --help print help

hammer organization set-parameter

Usage:

hammer organization set-parameter [OPTIONS]

Options:

--name NAME parameter name

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--value VALUE parameter value

-h, --help print help

hammer organization update

Usage:

hammer organization update [OPTIONS]

Options:

Comma separated list of values.

values.

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values.

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values.

--description DESCRIPTION

--domain-ids DOMAIN IDS Domain IDs

Comma separated list of values.

--domains DOMAIN_NAMES Comma separated list of values.

--environment-ids ENVIRONMENT_IDS Environment IDs

Comma separated list of values.

--environments ENVIRONMENT_NAMES Comma separated list of values.

--hostgroup-ids HOSTGROUP_IDS Host group IDs

Comma separated list of values.

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values.
--hostgroups HOSTGROUP_NAMES Comma separated list of values.

--id ID

--label LABEL Organization label to search by

--media MEDIUM_NAMES Comma separated list of values.

--media-ids MEDIA_IDS Media IDs

Comma separated list of values.

--name NAME Organization name

--new-name NEW_NAME

--parent-id PARENT_ID Parent ID

--partition-table-ids PARTITION_TABLE_IDS Partition template IDs

Comma separated list of values.

 $\hbox{\it --provisioning-template-ids} \ PROVISIONING_TEMPLATE_IDS \ Provisioning \ template \ IDs$

Comma separated list of values.

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values.

--ptable-ids PTABLE_IDS Partition template IDs

Comma separated list of values.

--ptables PTABLE NAMES Comma separated list of values.

--realm-ids REALM_IDS Realm IDs

Comma separated list of values.

--realms REALM_NAMES Comma separated list of values.

--redhat-repository-url REDHAT REPOSITORY URL Red Hat CDN URL

--smart-proxies SMART_PROXY_NAMES Comma separated list of values.

--smart-proxy-ids SMART_PROXY_IDS Capsule IDs

Comma separated list of values.

--subnet-ids SUBNET IDS Subnet IDs

Comma separated list of values.

--subnets SUBNET_NAMES Comma separated list of values.

--user-ids USER IDS User IDs

Comma separated list of values.

--users USER_LOGINS Comma separated list of values.

hammer os

Usage:

hammer os [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-architecture Associate an architecture

add-config-template Associate a configuration template

add-ptable Associate a partition table create Create an operating system delete Delete an operating system

delete-default-template

delete-parameter Delete parameter for an operating system.

info Show an operating system list List all operating systems

remove-architecture Disassociate an architecture

remove-config-template Disassociate a configuration template

remove-ptable Disassociate a partition table

set-default-template

set-parameter Create or update parameter for an operating system.

update Update an operating system

Options:

-h, --help print help

hammer os add-architecture

Usage:

hammer os add-architecture [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--id ID

--title TITLE Operating system title

hammer os add-config-template

Usage:

hammer os add-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID

--id ID

--title TITLE Operating system title

-h, --help print help

hammer os add-ptable

Usage:

hammer os add-ptable [OPTIONS]

Options:

--id ID

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--title TITLE Operating system title

-h, --help print help

hammer os create

Usage:

hammer os create [OPTIONS]

Options:

--architecture-ids ARCHITECTURE IDS IDs of associated architectures

Comma separated list of values.

--architectures ARCHITECTURE_NAMES Comma separated list of values.

templates

Comma separated list of values.

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values.

- --description DESCRIPTION
- --family FAMILY
- --major MAJOR
- --media MEDIUM_NAMES Comma separated list of values.

Comma separated list of values.

- --minor MINOR
- --name NAME
- --os-parameters-attributes OS_PARAMETERS_ATTRIBUTES OS' parameters (array or indexed hash)

Comma separated list of values.

Comma separated list of values.

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values.

--password-hash PASSWORD_HASH Root password hash function to use, one

of MD5, SHA256, SHA512, Base64

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning templates

Comma separated list of values.

- --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values.
- --release-name RELEASE_NAME

-h, --help print help

hammer os delete

Usage:

hammer os delete [OPTIONS]

Options:

--id ID

--title TITLE Operating system title

-h, --help print help

hammer os delete-default-template

Usage:

hammer os delete-default-template [OPTIONS]

Options:

--id OS ID operatingsystem id

--type TPL TYPE Type of the config template

-h, --help print help

hammer os delete-parameter

Usage:

hammer os delete-parameter [OPTIONS]

Options:

--name NAME parameter name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer os info

Usage:

hammer os info [OPTIONS]

Options:

--id ID

--title TITLE Operating system title

-h, --help print help

hammer os list

Usage:

hammer os list [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--config-template-id CONFIG_TEMPLATE_ID

--medium MEDIUM_NAME Medium name

--medium-id MEDIUM_ID

--order ORDER sort results
--page PAGE paginate results

--partition-table PARTITION_TABLE_NAME Partition table name

- --partition-table-id PARTITION_TABLE_ID
- --per-page PER_PAGE number of entries per request
- --provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by
- --provisioning-template-id PROVISIONING_TEMPLATE_ID
- --search SEARCH filter results
- -h, --help print help

hammer os remove-architecture

Usage:

hammer os remove-architecture [OPTIONS]

Options:

- --architecture ARCHITECTURE_NAME Architecture name
- --architecture-id ARCHITECTURE_ID
- --id ID
- --title TITLE Operating system title
- -h, --help print help

hammer os remove-config-template

Usage:

hammer os remove-config-template [OPTIONS]

Options:

- --config-template CONFIG_TEMPLATE_NAME Name to search by
- --config-template-id CONFIG_TEMPLATE_ID
- --id ID
- --title TITLE Operating system title

-h, --help print help

hammer os remove-ptable

Usage:

hammer os remove-ptable [OPTIONS]

Options:

- --id ID
- --partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--title TITLE Operating system title

-h, --help print help

hammer os set-default-template

Usage:

hammer os set-default-template [OPTIONS]

Options:

--config-template-id TPL ID config template id to be set

--id OS ID operatingsystem id

-h, --help print help

hammer os set-parameter

Usage:

hammer os set-parameter [OPTIONS]

Options:

--name NAME parameter name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID
--value VALUE parameter value

-h, --help print help

hammer os update

Usage:

hammer os update [OPTIONS]

Options:

--architecture-ids ARCHITECTURE IDS IDs of associated architectures

Comma separated list of values.

--architectures ARCHITECTURE_NAMES Comma separated list of values.

templates

Comma separated list of values.

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values.

- --description DESCRIPTION
- --family FAMILY
- --id ID
- --major MAJOR
- --media MEDIUM_NAMES Comma separated list of values.
- --medium-ids MEDIUM IDS IDs of associated media

Comma separated list of values.

- --minor MINOR
- --name NAME
- --os-parameters-attributes OS_PARAMETERS_ATTRIBUTES OS' parameters (array or indexed hash)

Comma separated list of values.

Comma separated list of values.

--partition-tables PARTITION TABLE NAMES Comma separated list of values.

--password-hash PASSWORD_HASH Root password hash function to use, one

of MD5, SHA256, SHA512, Base64

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning templates

Comma separated list of values.

- --provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values.
- --release-name RELEASE NAME

--title TITLE Operating system title

-h, --help print help

hammer ostree-branch

Usage:

hammer ostree-branch [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show an ostree branch list List ostree_branches

Options:

hammer ostree-branch info

Usage:

hammer ostree-branch info [OPTIONS]

Options:

--id ID an ostree branch identifier --name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

-h, --help print help

hammer ostree-branch list

Usage:

hammer ostree-branch list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME
Name to search by

--content-view-filter-id CONTENT VIEW FILTER ID filter identifier

--content-view-id CONTENT VIEW ID content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT NAME Name to search by

--environment-id ENVIRONMENT ID

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS ids to filter content by

Comma separated list of values.

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
product numeric identifier

--repository REPOSITORY NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID
--search SEARCH Search string
-h, --help print help

hammer package

Usage:

hammer package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a package list List packages

Options:

-h, --help print help

hammer package info

Usage:

hammer package info [OPTIONS]

Options:

--id ID a package identifier
--name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

-h, --help print help

hammer package list

Usage:

hammer package list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT VIEW FILTER NAME Name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID filter identifier

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT_NAME Name to search by

--environment-id ENVIRONMENT ID

--full-results FULL RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS ids to filter content by

Comma separated list of values.

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID
--search SEARCH Search string

-h, --help print help

hammer package-group

Usage:

hammer package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a package group list List package_groups

Options:

hammer package-group info

Usage:

hammer package-group info [OPTIONS]

Options:

--id ID a package group identifier --name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

-h, --help print help

hammer package-group list

Usage:

hammer package-group list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT VIEW NAME Content view name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID filter identifier

--content-view-id CONTENT VIEW ID content view numeric identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT NAME Name to search by

--environment-id ENVIRONMENT ID

--full-results FULL RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS ids to filter content by

Comma separated list of values.

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

--search SEARCH Search string

-h, --help print help

hammer partition-table

Usage:

hammer partition-table [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

create Create a partition table
delete Delete a partition table
dump View partition table content.

info Show a partition table list List all partition tables

remove-operatingsystem Disassociate an operating system

update Update a partition table

Options:

-h, --help print help

hammer partition-table add-operatingsystem

Usage:

hammer partition-table add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Partition table name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

hammer partition-table create

Usage:

hammer partition-table create [OPTIONS]

Options:

- --audit-comment AUDIT_COMMENT
- --file LAYOUT Path to a file that contains the partition layout
- --host-ids HOST_IDS Array of host IDs to associate with the partition table

Comma separated list of values.

--hostgroup-ids HOSTGROUP_IDS Array of host group IDs to associate with the partition table

Comma separated list of values.

- --hostgroup-titles HOSTGROUP_TITLES Comma separated list of values.
 --hostgroups HOSTGROUP_NAMES Comma separated list of values.
- --hosts HOST_NAMES Comma separated list of values.
 --location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values.

- --locations LOCATION_NAMES Comma separated list of values.
- --locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

- --name NAME
- --operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the partition table

Comma separated list of values.

- --operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.
- --organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values.

- --organizations ORGANIZATION_NAMES Comma separated list of values.
- --os-family OS_FAMILY
- --snippet SNIPPET One of true/false, yes/no, 1/0.
- -h, --help print help

hammer partition-table delete

Usage:

hammer partition-table delete [OPTIONS]

Options:

- --id ID
- --name NAME Partition table name

hammer partition-table dump

Usage:

hammer partition-table dump [OPTIONS]

Options:

--id ID

--name NAME Partition table name

-h, --help print help

hammer partition-table info

Usage:

hammer partition-table info [OPTIONS]

Options:

--id ID

--name NAME Partition table name

-h, --help print help

hammer partition-table list

Usage:

hammer partition-table list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--order ORDER sort results

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

hammer partition-table remove-operatingsystem

Usage:

hammer partition-table remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Partition table name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer partition-table update

Usage:

hammer partition-table update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file LAYOUT Path to a file that contains the partition layout

--host-ids HOST IDS Array of host IDs to associate with the partition table

Comma separated list of values.

partition table

Comma separated list of values.

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values.
--hostgroups HOSTGROUP_NAMES Comma separated list of values.

--hosts HOST_NAMES Comma separated list of values.

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Partition table name

--new-name NEW_NAME

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the partition table

Comma separated list of values.

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--os-family OS_FAMILY

--snippet SNIPPET One of true/false, yes/no, 1/0.

-h, --help print help

hammer ping

Usage:

hammer ping [OPTIONS]

Options:

-h, --help print help

hammer product

Usage:

hammer product [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a product
delete Destroy a product
info Show a product
list List products

remove-sync-plan Delete assignment sync plan and product.

set-sync-plan Assign sync plan to product.

synchronize Sync all repositories for a product

update Updates a product

Options:

hammer product create

Usage:

hammer product create [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID gpg key numeric identifier

--label LABEL

--name NAME Product name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--sync-plan SYNC_PLAN_NAME Sync plan name to search by --sync-plan-id SYNC PLAN ID sync plan numeric identifier

-h, --help print help

hammer product delete

Usage:

hammer product delete [OPTIONS]

Options:

--id ID product numeric identifier

--name NAME Product name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer product info

Usage:

hammer product info [OPTIONS]

Options:

--id ID product numeric identifier

--name NAME Product name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer product list

Usage:

hammer product list [OPTIONS]

Options:

--available-for AVAILABLE_FOR Interpret specified object to return only

Products that can be associated

with specified object. Only 'sync_plan' is supported.

--by BY Field to sort the results on

--custom CUSTOM Filter products by custom

One of true/false, yes/no, 1/0.

--enabled ENABLED Filter products by enabled or disabled

One of true/false, yes/no, 1/0.

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--include-available-content INCLUDE_AVAILABLE_CONTENT Whether to include available

content attribute in results

One of true/false, yes/no, 1/0.

--name NAME Filter products by name

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--subscription SUBSCRIPTION_NAME Subscription name to search by

--subscription-id SUBSCRIPTION_ID Subscription identifier

--sync-plan SYNC_PLAN_NAME Sync plan name to search by --sync-plan-id SYNC_PLAN_ID sync plan numeric identifier

-h, --help print help

hammer product remove-sync-plan

Usage:

hammer product remove-sync-plan [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG KEY ID gpg key numeric identifier

--id ID product numeric identifier

--name NAME Product name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer product set-sync-plan

Usage:

hammer product set-sync-plan [OPTIONS]

Options:

--gpg-key GPG_KEY_NAME Name to search by --gpg-key-id GPG_KEY_ID gpg key numeric identifier

--id ID product numeric identifier

--name NAME Product name to search by

--new-name NEW_NAME Product name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--sync-plan SYNC_PLAN_NAME Sync plan name to search by --sync-plan-id SYNC_PLAN_ID sync plan numeric identifier

-h, --help print help

hammer product synchronize

Usage:

hammer product synchronize [OPTIONS]

Options:

--async Do not wait for the task

--id ID product ID

--name NAME Product name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer product update

Usage:

hammer product update [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID gpg key numeric identifier

--id ID product numeric identifier

--name NAME Product name to search by

--new-name NEW NAME Product name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--sync-plan SYNC_PLAN_NAME Sync plan name to search by --sync-plan-id SYNC_PLAN_ID sync plan numeric identifier

-h, --help print help

hammer proxy

Usage:

hammer proxy [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

content Manage the capsule content

create Create a capsule delete Delete a capsule

import-classes Import puppet classes from puppet Capsule.

info Show a capsule

list List all capsules

refresh-features Refresh capsule features

update Update a capsule

Options:

-h, --help print help

hammer proxy content

Usage:

hammer proxy content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-lifecycle-environment
Add lifecycle environments to the capsule

available-lifecycle-environments List the lifecycle environments not attached to the capsule

cancel-synchronization Cancel running capsule synchronization.

info Get current capsule synchronization status

lifecycle-environments List the lifecycle environments attached to the capsule remove-lifecycle-environment Remove lifecycle environments from the capsule

synchronization-status Get current capsule synchronization status

synchronize Synchronize the content to the capsule

Options:

-h, --help print help

hammer proxy create

Usage:

hammer proxy create [OPTIONS]

Options:

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--url URL

-h, --help print help

hammer proxy delete

Usage:

hammer proxy delete [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer proxy import-classes

Usage:

hammer proxy import-classes [OPTIONS]

Options:

--dryrun Do not run the import

--environment ENVIRONMENT_NAME Environment name

--environment-id ENVIRONMENT_ID

--except EXCEPT Optional comma-delimited string containing either 'new',

'updated', or 'obsolete' that is used to limit the imported

Puppet classes

--id ID

--name NAME Name to search by

-h, --help print help

hammer proxy info

Usage:

hammer proxy info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

hammer proxy list

Usage:

hammer proxy list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer proxy refresh-features

Usage:

hammer proxy refresh-features [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer proxy update

Usage:

hammer proxy update [OPTIONS]

Options:

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--name NAME Name to search by

--new-name NEW NAME

- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.
 - Comma separated list of values.
- --organizations ORGANIZATION_NAMES Comma separated list of values.
- --url URL

-h, --help print help

hammer puppet-class

Usage:

hammer puppet-class [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a Puppet class list List all Puppet classes

sc-params List all smart class parameters

smart-variables List all smart variables

Options:

-h, --help print help

hammer puppet-class info

Usage:

hammer puppet-class info [OPTIONS]

Options:

--environment-id ENVIRONMENT_ID

--host HOST_NAME Host name

--host-id HOST ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID ID of Puppet class

--name NAME Puppet class name

hammer puppet-class list

Usage:

hammer puppet-class list [OPTIONS]

Options:

--environment-id ENVIRONMENT_ID

--host HOST_NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer puppet-class sc-params

Usage:

hammer puppet-class sc-params [OPTIONS]

Options:

--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

-h, --help print help

hammer puppet-class smart-variables

Usage:

hammer puppet-class smart-variables [OPTIONS]

Options:

--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

-h, --help print help

hammer puppet-module

Usage:

hammer puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info Show a puppet module list List puppet_modules

Options:

-h, --help print help

hammer puppet-module info

Usage:

hammer puppet-module info [OPTIONS]

Options:

--id ID a puppet module identifier --name NAME Name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID repository ID

hammer puppet-module list

Usage:

hammer puppet-module list [OPTIONS]

Options:

--by BY Field to sort the results on

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID filter identifier

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT NAME Name to search by

--environment-id ENVIRONMENT ID

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS ids to filter content by

Comma separated list of values.

--order ORDER Sort field and order, eq. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product id PRODUCT_ID
--product numeric identifier

--product-id PRODUCT_ID product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID repository ID

--search SEARCH Search string

-h, --help print help

hammer recurring-logic

Usage:

hammer recurring-logic [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

cancel Cancel recurring logic info Show recurring logic details

list List recurring logics

Options:

-h, --help print help

hammer recurring-logic cancel

Usage:

hammer recurring-logic cancel [OPTIONS]

Options:

--id ID ID of the recurring logic --name NAME Name to search by

-h, --help print help

hammer recurring-logic info

Usage:

hammer recurring-logic info [OPTIONS]

Options:

--id ID ID of the recurring logic --name NAME Name to search by

-h, --help print help

hammer recurring-logic list

Usage:

hammer recurring-logic list [OPTIONS]

Options:

hammer remote-execution-feature

Usage:

hammer remote-execution-feature [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

info list update

Options:

-h, --help print help

hammer remote-execution-feature info

Usage:

hammer remote-execution-feature info [OPTIONS]

Options:

-h, --help print help

hammer remote-execution-feature list

Usage:

hammer remote-execution-feature list [OPTIONS]

Options:

-h, --help print help

hammer remote-execution-feature update

Usage:

Options:

-h, --help print help

hammer report

Usage:

hammer report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

delete Delete a report info Show a report list List all reports

Options:

-h, --help print help

hammer report delete

Usage:

hammer report delete [OPTIONS]

Options:

--id ID

--name NAME Report name

-h, --help print help

hammer report info

Usage:

hammer report info [OPTIONS]

Options:

--id ID

--name NAME Report name

-h, --help print help

hammer report list

Usage:

hammer report list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer repository

Usage:

hammer repository [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a custom repository delete Destroy a custom repository

export Export a repository info Show a repository

list List of enabled repositories

remove-content

synchronize Sync a repository update Update a repository

upload-content Upload content into the repository

Options:

hammer repository create

Usage:

hammer repository create [OPTIONS]

Options:

--checksum-type CHECKSUM_TYPE checksum of the repository, currently 'sha1' & 'sha256'

are supported.'

--content-type CONTENT_TYPE type of repo (either 'yum', 'puppet', 'docker', or

'ostree')

Possible value(s): 'docker', 'file', 'puppet', 'yum'

--docker-upstream-name DOCKER_UPSTREAM_NAME name of the upstream docker repository

--download-policy DOWNLOAD_POLICY download policy for yum repos (either 'immediate'.

'on demand', or 'background')

Possible value(s): 'immediate', 'on_demand', 'background'

--gpg-key GPG_KEY_NAME Name to search by --gpg-key-id GPG_KEY_ID gpg key numeric identifier

--label LABEL

--mirror-on-sync MIRROR_ON_SYNC true if this repository when synced has to be mirrored from the source and

stale rpms removed.

One of true/false, yes/no, 1/0.

--name NAME

--organization-id ORGANIZATION_ID organization ID

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID product numeric identifier

--publish-via-http ENABLE Publish Via HTTP

One of true/false, yes/no, 1/0.

--url URL repository source url

-h, --help print help

hammer repository delete

Usage:

hammer repository delete [OPTIONS]

Options:

--id ID

--name NAME Repository name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

-h, --help print help

hammer repository export

Usage:

hammer repository export [OPTIONS]

Options:

--async Do not wait for the task

One of true/false, yes/no, 1/0.

--id ID Repository identifier

--iso-mb-size ISO_MB_SIZE maximum size of each ISO in MB

--name NAME Repository name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier

--since SINCE Optional date of last export (ex: 2010-01-01T12:00:00Z)

-h, --help print help

hammer repository info

Usage:

hammer repository info [OPTIONS]

Options:

--id ID repository ID

--name NAME Repository name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier
-h, --help print help

hammer repository list

Usage:

hammer repository list [OPTIONS]

Options:

--available-for AVAILABLE_FOR interpret specified object to return only

Repositories that can be

associated with specified object. Only 'content_view' is

supported.

--by BY Field to sort the results on

--content-type CONTENT_TYPE limit to only repositories of this type

Possible value(s): 'docker', 'file', 'puppet', 'yum'

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-id CONTENT_VIEW_ID content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT_NAME Name to search by

--environment-id ENVIRONMENT ID

--erratum-id ERRATUM ID Id of an erratum to find repositories that contain

the erratum

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--library LIBRARY show repositories in Library and the default content

view

One of true/false, yes/no, 1/0.

--name NAME name of the repository

--order ORDER Sort field and order, eg. 'name DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
product numeric identifier

--rpm-id RPM_ID Id of a package to find repositories that contain the rpm

--search SEARCH Search string

hammer repository remove-content

Usage:

hammer repository remove-content [OPTIONS]

Options:

--content-ids CONTENT_IDS package IDs, puppet module IDs, and/or docker manifest

IDs

Comma separated list of values.

--id ID repository ID

--name NAME Repository name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer repository synchronize

Usage:

hammer repository synchronize [OPTIONS]

Options:

--async Do not wait for the task

--id ID repository ID

--incremental INCREMENTAL perform an incremental import

One of true/false, yes/no, 1/0.

--name NAME Repository name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

--source-url SOURCE URL temporarily override feed URL for sync

-h, --help print help

hammer repository update

Usage:

hammer repository update [OPTIONS]

Options:

--checksum-type CHECKSUM_TYPE checksum of the repository, currently 'sha1' & 'sha256'

are supported.'

--docker-upstream-name DOCKER_UPSTREAM_NAME name of the upstream docker repository

--download-policy DOWNLOAD_POLICY download policy for yum repos (either 'immediate',

'on_demand', or 'background')

Possible value(s): 'immediate', 'on demand', 'background'

--gpg-key GPG_KEY_NAME Name to search by --gpg-key-id GPG_KEY_ID gpg key numeric identifier

--id ID repository ID

--mirror-on-sync MIRROR_ON_SYNC true if this repository when synced has to be mirrored from the source and

stale rpms removed.

One of true/false, yes/no, 1/0.

--name NAME Repository name to search by
--new-name NEW_NAME New name for the repository

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

--publish-via-http ENABLE Publish Via HTTP

One of true/false, yes/no, 1/0.

--url URL the feed url of the original repository

-h, --help print help

hammer repository upload-content

Usage:

hammer repository upload-content [OPTIONS]

Options:

--id ID repository ID

--name NAME Repository name to search by

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--path PATH Upload file or directory of files as content for a repository

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier

-h, --help print help

hammer repository-set

Usage:

hammer repository-set [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

available-repositories Get list or available repositories for the repository set

disable Disable a repository form the set enable Enable a repository from the set info Get info about a repository set list List repository sets for a product.

Options:

-h, --help print help

hammer repository-set available-repositories

Usage:

hammer repository-set available-repositories [OPTIONS]

Options:

--id ID ID of the repository set

--name NAME Repository set name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

hammer repository-set disable

Usage:

hammer repository-set disable [OPTIONS]

Options:

--basearch BASEARCH Basearch to disable
--id ID ID of the repository set to enable

--name NAME Repository set name to search by

--new-name NEW_NAME

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier
--releasever RELEASEVER Releasever to disable

-h, --help print help

hammer repository-set enable

Usage:

hammer repository-set enable [OPTIONS]

Options:

--basearch BASEARCH Basearch to enable
--id ID ID of the repository set to enable

--name NAME Repository set name to search by

--new-name NEW_NAME

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID product numeric identifier
--releasever RELEASEVER Releasever to enable

-h, --help print help

hammer repository-set info

Usage:

hammer repository-set info [OPTIONS]

Options:

--id ID ID of the repository set

--name NAME Repository set name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID product numeric identifier

-h, --help print help

hammer repository-set list

Usage:

hammer repository-set list [OPTIONS]

Options:

--name NAME Repository set name to search on

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by product-id PRODUCT_ID product numeric identifier

-h, --help print help

hammer role

Usage:

hammer role [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a role delete Delete a role filters List all filters

info Show a role
list List all roles
update Update a role

Options:

-h, --help print help

hammer role create

Usage:

hammer role create [OPTIONS]

Options:

--name NAME

-h, --help print help

hammer role delete

Usage:

hammer role delete [OPTIONS]

Options:

--id ID

--name NAME User role name

-h, --help print help

hammer role filters

Usage:

hammer role filters [OPTIONS]

Options:

--id ID User role id

--name NAME User role name
--order ORDER sort results
--page PAGE paginate results

--per-page PER_PAGE number of entries per request

hammer role info

Usage:

hammer role info [OPTIONS]

Options: --id ID

--name NAME User role name

-h, --help print help

hammer role list

Usage:

hammer role list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer role update

Usage:

hammer role update [OPTIONS]

Options:

--id ID

--name NAME User role name

--new-name NEW_NAME

-h, --help print help

hammer sc-param

Usage:

hammer sc-param [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-override-value Create an override value for a specific smart variable

info Show a smart class parameter list List all smart class parameters

remove-override-value Delete an override value for a specific smart variable

update Update a smart class parameter

Options:

-h, --help print help

hammer sc-param add-override-value

Usage:

hammer sc-param add-override-value [OPTIONS]

Options:

--match MATCH Override match

--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET CLASS ID ID of Puppet class

--smart-class-parameter-id SMART_CLASS_PARAMETER_ID

--use-puppet-default USE_PUPPET_DEFAULT One of true/false, yes/no, 1/0.

--value VALUE Override value

-h, --help print help

hammer sc-param info

Usage:

hammer sc-param info [OPTIONS]

Options:

--id ID

--name NAME Smart class parameter name
--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class
-h, --help print help

hammer sc-param list

Usage:

hammer sc-param list [OPTIONS]

Options:

--environment-id ENVIRONMENT_ID

--host HOST_NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name

--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

-h, --help print help

hammer sc-param remove-override-value

Usage:

hammer sc-param remove-override-value [OPTIONS]

Options:

--id ID

--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET CLASS ID ID of Puppet class

--smart-class-parameter-id SMART_CLASS_PARAMETER_ID

-h, --help print help

hammer sc-param update

Usage:

hammer sc-param update [OPTIONS]

Options:

--avoid-duplicates AVOID_DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value DEFAULT_VALUE Value to use when there is no match

--description DESCRIPTION Description of smart class

--hidden-value HIDDEN_VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--id ID

--merge-default MERGE_DEFAULT Include default value when merging all matching

values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash

type)

One of true/false, yes/no, 1/0.

--name NAME Smart class parameter name --override OVERRIDE Override this parameter.

One of true/false, yes/no, 1/0.

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

--parameter-type PARAMETER_TYPE Type of the parameter.

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash',

'yaml', 'json'

--path PATH The order in which values are resolved

--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class
--required REQUIRED This parameter is required.

One of true/false, yes/no, 1/0.

--use-puppet-default USE_PUPPET_DEFAULT Do not send this parameter via the ENC.

Puppet will use the value defined

in the Puppet manifest for this parameter

One of true/false, yes/no, 1/0.

values

--validator-type VALIDATOR_TYPE Type of the validator.

Possible value(s): 'regexp', 'list', "

-h, --help print help

hammer settings

Usage:

hammer settings [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

list List all settings set Update a setting

Options:

-h, --help print help

hammer settings list

Usage:

hammer settings list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer settings set

Usage:

hammer settings set [OPTIONS]

Options:

--id ID

--name NAME Setting name

--value VALUE

-h, --help print help

hammer shell

Usage:

hammer shell [OPTIONS]

Options:

-h, --help print help

hammer smart-variable

Usage:

hammer smart-variable [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-override-value Create an override value for a specific smart variable

create Create a smart variable delete Delete a smart variable info Show a smart variable list List all smart variables

remove-override-value Delete an override value for a specific smart variable

update Update a smart variable

Options:

-h, --help print help

hammer smart-variable add-override-value

Usage:

hammer smart-variable add-override-value [OPTIONS]

Options:

--match MATCH Override match

--smart-variable-id SMART_VARIABLE_ID

--use-puppet-default USE_PUPPET_DEFAULT One of true/false, yes/no, 1/0.

--value VALUE Override value

hammer smart-variable create

Usage:

hammer smart-variable create [OPTIONS]

Options:

--avoid-duplicates AVOID_DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value DEFAULT_VALUE Default value of variable
--description DESCRIPTION Description of variable

--hidden-value HIDDEN_VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--merge-default MERGE DEFAULT Include default value when merging all matching

values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash

type)

One of true/false, yes/no, 1/0.

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

values

--validator-type VALIDATOR_TYPE Type of the validator.

Possible value(s): 'regexp', 'list', "

--variable VARIABLE Name of variable

--variable-type VARIABLE_TYPE Type of the variable.

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash',

'yaml', 'json'

-h, --help print help

hammer smart-variable delete

Usage:

hammer smart-variable delete [OPTIONS]

Options:

--id ID

--name NAME Smart variable name

hammer smart-variable info

Usage:

hammer smart-variable info [OPTIONS]

Options:

--id ID

--name NAME Smart variable name

-h, --help print help

hammer smart-variable list

Usage:

hammer smart-variable list [OPTIONS]

Options:

--host HOST NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH filter results

-h, --help print help

hammer smart-variable remove-override-value

Usage:

hammer smart-variable remove-override-value [OPTIONS]

Options:

--id ID

--smart-variable SMART_VARIABLE_NAME Smart variable name

--smart-variable-id SMART_VARIABLE_ID

hammer smart-variable update

Usage:

hammer smart-variable update [OPTIONS]

Options:

--avoid-duplicates AVOID_DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value DEFAULT_VALUE Default value of variable --description DESCRIPTION Description of variable

--hidden-value HIDDEN_VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--id ID

--merge-default MERGE_DEFAULT Include default value when merging all matching

values

One of true/false, yes/no, 1/0.

type)

One of true/false, yes/no, 1/0.

--name NAME Smart variable name

--new-name NEW NAME

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

--puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

values

--validator-type VALIDATOR TYPE Type of the validator.

Possible value(s): 'regexp', 'list', "

--variable VARIABLE Name of variable

--variable-type VARIABLE TYPE Type of the variable.

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash',

'yaml', 'json'

-h, --help print help

hammer subnet

Usage:

hammer subnet [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a subnet
delete Delete a subnet
info Show a subnet
list List of subnets
update Update a subnet

Options:

-h, --help print help

hammer subnet create

Usage:

hammer subnet create [OPTIONS]

Options:

--boot-mode BOOT_MODE Default boot mode for interfaces assigned to this subnet,

valid values are

"Static", "DHCP"

--dhcp-id DHCP_ID DHCP Capsule to use within this subnet
--dns-id DNS_ID DNS Capsule to use within this subnet
--dns-primary DNS_PRIMARY Primary DNS for this subnet

--dns-secondary DNS_SECONDARY Secondary DNS for this subnet --domain-ids DOMAIN_IDS Domains in which this subnet is part

Comma separated list of values.

--domains DOMAIN_NAMES Comma separated list of values.
--from FROM Starting IP Address for IP auto suggestion

--gateway GATEWAY Primary DNS for this subnet

--ipam IPAM IP Address auto suggestion mode for this subnet, valid values are

"DHCP",

"Internal DB", "None"

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--mask MASK Netmask for this subnet

--name NAME Subnet name

--network NETWORK Subnet network

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

--tftp-id TFTP_ID TFTP Capsule to use within this subnet
--to TO Ending IP Address for IP auto suggestion

--vlanid VLANID VLAN ID for this subnet

-h, --help print help

hammer subnet delete

Usage:

hammer subnet delete [OPTIONS]

Options:

--id ID Subnet numeric identifier

--name NAME Subnet name

-h, --help print help

hammer subnet info

Usage:

hammer subnet info [OPTIONS]

Options:

--id ID

--name NAME Subnet name

-h, --help print help

hammer subnet list

Usage:

hammer subnet list [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--location LOCATION_NAME Location name

--location-id LOCATION ID

--order ORDER sort results

- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer subnet update

Usage:

hammer subnet update [OPTIONS]

Options:

--boot-mode BOOT_MODE Default boot mode for interfaces assigned to this subnet, valid values are

"Static", "DHCP"

--dhcp-id DHCP_ID DHCP Capsule to use within this subnet --dns-id DNS_ID DNS Capsule to use within this subnet --dns-primary DNS_PRIMARY Primary DNS for this subnet

--dns-secondary DNS_SECONDARY Secondary DNS for this subnet --domain-ids DOMAIN_IDS Domains in which this subnet is part

Comma separated list of values.

--domains DOMAIN_NAMES Comma separated list of values.
--from FROM Starting IP Address for IP auto suggestion

--gateway GATEWAY Primary DNS for this subnet

--id ID Subnet numeric identifier

--ipam IPAM IP Address auto suggestion mode for this subnet, valid values are

"DHCP",

"Internal DB", "None"

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--mask MASK Netmask for this subnet

--name NAME Subnet name

--network NETWORK Subnet network --new-name NEW_NAME Subnet name

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION NAMES Comma separated list of values.

--tftp-id TFTP_ID TFTP Capsule to use within this subnet
--to TO Ending IP Address for IP auto suggestion

--vlanid VLANID VLAN ID for this subnet

hammer subscription

Usage:

hammer subscription [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

delete-manifest Delete manifest from Red Hat provider

list List organization subscriptions

manifest-history obtain manifest history for subscriptions

refresh-manifest Refresh previously imported manifest for Red Hat provider

upload Upload a subscription manifest

Options:

-h, --help print help

hammer subscription delete-manifest

Usage:

hammer subscription delete-manifest [OPTIONS]

Options:

--async Do not wait for the task

--content-host CONTENT_HOST_NAME Name to search by --content-host-id CONTENT_HOST_ID UUID of the content host

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer subscription list

Usage:

hammer subscription list [OPTIONS]

Options:

- --activation-key-id ACTIVATION_KEY_ID ID of the activation key
- --available-for AVAILABLE_FOR Object to show subscriptions available for, either 'host' or

'activation_key'

--by BY Field to sort the results on

--full-results FULL_RESULTS Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Name to search by

--host-id HOST_ID

--match-host MATCH_HOST Ignore subscriptions that are unavailable to the

specified host

One of true/false, yes/no, 1/0.

--match-installed MATCH_INSTALLED Return subscriptions that match installed products of the specified host

One of true/false, yes/no, 1/0.

--no-overlap NO_OVERLAP Return subscriptions which do not overlap with a currently-attached

subscription

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'name DESC'

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help print help

hammer subscription manifest-history

Usage:

hammer subscription manifest-history [OPTIONS]

Options:

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

hammer subscription refresh-manifest

Usage:

hammer subscription refresh-manifest [OPTIONS]

Options:

--async Do not wait for the task

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer subscription upload

Usage:

hammer subscription upload [OPTIONS]

Options:

--async Do not wait for the task

--file MANIFEST Subscription manifest file

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--repository-url REPOSITORY_URL repository url

-h, --help print help

hammer sync-plan

Usage:

hammer sync-plan [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create a sync plan

delete Destroy a sync plan info Show a sync plan list List sync plans

update Update a sync plan

Options:

-h, --help print help

hammer sync-plan create

Usage:

hammer sync-plan create [OPTIONS]

Options:

--description DESCRIPTION sync plan description

--enabled ENABLED enables or disables synchronization

One of true/false, yes/no, 1/0.

--interval INTERVAL how often synchronization should run

Possible value(s): 'hourly', 'daily', 'weekly'

--name NAME sync plan name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--sync-date SYNC_DATE start date and time of the synchronization defaults to now

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

-h, --help print help

hammer sync-plan delete

Usage:

hammer sync-plan delete [OPTIONS]

Options:

--id ID sync plan numeric identifier

--name NAME Sync plan name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

hammer sync-plan info

Usage:

hammer sync-plan info [OPTIONS]

Options:

--id ID sync plan numeric identifier

--name NAME Sync plan name to search by

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help print help

hammer sync-plan list

Usage:

hammer sync-plan list [OPTIONS]

Options:

--interval INTERVAL filter by interval

Possible value(s): 'hourly', 'daily', 'weekly'

--name NAME filter by name

--organization-id ORGANIZATION ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--sync-date SYNC_DATE filter by sync date

-h, --help print help

hammer sync-plan update

Usage:

hammer sync-plan update [OPTIONS]

Options:

--description DESCRIPTION sync plan description

--enabled ENABLED enables or disables synchronization

One of true/false, yes/no, 1/0.

--id ID sync plan numeric identifier

--interval INTERVAL how often synchronization should run

Possible value(s): 'hourly', 'daily', 'weekly'

--name NAME Sync plan name to search by

--new-name NEW_NAME sync plan name

--organization-id ORGANIZATION_ID organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by --sync-date SYNC_DATE start date and time of the synchronization

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

-h, --help print help

hammer task

Usage:

hammer task [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

list List tasks

progress Show the progress of the task

resume Resume all tasks paused in error state

Options:

-h, --help print help

hammer task list

Usage:

hammer task list [OPTIONS]

Options:

--by BY Field to sort the results on

--order ORDER Sort field and order, e.g. 'name DESC'

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

hammer task progress

Usage:

hammer task progress [OPTIONS]

Options:

--id ID UUID of the task

--name NAME Name to search by

-h, --help print help

hammer task resume

Usage:

hammer task resume [OPTIONS]

Options:

--search SEARCH Resume tasks matching search string

--task-ids TASK_IDS Resume specific tasks by ID

Comma separated list of values.

--tasks TASK_NAMES Comma separated list of values.

-h, --help print help

hammer template

Usage:

hammer template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

clone Clone a provision template
create Create a provisioning template
delete Delete a provisioning template

dump View config template content.
info Show provisioning template details
kinds List available config template kinds.

list List provisioning templates

remove-operatingsystem Disassociate an operating system

update Update a provisioning template

Options:

-h, --help print help

hammer template add-operatingsystem

Usage:

hammer template add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer template build-pxe-default

Usage:

hammer template build-pxe-default [OPTIONS]

Options:

-h, --help print help

hammer template clone

Usage:

hammer template clone [OPTIONS]

Options:

--id ID

--name NAME Name to search by --new-name NEW NAME template name

hammer template create

Usage:

hammer template create [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file TEMPLATE Path to a file that contains the template --location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME template name

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the template

Comma separated list of values.

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.
--type TYPE Template type. Eg. snippet, script, provision

-h, --help print help

hammer template delete

Usage:

hammer template delete [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer template dump

Usage:

hammer template dump [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer template info

Usage:

hammer template info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

-h, --help print help

hammer template kinds

Usage:

hammer template kinds [OPTIONS]

Options:

-h, --help print help

hammer template list

Usage:

hammer template list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--order ORDER sort results

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer template remove-operatingsystem

Usage:

hammer template remove-operating system [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help print help

hammer template update

Usage:

hammer template update [OPTIONS]

Options:

--audit-comment AUDIT COMMENT

--file TEMPLATE Path to a file that contains the template

--id ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION_NAMES Comma separated list of values.

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by --new-name NEW_NAME template name

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate

with the template

Comma separated list of values.

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values.

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--type TYPE Template type. Eg. snippet, script, provision

hammer template-input

Usage:

hammer template-input [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create delete

info

Options:

-h, --help print help

hammer template-input create

Usage:

hammer template-input create [OPTIONS]

Options:

-h, --help print help

hammer template-input delete

Usage:

hammer template-input delete [OPTIONS]

Options:

hammer template-input info

Usage:

hammer template-input info [OPTIONS]

Options:

-h, --help print help

hammer template-input list

Usage:

hammer template-input list [OPTIONS]

Options:

-h, --help print help

hammer user

Usage:

hammer user [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-role Assign a user role create Create a user delete Delete a user info Show a user list List all users

remove-role Remove a user role

update Update a user

Options:

hammer user add-role

Usage:

hammer user add-role [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by --role ROLE NAME User role name

--role-id ROLE_ID

-h, --help print help

hammer user create

Usage:

hammer user create [OPTIONS]

Options:

--admin ADMIN is an admin account

One of true/false, yes/no, 1/0.

- --auth-source-id AUTH_SOURCE_ID
- --default-location-id DEFAULT_LOCATION ID
- --default-organization-id DEFAULT_ORGANIZATION_ID
- --firstname FIRSTNAME
- --lastname LASTNAME
- --locale LOCALE User's preferred locale

Possible value(s): 'ca', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja',

'ko', 'pt_BR', 'ru', 'sv_SE', 'zh_CN', 'zh_TW'

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION NAMES Comma separated list of values.

- --login LOGIN
- --mail MAIL
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES Comma separated list of values.

- --password PASSWORD
- --timezone TIMEZONE User's timezone

Possible value(s): 'UTC', 'International Date Line West', 'Midway

Island', 'American Samoa', 'Hawaii', 'Alaska', 'Pacific Time (US & Canada)', 'Tijuana', 'Mountain

Time (US & Canada)', 'Arizona', 'Chihuahua', 'Mazatlan', 'Central Time (US & Canada)',

'Saskatchewan', 'Guadalajara', 'Mexico City', 'Monterrey', 'Central America', 'Eastern Time (US & Canada)', 'Indiana (East)', 'Bogota', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'La Paz', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Montevideo', 'Georgetown', 'Greenland', 'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Dublin', 'Edinburgh', 'Lisbon', 'London', 'Casablanca', 'Monrovia', 'Belgrade', 'Bratislava', 'Budapest', 'Ljubljana', 'Prague', 'Sarajevo', 'Skopje', 'Warsaw', 'Zagreb', 'Brussels', 'Copenhagen', 'Madrid', 'Paris', 'Amsterdam', 'Berlin', 'Bern', 'Rome', 'Stockholm', 'Vienna', 'West Central Africa', 'Bucharest', 'Cairo', 'Helsinki', 'Kyiv', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Athens', 'Istanbul', 'Minsk', 'Jerusalem', 'Harare', 'Pretoria', 'Moscow', 'St. Petersburg', 'Volgograd', 'Kuwait', 'Riyadh', 'Nairobi', 'Baghdad', 'Tehran', 'Abu Dhabi', 'Muscat', 'Baku', 'Tbilisi', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent', 'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Kathmandu', 'Astana', 'Dhaka', 'Sri Jayawardenepura', 'Almaty', 'Novosibirsk', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Beijing', 'Chongging', 'Hong Kong', 'Urumgi', 'Kuala Lumpur', 'Singapore', 'Taipei', 'Perth', 'Irkutsk', 'Ulaanbaatar', 'Seoul', 'Osaka', 'Sapporo', 'Tokyo', 'Yakutsk', 'Darwin', 'Adelaide', 'Canberra', 'Melbourne', 'Sydney', 'Brisbane', 'Hobart', 'Vladivostok', 'Guam', 'Port Moresby', 'Magadan', 'Solomon Is.', 'New Caledonia', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Auckland', 'Wellington', 'Nuku'alofa', 'Tokelau Is.', 'Chatham Is.', 'Samoa' -h, --help print help

hammer user delete

Usage:

hammer user delete [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by

-h, --help print help

hammer user info

Usage:

hammer user info [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by

hammer user list

Usage:

hammer user list [OPTIONS]

Options:

--auth-source-Idap AUTH_SOURCE_LDAP_NAME Name to search by

--auth-source-Idap-id AUTH_SOURCE_LDAP_ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--order ORDER sort results

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID organization ID

--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--role ROLE_NAME User role name

--role-id ROLE ID

--search SEARCH filter results

--user-group-id USER_GROUP_ID -h, --help print help

hammer user remove-role

Usage:

hammer user remove-role [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by --role ROLE NAME User role name

--role-id ROLE_ID

-h, --help print help

hammer user update

Usage:

hammer user update [OPTIONS]

```
Options:
```

--admin ADMIN

is an admin account

One of true/false, yes/no, 1/0.

- --auth-source-id AUTH_SOURCE_ID
- --default-location-id DEFAULT LOCATION ID
- --default-organization-id DEFAULT ORGANIZATION ID
- --firstname FIRSTNAME
- --id ID
- --lastname LASTNAME
- --locale LOCALE

User's preferred locale

Possible value(s): 'ca', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja',

'ko', 'pt BR', 'ru', 'sv SE', 'zh CN', 'zh TW'

--location-ids LOCATION_IDS

REPLACE locations with given ids

Comma separated list of values.

--locations LOCATION NAMES

Comma separated list of values.

--login LOGIN

User's login to search by

- --mail MAIL
- --new-login NEW_LOGIN
- --organization-ids ORGANIZATION IDS

REPLACE organizations with given ids.

Comma separated list of values.

--organizations ORGANIZATION_NAMES

Comma separated list of values.

- --password PASSWORD
- --timezone TIMEZONE

User's timezone

Possible value(s): 'UTC', 'International Date Line West', 'Midway Island', 'American Samoa', 'Hawaii', 'Alaska', 'Pacific Time (US & Canada)', 'Tijuana', 'Mountain Time (US & Canada)', 'Arizona', 'Chihuahua', 'Mazatlan', 'Central Time (US & Canada)', 'Saskatchewan', 'Guadalajara', 'Mexico City', 'Monterrey', 'Central America', 'Eastern Time (US & Canada)', 'Indiana (East)', 'Bogota', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'La Paz', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Montevideo', 'Georgetown', 'Greenland', 'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Dublin', 'Edinburgh', 'Lisbon', 'London', 'Casablanca', 'Monrovia', 'Belgrade', 'Bratislava', 'Budapest', 'Ljubljana', 'Prague', 'Sarajevo', 'Skopje', 'Warsaw', 'Zagreb', 'Brussels', 'Copenhagen', 'Madrid', 'Paris', 'Amsterdam', 'Berlin', 'Bern', 'Rome', 'Stockholm', 'Vienna', 'West Central Africa', 'Bucharest', 'Cairo', 'Helsinki', 'Kyiv', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Athens', 'Istanbul', 'Minsk', 'Jerusalem', 'Harare', 'Pretoria', 'Moscow', 'St. Petersburg', 'Volgograd', 'Kuwait', 'Riyadh', 'Nairobi', 'Baghdad', 'Tehran', 'Abu Dhabi', 'Muscat', 'Baku', 'Tbilisi', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent', 'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Kathmandu', 'Astana', 'Dhaka', 'Sri Jayawardenepura', 'Almaty', 'Novosibirsk', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Beijing', 'Chongqing', 'Hong Kong', 'Urumqi', 'Kuala Lumpur', 'Singapore', 'Taipei', 'Perth', 'Irkutsk', 'Ulaanbaatar', 'Seoul', 'Osaka', 'Sapporo', 'Tokyo', 'Yakutsk', 'Darwin', 'Adelaide', 'Canberra', 'Melbourne', 'Sydney', 'Brisbane', 'Hobart', 'Vladivostok', 'Guam', 'Port Moresby', 'Magadan', 'Solomon Is.', 'New Caledonia', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Auckland', 'Wellington', 'Nuku'alofa', 'Tokelau Is.', 'Chatham Is.', 'Samoa'

hammer user-group

Usage:

hammer user-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

add-role Assign a user role add-user Associate an user

add-user-group Associate an user group

create Create a user group delete Delete a user group

external View and manage user group's external user groups

Disassociate an user group

info Show a user group list List all user groups remove-role Remove a user role

remove-user Disassociate an user

update Update a user group

Options:

remove-user-group

-h, --help print help

hammer user-group add-role

Usage:

hammer user-group add-role [OPTIONS]

Options:

--id ID

--name NAME Name to search by --role ROLE_NAME User role name

--role-id ROLE_ID

hammer user-group add-user

Usage:

hammer user-group add-user [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--user-id USER_ID

-h, --help print help

hammer user-group add-user-group

Usage:

hammer user-group add-user-group [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--user-group USER_GROUP_NAME Name to search by

--user-group-id USER_GROUP_ID

-h, --help print help

hammer user-group create

Usage:

hammer user-group create [OPTIONS]

Options:

--name NAME

--role-ids ROLE_IDS Comma separated list of values.
--roles ROLE NAMES Comma separated list of values.

--user-group-ids USER_GROUP_IDS Comma separated list of values.

--user-groups USER_GROUP_NAMES Comma separated list of values.

--user-ids USER_IDS Comma separated list of values.
--users USER_LOGINS Comma separated list of values.

hammer user-group delete

Usage:

hammer user-group delete [OPTIONS]

Options: --id ID

--name NAME Name to search by

-h, --help print help

hammer user-group external

Usage:

hammer user-group external [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND subcommand [ARG] ... subcommand arguments

Subcommands:

create Create an external user group linked to a user group

delete Delete an external user group

info Show an external user group for user group list List all external user groups for user group

refresh Refresh external user group update Update external user group

Options:

-h, --help print help

hammer user-group info

Usage:

hammer user-group info [OPTIONS]

Options:

--id ID

--name NAME Name to search by

hammer user-group list

Usage:

hammer user-group list [OPTIONS]

Options:

--order ORDER sort results--page PAGE paginate results

--per-page PER_PAGE number of entries per request

--search SEARCH filter results

-h, --help print help

hammer user-group remove-role

Usage:

hammer user-group remove-role [OPTIONS]

Options:

--id ID

--name NAME Name to search by --role ROLE_NAME User role name

--role-id ROLE ID

-h, --help print help

hammer user-group remove-user

Usage:

hammer user-group remove-user [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--user-id USER_ID

hammer user-group remove-user-group

Usage:

hammer user-group remove-user-group [OPTIONS]

Options:

- --id ID
- --name NAME Name to search by
- --user-group USER_GROUP_NAME Name to search by
- --user-group-id USER_GROUP_ID
- -h, --help print help

hammer user-group update

Usage:

hammer user-group update [OPTIONS]

Options:

- --id ID
- --name NAME Name to search by
- --new-name NEW_NAME
- --role-ids ROLE_IDS Comma separated list of values.
 --roles ROLE_NAMES Comma separated list of values.
- $\hbox{--user-group-ids USER_GROUP_IDS Comma separated list of values}.$
- --user-groups USER_GROUP_NAMES Comma separated list of values.
- --user-ids USER_IDS Comma separated list of values.
 --users USER_LOGINS Comma separated list of values.
- -h, --help print help