ELECTRIC CURRENT AND RESISTANCE

Chapter 25



Alessandro Bombelli

Operations & Environment

Faculty of Aerospace Engineering



Structure of the lecture

- 1. Electric battery and Electric Current
- 2. Ohm's Law: Resistance and Resistors
- 3. Resistivity
- 4. Electric Power
- 5. Alternating Current
- 6. Microscopic view of Electric Current



After this lecture you should be able to:

Understand the general characteristics of electric current



After this lecture you should be able to:

- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance



After this lecture you should be able to:


- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance
- Determine the resistance of a wire or other conducting mean given its geometric and material properties



After this lecture you should be able to:


- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance and determine the resistance of a wire or other conducting mean given its geometric and material properties
- Understand the basics of alternate current
- Understand the basics of electric current at the microscopic level





Alessandro Volta discovered that electricity could be created by connecting two moist (i.e., both metals were inserted into a conductive solution called electrolyte) dissimilar metals with a wire.






Alessandro Volta discovered that electricity could be created by connecting two moist (i.e., both metals were inserted into a conductive solution called electrolyte) dissimilar metals with a wire.

He also found out that some combinations of metals worked much better than others.






Alessandro Volta discovered that electricity could be created by connecting two moist (i.e., both metals were inserted into a conductive solution called electrolyte) dissimilar metals with a wire.

He also found out that some combinations of metals worked much better than others.


A battery produces electricity by transforming chemical energy into electrical energy. The simplest version of a battery consists of two electrodes (two metal plates or rods) immersed into a solution, namely the aforementioned electrolyte.





In the example, the acid tends to dissolve the zinc electrode. Each zinc atom leaves two electrons behind and enters the acid as a positive ion.






In the example, the acid tends to dissolve the zinc electrode. Each zinc atom leaves two electrons behind and enters the acid as a positive ion.

The electrolyte becomes positively charged and pulls electrons from the carbon electrode, which charges positively. The carbon electrode is the anode and the zinc one the cathode of the battery.





In the example, the acid tends to dissolve the zinc electrode. Each zinc atom leaves two electrons behind and enters the acid as a positive ion.


The electrolyte becomes positively charged and pulls electrons from the carbon electrode, which charges positively. The carbon electrode is the anode and the zinc one the cathode of the battery.

Once one of the two electrodes has run out of electrons, the battery is dead. The advantage of such a battery, when the electrodes are connected to an electricity-demanding device, is that the provided voltage is basically constant.






The purpose of a battery is to produce a potential difference so charges can move. When a continuous conducting path connects the terminals of a battery, then we have an electric circuit.










The purpose of a battery is to produce a potential difference so charges can move. When a continuous conducting path connects the terminals of a battery, then we have an electric circuit.

Any flow of charge is called electric current. The electric current is the net amount of charge passing through a wire's full cross section per unit time, namely

$$I = \frac{dQ}{dt}$$








The purpose of a battery is to produce a potential difference so charges can move. When a continuous conducting path connects the terminals of a battery, then we have an electric circuit.

Any flow of charge is called electric current. The electric current is the net amount of charge passing through a wire's full cross section per unit time, namely

$$I = \frac{dQ}{dt}$$


Electric current is measured in Amperes A, being 1 Ampere $1\frac{C}{s}$.





In many real circuits, wires are connected to a common conductor that provides continuity, as there should be no break in the circuit.






In many real circuits, wires are connected to a common conductor that provides continuity, as there should be no break in the circuit.

This common conductor is generally called ground, and is literally that for houses, whereas it is generally the car frame for a car.







In many real circuits, wires are connected to a common conductor that provides continuity, as there should be no break in the circuit.


This common conductor is generally called ground, and is literally that for houses, whereas it is generally the car frame for a car.

In a circuit, electrons move from the negative to the positive terminal of a battery (electron flow). When electricity was discovered, it was thought that positive charges flowed in a wire. We still keep this convention, assuming that electric current flows from the positive to the negative terminal












Georg Simon Ohm established experimentally that the current in a metal wire I is proportional to the potential difference $V: I \propto V$.











Georg Simon Ohm established experimentally that the current in a metal wire I is proportional to the potential difference $V: I \propto V$.


More specifically, an increase in voltage implied an increase in current. Such an increase was found to be linear for metal conductor so that voltage and current are proportional via a constant, the resistance *R* as follows

$$V = IR$$










Georg Simon Ohm established experimentally that the current in a metal wire I is proportional to the potential difference $V: I \propto V$.


More specifically, an increase in voltage implied an increase in current. Such an increase was found to be linear for metal conductor so that voltage and current are proportional via a constant, the resistance *R* as follows


$$V = IR$$

Note that, even for metals, the resistance is not constant if the material is subject to severe changes in temperature.









Georg Simon Ohm established experimentally that the current in a metal wire I is proportional to the potential difference $V: I \propto V$.

More specifically, an increase in voltage implied an increase in current. Such an increase was found to be linear for metal conductor so that voltage and current are proportional via a constant, the resistance *R* as follows


$$V = IR$$

Note that, even for metals, the resistance is not constant if the material is subject to severe changes in temperature. Materials for which Ohm's law applies (resistance is a constant) are called ohmic materials. The unit is the Ohm $\Omega \to 1$ $\Omega = \frac{1V}{1.4}$





In many circuits, resistors are used to control the amount of current given a certain voltage.









In many circuits, resistors are used to control the amount of current given a certain voltage.

Resistors have values of resistance ranging from less than 1 Ohm to millions of Ohms. Color codes are used on resistors to univocally define their resistance value.









In many circuits, resistors are used to control the amount of current given a certain voltage.

Resistors have values of resistance ranging from less than 1 Ohm to millions of Ohms. Color codes are used on resistors to univocally define their resistance value.

Resistances always dissipate energy. Hence, a drop in potential occurs between the point before and after the resistance itself.



It is found experimentally that the resistance R of a wire is directly proportional to its length l and inversely proportional to its cross-sectional area A. Hence

$$R = \frac{\rho l}{A}$$



It is found experimentally that the resistance R of a wire is directly proportional to its length l and inversely proportional to its cross-sectional area A. Hence

$$R = \frac{\rho l}{A}$$

where ρ is called resistivity. Its inverse is σ and is called conductivity (the smaller the former, the more conductive the material)



It is found experimentally that the resistance R of a wire is directly proportional to its length l and inversely proportional to its cross-sectional area A. Hence

$$R = \frac{\rho l}{A}$$

where ρ is called resistivity. Its inverse is σ and is called conductivity (the smaller the former, the more conductive the material)

For good conductors (e.g., copper or gold), the resistivity is in the order of $1 \times 10^{-8} \Omega \cdot m$, whereas for insulators (e.g., glass) it can range between 1×10^{9} and $1 \times 10^{15} \Omega \cdot m$.



It is found experimentally that the resistance R of a wire is directly proportional to its length l and inversely proportional to its cross-sectional area A. Hence

$$R = \frac{\rho l}{A}$$

where ρ is called resistivity. Its inverse is σ and is called conductivity (the smaller the former, the more conductive the material)

For good conductors (e.g., copper or gold), the resistivity is in the order of $1 \times 10^{-8} \Omega \cdot m$, whereas for insulators (e.g., glass) it can range between 1×10^{9} and $1 \times 10^{15} \Omega \cdot m$.

The resistivity of a material depends on its temperature:

$$\rho_T = \rho_0 [1 + \alpha (T - T_0)]$$

where α is the temperature coefficient of resistivity and T_0 is a reference temperature.



It is found experimentally that the resistance R of a wire is directly proportional to its length l and inversely proportional to its cross-sectional area A. Hence

$$R = \frac{\rho l}{A}$$

where ρ is called resistivity. Its inverse is σ and is called conductivity (the smaller the former, the more conductive the material)

For good conductors (e.g., copper or gold), the resistivity is in the order of $1 \times 10^{-8} \Omega \cdot m$, whereas for insulators (e.g., glass) it can range between 1×10^{9} and $1 \times 10^{15} \Omega \cdot m$.

The resistivity of a material depends on its temperature:

$$\rho_T = \rho_0 [1 + \alpha (T - T_0)]$$

where α is the temperature coefficient of resistivity and T_0 is a reference temperature.

 α is generally positive, but some materials (semiconductors) have it negative.



Suppose a wire of resistance R is stretched until it is twice the original length. What would happen to the resistance? (hint: conservation of volume)



Suppose a wire of resistance R is stretched until it is twice the original length. What would happen to the resistance? (hint: conservation of volume)

$$V_1 = l_1 A_1, V_2 = 2 l_1 A_2 = V_1 \rightarrow A_2 = \frac{l_1 A_1}{2 l_1} = \frac{A_1}{2}$$
 $R_{new} = \rho \frac{l_2}{A_2} = \rho \frac{2 l_1}{\frac{A_1}{2}} = 4 \rho \frac{l_1}{A_1} = 4 R$



The variation in electrical resistance with temperature can be used to make precise temperature measurements. Platinum is commonly used since it is relatively free from corrosive effects and has a high melting point. Suppose at $20.0^{\circ}C$ the resistance of a platinum resistance thermometer is 164.2Ω . When placed in a particular solution, the resistance is 187.4Ω . What is the temperature of this solution?



The variation in electrical resistance with temperature can be used to make precise temperature measurements. Platinum is commonly used since it is relatively free from corrosive effects and has a high melting point. Suppose at $20.0^{\circ}C$ the resistance of a platinum resistance thermometer is 164.2Ω . When placed in a particular solution, the resistance is 187.4Ω . What is the temperature of this solution?

$$R = R_0[1 + \alpha(T - T_0)] \rightarrow T = T_0 + \frac{\left(\frac{R}{R_0} - 1\right)}{\alpha} = 56^{\circ}C$$

where the value for α has been retrieved from a table



25.5 – Electric Power





Power, as in kinematics, is the energy transformed by a device per unit time. Here we are still dealing with a (difference of) potential and charges being moved, hence we can use dU = Vdq:



25.5 – Electric Power





Power, as in kinematics, is the energy transformed by a device per unit time. Here we are still dealing with a (difference of) potential and charges being moved, hence we can use dU = Vdq:

$$P = \frac{dU}{dt} = V \frac{dq}{dt} \to P = VI$$







Reminder:

$$V = IR$$

for ohmic materials


Power, as in kinematics, is the energy transformed by a device per unit time. Here we are still dealing with a (difference of) potential and charges being moved, hence we can use dU = Vdq:

$$P = \frac{dU}{dt} = V \frac{dq}{dt} \to P = VI$$

For ohmic devices, we can express power (in Watts *W*) in the equivalent forms (using Ohm's law):

$$P = VI = I^2R = \frac{V^2}{R}$$







Reminder:

$$V = IR$$

for ohmic materials

Power, as in kinematics, is the energy transformed by a device per unit time. Here we are still dealing with a (difference of) potential and charges being moved, hence we can use dU = Vdq:

$$P = \frac{dU}{dt} = V \frac{dq}{dt} \to P = VI$$


For ohmic devices, we can express power (in Watts *W*) in the equivalent forms (using Ohm's law):

$$P = VI = I^2R = \frac{V^2}{R}$$

When using electricity, what matters is the energy we use, hence the power times the time of utilization. In general, we use Joules J for energy, but in this context kilowatt-hours kWh are used:


$$1 \, kWh = (1000 \, W) \times (3600 \, s) = 3.6 \times 10^6 \, J$$





Calculate the resistance and the peak current in a 1,000 W hair dryer connected to a 120 V line. What happens if it is connected to a 240 V line in Britain?






Calculate the resistance and the peak current in a 1,000 W hair dryer connected to a 120 V line. What happens if it is connected to a 240 V line in Britain?

The power is the average power \bar{P} and the voltage is rms, hence

$$I_{rms} = \frac{\overline{P}}{V_{rms}} = 8.33 A$$
 $R = \frac{V_{rms}}{I_{rms}} = 14.4 \Omega$





Calculate the resistance and the peak current in a 1,000 W hair dryer connected to a 120 V line. What happens if it is connected to a 240 V line in Britain?


The power is the average power \bar{P} and the voltage is rms, hence


$$I_{rms} = \frac{\overline{P}}{V_{rms}} = 8.33 A$$
 $R = \frac{V_{rms}}{I_{rms}} = 14.4 \Omega$

Assuming resistance does not change, we have

$$\overline{P} = \frac{V_{rms}^2}{R} = 4,000 W$$









While a battery provides a current that is constant and moves steadily in one direction (left, top figure), power plants generate alternate current (left, bottom figure) that changes direction many times per second and is generally sinusoidal.









While a battery provides a current that is constant and moves steadily in one direction (left, top figure), power plants generate alternate current (left, bottom figure) that changes direction many times per second and is generally sinusoidal.

While the details of why this is the case (spoiler: it has to do with the functioning behind electric generators) will be revealed later in the course, we discuss some basics here given the relevance of the topic.








While a battery provides a current that is constant and moves steadily in one direction (left, top figure), power plants generate alternate current (left, bottom figure) that changes direction many times per second and is generally sinusoidal.


While the details of why this is the case (spoiler: it has to do with the functioning behind electric generators) will be revealed later in the course, we discuss some basics here given the relevance of the topic.

The voltage provided by an electric generator is sinusoidal in nature and can be expressed as

$$V = V_0 \sin 2\pi f t = V_0 \sin \omega t$$







While a battery provides a current that is constant and moves steadily in one direction (left, top figure), power plants generate alternate current (left, bottom figure) that changes direction many times per second and is generally sinusoidal.


While the details of why this is the case (spoiler: it has to do with the functioning behind electric generators) will be revealed later in the course, we discuss some basics here given the relevance of the topic.


The voltage provided by an electric generator is sinusoidal in nature and can be expressed as

$$V = V_0 \sin 2\pi f t = V_0 \sin \omega t$$

where ω is the angular frequency of the voltage signal and V_0 is referred to as the peak voltage.









Using Ohm's law, we can express the current as well as a sinusoidal wave

$$I = \frac{V}{R} = \frac{V_0}{R} \sin \omega t = I_0 \sin \omega t$$

where I_0 is the peak current.








Using Ohm's law, we can express the current as well as a sinusoidal wave


$$I = \frac{V}{R} = \frac{V_0}{R} \sin \omega t = I_0 \sin \omega t$$

where I_0 is the peak current.

While the average current (over a period) is zero, this does not mean no power is needed to generate such a sinusoidal wave.







Using Ohm's law, we can express the current as well as a sinusoidal wave

$$I = \frac{V}{R} = \frac{V_0}{R} \sin \omega t = I_0 \sin \omega t$$


where I_0 is the peak current.


While the average current (over a period) is zero, this does not mean no power is needed to generate such a sinusoidal wave. In fact

$$P = I^2 R = I_0^2 R \sin^2 \omega t$$

is always non-negative. The integral over one period of $\sin^2 \omega t$ is $\int_0^T \sin^2 \omega t \, dt = \frac{1}{2}$, hence the average power transformed (by a resistance R) is







Using Ohm's law, we can express the current as well as a sinusoidal wave

$$I = \frac{V}{R} = \frac{V_0}{R} \sin \omega t = I_0 \sin \omega t$$

where I_0 is the peak current.


While the average current (over a period) is zero, this does not mean no power is needed to generate such a sinusoidal wave. In fact

$$P = I^2 R = I_0^2 R \sin^2 \omega t$$

is always non-negative. The integral over one period of $\sin^2 \omega t$ is $\int_0^T \sin^2 \omega t \, dt = \frac{1}{2}T$, hence the average power transformed (by a resistance R) is


$$\overline{P} = I_0^2 R \frac{1}{T} \int_0^T \sin^2 \omega t \, dt = \frac{1}{2} I_0^2 R = \frac{1}{2} \frac{V_0^2}{R}$$





Given that we have been using $P = \frac{V^2}{R} = I^2 R$ before, we want to use a similar expression now.






Given that we have been using $P = \frac{V^2}{R} = I^2 R$ before, we want to use a similar expression now. Hence, we can define $\overline{I^2} = \frac{1}{2}I_0^2$ and $\overline{V^2} = \frac{1}{2}V_0^2$ so that the square root of those values is the rms (root-mean-square) value of current of voltage

$$I_{rms} = \sqrt{\overline{I^2}} = \frac{I_0}{\sqrt{2}}, V_{rms} = \sqrt{\overline{V^2}} = \frac{V_0}{\sqrt{2}}$$






Given that we have been using $P=\frac{V^2}{R}=I^2R$ before, we want to use a similar expression now. Hence, we can define $\overline{I^2}=\frac{1}{2}I_0^2$ and $\overline{V^2}=\frac{1}{2}V_0^2$ so that the square root of those values is the rms (root-mean-square) value of current of voltage

$$I_{rms} = \sqrt{\overline{I^2}} = \frac{I_0}{\sqrt{2}}, V_{rms} = \sqrt{\overline{V^2}} = \frac{V_0}{\sqrt{2}}$$

These rms values are called effective values, and they can be substituted in the power formulas to get the average power


$$\overline{P} = I_{rms}V_{rms} = \frac{1}{2}I_0^2R = I_{rms}^2R = \frac{1}{2}\frac{V_0^2}{R} = \frac{V_{rms}^2}{R}$$





Thus, a direct current whose values of I and V are equal to the rms values of I and V for an alternate current, will produce the same power.






Thus, a direct current whose values of I and V are equal to the rms values of I and V for an alternate current, will produce the same power.

It is generally the rms value of current and voltage that is specified for homes and most applications.






Thus, a direct current whose values of I and V are equal to the rms values of I and V for an alternate current, will produce the same power.

It is generally the rms value of current and voltage that is specified for homes and most applications. For example, in the United States and Canada standard lines are 120 V, which is a V_{rms} . The peak voltage is $V_0 = \sqrt{2}V_{rms} = 170 V$.

In much of the world, the rms voltage is 240 V.

The frequency of the voltage signal is either 50 or $60 \ Hz$.





Thus, a direct current whose values of I and V are equal to the rms values of I and V for an alternate current, will produce the same power.


It is generally the rms value of current and voltage that is specified for homes and most applications. For example, in the United States and Canada standard lines are 120 V, which is a V_{rms} . The peak voltage is $V_0 = \sqrt{2}V_{rms} = 170 V$.

In much of the world, the rms voltage is 240 V.

The frequency of the voltage signal is either 50 or $60 \ Hz$.


The specified power required by a device is \overline{P} , with the actual power required ranging between 0 and $\overline{2P}$ (see figure to the left).





So far, we modeled current using a macroscopic approach. We now dive a bit deeper into the atomic (microscopic) view.






So far, we modeled current using a macroscopic approach. We now dive a bit deeper into the atomic (microscopic) view.

When a voltage is applied at the extremes of a wire of uniform cross-section, the direction of the electric field \vec{E} is parallel to the walls of the wire. Note that this is consistent with what seen in previous chapters about conductors and electric fields, as we now deal with moving charges and not with the electrostatic case.






So far, we modeled current using a macroscopic approach. We now dive a bit deeper into the atomic (microscopic) view.

When a voltage is applied at the extremes of a wire of uniform cross-section, the direction of the electric field \vec{E} is parallel to the walls of the wire. Note that this is consistent with what seen in previous chapters about conductors and electric fields, as we now deal with moving charges and not with the electrostatic case.

We now define the current density \vec{j} as the electric current per unit cross-sectional area at any point in space.






If the current density in a wire of cross-section A is uniform, then $j = \frac{I}{A} \rightarrow I = jA$. If not, we need to use an integral notation

$$I = \int \vec{j} \vec{d}A$$






If the current density in a wire of cross-section A is uniform, then $j = \frac{I}{A} \rightarrow I = jA$. If not, we need to use an integral notation

$$I = \int \vec{j} \vec{d}A$$

The direction of \vec{j} is chosen to represent the direction of net flow of positive charge. In a metal, negatively charged electrons move in the direction of $-\vec{j}$ or $-\vec{E}$.






If the current density in a wire of cross-section A is uniform, then $j = \frac{I}{A} \rightarrow I = jA$. If not, we need to use an integral notation


$$I = \int \vec{j} \vec{d} A$$

The direction of \vec{j} is chosen to represent the direction of net flow of positive charge. In a metal, negatively charged electrons move in the direction of $-\vec{j}$ or $-\vec{E}$.






Free electrons initially move randomly at high speeds in a wire bouncing off the metal atoms of the wire, then they will eventually reach an almost steady average speed, known as drift speed v_d .



We can express the drift speed (which is much smaller than the thermal speed!) as follows. In a time Δt , electrons travel a distance $l = v_d \Delta t$ and hence occupy a volume $V = A v_d \Delta t$.






We can express the drift speed (which is much smaller than the thermal speed!) as follows.

In a time Δt , electrons travel a distance $l=v_d\Delta t$ and hence occupy a volume $V=Av_d\Delta t$. Assuming n electrons, each of charge -e, per unit volume, then the overall number of electrons is $N=nV=nAv_d\Delta t$ and the total charge passing through the area in the given time is

$$\Delta Q = (nV) \times (-e) = -nAv_d \Delta te$$





We can express the drift speed (which is much smaller than the thermal speed!) as follows.


In a time Δt , electrons travel a distance $l = v_d \Delta t$ and hence occupy a volume $V = A v_d \Delta t$. Assuming n electrons, each of charge -e, per unit volume, then the overall number of electrons is $N = nV = nAv_d \Delta t$ and the total charge passing through the area in the given time is

$$\Delta Q = (nV) \times (-e) = -nAv_d \Delta te$$

The current in the wire is

$$I = \frac{\Delta Q}{\Delta t} = -neAv_d$$





We can express the drift speed (which is much smaller than the thermal speed!) as follows.

In a time Δt , electrons travel a distance $l = v_d \Delta t$ and hence occupy a volume $V = A v_d \Delta t$. Assuming n electrons, each of charge -e, per unit volume, then the overall number of electrons is $N = nV = nAv_d \Delta t$ and the total charge passing through the area in the given time is

$$\Delta Q = (nV) \times (-e) = -nAv_d \Delta te$$


The current in the wire is

$$I = \frac{\Delta Q}{\Delta t} = -neAv_d$$

while the current density is


$$j = \frac{I}{A} = -nev_d$$






Drift speed is generally very small, $\sim 0.05 \, \frac{mm}{s}$, so that an electron takes $5 \, \frac{1}{2} \, h$ to travel $1 \, m$.





Drift speed is generally very small, $\sim 0.05 \, \frac{mm}{s}$, so that an electron takes $5\frac{1}{2} \, h$ to travel $1 \, m$. This is not how fast "electricity travels": a wire is full of electrons, so when we turn on the light, the electrons at the end of the wire immediately flow inside the lamp or light-providing device.






Drift speed is generally very small, $\sim 0.05 \, \frac{mm}{s}$, so that an electron takes $5 \, \frac{1}{2} \, h$ to travel $1 \, m$. This is not how fast "electricity travels": a wire is full of electrons, so when we turn on the light, the electrons at the end of the wire immediately flow inside the lamp or light-providing device.

We wrap up this section by determining the electric field inside a wire of length l using a mix of the macroscopic and microscopic properties unfolded so far.

The resistance of such a wire is



$$R = \rho \frac{l}{A}$$




while the current is

and the voltage

$$I = jA$$

$$V = El$$





while the current is

$$I = jA$$


and the voltage

$$V = El$$

where we assume a constant electric field across the wire and a potential *V* across it.

$$V = IR \rightarrow El = \frac{jA\rho l}{A} = j\rho l$$
$$j = \frac{1}{\rho}E = \sigma E$$





while the current is

$$I = jA$$

and the voltage

$$V = El$$

where we assume a constant electric field across the wire and a potential *V* across it.

$$V = IR \rightarrow El = \frac{jA\rho l}{A} = j\rho l$$
$$j = \frac{1}{\rho}E = \sigma E$$

For metal conductors, ρ and σ do not depend on V (and hence on E), hence the current density is proportional (vectorially) to the electric field:

$$\vec{J} = \sigma \vec{E} = \frac{1}{\rho} \vec{E}$$





$$j = \frac{I}{A} = 5.0 \frac{A}{\pi (0.0016 m)^2} = 6.2 \times 10^5 \frac{A}{m^2}$$



A copper wire 3.2 mm in diameter carries a 5.0 A current. Determine (a) the current density in the wire, and (b) the drift velocity of the free electrons. (c) Estimate the rms speed of electrons assuming they behave like an ideal gas at 20°C. Assume that one electron per Cu atom is free to move (the others remain bound to the atom).

$$j = \frac{I}{A} = 5.0 \frac{A}{\pi (0.0016 m)^2} = 6.2 \times 10^5 \frac{A}{m^2}$$

For the drift velocity, we first need to determine the number of free electrons per unit volume

$$n = \frac{6.02 \times 10^{23} \frac{electrons}{mol}}{\frac{63.5 \times 10^{-3} \frac{kg}{mol}}{8.9 \times 10^{3} \frac{kg}{m^{3}}}} = 8.4 \times 10^{28} \frac{electrons}{m^{3}}$$



$$v_d = \frac{j}{ne} = 4.6 \times 10^{-5} \frac{m}{s} \simeq 0.05 \frac{mm}{s}$$



$$v_d = \frac{j}{ne} = 4.6 \times 10^{-5} \frac{m}{s} \simeq 0.05 \frac{mm}{s}$$

$$v_{rms} = \sqrt{\frac{3kT}{m}} = \sqrt{\frac{3(1.38 \times 10^{-23} \frac{J}{K})(293 K)}{9.11 \times 10^{-31} kg}} = 1.2 \times 10^{5} \frac{m}{s} \rightarrow v_{rms} \gg v_{d}$$



Exercise: car with lights on

A person accidentally leaves a car with the lights on. If each of the two headlights uses 40 W and each of the two tail-lights 6 W, for a total of 92 W, how long will a fresh 12 V battery last if it is rated at 85 Ah? Assume the full 12 V appears across each bulb.



Exercise: car with lights on

A person accidentally leaves a car with the lights on. If each of the two headlights uses 40 W and each of the two tail-lights 6 W, for a total of 92 W, how long will a fresh 12 V battery last if it is rated at 85 Ah? Assume the full 12 V appears across each bulb.


The full energy supplied by the battery is consumed by the lights:

$$QV = P\Delta t$$

$$\Delta t = \frac{QV}{P} = \frac{(85 Ah) \left(3,600 \frac{s}{h}\right) (12 V)}{92 W} = 39,913 s \approx 11 h$$




Exercise: household current consumption



Determine the total current needed by the appliances showed in the figure.



Exercise: household current consumption




Determine the total current needed by the appliances showed in the figure.

Each appliance requires a current $I_{rms} = \frac{P}{V_{rms}}$, where all power/voltage values in the figure are average/rms. In addition, each device sees the same voltage. Hence:

$$I = \frac{(100 + 1,800 + 175 + 1,500)W}{120 V} = 29.8 A$$



Exercise: household current consumption



Determine the total current needed by the appliances showed in the figure.

Each appliance requires a current $I_{rms} = \frac{P}{V_{rms}}$, where all power/voltage values in the figure are average/rms. In addition, each device sees the same voltage. Hence:

$$I = \frac{(100 + 1,800 + 175 + 1,500)W}{120 V} = 29.8 A$$

The fuse in the household should be designed to withstand currents greater than 29.8 *A*. If not, the fuse should blow to open the circuit and prevent excessive heating that might cause fires



An air conditioner draws 14 A at 200 V ac. The connecting cord is copper wire with a diameter of $1.628 \ mm$.

- How much power does the air conditioner draw?
- If the total length of wire is 15 m, how much power is dissipated in the wiring?
- If a no. 12 wire with a diameter of $2.053 \ mm$, was used instead, how much power would be dissipated in the wiring?
- Assuming that the air conditioner is run 12 h per day, how much money per month (30 days) would be saved by using no. 12 wire?

Assume that the cost of electricity is $12 \frac{cents}{kWh}$.



An air conditioner draws 14 A at 200 V ac. The connecting cord is copper wire with a diameter of $1.628 \ mm$.

The power drawn is $P = IV \simeq 3,100 W$ (we dropped all the additional symbols/subscripts for simplicity).



An air conditioner draws 14 A at 200 V ac. The connecting cord is copper wire with a diameter of $1.628 \ mm$.

The power drawn is $P = IV \simeq 3,100 W$ (we dropped all the additional symbols/subscripts for simplicity).

The power dissipated by the wire is $P = I^2 R = I^2 \rho \frac{l}{A} = I^2 \rho \frac{4l}{\pi d^2} \simeq 24 W$



An air conditioner draws 14 A at 200 V ac. The connecting cord is copper wire with a diameter of $1.628 \ mm$.

The power drawn is $P = IV \simeq 3,100 W$ (we dropped all the additional symbols/subscripts for simplicity).

The power dissipated by the wire is $P = I^2 R = I^2 \rho \frac{l}{A} = I^2 \rho \frac{4l}{\pi d^2} \simeq 24 W$ With the different wire, the formula is the same as above, with the only change being in the diameter $\rightarrow P \simeq 15 W$



An air conditioner draws 14 A at 200 V ac. The connecting cord is copper wire with a diameter of $1.628 \ mm$.

The power drawn is $P = IV \simeq 3,100 W$ (we dropped all the additional symbols/subscripts for simplicity).

The power dissipated by the wire is $P = I^2 R = I^2 \rho \frac{l}{A} = I^2 \rho \frac{4l}{\pi d^2} \simeq 24 W$ With the different wire, the formula is the same as above, with the only change being in the diameter $\rightarrow P \simeq 15 W$

The savings *S* are due to the smaller dissipation of power within the wire:


$$S = (24 - 15 W)(30 days) \left(12 \frac{h}{days}\right) \left(0.00012 \frac{\$}{W}\right) = 0.038\$$$



Wrap-up: revisiting Learning objectives

After this lecture you should be able to:

- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance and determine the resistance of a wire or other conducting mean given its geometric and material properties
- Understand the basics of alternate current
- Understand the basics of electric current at the microscopic level



Wrap-up: revisiting Learning objectives

After this lecture you should be able to:

- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance and determine the resistance of a wire or other conducting mean given its geometric and material properties
- Understand the basics of alternate current
- Understand the basics of electric current at the microscopic level

$$V = IR$$

$$R = \rho \frac{l}{A},$$

$$\rho = \rho_0 [1 + \alpha (T - T_0)]$$

$$\overline{P} = I_{rms}V_{rms}$$



Wrap-up: revisiting Learning objectives

After this lecture you should be able to:

- Understand the general characteristics of electric current
- Understand the Ohm's Law and the relationship between voltage, current, and resistance and determine the resistance of a wire or other conducting mean given its geometric and material properties
- Understand the basics of alternate current
- Understand the basics of electric current at the microscopic level

$$V = IR$$

$$R = \rho \frac{l}{A},$$

$$\rho = \rho_0 [1 + \alpha (T - T_0)]$$

$$\overline{P} = I_{rms}V_{rms}$$

$$j = \frac{I}{A} = -nev_d, \vec{j} = \sigma \vec{E}$$

$$= \frac{1}{o} \vec{E}$$

