COMPUTER NETWORKS LAB (CS315)

Assignment-5
TCP

Date: 31 Jan 2023

TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
  - one sender, one receiver
- reliable, in-order *byte steam:*
  - no “message boundaries"
- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- cumulative ACKs
- pipelining:
  - TCP congestion and flow control set window size
- connection-oriented:
  - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

TCP segment structure



TCP sequence numbers, ACKs

Sequence numbers:
- byte stream "number" of first byte in segment's data

Acknowledgments:
- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments
- A: TCP spec doesn't say, - up to implementer



TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

Q: how to set TCP timeout value?

- longer than RTT, but RTT varies!
- *too short:* premature timeout, unnecessary retransmissions
- *too long:* slow reaction to segment loss

Q: how to estimate RTT?

- `SampleRTT`: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- `SampleRTT` will vary, want estimated RTT "smoother"
  - average several *recent* measurements, not just current `SampleRTT`

TCP round trip time, timeout

`EstimatedRTT = (1- α)*EstimatedRTT + α*SampleRTT`

- exponential weighted moving average (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125



Transport Layer: 3-<number>

TCP round trip time, timeout

- timeout interval: **EstimatedRTT** plus "safety margin"
  - large variation in **EstimatedRTT** : want a larger safety margin

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

estimated RTT　　"safety margin"

- **DevRTT**: EWMA of **SampleRTT** deviation from **EstimatedRTT**:

```
DevRTT = (1-β)*DevRTT + β*|SampleRTT-EstimatedRTT|
```

(typically, β = 0.25)

* Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval: `TimeOutInterval`

event: timeout

- retransmit segment that caused timeout
- restart timer

event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments

TCP Receiver: ACK generation [RFC 5681]

Event at receiver	*TCP receiver action*

TCP: retransmission scenarios



lost ACK scenario

premature timeout

TCP: retransmission scenarios



cumulative ACK covers for earlier lost ACK

TCP fast retransmit

TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

- likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!



Principles of congestion control

Congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!

congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver

Causes/costs of congestion: scenario 1



Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed

Q: What happens as arrival rate λ_{in} approaches R/2?



maximum per-connection throughput: R/2



large delays as arrival rate λ_{in} approaches capacity

Causes/costs of congestion: scenario 2

- one router, *finite* buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes *retransmissions* : $\lambda'_{in} \geq \lambda_{in}$



Transport Layer: 3-<number>

Causes/costs of congestion: scenario 2

Idealization: perfect knowledge

- sender sends only when router buffers available





Transport Layer: 3-<number>

Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost





Transport Layer: 3-<number>

Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered





Transport Layer: 3-<number>

Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered



"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput

Transport Layer: 3-<number>

Causes/costs of congestion: scenario 3

- *four* senders
- *multi-hop* paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in}' increase ?

A: as red λ_{in}' increases, all arriving blue pkts at upper queue are dropped, blue throughput g 0



Causes/costs of congestion: scenario 3





another "cost" of congestion:

- when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!

Causes/costs of congestion: insights

- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream



Approaches towards congestion control

End-end congestion control:

- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Thank you