# Amazon Kinesis Video Streams Developer Guide



#### Amazon Kinesis Video Streams: Developer Guide

Copyright © 2022 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

## **Table of Contents**

What Is Amazon Kinesis Video Streams?	
Are You a First-Time User of Kinesis Video Streams?	2
System Requirements	
Camera Requirements	
Tested Operating Systems	3
SDK Storage Requirements	4
How It Works	5
API and Producer Libraries	6
Kinesis Video Streams API	6
Producer Libraries	8
Video Playback	9
Video Playback with HLS	9
Video Playback with MPEG-DASH	12
Using Streaming Metadata	
Adding Metadata to a Kinesis Video Stream	
Consuming Metadata Embedded in a Kinesis Video Stream	
Streaming Metadata Limitations	
Data Model	
Stream Header Elements	
Stream Track Data	
Frame Header Elements	
MKV Frame Data	
Getting Started	
Step 1: Set Up an Account	
Sign Up for AWS	
Create an Administrator IAM User	
Create an AWS Account Key	
Next Step	
Step 2: Create a Kinesis Video Stream	
Create a Video Stream Using the Console	
Create a Video Stream Using the Console	
Next Step	
Step 3: Send Data to a Kinesis Video Stream	
·	
Next Step	
Step 4: Consume Media Data	
View Media Data in the Console	
Consume Media Data using HLS	
Next Step	
What's Next?	
Images	
Getting Started with GetImages	
Getting Started with Amazon S3 delivery	
UpdateImageGenerationConfiguration	
DescribeImageGenerationConfiguration	
Producer MKV tags	
Adding metadata tags in Producer SDK using PutEventMetaData	
Limits	
S3 Object Metadata	
S3 object path (image)	
Amazon S3 URI recommendations to protect against throttling	
Notifications	
UpdateNotificationConfiguration	
DescribeNotificationConfiguration	
Producer MKV Tags	31

Sy	yntax for Producer MKV Tags	32
MKV Ta	ag Limits	35
	mazon SNS Topic Payload	
	iewing your Amazon SNS Messages	
	rotection	
	/hat Is Server-Side Encryption for Kinesis Video Streams?	
	osts, Regions, and Performance Considerations	
	low Do I Get Started with Server-Side Encryption?	
	reating and Using User-Generated AWS KMS Master Keys	
	ermissions to Use User-Generated AWS KMS Master Keys	
	lling Access to Kinesis Video Streams Resources Using IAM	
	olicy Syntax	
	ctions for Kinesis Video Streams	
	mazon Resource Names (ARNs) for Kinesis Video Streams	
	ranting Other IAM Accounts Access to a Kinesis Video Stream	
	xample Policies	
	lling Access to Kinesis Video Streams Resources Using AWS IoT	
	oT ThingName as Stream Name	
	oT CertificateId as Stream Name	
	ring	
•	ance Validation	
	nce	
	ructure Security	
	y Best Practices	
	mplement least privilege access	
	se IAM roles	
	se CloudTrail to Monitor API Calls	
	raries	
	Video Streams Producer Client	
	Video Streams Producer Library	
	1 Topics	
	oducer Library	
	rocedure: Using the Java Producer SDK	
	tep 1: Download and Configure the Code	
	tep 2: Write and Examine the Code	
	tep 3: Run and Verify the Code	
	d Producer Library	
	rocedure: Using the Android Producer SDK	
	tep 1: Download and Configure the Code	
	tep 2: Examine the Code	
	tep 3: Run and Verify the Code	
	oducer Library	
	bject Model	
	utting Media into the Stream	
	allback Interfaces	
	rocedure: Using the C++ Producer SDK	
	tep 1: Download and Configure the Code	
St	tep 2: Write and Examine the Code	66
	tep 3: Run and Verify the Code	
	sing the C++ Producer SDK as a GStreamer Plugin	
U	sing the C++ Producer SDK as a GStreamer Plugin in a Docker Container	71
	sing Logging	
C Produ	ucer Library	72
^	hiect Model	72

Putting Media Into the Stream	
Procedure: Using the C Producer SDK	
Step 1: Download the Code	
Step 2: Write and Examine the Code	75
Step 3: Run and Verify the Code	
Reference	
Producer SDK Limits	
Error Code Reference	
NAL Adaptation Flags	
Producer Structures	
Stream Structures	
Callbacks	
Stream Parser Library	
Procedure: Using the Kinesis Video Stream Parser Library	
Prerequisites	124
Step 1: Download and Configure the Code	
Next Step	
Step 2: Write and Examine the Code	
StreamingMkvReader	
FragmentMetadataVisitor	
OutputSegmentMerger	
KinesisVideoExample	
Next StepStep 3: Run and Verify the Code	
· · · · · · · · · · · · · · · · · · ·	
Examples Examples: Sending Data to Kinesis Video Streams	
Examples: Retrieving Data from Kinesis Video Streams	
Examples: Playing Back Video Data	
Prerequisites	
GStreamer	
Download, Build, and Configure the GStreamer Element	
Run the GStreamer Element	
Launch Commands	
Run the GStreamer Element in a Docker Container	
Parameter Reference	
PutMedia API	
Step 1: Download and Configure the Code	
Step 2: Write and Examine the Code	
Step 3: Run and Verify the Code	
RTSP and Docker	143
Prerequisites	144
Build the Docker Image	144
Run the RTSP Example Application	144
Renderer	145
Prerequisites	
Running the Renderer Example	145
How It Works	
SageMaker	
Prerequisites	
Creating the Application	
Monitoring the Application	
Extending the Application	
Cleaning up the Application	
Monitoring	
Monitoring Metrics with CloudWatch	
CloudWatch Metrics Guidance	
Logging API Calls with CloudTrail	164

	Kinesis Video Streams and CloudTrail	
	Example: Amazon Kinesis Video Streams Log File Entries	165
Limits		
Conti	rol-plane API limits	168
Media	a and archived-media API limits	169
Fragr	nent-metadata and fragment-media quotas	171
Troublesho	oting	174
Troub	pleshooting General Issues	174
	Latency too high	174
Troub	pleshooting API Issues	174
	Error: "Unknown options"	
	Error: "Unable to determine service/operation name to be authorized"	175
	Error: "Failed to put a frame in the stream"	175
	Error: "Service closed connection before final AckEvent was received"	175
	Error: "STATUS_STORE_OUT_OF_MEMORY"	176
Trouk	oleshooting HLS Issues	
	Retrieving HLS streaming session URL succeeds, but playback fails in video player	176
	Latency too high between producer and player	
Trouk	oleshooting Java Issues	
	Enabling Java logs	
Troub	oleshooting Producer Library Issues	
	Cannot compile the Producer SDK	
	Video stream does not appear in the console	179
	Error: "Security token included in the request is invalid" when streaming data using the	
	GStreamer demo application	179
	Error: "Failed to submit frame to Kinesis Video client"	
	GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS	
	Χ	180
	Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on	
	Raspberry Pi	180
	Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi	180
	Camera fails to load on Raspberry Pi	180
	Camera can't be found on macOS High Sierra	181
	jni.h file not found when compiling on macOS High Sierra	181
	Curl errors when running the GStreamer demo application	
	Timestamp/range assertion at runtime on Raspberry Pi	181
	Assertion on gst_value_set_fraction_range_full on Raspberry Pi	
	STATUS_MKV_INVALID_ANNEXB_NALU_IN_FRAME_DATA (0x3200000d) error on Android	
	Maximum Fragment Duration Was Reached Error	
	"Invalid thing name passed" error when using IoT authorization	182
Troub	pleshooting Stream Parser Library Issues	183
	Cannot access a single frame from the stream	
	Fragment decoding error	183
Document	History	184
API Refere	nce	187
Actio	ns	187
	Amazon Kinesis Video Streams	188
	Amazon Kinesis Video Streams Media	256
	Amazon Kinesis Video Streams Archived Media	268
	Amazon Kinesis Video Signaling Channels	299
Data	Types	
	Amazon Kinesis Video Streams	
	Amazon Kinesis Video Streams Media	
	Amazon Kinesis Video Streams Archived Media	
	Amazon Kinesis Video Signaling Channels	
Comr	mon Errors	
	non Parameters	

# What Is Amazon Kinesis Video Streams?

Amazon Kinesis Video Streams is a fully managed AWS service that you can use to stream live video from devices to the AWS Cloud, or build applications for real-time video processing or batch-oriented video analytics.

Kinesis Video Streams isn't just storage for video data. You can use it to watch your video streams in real time as they are received in the cloud. You can either monitor your live streams in the AWS Management Console, or develop your own monitoring application that uses the Kinesis Video Streams API library to display live video.

You can use Kinesis Video Streams to capture massive amounts of live video data from millions of sources, including smartphones, security cameras, webcams, cameras embedded in cars, drones, and other sources. You can also send non-video time-serialized data such as audio data, thermal imagery, depth data, RADAR data, and more. As live video streams from these sources into a Kinesis video stream, you can build applications that can access the data, frame-by-frame, in real time for low-latency processing. Kinesis Video Streams is source-agnostic; you can stream video from a computer's webcam using the GStreamer (p. 132) library, or from a camera on your network using real-time streaming protocol (RTSP)".

You can also configure your Kinesis video stream to durably store media data for the specified retention period. Kinesis Video Streams automatically stores this data and encrypts it at rest. Additionally, Kinesis Video Streams time-indexes stored data based on both the producer time stamps and ingestion time stamps. You can build applications that periodically batch-process the video data, or you can create applications that require ad hoc access to historical data for different use cases.

Your custom applications, real-time or batch-oriented, can run on Amazon EC2 instances. These applications might process data using open source deep-learning algorithms, or use third-party applications that integrate with Kinesis Video Streams.

Benefits of using Kinesis Video Streams include the following:

- Connect and stream from millions of devices Kinesis Video Streams enables you to connect and stream video, audio, and other data from millions of devices ranging from consumer smartphones, drones, dash cams, and more. You can use the Kinesis Video Streams producer libraries to configure your devices and reliably stream in real time, or as after-the-fact media uploads.
- **Durably store, encrypt, and index data** You can configure your Kinesis video stream to durably store media data for custom retention periods. Kinesis Video Streams also generates an index over the stored data based on producer-generated or service-side time stamps. Your applications can easily retrieve specified data in a stream using the time-index.
- Focus on managing applications instead of infrastructure Kinesis Video Streams is serverless, so there is no infrastructure to set up or manage. You don't need to worry about the deployment, configuration, or elastic scaling of the underlying infrastructure as your data streams and number of consuming applications grow and shrink. Kinesis Video Streams automatically does all the administration and maintenance required to manage streams, so you can focus on the applications, not the infrastructure.
- Build real-time and batch applications on data streams You can use Kinesis Video Streams to build custom real-time applications that operate on live data streams, and create batch or ad hoc applications that operate on durably persisted data without strict latency requirements. You can build, deploy, and manage custom applications: open source (Apache MXNet, OpenCV), homegrown, or third-party solutions via the AWS Marketplace to process and analyze your streams. Kinesis Video Streams

Get APIs enable you to build multiple concurrent applications processing data in a real-time or batchoriented basis.

- Stream data more securely Kinesis Video Streams encrypts all data as it flows through the service and when it persists the data. Kinesis Video Streams enforces Transport Layer Security (TLS)-based encryption on data streaming from devices, and encrypts all data at rest using AWS Key Management Service (AWS KMS). Additionally, you can manage access to your data using AWS Identity and Access Management (IAM).
- Pay as you go For more information, see AWS Pricing.

## Are You a First-Time User of Kinesis Video Streams?

If you're a first-time user of Kinesis Video Streams, we recommend that you read the following sections in order:

- Amazon Kinesis Video Streams: How It Works (p. 5) To learn about Kinesis Video Streams concepts.
- Getting Started with Kinesis Video Streams (p. 24) To set up your account and test Kinesis Video Streams.
- Kinesis Video Streams Producer Libraries (p. 53) To learn about creating a Kinesis Video Streams producer application.
- 4. Kinesis Video Stream Parser Library (p. 124) To learn about processing incoming data frames in a Kinesis Video Streams consumer application.
- 5. Amazon Kinesis Video Streams Examples (p. 131) To see more examples of what you can do with Kinesis Video Streams.

# Kinesis Video Streams System Requirements

The following sections contain hardware, software, and storage requirements for Amazon Kinesis Video Streams.

#### **Topics**

- Camera Requirements (p. 3)
- Tested Operating Systems (p. 3)
- SDK Storage Requirements (p. 4)

## Camera Requirements

Cameras that are used for running the Kinesis Video Streams Producer SDK and samples have the following memory requirements:

- The SDK content view requires 16 MB of memory.
- The sample application default configuration is 512 MB. This value is appropriate for producers that have good network connectivity and no requirements for additional buffering. If the network connectivity is poor and more buffering is required, you can calculate the memory requirement per second of buffering by multiplying the frame rate per second by the frame memory size. For more information about allocating memory, see StorageInfo (p. 105).

We recommend using USB or RTSP (Real Time Streaming Protocol) cameras that encode data using H.264 because this removes the encoding workload from the CPU.

Currently, the demo application does not support the User Datagram Protocol (UDP) for RTSP streaming. This capability will be added in the future.

The Producer SDK supports the following types of cameras:

- · Web cameras.
- · USB cameras.
- · Cameras with H.264 encoding (preferred).
- · Cameras without H.264 encoding.
- Raspberry Pi camera module. This is preferred for Raspberry Pi devices because it connects to the GPU for video data transfer, so there is no overhead for CPU processing.
- RTSP (network) cameras. These cameras are preferred because the video streams are already encoded with H.264.

## **Tested Operating Systems**

We have tested web cameras and RTSP cameras with the following devices and operating systems:

Mac mini

## Amazon Kinesis Video Streams Developer Guide SDK Storage Requirements

- High Sierra
- MacBook Pro laptops
  - Sierra (10.12)
  - El Capitan (10.11)
- HP laptops running Ubuntu 16.04
- Ubuntu 17.10 (Docker container)
- Raspberry Pi 3

## **SDK Storage Requirements**

Installing the Kinesis Video Streams Producer Libraries (p. 53) has a minimum storage requirement of 170 MB and a recommended storage requirement of 512 MB.


# Amazon Kinesis Video Streams: How It Works

#### **Topics**

- Kinesis Video Streams API and Producer Libraries Support (p. 6)
- Kinesis Video Streams Playback (p. 9)
- Using Streaming Metadata with Kinesis Video Streams (p. 15)
- Kinesis Video Streams Data Model (p. 18)

Amazon Kinesis Video Streams is a fully managed AWS service that enables you to stream live video from devices to the AWS Cloud and durably store it. You can then build your own applications for real-time video processing or perform batch-oriented video analytics.

The following diagram provides an overview of how Kinesis Video Streams works.



#### Amazon Kinesis Video Streams Developer Guide API and Producer Libraries

The diagram demonstrates the interaction among the following components:

 Producer – Any source that puts data into a Kinesis video stream. A producer can be any videogenerating device, such as a security camera, a body-worn camera, a smartphone camera, or a dashboard camera. A producer can also send non-video data, such as audio feeds, images, or RADAR data.

A single producer can generate one or more video streams. For example, a video camera can push video data to one Kinesis video stream and audio data to another.

- Kinesis Video Streams Producer libraries A set of easy-to-use software and libraries that you can install and configure on your devices. These libraries make it easy to securely connect and reliably stream video in different ways, including in real time, after buffering it for a few seconds, or as after-the-fact media uploads.
- **Kinesis video stream** A resource that enables you to transport live video data, optionally store it, and make the data available for consumption both in real time and on a batch or ad hoc basis. In a typical configuration, a Kinesis video stream has only one producer publishing data into it.

The stream can carry audio, video, and similar time-encoded data streams, such as depth sensing feeds, RADAR feeds, and more. You create a Kinesis video stream using the AWS Management Console or programmatically using the AWS SDKs.

Multiple independent applications can consume a Kinesis video stream in parallel.

- Consumer Gets data, such as fragments and frames, from a Kinesis video stream to view, process, or analyze it. Generally these consumers are called Kinesis Video Streams applications. You can write applications that consume and process data in Kinesis video streams in real time, or after the data is durably stored and time-indexed when low latency processing is not required. You can create these consumer applications to run on Amazon EC2 instances.
  - Kinesis Video Stream Parser Library (p. 124) Enables Kinesis Video Streams applications to
    reliably get media from Kinesis video streams in a low-latency manner. Additionally, it parses the
    frame boundaries in the media so that applications can focus on processing and analyzing the
    frames themselves.

## Kinesis Video Streams API and Producer Libraries Support

Kinesis Video Streams provides APIs for you to create and manage streams and read or write media data to and from a stream. The Kinesis Video Streams console, in addition to administration functionality, also supports live and video-on-demand playback. Kinesis Video Streams also provides a set of producer libraries that you can use in your application code to extract data from your media sources and upload to your Kinesis video stream.

#### **Topics**

- Kinesis Video Streams API (p. 6)
- Producer Libraries (p. 8)

### Kinesis Video Streams API

Kinesis Video Streams provides APIs for creating and managing Kinesis video streams. It also provides APIs for reading and writing media data to a stream, as follows:

 Producer API – Kinesis Video Streams provides a PutMedia API to write media data to a Kinesis video stream. In a PutMedia request, the producer sends a stream of media fragments. A fragment is a self-

#### Amazon Kinesis Video Streams Developer Guide Kinesis Video Streams API

contained sequence of frames. The frames belonging to a fragment should have no dependency on any frames from other fragments. For more information, see PutMedia (p. 262).

As fragments arrive, Kinesis Video Streams assigns a unique fragment number, in increasing order. It also stores producer-side and server-side time stamps for each fragment, as Kinesis Video Streams-specific metadata.

- Consumer APIs –The following APIs enable consumers to get data from a stream:
  - GetMedia When using this API, consumers must identify the starting fragment. The API then returns fragments in the order in which they were added to the stream (in increasing order by fragment number). The media data in the fragments is packed into a structured format such as Matroska (MKV). For more information, see GetMedia (p. 258).

#### Note

GetMedia knows where the fragments are (archived in the data store or available in real time). For example, if GetMedia determines that the starting fragment is archived, it starts returning fragments from the data store. When it needs to return newer fragments that are not archived yet, GetMedia switches to reading fragments from an in-memory stream buffer.

This is an example of a continuous consumer, which processes fragments in the order that they are ingested by the stream.

GetMedia enables video-processing applications to fail or fall behind, and then catch up with no additional effort. Using GetMedia, applications can process data that's archived in the data store, and as the application catches up, GetMedia continues to feed media data in real time as it arrives.

GetMediaFromFragmentList (and ListFragments) - Batch processing applications
are considered offline consumers. Offline consumers might choose to explicitly fetch
particular media fragments or ranges of video by combining the ListFragments and
GetMediaFromFragmentList APIs. ListFragments and GetMediaFromFragmentList enable
an application to identify segments of video for a particular time range or fragment range, and then
fetch those fragments either sequentially or in parallel for processing. This approach is suitable for
MapReduce application suites, which must quickly process large amounts of data in parallel.


For example, suppose that a consumer wants to process one day's worth of video fragments. The consumer would do the following:

1. Get a list of fragments by calling the ListFragments API and specifying a time range to select the desired collection of fragments.

The API returns metadata from all the fragments in the specified time range. The metadata provides information such as fragment number, producer-side/server-side time stamps, and so on

2. Take the fragment metadata list and retrieve fragments, in any order. For example, to process all the fragments for the day, the consumer might choose to split the list into sub-lists and have workers (for example, multiple Amazon EC2 instances) fetch the fragments in parallel using the GetMediaFromFragmentList, and process them in parallel.

The following diagram shows the data flow for fragments and chunks during these API calls.



When a producer sends a PutMedia request, it sends media metadata in the payload, and then sends a sequence of media data fragments. Upon receiving the data, Kinesis Video Streams stores incoming media data as Kinesis Video Streams chunks. Each chunk consists of the following:

- · A copy of the media metadata
- A fragment
- Kinesis Video Streams-specific metadata; for example, the fragment number and server-side and producer-side time stamps

When a consumer requests media metadata, Kinesis Video Streams returns a stream of chunks, starting with the fragment number that you specify in the request.

If you enable data persistence for the stream, after receiving a fragment on the stream, Kinesis Video Streams also saves a copy of the fragment to the data store.

### **Producer Libraries**

After you create a Kinesis video stream, you can start sending data to the stream. In your application code, you can use these libraries to extract data from your media sources and upload to your Kinesis video stream. For more information about the available producer libraries, see Kinesis Video Streams Producer Libraries (p. 53).

## Kinesis Video Streams Playback

You can view a Kinesis video stream using the following methods:

- **GetMedia**: You can use the GetMedia API to build your own applications to process Kinesis video streams. GetMedia is a real-time API with low latency. If you want to create a player that uses GetMedia, you have to build it yourself. For information about how to develop an application that displays a Kinesis video stream using GetMedia, see Stream Parser Library (p. 124).
- HLS: HTTP Live Streaming (HLS) is an industry-standard HTTP-based media streaming communications protocol. You can use HLS to view an Amazon Kinesis video stream, either for live playback or to view archived video.

You can use HLS for live playback. Latency is typically between 3 and 5 seconds, but it can be between 1 and 10 seconds, depending on the use case, player, and network conditions. You can use a third-party player (such as Video.js or Google Shaka Player) to display the video stream by providing the HLS streaming session URL, either programmatically or manually. You can also play back video by typing the HLS streaming session URL in the **Location** bar of the Apple Safari or Microsoft Edge browsers.

• MPEG-DASH: Dynamic Adaptive Streaming over HTTP (DASH), also known as MPEG-DASH, is an adaptive bitrate streaming protocol that enables high quality streaming of media content over the Internet delivered from conventional HTTP web servers.

You can use MPEG-DASH for live playback. Latency is typically between 3 and 5 seconds, but it can be between 1 and 10 seconds, depending on the use case, player, and network conditions. You can use a third-party player (such as dash.js or Google Shaka Player to display the video stream by providing the MPEG-DASH streaming session URL, either programmatically or manually.

• **GetClip API**: You can use the GetClip API to download a clip (in an MP4 file) containing the archived, on-demand media from the specified video stream over the specified time range. For more information, see the GetClip API reference.

#### **Topics**

- Video Playback with HLS (p. 9)
- Video Playback with MPEG-DASH (p. 12)

## Video Playback with HLS

To view a Kinesis video stream using HLS, you first create a streaming session using GetHLSStreamingSessionURL. This action returns a URL (containing a session token) for accessing the HLS session. You can then use the URL in a media player or a standalone application to display the stream.

An Amazon Kinesis video stream has the following requirements for providing video through HLS:

- For streaming video, the media must contain H.264 or H.265 encoded video and, optionally, AAC encoded audio. Specifically, the codec ID of track 1 should be V\_MPEG/ISO/AVC (for H.264) or V\_MPEG/ISO/HEVC (for H.265). Optionally, the codec ID of track 2 should be A\_AAC. For audio only streaming, the codec ID of track 1 should be A\_AAC.
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format or HEVC for H.265 format (MPEG-4 specification ISO/IEC 14496-15). For information about adapting stream data to a given format, see NAL Adaptation Flags (p. 104).
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7).

#### Example: Using HLS in HTML and JavaScript

The following example shows how to retrieve an HLS streaming session for a Kinesis video stream and play it back in a webpage. The example shows how to play back video in the following players:

- · Video.js
- · Google Shaka Player
- hls.is

#### **Topics**

- Set Up the Kinesis Video Streams Client for HLS Playback (p. 10)
- Retrieve the Kinesis Video Streams Archived Content Endpoint for HLS Playback (p. 10)
- Retrieve the HLS Streaming Session URL (p. 11)
- Display the Streaming Video with HLS Playback (p. 11)
- Troubleshooting HLS Issues (p. 12)
- Completed Example for HLS Playback (p. 12)

#### Set Up the Kinesis Video Streams Client for HLS Playback

To access streaming video with HLS, first create and configure the Kinesis Video Streams client (to retrieve the service endpoint) and archived media client (to retrieve the HLS streaming session). The application retrieves the necessary values from input boxes on the HTML page.

```
<script src="https://cdnjs.cloudflare.com/ajax/libs/aws-sdk/2.278.1/aws-sdk.min.js"></
script>
...

var protocol = $('#protocol').val();
var streamName = $('#streamName').val();

// Step 1: Configure SDK Clients
var options = {
    accessKeyId: $('#accessKeyId').val(),
    secretAccessKey: $('#secretAccessKey').val(),
    sessionToken: $('#sessionToken').val() || undefined,
    region: $('#region').val(),
    endpoint: $('#endpoint').val() || undefined
}
var kinesisVideo = new AWS.KinesisVideo(options);
var kinesisVideoArchivedContent = new AWS.KinesisVideoArchivedMedia(options);
```

#### Retrieve the Kinesis Video Streams Archived Content Endpoint for HLS Playback

After the clients are initiated, retrieve the Kinesis Video Streams archived content endpoint to retrieve the HLS streaming session URL:

```
// Step 2: Get a data endpoint for the stream
console.log('Fetching data endpoint');
kinesisVideo.getDataEndpoint({
    StreamName: streamName,
    APIName: "GET_HLS_STREAMING_SESSION_URL"
    }, function(err, response) {
        if (err) { return console.error(err); }
        console.log('Data endpoint: ' + response.DataEndpoint);
```

kinesisVideoArchivedContent.endpoint = new AWS.Endpoint(response.DataEndpoint);

#### Retrieve the HLS Streaming Session URL

When you have the archived content endpoint, call the GetHLSStreamingSessionURL API to retrieve the HLS streaming session URL:

```
// Step 3: Get a Streaming Session URL
var consoleInfo = 'Fetching ' + protocol + ' Streaming Session URL';
console.log(consoleInfo);
. . .
else {
    kinesisVideoArchivedContent.getHLSStreamingSessionURL({
        StreamName: streamName,
        PlaybackMode: $('#playbackMode').val(),
        HLSFragmentSelector: {
            FragmentSelectorType: $('#fragmentSelectorType').val(),
            TimestampRange: $('#playbackMode').val() === "LIVE" ? undefined : {
                StartTimestamp: new Date($('#startTimestamp').val()),
                EndTimestamp: new Date($('#endTimestamp').val())
                }
            ContainerFormat: $('#containerFormat').val(),
            DiscontinuityMode: $('#discontinuityMode').val(),
            DisplayFragmentTimestamp: $('#displayFragmentTimestamp').val(),
            MaxMediaPlaylistFragmentResults: parseInt($('#maxResults').val()),
            Expires: parseInt($('#expires').val())
        }, function(err, response) {
            if (err) { return console.error(err); }
            console.log('HLS Streaming Session URL: ' + response.HLSStreamingSessionURL);
```

#### Display the Streaming Video with HLS Playback

When you have the HLS streaming session URL, provide it to the video player. The method for providing the URL to the video player is specific to the player used.

The following code example shows how to provide the streaming session URL to a Video.js player:

```
// VideoJS elements
<video id="videojs" class="player video-js vjs-default-skin" controls autoplay></video>
<link rel="stylesheet" href="https://vjs.zencdn.net/6.6.3/video-js.css">
<script src="https://vjs.zencdn.net/6.6.3/video.js"></script>
<script src="https://cdnjs.cloudflare.com/ajax/libs/videojs-contrib-hls/5.14.1/videojs-</pre>
contrib-hls.js"></script>
else if (playerName === 'VideoJS') {
var playerElement = $('#videojs');
playerElement.show();
var player = videojs('videojs');
console.log('Created VideoJS Player');
player.src({
    src: response.HLSStreamingSessionURL,
    type: 'application/x-mpegURL'
console.log('Set player source');
player.play();
```

```
console.log('Starting playback');
```

The following code example shows how to provide the streaming session URL to a Google Shaka player:

```
// Shaka Player elements
<video id="shaka" class="player" controls autoplay></video>
<script src="https://cdnjs.cloudflare.com/ajax/libs/shaka-player/2.4.1/shaka-
player.compiled.js">
</script>

...

else if (playerName === 'Shaka Player') {
    var playerElement = $('#shaka');
    playerElement.show();
    var player = new shaka.Player(playerElement[0]);
    console.log('Created Shaka Player');
    player.load(response.HLSStreamingSessionURL).then(function() {
        console.log('Starting playback');
    });
    console.log('Set player source');
```

The following code example shows how to provide the streaming session URL to an hls.js player:

```
// HLS.js elements
<video id="hlsjs" class="player" controls autoplay></video>
<script src="https://cdn.jsdelivr.net/npm/hls.js@latest"></script>
var playerName = $('#player').val();
if (playerName == 'HLS.js') {
    var playerElement = $('#hlsjs');
    playerElement.show();
    var player = new Hls();
    console.log('Created HLS.js Player');
    player.loadSource(response.HLSStreamingSessionURL);
    player.attachMedia(playerElement[0]);
    console.log('Set player source');
    player.on(Hls.Events.MANIFEST_PARSED, function() {
        video.play();
        console.log('Starting playback');
    });
}
```

#### Troubleshooting HLS Issues

If the video stream does not play back correctly, see Troubleshooting HLS Issues (p. 176).

#### Completed Example for HLS Playback

You can download or view the completed example code.

## Video Playback with MPEG-DASH

To view a Kinesis video stream using MPEG-DASH, you first create a streaming session using GetDASHStreamingSessionURL. This action returns a URL (containing a session token) for accessing the MPEG-DASH session. You can then use the URL in a media player or a standalone application to display the stream.

#### Amazon Kinesis Video Streams Developer Guide Video Playback with MPEG-DASH

An Amazon Kinesis video stream has the following requirements for providing video through MPEG-DASH:

- The media must contain H.264 or H.265 encoded video and, optionally, AAC or G.711 encoded audio. Specifically, the codec ID of track 1 should be V\_MPEG/ISO/AVC (for h.264) or V\_MPEGH/ISO/HEVC (for H.265). Optionally, the codec ID of track 2 should be A\_AAC (for AAC) or A\_MS/ACM (for G.711).
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format and HEVC for H.265 format. For more information, see MPEG-4 specification ISO/IEC 14496-15. For information about adapting stream data to a given format, see NAL Adaptation Flags.
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7) or the MS Wave format.

#### Example: Using MPEG-DASH in HTML and JavaScript

The following example shows how to retrieve an MPEG-DASH streaming session for a Kinesis video stream and play it back in a webpage. The example shows how to play back video in the following players:

- · Google Shaka Player
- · dash.js

#### **Topics**

- Set Up the Kinesis Video Streams Client for MPEG-DASH Playback (p. 13)
- Retrieve the Kinesis Video Streams Archived Content Endpoint for MPEG-DASH Playback (p. 13)
- Retrieve the MPEG-DASH Streaming Session URL (p. 14)
- Display the Streaming Video with MPEG-DASH Playback (p. 14)
- Completed Example (p. 15)

#### Set Up the Kinesis Video Streams Client for MPEG-DASH Playback

To access streaming video with MPEG-DASH, first create and configure the Kinesis Video Streams client (to retrieve the service endpoint) and archived media client (to retrieve the MPEG-DASH streaming session). The application retrieves the necessary values from input boxes on the HTML page.

```
var streamName = $('#streamName').val();

// Step 1: Configure SDK Clients
var options = {
    accessKeyId: $('#accessKeyId').val(),
    secretAccessKey: $('#secretAccessKey').val(),
    sessionToken: $('#sessionToken').val() || undefined,
    region: $('#region').val(),
    endpoint: $('#endpoint').val() || undefined
    }

var kinesisVideo = new AWS.KinesisVideo(options);
var kinesisVideoArchivedContent = new AWS.KinesisVideoArchivedMedia(options);
```

## Retrieve the Kinesis Video Streams Archived Content Endpoint for MPEG-DASH Playback

After the clients are initiated, retrieve the Kinesis Video Streams archived content endpoint so that you can retrieve the MPEG-DASH streaming session URL as follows:

```
// Step 2: Get a data endpoint for the stream
console.log('Fetching data endpoint');
kinesisVideo.getDataEndpoint({
    StreamName: streamName,
    APIName: "GET_DASH_STREAMING_SESSION_URL"
}, function(err, response) {
    if (err) { return console.error(err); }
    console.log('Data endpoint: ' + response.DataEndpoint);
    kinesisVideoArchivedContent.endpoint = new AWS.Endpoint(response.DataEndpoint);
```

#### Retrieve the MPEG-DASH Streaming Session URL

When you have the archived content endpoint, call the GetDASHStreamingSessionURL API to retrieve the MPEG-DASH streaming session URL as follows:

```
// Step 3: Get a Streaming Session URL
var consoleInfo = 'Fetching ' + protocol + ' Streaming Session URL';
console.log(consoleInfo);
if (protocol === 'DASH') {
    kinesisVideoArchivedContent.getDASHStreamingSessionURL({
        StreamName: streamName,
        PlaybackMode: $('#playbackMode').val(),
        DASHFragmentSelector: {
            FragmentSelectorType: $('#fragmentSelectorType').val(),
            TimestampRange: $('#playbackMode').val() === "LIVE" ? undefined : {
                StartTimestamp: new Date($('#startTimestamp').val()),
                EndTimestamp: new Date($('#endTimestamp').val())
        DisplayFragmentTimestamp: $('#displayFragmentTimestamp').val(),
        DisplayFragmentNumber: $('#displayFragmentNumber').val(),
        MaxManifestFragmentResults: parseInt($('#maxResults').val()),
       Expires: parseInt($('#expires').val())
    }, function(err, response) {
        if (err) { return console.error(err); }
        console.log('DASH Streaming Session URL: ' + response.DASHStreamingSessionURL);
```

#### Display the Streaming Video with MPEG-DASH Playback

When you have the MPEG-DASH streaming session URL, provide it to the video player. The method for providing the URL to the video player is specific to the player that you use.

The following code example shows how to provide the streaming session URL to a Google Shaka player:

```
// Step 4: Give the URL to the video player.

//Shaka Player elements
<video id="shaka" class="player" controls autoplay></video>
<script src="https://cdnjs.cloudflare.com/ajax/libs/shaka-player/2.4.1/shaka-player.compiled.js">
</script>
</script>
</rr>
var playerName = $('#player').val();

if (playerName === 'Shaka Player') {
    var playerElement = $('#shaka');
```

#### Amazon Kinesis Video Streams Developer Guide Using Streaming Metadata

```
playerElement.show();

var player = new shaka.Player(playerElement[0]);
console.log('Created Shaka Player');

player.load(response.DASHStreamingSessionURL).then(function() {
      console.log('Starting playback');
    });
    console.log('Set player source');
}
```

The following code example shows how to provide the streaming session URL to an dash, is player:

```
<!-- dash.js Player elements -->
<video id="dashjs" class="player" controls autoplay=""></video>
<script src="https://cdn.dashjs.org/latest/dash.all.min.js"></script>

...

var playerElement = $('#dashjs');
playerElement.show();

var player = dashjs.MediaPlayer().create();
console.log('Created DASH.js Player');

player.initialize(document.querySelector('#dashjs'), response.DASHStreamingSessionURL,
    true);
console.log('Starting playback');
console.log('Set player source');
}
```

#### Completed Example

You can download or view the completed example code on GitHub.

## Using Streaming Metadata with Kinesis Video Streams

You can use the Amazon Kinesis Video Streams Producer SDK to embed metadata at the individual fragment level in a Kinesis video stream. Metadata in Kinesis Video Streams is a mutable key-value pair. You can use it to describe the content of the fragment, embed associated sensor readings that need to be transferred along with the actual fragment, or meet other custom needs. The metadata is made available as part of the the section called "GetMedia" (p. 258) or the section called "GetMediaForFragmentList" (p. 293) API operations. It is stored along with the fragments for the entire duration of the stream's retention period. Your consuming applications can read, process, and take action based on the metadata using the Kinesis Video Stream Parser Library (p. 124).

There are two modes in which the metadata can be embedded with fragments in a stream:

- Nonpersistent: You can affix metadata on an ad hoc basis to fragments in a stream, based on business-specific criteria that have occurred. An example is a smart camera that detects motion and adds metadata to the corresponding fragments that contain the motion before sending the fragments to its Kinesis video stream. You might apply metadata to the fragment in the following format:

  Motion = true.
- **Persistent:** You can affix metadata to successive, consecutive fragments in a stream based on a continuing need. An example is a smart camera that sends the current latitude and longitude

coordinates associated with all fragments that it sends to its Kinesis video stream. You might apply metadata to all the fragments in the following format: Lat = 47.608013N, Long = -122.335167W

You can affix metadata in both of these modes to the same fragment simultaneously, based on your application's needs. The embedded metadata might include objects detected, activity tracked, GPS coordinates, or any other custom data that you want to associate with the fragments in the stream. Metadata is encoded as key-value string pairs.

#### **Topics**

- Adding Metadata to a Kinesis Video Stream (p. 16)
- Consuming Metadata Embedded in a Kinesis Video Stream (p. 17)
- Streaming Metadata Limitations (p. 18)

## Adding Metadata to a Kinesis Video Stream

Metadata that you add to a Kinesis video stream is modeled as MKV tags, which are implemented as key-value pairs.

Metadata can either be *transient*, such as to mark an event within the stream, or *persistent*, such as to identify fragments where a given event is taking place. A persistent metadata item remains, and is applied to each consecutive fragment, until it is canceled.

#### Note

The metadata items added using the Producer Libraries (p. 53) are distinct from the stream-level tagging APIs implemented with the section called "TagStream" (p. 234), the section called "UntagStream" (p. 239), and the section called "ListTagsForStream" (p. 229).

#### Streaming Metadata API

You can use the following operations in the Producer SDK to implement streaming metadata.

#### PIC

```
PUBLIC_API STATUS putKinesisVideoFragmentMetadata(STREAM_HANDLE streamHandle,
PCHAR name,
PCHAR value,
BOOL persistent);
```

#### C++ Producer SDK

```
/**

* Appends a "tag" or metadata - a key/value string pair into the stream.

*/
bool putFragmentMetadata(const std::string& name, const std::string& value, bool persistent

= true);
```

#### Java Producer SDK

Using the Java Producer SDK, you add metadata to a MediaSource using MediaSourceSink.onCodecPrivateData:

```
void onFragmentMetadata(final @Nonnull String metadataName, final @Nonnull String
  metadataValue, final boolean persistent)
```

throws KinesisVideoException;

#### Persistent and Nonpersistent Metadata

For nonpersistent metadata, you can add multiple metadata items with the same *name*. The Producer SDK collects the metadata items in the metadata queue until they are prepended to the next fragment. The metadata queue is cleared as the metadata items are applied to the stream. To repeat the metadata, call putKinesisVideoFragmentMetadata or putFragmentMetadata again.

For persistent metadata, the Producer SDK collects the metadata items in the metadata queue in the same way as for nonpersistent metadata. However, the metadata items are not removed from the queue when they are prepended to the next fragment.

Calling putKinesisVideoFragmentMetadata or putFragmentMetadata with persistent set to true has the following behavior:

- Calling the API puts the metadata item in the queue. The metadata is added as an MKV tag to every fragment while the item is in the queue.
- Calling the API with the same *name* and a different *value* as a previously added metadata item overwrites the item.
- Calling the API with an empty value removes (cancels) the metadata item from the metadata queue.

## Consuming Metadata Embedded in a Kinesis Video Stream

To consume the metadata in a Kinesis video stream, use an implementation of MkvTagProcessor:

```
public interface MkvTagProcessor {
          default void process(MkvTag mkvTag, Optional<FragmentMetadata> 
          currentFragmentMetadata) {
                throw new NotImplementedException("Default
FragmentMetadataVisitor.MkvTagProcessor");
        }
        default void clear() {
                throw new NotImplementedException("Default
FragmentMetadataVisitor.MkvTagProcessor");
        }
    }
}
```

This interface is found in the FragmentMetadataVisitor (p. 126) class in the Kinesis Video Stream Parser Library (p. 124).

The FragmentMetadataVisitor class contains an implementation of MkvTagProcessor:

```
public static final class BasicMkvTagProcessor implements
FragmentMetadataVisitor.MkvTagProcessor {
    @Getter
    private List<MkvTag> tags = new ArrayList<>();

    @Override
    public void process(MkvTag mkvTag, Optional<FragmentMetadata> currentFragmentMetadata)
{
        tags.add(mkvTag);
    }
}
```

#### Amazon Kinesis Video Streams Developer Guide Streaming Metadata Limitations

```
@Override
  public void clear() {
    tags.clear();
}
```

The KinesisVideoRendererExample class contains an example of how to use a BasicMkvTagProcessor. In the following example, a BasicMkvTagProcessor is added to the MediaProcessingArguments of an application:

The BasicMkvTagProcessor.process method is called when fragment metadata arrives. You can retrieve the accumulated metadata with GetTags. If you want to retrieve a single metadata item, first call clear to clear the collected metadata, and then retrieve the metadata items again.

## **Streaming Metadata Limitations**

The following limitations apply to adding streaming metadata to a Kinesis video stream:

- You can prepend up to 10 metadata items to a fragment.
- A fragment metadata name can be up to 128 bytes in length.
- A fragment metadata *value* can be up to 256 bytes in length.
- A fragment metadata *name* cannot begin with the string "AWS". If such a metadata item is added, the putFragmentMetadata method in the PIC returns a STATUS\_INVALID\_METADATA\_NAME error (error code 0x52000077). Your application can then either ignore the error (the PIC doesn't add the metadata item), or respond to the error.

## Kinesis Video Streams Data Model

The Producer Libraries (p. 53) and Stream Parser Library (p. 124) send and receive video data in a format that supports embedding information alongside video data. This format is based on the Matroska (MKV) specification.

The MKV format is an open specification for media data. All the libraries and code examples in the *Amazon Kinesis Video Streams Developer Guide* send or receive data in the MKV format.

The Kinesis Video Streams Producer Libraries (p. 53) use the StreamDefinition and Frame types to produce MKV stream headers, frame headers, and frame data.

For information about the full MKV specification, see Matroska Specifications.

The following sections describe the components of MKV-formatted data produced by the C++ Producer Library (p. 63).

#### **Topics**

- Stream Header Elements (p. 19)
- Stream Track Data (p. 22)
- Frame Header Elements (p. 23)

• MKV Frame Data (p. 23)

## **Stream Header Elements**

The following MKV header elements are used by StreamDefinition (defined in StreamDefinition.h).

Element	Description	Typical Values
stream_name	Corresponds to the name of the Kinesis video stream.	my-stream
retention_period	The duration that stream data is persisted by Kinesis Video Streams. Specify 0 for a stream that does not retain data.	24
tags	A key-value collection of user data. This data is displayed in the AWS Management Console and can be read by client applications to filter or get information about a stream.	
kms_key_id	If present, the user-defined AWS KMS master key that is used to encrypt data on the stream. If it is absent, the data is encrypted by the Kinesis-supplied master key (aws/kinesis-video).	01234567-89ab- cdef-0123-456789ab
streaming_type	Currently, the only valid streaming type is STREAMING_TYPE_REALTIME.	STREAMING_TYPE_REALTIME
content_type	The user-defined content type. For streaming video data to play in the console, the content type must be video/h264.	video/h264
max_latency	This value is not currently used and should be set to 0.	0
fragment_duration	The estimate of how long your fragments should be, which is used for optimization. The actual fragment duration is determined by the streaming data.	2
timecode_scale	Indicates the scale used by frame time stamps. The default is 1 millisecond. Specifying 0 also assigns the default value of 1 millisecond. This value can be between 100 nanoseconds and 1 second.	

#### Amazon Kinesis Video Streams Developer Guide Stream Header Elements

Element	Description	Typical Values
	For more information, see TimecodeScale in the Matroska documentation.	
key_frame_fragmentation	If true, the stream starts a new cluster when a keyframe is received.	true
frame_timecodes	If true, Kinesis Video Streams stamps the frames when they are received. If false, Kinesis Video Streams uses the decode time of the received frames.	true
absolute_fragment_time	If true, the cluster timecodes are interpreted as using absolute time (for example, from the producer's system clock). If false, the cluster timecodes are interpreted as being relative to the start time of the stream.	true
fragment_acks	If true, acknowledgements (ACKs) are sent when Kinesis Video Streams receives the data. The ACKs can be received using the KinesisVideoStreamFragment or KinesisVideoStreamParseFracallbacks.	
restart_on_error	Indicates whether the stream should resume transmission after a stream error is raised.	true
nal_adaptation_flags	Indicates whether NAL (Network Abstraction Layer) adaptation or codec private data is present in the content. Valid flags include NAL_ADAPTATION_ANNEXB_NALS and NAL_ADAPTATION_ANNEXB_CPD_	
frame_rate	An estimate of the content frame rate. This value is used for optimization; the actual frame rate is determined by the rate of incoming data. Specifying 0 assigns the default of 24.	24

#### Amazon Kinesis Video Streams Developer Guide Stream Header Elements

Element	Description	Typical Values
avg_bandwidth_bps	An estimate of the content bandwidth. This value is used for optimization; the actual rate is determined by the bandwidth of incoming data. For example, for a 720 p resolution video stream running at 25 FPS, you can expect the average bandwidth to be 5 Mbps.	5
buffer_duration	The duration that content is to be buffered on the producer. If there is low network latency, this value can be reduced; if network latency is high, increasing this value prevents frames from being dropped before they can be sent, due to allocation failing to put frames into the smaller buffer.	
replay_duration	The amount of time the video data stream is "rewound" in the case of connection loss. This value can be zero if lost frames due to connection loss are not a concern; the value can be increased if the consuming application can eliminate redundant frames. This value should be less than the buffer duration; otherwise the buffer duration is used.	
connection_staleness	The duration that a connection is maintained when no data is received.	
codec_id	The codec used by the content. For more information, see CodecID in the Matroska specification.	V_MPEG2
track_name	The user-defined name of the track.	my_track

#### Amazon Kinesis Video Streams Developer Guide Stream Track Data

Element	Description	Typical Values
codecPrivateData	Data provided by the encoder used to decode the frame data, such as the frame width and height in pixels, which is needed by many downstream consumers. In the C++ Producer Library (p. 63), the gMkvTrackVideoBits array in MkvStatics.cpp includes pixel width and height for the frame.	
codecPrivateDataSize	The size of the data in the codecPrivateData parameter.	
track_type	The type of the track for the stream.	MKV_TRACK_INFO_TYPE_AUDIO or MKV_TRACK_INFO_TYPE_VIDEO
segment_uuid	User-defined segment uuid (16 bytes).	
default_track_id	Unique non-zero number for the track.	1

## Stream Track Data

The following MKV track elements are used by StreamDefinition (defined in StreamDefinition.h).

Element	Description	Typical Values
track_name	User-defined track name. For example, "audio" for the audio track.	audio
codec_id	Codec id for the track. For example, "A_AAC" for an audio track.	A_AAC
cpd	Data provided by the encoder used to decode the frame data. This data can include frame width and height in pixels, which is needed by many downstream consumers. In the C++ Producer Library, the gMkvTrackVideoBits array in MkvStatics.cpp includes pixel width and height for the frame.	
cpd_size	The size of the data in the codecPrivateData parameter.	
track_type	The type of the track. For example, you can	MKV_TRACK_INFO_TYPE_AUDIO

#### Amazon Kinesis Video Streams Developer Guide Frame Header Elements

Element	Description	Typical Values
	use the enum value of MKV_TRACK_INFO_TYPE_AUDIO for audio.	

## Frame Header Elements

The following MKV header elements are used by Frame (defined in the KinesisVideoPic package, in mkvgen/Include.h):

- Frame Index: A monotonically increasing value.
- Flags: The type of frame. Valid values include the following:
  - FRAME\_FLAGS\_NONE
  - FRAME\_FLAG\_KEY\_FRAME: If key\_frame\_fragmentation is set on the stream, key frames start a new fragment.
  - FRAME\_FLAG\_DISCARDABLE\_FRAME: Tells the decoder that it can discard this frame if decoding is slow.
  - FRAME\_FLAG\_INVISIBLE\_FRAME: Duration of this block is 0.
- **Decoding Timestamp:** The time stamp of when this frame was decoded. If previous frames depend on this frame for decoding, this time stamp might be earlier than that of earlier frames. This value is relative to the start of the fragment.
- **Presentation Timestamp:** The time stamp of when this frame is displayed. This value is relative to the start of the fragment.
- **Duration:** The playback duration of the frame.
- Size: The size of the frame data in bytes

### **MKV Frame Data**

The data in frame.frameData might contain only media data for the frame, or it might contain further nested header information, depending on the encoding schema used. To be displayed in the AWS Management Console, the data must be encoded in the H.264 codec, but Kinesis Video Streams can receive time-serialized data streams in any format.

# Getting Started with Kinesis Video Streams

This section describes how to perform the following tasks in Amazon Kinesis Video Streams:

- · Set up your AWS account and create an administrator, if you haven't already done so.
- Create a Kinesis video stream.
- Send data to the Kinesis video stream from your camera and view the media in the console.

If you are new to Amazon Kinesis Video Streams, we recommend that you read Amazon Kinesis Video Streams: How It Works (p. 5) first.

#### Note

Following the Getting Started sample will not incur any charges to your AWS account. See Amazon Kinesis Video Streams Pricing for data costs in your region.

#### Topics

- Step 1: Set Up an AWS Account and Create an Administrator (p. 24)
- Step 2: Create a Kinesis Video Stream (p. 26)
- Step 3: Send Data to a Kinesis Video Stream (p. 26)
- Step 4: Consume Media Data (p. 27)
- What's Next? (p. 27)

## Step 1: Set Up an AWS Account and Create an Administrator

Before you use Kinesis Video Streams for the first time, complete the following tasks:

- 1. Sign Up for AWS (p. 24) (unless you already have an account)
- 2. Create an Administrator IAM User (p. 25)
- 3. Create an AWS Account Key (p. 25)

## Sign Up for AWS

If you already have an AWS account, you can skip this step.

When you sign up for Amazon Web Services (AWS), your AWS account is automatically signed up for all services in AWS, including Kinesis Video Streams. When you use Kinesis Video Streams, you are charged based on the amount of data ingested into, stored by, and consumed from the service. If you are a new AWS customer, you can get started with Kinesis Video Streams for free. For more information, see AWS Free Usage Tier.

#### To create an AWS account

1. Open https://portal.aws.amazon.com/billing/signup.

2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a verification code on the phone keypad.

When you sign up for an AWS account, an AWS account root user is created. The root user has access to all AWS services and resources in the account. As a security best practice, assign administrative access to an administrative user, and use only the root user to perform tasks that require root user access.

Write down your AWS account ID because you need it for the next task.

#### Create an Administrator IAM User

When you sign up for AWS, you provide an email address and password that is associated with your AWS account. This is your AWS account root user. Its credentials provide complete access to all of your AWS resources.

#### Note

For security reasons, we recommend that you use the root user only to create an *administrator*, which is an *IAM user* with full permissions to your AWS account. You can then use this administrator to create other IAM users and roles with limited permissions. For more information, see IAM Best Practices and Creating an Admin User and Group in the *IAM User Guide*.

#### To create an administrator and sign into the console

- 1. Create an administrator in your AWS account. For instructions, see Creating Your First IAM User and Administrators Group in the *IAM User Guide*.
- 2. As an administrator, you can sign in to the console using a special URL. For more information, see How Users Sign in to Your Account in the *IAM User Guide*.

The administrator can create more users in the account. IAM users by default don't have any permissions. The administrator can create users and manage their permissions. For more information, see Creating Your First IAM User and Administrators Group.

For more information about IAM, see the following:

- AWS Identity and Access Management (IAM)
- Getting started
- IAM User Guide

## Create an AWS Account Key

You will need an AWS Account Key to access Kinesis Video Streams programmatically.

To create an AWS Account Key, do the following:

- Sign in to the AWS Management Console and open the IAM console at https:// console.aws.amazon.com/iam/.
- 2. Choose **Users** in the navigation bar, and choose the **Administrator** user.
- 3. Choose the Security credentials tab, and choose Create access key.
- 4. Record the Access key ID. Choose Show under Secret access key. Record the Secret access key.

## **Next Step**

Step 2: Create a Kinesis Video Stream (p. 26)

## Step 2: Create a Kinesis Video Stream

This section describes how to create a Kinesis video stream.

This section contains the following procedures:

- the section called "Create a Video Stream Using the Console" (p. 26)
- the section called "Create a Video Stream Using the AWS CLI" (p. 26)

## Create a Video Stream Using the Console

- 1. Open the console at https://console.aws.amazon.com/kinesisvideo/home.
- 2. On the Video streams page, choose Create video stream.
- 3. On the **Create a new video stream** page, type **ExampleStream** for the stream name. Leave the **Default configuration** radio button selected.
- 4. Choose Create video stream.
- 5. After Kinesis Video Streams creates the stream, review the details on the **ExampleStream** page.

## Create a Video Stream Using the AWS CLI

- Ensure that you have the AWS CLI installed and configured. For more information, see the AWS Command Line Interface documentation.
- Run the following Create-Stream command in the AWS CLI:

```
aws kinesisvideo create-stream --stream-name "MyKVStream" --data-retention-in-hours "24"
```

The response will look similar to the following:

```
{
    "StreamARN": "arn:aws:kinesisvideo:us-west-2:123456789012:stream/
MyKVSStream/123456789012"
}
```

## **Next Step**

Step 3: Send Data to a Kinesis Video Stream (p. 26)

## Step 3: Send Data to a Kinesis Video Stream

This section describes how to send media data from a camera to the Kinesis video stream that you created in the previous step. This section uses the C++ Producer Library (p. 63) as a GStreamer (p. 132) plugin.

#### Amazon Kinesis Video Streams Developer Guide Next Step

To easily send media from a variety of devices on a variety of operating systems, this tutorial uses the Kinesis Video Streams C++ producer library and GStreamer, an open-source media framework that standardizes access to cameras and other media sources.

First, use the following instructions to build the producer library: https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp.

Next, choose your operating system from one of the four options below and follow the instructions to send video data to your stream.

- Linux
- macOS
- Microsoft Windows
- Raspberry Pi OS

For more information about using the GStreamer plugin to stream video from a file or an RTSP stream from a camera, see Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 132).

## **Next Step**

Step 4: Consume Media Data (p. 27)

## Step 4: Consume Media Data

You can consume media data by either viewing it in the console, or by creating an application that reads media data from a stream using HLS.

### View Media Data in the Console

To view the media data sent from your camera in the Kinesis Video Streams console, open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/home, and choose the **MyKinesisVideoStream** stream on the Manage Streams page. The video plays in the Video Preview pane.

## Consume Media Data using HLS

You can create a client application that consumes data from a Kinesis video stream using Hypertext Live Streaming (HLS). For information about creating an application that consumes media data using HLS, see the section called "Video Playback" (p. 9).

## Next Step

What's Next? (p. 27)

## What's Next?

See the following topics for further information about Kinesis Video Streams:

 Producer Libraries (p. 53): Describes the classes and methods used to send media data to the Kinesis Video Streams service.

## Amazon Kinesis Video Streams Developer Guide What's Next?

•	Stream Parser Library (p. 124): Describes how to create an application that reads and displays medi
	data from a Kinesis video stream.

•	RTSP and Docker (p. 143): Describes how to stream video to the Kinesis Video Streams service from a
	network (RTSP) camera.

## Images in Amazon Kinesis Video Streams

Amazon Kinesis Video Streams APIs and SDKs can help you extract images from your video streams. You can use these images for enhanced playback applications such as thumbnails or enhanced scrubbing, or for use in machine learning pipelines. Kinesis Video Streams offers on-demand image extraction through an API, or automated image extraction from metadata tags in an ingested video.

For information about using Kinesis Video Streams managed support for images, see:

- On-demand Image Generation (GetImages) This API allows customers to extract a single image or multiple images from video stored in Kinesis Video Streams.
- Automated Image Generation (S3 Delivery) Configure Kinesis Video Streams to automatically
  extract images from video data in real time based on tags in an uploaded video, and deliver the images
  to the customer-specified S3 bucket.

#### **Topics**

- Getting started with GetImages (p. 29)
- Getting Started with Amazon S3 delivery (p. 29)

## Getting started with GetImages

Managed support for Images provides customers a fully managed way to get images from the video data streamed and stored in Kinesis Video Streams. Customers can use images to run machine learning (ML) workloads such as person, pet, or vehicle detection. Images can also be used to add interactive elements to playback, such as image previews for motion events and scrubbing for a video clip.

For more information about the GetImages feature, see GetImages in the Amazon Kinesis Video Streams Archived Media API reference quide.

## Getting Started with Amazon S3 delivery

Currently, customers run and manage their own image transcoding pipeline to create images for various purposes like scrubbing, image preview, running ML models on images, and more. Kinesis Video Streams offers the customer the capability to transcode and deliver the images. Kinesis Video Streams will automatically extract images from video data in real-time based on a tag, and deliver the images to a customer specified S3 bucket.

## **UpdateImageGenerationConfiguration**

To set up a Kinesis video stream to enable image generation to Amazon S3:

- Create an S3 Bucket for image generation based on the tags added in the SDK using the new API. Note the S3 URI, which is required in the next step, when updating the image generation configurations for the streams.
- 2. Create a JSON file called update-image-generation-input.json with the following content as input.

{

You can use the AWS CLI to invoke the UpdateImageGenerationConfiguration API operation to add the Amazon S3 ARN created previously and change the status to ENABLED.

```
aws kinesisvideo update-image-generation-configuration \
--cli-input-json file://./update-image-generation-input.json \
```

#### Request:

```
UpdateImageGenerationConfiguration HTTP/1.1
  Method: 'POST'
  Path: '/updateImageGenerationConfiguration'
    StreamName: 'String', // Optional. Either stream name or arn should be passed StreamArn: 'String', // Optional. Either stream name or arn should be passed
     ImageGenerationConfiguration : {
          // required
        Status: 'Enum', // ENABLED | DISABLED,
ImageSelectorType: 'Enum', // SERVER_TIMESTAMP | PRODUCER_TIMESTAMP...
          DestinationConfig: {
               DestinationRegion: 'String',
               Uri: string,
          },
          SamplingInterval: 'Number'//
          Format: 'Enum', // JPEG | PNG
          // Optional parameters
          FormatConfig: {
                     'String': 'String',
          WidthPixels: 'Number', // 1 - 3840 (4k).
HeightPixels: 'Number' // 1 - 2160 (4k).
    }
  }
```

#### Response:

```
HTTP/1.1 200
Content-type: application/json
Body: {
}
```

#### Note

It takes at least 1 minute to initiate the image generation workflow after updating the image generation configuration. Wait at least 1 minute before invoking PutMedia after the update call

### DescribeImageGenerationConfiguration

To view image generation configurations already set for a stream, customers can make a DescribeImageGenerationConfiguration request, as follows.

#### Request:

```
DescribeImageGenerationConfiguration HTTP/1.1

Method: 'POST'
Path: '/describeImageGenerationConfiguration'
Body: {
   StreamName: 'String', // Optional. Either stream name or arn should be passed StreamArn: 'String', // Optional. Either stream name or arn should be passed }
```

#### Response:

```
HTTP/1.1 200
 Content-type: application/json
 Body: {
    ImageGenerationConfiguration : {
        Status: 'Enum',
        ImageSelectorType: 'Enum', // SERVER_TIMESTAMP | PRODUCER_TIMESTAMP
        DestinationConfig: {
            DestinationRegion: 'String'
            Uri: 'string',
        SamplingInterval: 'Number',
        Format: 'Enum',
        FormatConfig: {
                'String': 'String',
        WidthPixels: 'Number',
       HeightPixels: 'Number'
   }
 }
```

To learn more about the DescribeImageGenerationConfiguration feature, see DescribeImageGenerationConfiguration in the Amazon Kinesis Video Streams Developer Guide.

### Producer MKV tags

The Kinesis Video Streams Producer SDK will allow the customer to tag specific fragments of interest by exposing an API operation in the SDK. You can see a sample of this here. Upon calling this API, the SDK will add a set of predefined MKV tags along with the fragment data. Kinesis Video Streams will recognize these special MKV tags and initiate the image generation workflow based on the image processing configuration of that stream.

Any fragment metadata provided along with the Amazon S3 Image generation tags will be saved as Amazon S3 metadata.

### Syntax for Producer MKV Tags

### Adding metadata tags in Producer SDK using PutEventMetaData

The PutEventMetaData function appends an MKV file that's associated with an event. PutEventMetaData takes two parameters, where the first parameter is an event whose value comes from the STREAM\_EVENT\_TYPE enum. The second parameter, pStreamEventMetadata, is optional and can be used to include additional metadata as key, value pairs. There is a limit of 5 key, value pairs of metadata that can be added.

### Limits

The following table lists the limitations associated with the metadata tags. If the metadata tag limit is adjustable, you can request an increase through your account manager.

Limit	Max value	Adjustable
Image Prefix Length	256	no
Optional metadata Key length	128	no
Optional metadata Value length	256	no
Max number of optional metadata	10	yes

### S3 Object Metadata

By default, Kinesis Video Streams will set the **fragment number**, **producer**, and **server timestamp** of the image generated as Amazon S3 object metadata. If any additional fragment data is specified in the MKV

tags, those tags will also be added to the Amazon S3 object metadata. The following example shows the correct syntax for the Amazon S3 object metadata.

```
{
  // KVS S3 object metadata
  x-amz-meta-aws_kinesisvideo_fragment_number : 'string',
  x-amz-meta-aws_kinesisvideo_producer_timestamp: 'number',
  x-amz-meta-aws_kinesisvideo_server_timestamp: 'number',

// Optional key value pair sent as part of the MKV tags
  custom_key_1: custom_value_1,
  custom_key_2: custom_value_2,
}
```

### S3 object path (image)

The following list shows the correct format of the object path and describes each element within the path.

#### Format:

ImagePrefix\_AccountID\_StreamName\_ImageTimecode\_RandomID.file-extension

- 1.ImagePrefix Value of AWS\_KINESISVIDEO\_IMAGE\_PREFIX.
- 2.Account ID Account ID under which the stream is created.
- 3.StreamName Name of the stream for which the image is generated.
- 4.ImageTimecode Epoch timecode in the fragment at which the image is generated.
- 5.RandomID Random GUID.
- 6.file-extension JPG or PNG based on the Image format requested.

## Amazon S3 URI recommendations to protect against throttling

If you write thousands of images to Amazon S3, there is a risk of throttling. For more information, see S3 Prefix Put Request Limits.

An Amazon S3 prefix starts with a PUT limit of 3,500 PUT requests per second, and will gradually ramp up over time for unique prefixes. Avoid using dates and times as Amazon S3 prefixes. Time coded data will impact one prefix at a time, and will also change regularly, invalidating previous prefix scale ups. To enable faster, consistent Amazon S3 scaling, consider adding a random prefix, like a hex code or UUID to the Amazon S3 Destination URI. For example, hex code prefixes will naturally split your requests randomly among 16 different prefixes (a prefix for each unique hex character), which will allow a 56,000 PUT requests per second after Amazon S3 has auto-scaled.

## Notifications in Amazon Kinesis Video Streams

When a media fragment is available for consumption, Kinesis Video Streams notifies customers using Amazon Simple Notification Service (Amazon SNS) notifications. The following topic explains how to get started with notifications.

### **UpdateNotificationConfiguration**

Use this API operation to update the notification information for a stream. For more information about the UpdateNotificationConfiguration feature, see UpdateNotificationConfiguration in the Amazon Kinesis Video Streams Developer Guide.

#### Note

It takes at least 1 minute to initiate the notification after updating the notification configuration. Wait at least 1 minute before invoking PutMedia after the update call.

### DescribeNotificationConfiguration

Use this API to describe a notification configuration attached to a stream. For more information about the DescribeNotificationConfiguration feature, see DescribeNotificationConfiguration in the Amazon Kinesis Video Streams Developer Guide.

### **Producer MKV Tags**

The Kinesis Video Streams Producer SDK allows the customer to tag specific fragments of interest by exposing an API operation in the SDK. See a sample of how this works here. Upon calling this API, the SDK will add a set of predefined MKV tags along with the fragment data. Kinesis Video Streams will recognize these special MKV tags and initiate notifications for the tagged fragments.

Any fragment metadata provided along with the Notification MKV tags will be published as part of the Amazon SNS topic payload.

### Syntax for Producer MKV Tags

```
|+ Tags
| + Tag
| // MANDATORY: Predefined MKV tag to trigger the notification for the fragment
| + Simple
| + Name: AWS_KINESISVIDEO_NOTIFICATION
| + String
| // OPTIONAL: Key value pairs that will be sent as part of the Notification payload
| + Simple
| + Name: CUSTOM_KEY_1 // Max 128 bytes
```

### Amazon Kinesis Video Streams Developer Guide MKV Tag Limits

```
| + String: CUSTOM_VALUE_1 // Max 256 bytes
| + Simple
| + Name: CUSTOM_KEY_2 // Max 128 bytes
| + String: CUSTOM_VALUE_2 // Max 256 bytes
```

### **MKV Tag Limits**

The following table lists the limitations associated with the metadata tags. If the metadata tag limit is adjustable, you can request an increase through your account manager.

Limit	Max value	Adjustable
Optional metadata Key length	128	no
Optional metadata Value length	256	no
Max number of optional metadata	10	yes

### **Amazon SNS Topic Payload**

Any notification initiated through the previous workflow will deliver the Amazon SNS topic payload, as shown in the following example. This example is an Amazon SNS message that occurs after consuming notification data from an Amazon Simple Queue Service (Amazon SQS) queue.

}

### Viewing your Amazon SNS Messages

You cannot read messages directly from an Amazon SNS topic, because there is no API for doing so. To view the messages, subscribe an SQS queue to the SNS topic, or choose any other Amazon SNS supported destination. However, the most efficient option for viewing messages is to use Amazon SQS.

#### To view your Amazon SNS messages using Amazon SQS

- 1. Create an Amazon SQS queue.
- 2. From the AWS Management Console, open the Amazon SNS topic set as a destination under NotificationConfiguration.
- Choose Create Subscription, and then choose the Amazon SQS queue created in the first step.
- Run a PutMedia session with the Notification configuration enabled and with the Notification MKV tags added to the fragments.
- 5. Choose the Amazon SQS queue in the Amazon SQS console, and then select **Send and receive messages** for the Amazon SQS queue.
- 6. Poll for messages. This command should show all notifications generated by the PutMedia session. For information about polling, see Amazon SQS short and long polling.

# Security in Amazon Kinesis Video Streams

Cloud security at AWS is the highest priority. As an AWS customer, you will benefit from a data center and network architecture built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between AWS and you. The shared responsibility model describes this as security *of* the cloud and security *in* the cloud:

- Security of the cloud AWS is responsible for protecting the infrastructure that runs AWS services
  in the AWS Cloud. AWS also provides you with services that you can use securely. The effectiveness
  of our security is regularly tested and verified by third-party auditors as part of the AWS compliance
  programs. To learn about the compliance programs that apply to Kinesis Video Streams, see AWS
  Services in Scope by Compliance Program.
- **Security in the cloud** Your responsibility is determined by the AWS service that you use. You are also responsible for other factors including the sensitivity of your data, your organization's requirements, and applicable laws and regulations.

This documentation helps you understand how to apply the shared responsibility model when using Kinesis Video Streams. The following topics show you how to configure Kinesis Video Streams to meet your security and compliance objectives. You'll also learn how to use other AWS services that can help you to monitor and secure your Kinesis Video Streams resources.

#### **Topics**

- Data Protection in Kinesis Video Streams (p. 37)
- Controlling Access to Kinesis Video Streams Resources Using IAM (p. 40)
- Controlling Access to Kinesis Video Streams Resources Using AWS IoT (p. 44)
- Monitoring Amazon Kinesis Video Streams (p. 50)
- Compliance Validation for Amazon Kinesis Video Streams (p. 50)
- Resilience in Amazon Kinesis Video Streams (p. 51)
- Infrastructure Security in Kinesis Video Streams (p. 51)
- Security Best Practices for Kinesis Video Streams (p. 51)

### Data Protection in Kinesis Video Streams

Server-side encryption using AWS Key Management Service (AWS KMS) keys makes it easier for you to meet strict data management requirements by encrypting your data at rest in Amazon Kinesis Video Streams.

#### **Topics**

- What Is Server-Side Encryption for Kinesis Video Streams? (p. 38)
- Costs, Regions, and Performance Considerations (p. 38)
- How Do I Get Started with Server-Side Encryption? (p. 38)
- Creating and Using User-Generated AWS KMS Master Keys (p. 39)
- Permissions to Use User-Generated AWS KMS Master Keys (p. 39)

## What Is Server-Side Encryption for Kinesis Video Streams?

Server-side encryption is a feature in Kinesis Video Streams that automatically encrypts data before it's at rest by using an AWS KMS customer master key (CMK) that you specify. Data is encrypted before it is written to the Kinesis Video Streams stream storage layer, and it is decrypted after it is retrieved from storage. As a result, your data is always encrypted at rest within the Kinesis Video Streams service.

With server-side encryption, your Kinesis video stream producers and consumers don't need to manage master keys or cryptographic operations. If data retention is enabled, your data is automatically encrypted as it enters and leaves Kinesis Video Streams, so your data at rest is encrypted. AWS KMS provides all the master keys that are used by the server-side encryption feature. AWS KMS makes it easier to use a CMK for Kinesis Video Streams that is managed by AWS, a user-specified AWS KMS CMK, or a master key imported into the AWS KMS service.

### Costs, Regions, and Performance Considerations

When you apply server-side encryption, you are subject to AWS KMS API usage and key costs. Unlike custom AWS KMS master keys, the (Default) aws/kinesis-video customer master key (CMK) is offered free of charge. However, you still must pay for the API usage costs that Kinesis Video Streams incurs on your behalf.

API usage costs apply for every CMK, including custom ones. The KMS costs scale with the number of user credentials that you use on your data producers and consumers because each user credential requires a unique API call to AWS KMS.

The following describes the costs by resource:

#### **Keys**

- The CMK for Kinesis Video Streams that's managed by AWS (alias = aws/kinesis-video) is free.
- User-generated AWS KMS keys are subject to AWS KMS key costs. For more information, see AWS Key Management Service Pricing.

### AWS KMS API Usage

API requests to generate new data encryption keys or to retrieve existing encryption keys increase as traffic increases, and are subject to AWS KMS usage costs. For more information, see AWS Key Management Service Pricing: Usage.

Kinesis Video Streams generates key requests even when retention is set to 0 (no retention).

### Availability of Server-Side Encryption by Region

Server-side encryption of Kinesis video streams is available in all the AWS Regions where Kinesis Video Streams is available.

### How Do I Get Started with Server-Side Encryption?

Server-side encryption is always enabled on Kinesis video streams. If a user-provided key is not specified when the stream is created, the default key (provided by Kinesis Video Streams) is used.

A user-provided AWS KMS master key must be assigned to a Kinesis video stream when it is created. You can't later assign a different key to a stream using the UpdateStream API.

You can assign a user-provided AWS KMS master key to a Kinesis video stream in two ways:

- When creating a Kinesis video stream in the AWS Management Console, specify the AWS KMS master key in the **Encryption** tab on the **Create a new video stream** page.
- When creating a Kinesis video stream using the CreateStream API, specify the key ID in the KmsKeyId parameter.

### Creating and Using User-Generated AWS KMS Master Keys

This section describes how to create and use your own AWS KMS master keys instead of using the master key administered by Amazon Kinesis Video Streams.

### Creating User-Generated AWS KMS Master Keys

For information about how to create your own master keys, see <u>Creating Keys</u> in the <u>AWS Key Management Service Developer Guide</u>. After you create keys for your account, the Kinesis Video Streams service returns these keys in the <u>KMS master key</u> list.

### Using User-Generated AWS KMS Master Keys

After the correct permissions are applied to your consumers, producers, and administrators, you can use custom AWS KMS master keys in your own AWS account or another AWS account. All AWS KMS master keys in your account appear in the **KMS Master Key** list on the console.

To use custom AWS KMS master keys that are located in another account, you must have permissions to use those keys. You must also create the stream using the CreateStream API. You can't use AWS KMS master keys from different accounts in streams created in the console.

#### Note

The AWS KMS key is not accessed until the PutMedia or GetMedia operation is executed. This has the following results:

- If the key you specify doesn't exist, the CreateStream operation succeeds, but PutMedia and GetMedia operations on the stream fail.
- If you use the provided master key (aws/kinesis-video), the key is not present in your account until the first PutMedia or GetMedia operation is performed.

### Permissions to Use User-Generated AWS KMS Master Keys

Before you can use server-side encryption with a user-generated AWS KMS master key, you must configure AWS KMS key policies to allow encryption of streams and encryption and decryption of stream records. For examples and more information about AWS KMS permissions, see AWS KMS API Permissions: Actions and Resources Reference.

#### Note

The use of the default service key for encryption does not require application of custom IAM permissions.

Before you use user-generated AWS KMS master keys, ensure that your Kinesis video stream producers and consumers (IAM principals) are users in the AWS KMS master key policy. Otherwise, writes and reads from a stream will fail, which could ultimately result in data loss, delayed processing, or hung applications. You can manage permissions for AWS KMS keys using IAM policies. For more information, see Using IAM Policies with AWS KMS.

### **Example Producer Permissions**

Your Kinesis video stream producers must have the kms: GenerateDataKey permission:

### **Example Consumer Permissions**

Your Kinesis video stream consumers must have the kms: Decrypt permission:

### Controlling Access to Kinesis Video Streams Resources Using IAM

By using AWS Identity and Access Management (IAM) with Amazon Kinesis Video Streams, you can control whether users in your organization can perform a task using specific Kinesis Video Streams API operations and whether they can use specific AWS resources.

For more information about IAM, see the following:

- AWS Identity and Access Management (IAM)
- Getting started
- IAM User Guide

#### **Contents**

- Policy Syntax (p. 41)
- Actions for Kinesis Video Streams (p. 41)
- Amazon Resource Names (ARNs) for Kinesis Video Streams (p. 42)
- Granting Other IAM Accounts Access to a Kinesis Video Stream (p. 42)
- Example Policies for Kinesis Video Streams (p. 43)

### **Policy Syntax**

An IAM policy is a JSON document that consists of one or more statements. Each statement is structured as follows:

```
{
    "Statement":[{
        "Effect":"effect",
        "Action":"action",
        "Resource":"arn",
        "Condition":{
            "condition":{
            "key":"value"
            }
        }
    }
}
```

There are various elements that make up a statement:

- Effect: The effect can be Allow or Deny. By default, IAM users don't have permission to use resources and API actions, so all requests are denied. An explicit allow overrides the default. An explicit deny overrides any allows.
- Action: The action is the specific API action for which you are granting or denying permission.
- **Resource**: The resource that's affected by the action. To specify a resource in the statement, you need to use its Amazon Resource Name (ARN).
- Condition: Conditions are optional. They can be used to control when your policy is in effect.

As you create and manage IAM policies, you might want to use the IAM Policy Generator and the IAM Policy Simulator.

### **Actions for Kinesis Video Streams**

In an IAM policy statement, you can specify any API action from any service that supports IAM. For Kinesis Video Streams, use the following prefix with the name of the API action: kinesisvideo: For example: kinesisvideo: CreateStream, kinesisvideo: ListStreams, and kinesisvideo: DescribeStream.

To specify multiple actions in a single statement, separate them with commas as follows:

#### Amazon Kinesis Video Streams Developer Guide Amazon Resource Names (ARNs) for Kinesis Video Streams

```
"Action": ["kinesisvideo:action1", "kinesisvideo:action2"]
```

You can also specify multiple actions using wildcards. For example, you can specify all actions whose name begins with the word "Get" as follows:

```
"Action": "kinesisvideo:Get*"
```

To specify all Kinesis Video Streams operations, use the asterisk (\*) wildcard as follows:

```
"Action": "kinesisvideo:*"
```

For the complete list of Kinesis Video Streams API actions, see the Kinesis Video Streams API reference.

## Amazon Resource Names (ARNs) for Kinesis Video Streams

Each IAM policy statement applies to the resources that you specify using their ARNs.

Use the following ARN resource format for Kinesis Video Streams:

```
arn:aws:kinesisvideo:region:account-id:stream/stream-name/code
```

For example:

```
"Resource": arn:aws:kinesisvideo::*:111122223333:stream/my-stream/0123456789012
```

You can get the ARN of a stream using DescribeStream.

## Granting Other IAM Accounts Access to a Kinesis Video Stream

You might need to grant permission to other IAM accounts to perform operations on Kinesis video streams. The following overview describes the general steps to grant access to video streams across accounts:

- 1. Get the 12-digit account ID of the account that you want to grant permissions to perform operations on your stream (for example, 11111111111).
- 2. Create a managed policy on the account that owns the stream that allows the level of access that you want to grant. For example policies for Kinesis Video Streams resources, see Example Policies (p. 43) in the next section.
- 3. Create a role, specifying the account to which you are granting permissions, and attach the policy that you created in the previous step.
- 4. Create a managed policy that allows the AssumeRole action on the role you created in the previous step. For example, the role might look like the following:

```
{
  "Version": "2012-10-17",
  "Statement": {
    "Effect": "Allow",
    "Action": "sts:AssumeRole",
    "Resource": "arn:aws:iam::123456789012:role/CustomRole"
```

```
}
```

For step-by-step instructions on granting cross-account access, see Delegate Access Across AWS Accounts Using IAM Roles.

### **Example Policies for Kinesis Video Streams**

The following example policies demonstrate how you can control user access to your Kinesis video streams.

#### Example 1: Allow users to get data from any Kinesis video stream

This policy allows a user or group to perform the DescribeStream, GetDataEndpoint, GetMedia, ListStreams, and ListTagsForStream operations on any Kinesis video stream. This policy is appropriate for users who can get data from any video stream.

#### Example 2: Allow a user to create a Kinesis video stream and write data to it

This policy allows a user or group to perform the CreateStream and PutMedia operations. This policy is appropriate for a security camera that can create a video stream and send data to it.

#### Example 3: Allow a user full access to all Kinesis Video Streams resources

This policy allows a user or group to perform any Kinesis Video Streams operation on any resource. This policy is appropriate for administrators.

```
{
    "Version": "2012-10-17",
    "Statement": [
```

#### Amazon Kinesis Video Streams Developer Guide Controlling Access to Kinesis Video Streams Resources Using AWS IoT

```
{
    "Effect": "Allow",
    "Action": "kinesisvideo:*",
    "Resource": "*"
  }
]
}
```

#### Example 4: Allow a user to write data to a specific Kinesis video stream

This policy allows a user or group to write data to a specific video stream. This policy is appropriate for a device that can send data to a single stream.

### Controlling Access to Kinesis Video Streams Resources Using AWS IoT

This section describes how to enable a device (for example, a camera) to send audio/video data to one particular Kinesis video stream only. You can do this by using the AWS IoT credentials provider and an AWS Identity and Access Management (IAM) role.

Devices can use X.509 certificates to connect to AWS IoT using TLS mutual authentication protocols. Other AWS services (for example, Kinesis Video Streams) do not support certificate-based authentication, but they can be called using AWS credentials in AWS Signature Version 4 format. The Signature Version 4 algorithm normally requires the caller to have an access key ID and a secret access key. AWS IoT has a credentials provider that allows you to use the built-in X.509 certificate as the unique device identity to authenticate AWS requests (for example, requests to Kinesis Video Streams). This eliminates the need to store an access key ID and a secret access key on your device.

The credentials provider authenticates a client (in this case, a Kinesis Video Streams SDK that is running on the camera from which you want to send data to a video stream) using an X.509 certificate and issues a temporary, limited-privilege security token. The token can be used to sign and authenticate any AWS request (in this case, a call to the Kinesis Video Streams). For more information, see Authorizing Direct Calls to AWS Services.

This way of authenticating your camera's requests to Kinesis Video Streams requires you to create and configure an IAM role and attach appropriate IAM policies to the role so that the IoT credentials provider can assume the role on your behalf.

For more information about AWS IoT, see AWS IoT Core Documentation. For more information about IAM, see AWS Identity and Access Management (IAM).

#### **Topics**

- IoT ThingName as Stream Name (p. 45)
- IoT CertificateId as Stream Name (p. 49)

### IoT ThingName as Stream Name

#### **Topics**

- Step 1: Create an IoT Thing Type and an IoT Thing (p. 45)
- Step 2: Create an IAM Role to be Assumed by IoT (p. 45)
- Step 3: Create and Configure the X.509 Certificate (p. 47)
- Step 4: Test the IoT Credentials with Your Kinesis Video Stream (p. 48)
- Step 5: Deploying IoT Certificates and Credentials on Your Camera's File System and Streaming Data to Your Video Stream (p. 48)

### Step 1: Create an IoT Thing Type and an IoT Thing

In IoT, a thing is a representation of a specific device or logical entity. In this case, an IoT thing represents your Kinesis video stream for which you want to configure resource-level access control. In order to create a thing, first, you must create an IoT thing type. IoT thing types enable you to store description and configuration information that is common to all things associated with the same thing type.

1. The following example command creates a thing type kvs\_example\_camera:

```
aws --profile default iot create-thing-type --thing-type-name kvs_example_camera >
iot-thing-type.json
```

2. And this example command creates the kvs\_example\_camera\_stream thing of the kvs\_example\_camera thing type:

```
aws --profile default iot create-thing --thing-name kvs_example_camera_stream --thing-
type-name kvs_example_camera > iot-thing.json
```

### Step 2: Create an IAM Role to be Assumed by IoT

IAM roles are similar to IAM users, in that a role is an AWS identity with permission policies that determine what the identity can and cannot do in AWS. A role can be assumed by anyone who needs it. When you assume a role, it provides you with temporary security credentials for your role session.

The role that you create in this step can be assumed by IoT in order to obtain temporary credentials from the security token service (STS) when performing credential authorization requests from the client. In this case, the client is the Kinesis Video Streams SDK that is running on your camera.

Perform the following steps to create and configure this IAM role:

1. Create an IAM role.

The following example command creates an IAM role called KVSCameraCertificateBasedIAMRole:

```
\hbox{aws --profile default iam create-role --role-name KVSCameraCertificateBasedIAMRole --assume-role-policy-document 'file://iam-policy-document.json' > iam-role.json}
```

You can use the following trust policy JSON for the iam-policy-document.json:

Next, you must attach a permissions policy to the IAM role you created above. This permissions
policy allows selective access control (a subset of supported operations) for an AWS resource. In this
case, the AWS resource is the video stream to which you want your camera to send data. In other
words, once all the configuration steps are complete, this camera will be able to send data only to
this video stream.

```
aws --profile default iam put-role-policy --role-name KVSCameraCertificateBasedIAMRole --policy-name KVSCameraIAMPolicy --policy-document 'file://iam-permission-document.json'
```

You can use the following IAM policy JSON for the iam-permission-document.json:

Note that this policy authorizes the specified actions only on a video stream (AWS resource) that is specified by the placeholder (\${credentials-iot:ThingName}). This placeholder takes on the value of the IoT thing attribute ThingName when the IoT credentials provider sends the video stream name in the request.

3. Next, create a Role Alias for your IAM Role. Role alias is an alternate data model that points to the IAM role. An IoT credentials provider request must include a role-alias to indicate which IAM role to assume in order to obtain the temporary credentials from the STS.

The following sample command creates a role alias called KvsCameraIoTRoleAlias,

#### Amazon Kinesis Video Streams Developer Guide IoT ThingName as Stream Name

```
aws --profile default iot create-role-alias --role-alias KvsCameraIoTRoleAlias --role-
arn $(jq --raw-output '.Role.Arn' iam-role.json) --credential-duration-seconds 3600 >
iot-role-alias.json
```

4. Now you can create the policy that will enable IoT to assume role with the certificate (once it is attached) using the role alias.

The following sample command creates a policy for IoT called KvsCameraIoTPolicy.

```
aws --profile default iot create-policy --policy-name KvsCameraIoTPolicy --policy-
document 'file://iot-policy-document.json'
```

You can use the following command to create the iot-policy-document.json document JSON:

### Step 3: Create and Configure the X.509 Certificate

Communication between a device (your video stream) and AWS IoT is protected through the use of X.509 certificates.

1. Create the certificate to which you must attach the policy for IoT that you created above.

```
aws --profile default iot create-keys-and-certificate --set-as-active --certificate-pem-outfile certificate.pem --public-key-outfile public.pem.key --private-key-outfile private.pem.key > certificate
```

Attach the policy for IoT (KvsCameraIoTPolicy created above) to this certificate.

```
aws --profile default iot attach-policy --policy-name KvsCameraIoTPolicy --target $(jq
--raw-output '.certificateArn' certificate)
```

#### Amazon Kinesis Video Streams Developer Guide IoT ThingName as Stream Name

Attach your IoT thing (kvs\_example\_camera\_stream) to the certificate you just created:

```
aws --profile default iot attach-thing-principal --thing-name
kvs_example_camera_stream --principal $(jq --raw-output '.certificateArn' certificate)
```

4. In order to authorize requests through the IoT credentials provider, you need the IoT credentials endpoint which is unique to your AWS account ID. You can use the following command to get the IoT credentials endpoint.

```
aws --profile default iot describe-endpoint --endpoint-type iot:CredentialProvider --
output text > iot-credential-provider.txt
```

5. In addition to the X.509 cerficiate created above, you must also have a CA certificate to establish trust with the back-end service through TLS. You can get the CA certificate using the following command:

```
curl --silent 'https://www.amazontrust.com/repository/SFSRootCAG2.pem' --output
  cacert.pem
```

### Step 4: Test the IoT Credentials with Your Kinesis Video Stream

Now you can test the IoT credentials that you've set up so far.

1. First, create a Kinesis video stream that you want to test this configuration with.

#### **Important**

Create a video stream with a name that is identical to the IoT thing name that you created in the previous step (kvs\_example\_camera\_stream).

```
aws kinesisvideo create-stream --data-retention-in-hours 24 --stream-name kvs_example_camera_stream
```

2. Next, call the IoT credentials provider to get the temporary credentials:

```
curl --silent -H "x-amzn-iot-thingname:kvs_example_camera_stream" --cert
  certificate.pem --key private.pem.key https://IOT_GET_CREDENTIAL_ENDPOINT/role-
aliases/KvsCameraIoTRoleAlias/credentials --cacert ./cacert.pem > token.json
```

#### Note

You can use the following command to get the IOT\_GET\_CREDENTIAL\_ENDPOINT:

```
IOT_GET_CREDENTIAL_ENDPOINT=`cat iot-credential-provider.txt`
```

The output JSON contains the accessKey, secretKey, and the sessionToken which you can use it for accessing the Kinesis Video Streams.

3. Now, for your test, you can use these credentials to invoke the Kinesis Video Streams DescribeStream API for the sample kvs\_example\_camera\_stream video stream.

```
AWS_ACCESS_KEY_ID=$(jq --raw-output '.credentials.accessKeyId' token.json)
AWS_SECRET_ACCESS_KEY=$(jq --raw-output '.credentials.secretAccessKey' token.json)
AWS_SESSION_TOKEN=$(jq --raw-output '.credentials.sessionToken' token.json) aws
kinesisvideo describe-stream --stream-name kvs_example_camera_stream
```

## Step 5: Deploying IoT Certificates and Credentials on Your Camera's File System and Streaming Data to Your Video Stream

#### Note

The steps in this section describe sending media to a Kinesis video stream from a camera that is using the C++ Producer Library.

- Copy the X.509 certificate, the private key, and the CA certificate generated in the steps above to your camera's file system. You need to specify the paths for where these files are stored, the role alias name, and the IOT credentials endpoint for running the gst-launch-1.0 command or your sample application.
- 2. The following sample command uses IoT certificate authorization to send video to Kinesis Video Streams:

```
$ gst-launch-1.0 rtspsrc location=rtsp://YourCameraRtspUrl short-header=TRUE ! rtph264depay ! video/x-h264, format=avc,alignment=au ! h264parse ! kvssink stream-name="kvs_example_camera_stream" iot-certificate="iot-certificate,endpoint=iot-credential-endpoint-host-name,cert-path=/path/to/certificate.pem,key-path=/path/to/private.pem.key,ca-path=/path/to/cacert.pem,role-aliases=KvsCameraIoTRoleAlias"
```

### IoT CertificateId as Stream Name

If you want to represent your device (for example, your camera) through an IoT thing but authorize a different stream name, then you can use the IoT certifiacateId attribute as your stream name and provide Kinesis Video Streams permissions on the stream using IoT. The steps for accomplishing this are similar to the ones outlined above, with a few changes.

Modify the permissions policy to your IAM role (iam-permission-document.json) as follows:

#### Amazon Kinesis Video Streams Developer Guide Monitoring

```
}
```

#### Note

The resource ARN uses certificate ID as the placeholder for the stream name. The IAM permission will work when you use the certificate id as the stream name. Get the certificate ID from the certificate so that we can use that as stream name in the following describe stream api call.

```
export CERTIFICATE_ID=`cat certificate | jq --raw-output '.certificateId'jq --
raw-output '.certificateId'`
```

Verify this change using the Kinesis Video Streams describe-stream CLI command:

```
AWS_ACCESS_KEY_ID=$(jq --raw-output '.credentials.accessKeyId' token.json)
AWS_SECRET_ACCESS_KEY=$(jq --raw-output '.credentials.secretAccessKey' token.json)
AWS_SESSION_TOKEN=$(jq --raw-output '.credentials.sessionToken' token.json) aws
kinesisvideo describe-stream --stream-name ${CERTIFICATE_ID}
```

 Pass the certificated to the IoT credentials provider in the sample application in the Kinesis Video Streams C++ SDK:

#### Note

Note that you are passing the thingname to the IoT credentials provider. You can use getenv to pass the thingname to the demo application similar to passing the other IoT attributes. Use the certificate ID as the stream name in the command line parameters when you are running the sample application.

### Monitoring Amazon Kinesis Video Streams

Kinesis Video Streams provides monitoring functionality for your delivery streams. For more information, see *Monitoring* (p. 153).

## Compliance Validation for Amazon Kinesis Video Streams

Third-party auditors assess the security and compliance of Amazon Kinesis Video Streams as part of multiple AWS compliance programs. These include SOC, PCI, HIPAA, and others.

#### Amazon Kinesis Video Streams Developer Guide Resilience

For a list of AWS services in scope of specific compliance programs, see AWS Services in Scope by Compliance Program. For general information, see AWS Compliance Programs.

You can download third-party audit reports using AWS Artifact. For more information, see Downloading Reports in AWS Artifact.

Your compliance responsibility when using Kinesis Video Streams is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. If your use of Kinesis Video Streams is subject to compliance with standards such as HIPAA or PCI, AWS provides resources to help:

- Security and Compliance Quick Start Guides These deployment guides discuss architectural
  considerations and provide steps for deploying security- and compliance-focused baseline
  environments on AWS.
- Architecting for HIPAA Security and Compliance Whitepaper This whitepaper describes how companies can use AWS to create HIPAA-compliant applications.
- AWS Compliance Resources This collection of workbooks and guides that might apply to your industry and location
- AWS Config This AWS service that assesses how well your resource configurations comply with internal practices, industry guidelines, and regulations
- AWS Security Hub This AWS service provides a comprehensive view of your security state within AWS that helps you check your compliance with security industry standards and best practices

### Resilience in Amazon Kinesis Video Streams

The AWS global infrastructure is built around AWS Regions and Availability Zones. AWS Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between Availability Zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

For more information about AWS Regions and Availability Zones, see AWS Global Infrastructure.

### Infrastructure Security in Kinesis Video Streams

As a managed service, Amazon Kinesis Video Streams is protected by the AWS global network security procedures that are described in the Amazon Web Services: Overview of Security Processes whitepaper.

You use AWS published API calls to access Kinesis Video Streams through the network. Clients must support Transport Layer Security (TLS) 1.2 or later. Clients must also support cipher suites with perfect forward secrecy (PFS) such as Ephemeral Diffie-Hellman (DHE) or Elliptic Curve Ephemeral Diffie-Hellman (ECDHE). Most modern systems such as Java 7 and later support these modes.

Additionally, requests must be signed by using an access key ID and a secret access key that is associated with an IAM principal. Or you can use the AWS Security Token Service (AWS STS) to generate temporary security credentials to sign requests.

### Security Best Practices for Kinesis Video Streams

Amazon Kinesis Video Streams provides a number of security features to consider as you develop and implement your own security policies. The following best practices are general guidelines and

don't represent a complete security solution. Because these best practices might not be appropriate or sufficient for your environment, treat them as helpful considerations rather than prescriptions.

For security best practices for your remote devices, see Security Best Practices for Device Agents.

### Implement least privilege access

When granting permissions, you decide who is getting what permissions to which Kinesis Video Streams resources. You enable specific actions that you want to allow on those resources. Therefore you should grant only the permissions that are required to perform a task. Implementing least privilege access is fundamental in reducing security risk and the impact that could result from errors or malicious intent.

For example, a producer that sends data to Kinesis Video Streams requires only PutMedia, GetStreamingEndpoint, and DescribeStream. Do not grant producer applications permissions for all actions (\*), or for other actions such as GetMedia.

For more information, see What Is Least Privilege & Why Do You Need It?

### Use IAM roles

Producer and client applications must have valid credentials to access Kinesis video streams. You should not store AWS credentials directly in a client application or in an Amazon S3 bucket. These are long-term credentials that are not automatically rotated and could have a significant business impact if they are compromised.

Instead, you should use an IAM role to manage temporary credentials for your producer and client applications to access Kinesis video streams. When you use a role, you don't have to use long-term credentials (such as a user name and password or access keys) to access other resources.

For more information, see the following topics in the IAM User Guide:

- IAM Roles
- Common Scenarios for Roles: Users, Applications, and Services

### Use CloudTrail to Monitor API Calls

Kinesis Video Streams is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Kinesis Video Streams.

Using the information collected by CloudTrail, you can determine the request that was made to Kinesis Video Streams, the IP address from which the request was made, who made the request, when it was made, and additional details.

For more information, see the section called "Logging API Calls with CloudTrail" (p. 164).

## Kinesis Video Streams Producer Libraries

The Amazon Kinesis Video Streams Producer libraries are a set of libraries that are part of the Kinesis Video Streams Producer SDK. The client uses the libraries and SDK to build the on-device application for securely connecting to Kinesis Video Streams, and streaming video and other media data to view in the console or client applications in real time.

Media data can be streamed in the following ways:

- In real time
- · After buffering it for a few seconds
- · After the media uploads

After you create a Kinesis Video Streams stream, you can start sending data to it. You can use the SDK to create application code that extracts the video data, known as frames, from the media source and uploads it to Kinesis Video Streams. These applications are also referred to as *producer* applications.

The Producer libraries contain the following components:

- Kinesis Video Streams Producer Client (p. 53)
- Kinesis Video Streams Producer Library (p. 54)

### Kinesis Video Streams Producer Client

The Kinesis Video Streams Producer Client includes a single KinesisVideoClient class. This class manages media sources, receives data from the sources, and manages the stream lifecycle as data flows from a media source to Kinesis Video Streams. Furthermore, it provides a MediaSource interface for defining the interaction between Kinesis Video Streams and your proprietary hardware and software.

A media source can be almost anything. For example, you can use a camera media source or a microphone media source. Media sources are not limited to audio and video sources only. For example, data logs might be text files, but they can still be sent as a stream of data. You could also have multiple cameras on your phone that stream data simultaneously.

To get data from any of these sources, you can implement the MediaSource interface. This interface enables additional scenarios for which we don't provide built-in support. For example, you might choose to send the following to Kinesis Video Streams:

- A diagnostic data stream (for example, application logs and events)
- · Data from infrared cameras, RADARs, or depth cameras

Kinesis Video Streams does not provide built-in implementations for media-producing devices such as cameras. To extract data from these devices, you must implement code, thus creating your own custom media source implementation. You can then explicitly register your custom media sources with KinesisVideoClient, which uploads the data to Kinesis Video Streams.

The Kinesis Video Streams Producer Client is available for Java and Android applications. For more information, see Using the Java Producer Library (p. 54) and Using the Android Producer Library (p. 58).

### Kinesis Video Streams Producer Library

The Kinesis Video Streams Producer Library is contained within the Kinesis Video Streams Producer Client. The library is also available to use directly for those who want a deeper integration with Kinesis Video Streams. It enables integration from devices with proprietary operating systems, network stacks, or limited on-device resources.

The Kinesis Video Streams Producer Library implements the state machine for streaming to Kinesis Video Streams. It provides callback hooks, which require that you provide your own transport implementation and explicitly handle each message going to and from the service.

You might choose to use the Kinesis Video Streams Producer Library directly for the following reasons:

- The device on which you want to run the application doesn't have a Java virtual machine.
- You want to write application code in languages other than Java.
- You might have Java on the device, but you want to reduce the amount of overhead in your code and limit it to the bare minimum level of abstraction, due to limitations such as memory and processing power.

Currently, the Kinesis Video Streams Producer Library is available for Android, C, C++ and Java applications. For more information, see the supported languages in the following *Related Topics*.

### **Related Topics**

Using the Java Producer Library (p. 54)

Using the Android Producer Library (p. 58)

Using the C++ Producer Library (p. 63)

Using the C Producer Library (p. 72)

### Using the Java Producer Library

Amazon Kinesis Video Streams provides the Java Producer Library, which you can use to write application code, with minimal configuration, to send media data from a device to a Kinesis video stream.

You must perform the following steps to integrate your code with Kinesis Video Streams, so that your application can start streaming data to your Kinesis video stream:

- 1. Create an instance of the KinesisVideoClient object.
- Create a MediaSource object by providing media source information. For example, when creating a camera media source, you provide information such as identifying the camera and specifying the encoding the camera uses.

When you want to start streaming, you must create a custom media source.

3. Register the media source with KinesisVideoClient.

After you register the media source with KinesisVideoClient, whenever the data becomes available with the media source, it calls KinesisVideoClient with the data.

### Procedure: Using the Java Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams Java Producer Client in your Java application to send data to your Kinesis video stream.

These steps don't require you to have a media source, such as a camera or microphone. Instead, for testing purposes, the code generates sample frames that consist of a series of bytes. You can use the same coding pattern when you send media data from real sources such as cameras and microphones.

The procedure includes the following steps:

- Download and Configure the Code
- · Write and Examine the Code
- · Run and Verify the Code

### **Prerequisites**

• In the sample code, you provide credentials by specifying a profile that you set up in your AWS credentials profile file. If you haven't already done so, first set up your credentials profile. For more information, see Set up AWS Credentials and Region for Development in the AWS SDK for Java.

#### Note

The Java example uses a SystemPropertiesCredentialsProvider object to obtain your credentials. The provider retrieves these credentials from the aws.accessKeyId and aws.secretKey Java system properties. You set these system properties in your Java development environment. For information about how to set Java system properties, see the documentation for your particular integrated development environment (IDE).

- Your NativeLibraryPath must contain your KinesisVideoProducerJNI file, available at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp. The file name extension for this file depends on your operating system:
  - KinesisVideoProducerJNI.so for Linux
  - KinesisVideoProducerJNI.dylib for macOS
  - KinesisVideoProducerJNI.dll for Windows

#### Note

Pre-built libraries for macOS, Ubuntu, Windows, and Raspbian are available in src/main/resources/lib at https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java.git. For other environments, compile the C++ Producer Library (p. 63).

## Step 1: Download and Configure the Java Producer Library Code

In this section of the Java Producer Library procedure, you download the Java example code, import the project into your Java IDE, and configure the library locations.

For prerequisites and other details about this example, see Using the Java Producer Library.

1. Create a directory, and then clone the example source code from the GitHub repository.

```
$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java
```

2. Open the Java integrated development environment (IDE) that you use (for example, Eclipse or JetBrains IntelliJ IDEA), and import the Apache Maven project that you downloaded:

- In Intellij IDEA: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.
- In Eclipse: Choose File, Import, Maven, Existing Maven Projects. Then navigate to the kinesis-video-java-demo directory.

For more information, see the documentation for your IDE.

The Java example code uses the current AWS credentials. To use a different credentials profile, locate the following code in DemoAppMain.java:

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
    .createKinesisVideoClient(
        Regions.US_WEST_2,
        AuthHelper.getSystemPropertiesCredentialsProvider());
```

Change the code to the following:

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
    .createKinesisVideoClient(
    Regions.US_WEST_2,
    new ProfileCredentialsProvider("credentials-profile-name"));
```

For more information, see ProfileCredentialsProvider in the AWS SDK for Java reference.

### **Next Step**

the section called "Step 2: Write and Examine the Code" (p. 56)

### Step 2: Write and Examine the Code

In this section of the Java Producer Library procedure, you write and examine the Java example code you downloaded in the previous section.

The Java test application (DemoAppMain) shows the following coding pattern:

- Create an instance of KinesisVideoClient.
- Create an instance of MediaSource.
- Register the MediaSource with the client.
- Start streaming. That is, start the MediaSource, and it starts sending data to the client.

The following sections provide details.

### Creating an Instance of KinesisVideoClient

You create the KinesisVideoClient object by calling the createKinesisVideoClient operation.

```
final KinesisVideoClient kinesisVideoClient = KinesisVideoJavaClientFactory
    .createKinesisVideoClient(
        Regions.US_WEST_2,
        AuthHelper.getSystemPropertiesCredentialsProvider());
```

#### Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

For KinesisVideoClient to make network calls, it needs credentials to authenticate. You pass in an instance of SystemPropertiesCredentialsProvider, which reads AWSCredentials for the default profile in the credentials file:

```
[default]
aws_access_key_id = ABCDEFGHIJKLMOPQRSTU
aws_secret_access_key = AbCd1234EfGh5678IjKl9012Mn0p3456QrSt7890
```

### Creating an Instance of MediaSource

To send bytes to your Kinesis video stream, you need to produce the data. Amazon Kinesis Video Streams provides the MediaSource interface, which represents the data source.

For example, the Kinesis Video Streams Java library provides the ImageFileMediaSource implementation of the MediaSource interface. This class only reads data from a series of media files rather than a Kinesis video stream, but you can use it for testing the code.

final MediaSource bytesMediaSource = createImageFileMediaSource();

### Registering the MediaSource with the Client

Register the media source that you created with the KinesisVideoClient so that it knows about the client (and can then send data to the client).

kinesisVideoClient.registerMediaSource(STREAM\_NAME, bytesMediaSource);

### Starting the Media Source

Start the media source so that it can begin generating data and sending it to the client.

```
bytesMediaSource.start();
```

### **Next Step**

the section called "Step 3: Run and Verify the Code" (p. 57)

### Step 3: Run and Verify the Code

To run the Java test harness for the Java Producer library, do the following.

- 1. Choose **DemoAppMain**.
- 2. Choose Run, Run 'DemoAppMain'.
- 3. Add your credentials to the JVM arguments for the application:
  - For non-temporary AWS credentials: "-Daws.accessKeyId={YourAwsAccessKey} Daws.secretKey={YourAwsSecretKey} -Djava.library.path={NativeLibraryPath}"
  - For temporary AWS credentials: "-Daws.accessKeyId={YourAwsAccessKey} Daws.secretKey={YourAwsSecretKey} -Daws.sessionToken={YourAwsSessionToken}
     -Djava.library.path={NativeLibraryPath}"

- 4. Sign in to the AWS Management Console and open the Kinesis Video Streams console.
  - On the Manage Streams page, choose your stream.
- 5. The sample video will play in the embedded player. You might need to wait a short time (up to ten seconds under typical bandwidth and processor conditions) while the frames accumulate before the video appears.

The code example creates a stream. As the MediaSource in the code starts, it begins sending sample frames to the KinesisVideoClient. The client then sends the data to your Kinesis video stream.

### Using the Android Producer Library

Amazon Kinesis Video Streams provides the Android Producer Library, which you can use to write application code, with minimal configuration, to send media data from an Android device to a Kinesis video stream.

You must perform the following steps to integrate your code with Kinesis Video Streams so that your application can start streaming data to your Kinesis video stream:

- 1. Create an instance of the KinesisVideoClient object.
- 2. Create a MediaSource object by providing media source information. For example, when creating a camera media source, you provide information such as identifying the camera and specifying the encoding the camera uses.

When you want to start streaming, you must create a custom media source.

### Procedure: Using the Android Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams Android Producer Client in your Android application to send data to your Kinesis video stream.

The procedure includes the following steps:

- Download and Configure the Code
- · Examine the Code
- · Run and Verify the Code

### Prerequisites

- We recommend Android Studio for examining, editing, and running the application code. We recommend at least version 3.0.0, released October 2017.
- In the sample code, you provide Amazon Cognito credentials. Follow these procedures to set up an Amazon Cognito user pool and identity pool:

#### To set up a user pool

- 1. Sign in to the Amazon Cognito console.
- 2. Choose Manage your User Pools.
- 3. Choose Create a user pool.
- 4. Type a value for Pool name; for example, <username>\_android\_user\_pool.
- 5. Choose Review defaults.

- Choose Create pool.
- 7. Copy and save the Pool Id value. You will need this value when you configure the example application.
- 8. On the page for your pool, choose **App clients**.
- 9. Choose Add an app client.
- 10. Type a value for App client name; for example, <username>\_android\_app\_client.
- 11. Choose Create app client.
- 12. Choose Show Details, and copy and save the App client ID and App client secret. You will need these values when you configure the example application.

#### To set up an identity pool

- 1. Open the Amazon Cognito console.
- 2. Choose Manage Identity Pools.
- 3. Choose Create new identity pool.
- 4. Type a value for Identity pool name; for example, <username>\_android\_identity\_pool.
- 5. Expand the Authentication providers section. On the Cognito tab, add the values for the User **Pool ID** and **App client ID** from the previous procedure.
- 6. Choose Create pool.
- 7. On the next page, expand the **Show Details** section.
- 8. In the section that has a value for **Role name** that ends in **Auth\_Role**, choose **View Policy** Document.
- 9. Choose **Edit**, and confirm the **Edit Policy** dialog box that appears. Then copy the following JSON and paste it into the editor:

```
{
    "Version": "2012-10-17",
    "Statement": [
      "Effect": "Allow",
      "Action": [
        "cognito-identity: *",
        "kinesisvideo:*"
      "Resource": [
 ]
```

- 10. Choose Allow.
- 11. On the next page, copy and save the **Identity pool ID** value from the **Get AWS Credentials** code snippet. You will need this value when you configure the example application.

### Step 1: Download and Configure the Android **Producer Library Code**

In this section of the Android Producer Library procedure, you download the Android example code and open the project in Android Studio.

1. Create a directory, and then clone the AWS Android SDK from the GitHub repository.

```
$ git clone https://github.com/awslabs/aws-sdk-android-samples
```

- 2. Open Android Studio.
- In the opening screen, choose Open an existing Android Studio project.
- 4. Navigate to the aws-sdk-android-samples/AmazonKinesisVideoDemoApp directory, and choose **OK**.
- 5. Open the AmazonKinesisVideoDemoApp/src/main/res/raw/awsconfiguration.json file.

In the CredentialsProvider node, provide the identity pool ID from the **To set up an identity pool** procedure in the Prerequisites section, and provide your AWS Region (for example, us-west-2).

In the CognitoUserPool node, provide the App client secret, App client ID, and Pool ID from the **To set up a user pool** procedure in the Prerequisites section, and provide your AWS Region (for example, us-west-2).

6. Your awsconfiguration. json file will look similar to the following:

```
"Version": "1.0",
  "CredentialsProvider": {
    "CognitoIdentity": {
      "Default": {
        "PoolId": "us-west-2:01234567-89ab-cdef-0123-456789abcdef",
        "Region": "us-west-2"
      }
    }
  "IdentityManager": {
    "Default": {}
  "CognitoUserPool": {
    "Default": {
      "AppClientSecret": "abcdefghijklmnopqrstuvwxyz0123456789abcdefghijklmno",
      "AppClientId": "0123456789abcdefghijklmnop",
      "PoolId": "us-west-2_qRsTuVwXy",
      "Region": "us-west-2"
    }
 }
}
```

7. Update the AmazonKinesisVideoDemoApp/src/main/java/com/amazonaws/kinesisvideo/demoapp/KinesisVideoDemoApp.java with your region (in the sample below, it's set to US\_WEST\_2):

```
public class KinesisVideoDemoApp extends Application {
   public static final String TAG = KinesisVideoDemoApp.class.getSimpleName();
   public static Regions KINESIS_VIDEO_REGION = Regions.US_WEST_2;
```

For information about AWS Region constants, see Regions.

### **Next Step**

the section called "Step 2: Examine the Code" (p. 61)

### Step 2: Examine the Code

In this section of the Android Producer Library procedure, you examine the example code.

The Android test application (AmazonKinesisVideoDemoApp) shows the following coding pattern:

- Create an instance of KinesisVideoClient.
- Create an instance of MediaSource.
- Start streaming—that is, start the MediaSource, and it starts sending data to the client.

The following sections provide details.

### Creating an Instance of KinesisVideoClient

You create the KinesisVideoClient object by calling the createKinesisVideoClient operation.

For KinesisVideoClient to make network calls, it needs credentials to authenticate. You pass in an instance of AWSCredentialsProvider, which reads your Amazon Cognito credentials from the awsconfiguration.json file that you modified in the previous section.

### Creating an Instance of MediaSource

To send bytes to your Kinesis video stream, you must produce the data. Amazon Kinesis Video Streams provides the MediaSource interface, which represents the data source.

For example, the Kinesis Video Streams Android library provides the AndroidCameraMediaSource implementation of the MediaSource interface. This class reads data from one of the device's cameras.

In the following code example (from the fragment/StreamConfigurationFragment.java file), the configuration for the media source is created:

```
private AndroidCameraMediaSourceConfiguration getCurrentConfiguration() {
return new AndroidCameraMediaSourceConfiguration(
        AndroidCameraMediaSourceConfiguration.builder()
                .withCameraId(mCamerasDropdown.getSelectedItem().getCameraId())
                .withEncodingMimeType(mMimeTypeDropdown.getSelectedItem().getMimeType())
                .withHorizontalResolution(mResolutionDropdown.getSelectedItem().getWidth())
                .withVerticalResolution(mResolutionDropdown.getSelectedItem().getHeight())
                .withCameraFacing(mCamerasDropdown.getSelectedItem().getCameraFacing())
                .withIsEncoderHardwareAccelerated(
                        mCamerasDropdown.getSelectedItem().isEndcoderHardwareAccelerated())
                .withFrameRate(FRAMERATE_20)
                .withRetentionPeriodInHours(RETENTION_PERIOD_48_HOURS)
                .withEncodingBitRate(BITRATE_384_KBPS)
                .withCameraOrientation(-
mCamerasDropdown.getSelectedItem().getCameraOrientation())
 .withNalAdaptationFlags(StreamInfo.NalAdaptationFlags.NAL_ADAPTATION_ANNEXB_CPD_AND_FRAME_NALS)
                .withIsAbsoluteTimecode(false));
}
```

#### Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

In the following code example (from the fragment/StreamingFragment.java file), the media source is created:

mCameraMediaSource = (AndroidCameraMediaSource) mKinesisVideoClient
 .createMediaSource(mStreamName, mConfiguration);

### Starting the Media Source

Start the media source so that it can begin generating data and sending it to the client. The following code example is from the fragment/StreamingFragment.java file:

mCameraMediaSource.start();

### **Next Step**

the section called "Step 3: Run and Verify the Code" (p. 62)

### Step 3: Run and Verify the Code

To run the Android example application for the Android Producer Library, do the following.

- 1. Connect to an Android device.
- 2. Choose Run, Run..., and choose Edit configurations....
- 3. Choose +, Android App. In the Name field, enter AmazonKinesisVideoDemoApp. In the Module pulldown, choose AmazonKinesisVideoDemoApp. Choose OK.
- 4. Choose Run, Run.
- 5. In the Select Deployment Target screen, choose your connected device, and choose OK.
- 6. In the AWSKinesisVideoDemoApp application on the device, choose Create new account.
- 7. Enter values for **USERNAME**, **Password**, **Given name**, **Email address**, and **Phone number**, and then choose **Sign up**.

#### Note

These values have the following constraints:

- Password: Must contain uppercase and lowercase letters, numbers, and special characters. You can change these constraints in your User pool page on the Amazon Cognito console.
- Email address: Must be a valid address so that you can receive a confirmation code.
- Phone number: Must be in the following format: +<Country code><Number>, for example, +12065551212.
- 8. Enter the code you receive by email, and choose Confirm. Choose Ok.
- 9. On the next page, leave the default values, and choose **Stream**.
- 10. Sign in to the AWS Management Console and open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/ in the US West (Oregon) Region.

On the Manage Streams page, choose demo-stream.

11. The streaming video plays in the embedded player. You might need to wait a short time (up to ten seconds under typical bandwidth and processor conditions) while the frames accumulate before the video appears.

#### Note

If the device's screen rotates (for example, from portrait to landscape), the application stops streaming video.

The code example creates a stream. As the MediaSource in the code starts, it begins sending frames from the camera to the KinesisVideoClient. The client then sends the data to a Kinesis video stream named **demo-stream**.

### Using the C++ Producer Library

Amazon Kinesis Video Streams provides the C++ Producer Library, which you can use to write application code to send media data from a device to a Kinesis video stream.

### **Object Model**

The C++ library provides the following objects to manage sending data to a Kinesis video stream:

- KinesisVideoProducer: Contains information about your media source and AWS credentials, and maintains callbacks to report on Kinesis Video Streams events.
- **KinesisVideoStream:** Represents the Kinesis video stream. Contains information about the video stream's parameters, such as name, data retention period, media content type, and so on.

### Putting Media into the Stream

The C++ library provides methods (for example, PutFrame) that you can use to put data into the KinesisVideoStream object. The library then manages the internal state of the data, which can include the following tasks:

- · Performing authentication.
- Watching for network latency. If the latency is too high, the library might choose to drop frames.
- · Tracking status of streaming in progress.

### Callback Interfaces

This layer exposes a set of callback interfaces, which enable it to talk to the application layer. These callback interfaces include the following:

- Service callbacks interface (CallbackProvider): The library invokes events obtained through this interface when it creates a stream, obtains a stream description, deletes a stream, and so on.
- Client-ready state or low storage events interface (ClientCallbackProvider): The library invokes events on this interface when the client is ready, or when it detects that it might run out of available storage or memory.
- Stream events callback interface (StreamCallbackProvider): The library invokes events on this
  interface when stream events occur, such as the stream entering the ready state, dropped frames, or
  stream errors.

Kinesis Video Streams provides default implementations for these interfaces. You can also provide your own custom implementation—for example, if you need custom networking logic or you want to expose a low storage condition to the user interface.

For more information about callbacks in the Producer Libraries, see Producer SDK Callbacks (p. 118).

### Procedure: Using the C++ Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams client and media sources in a C++ application to send data to your Kinesis video stream.

The procedure includes the following steps:

- Step 1: Download and Configure the Code
- Step 2: Write and Examine the Code
- · Step 3: Run and Verify the Code

### **Prerequisites**

• **Credentials:** In the sample code, you provide credentials by specifying a profile that you set up in your AWS credentials profile file. If you haven't already done so, first set up your credentials profile.

For more information, see Set up AWS Credentials and Region for Development.

• Certificate store integration: The Kinesis Video Streams Producer Library must establish trust with the service it calls. This is done through validating the certificate authorities (CAs) in the public certificate store. On Linux-based models, this store is located in the /etc/ssl/ directory.

Download the certificate from the following location to your certificate store:

https://www.amazontrust.com/repository/SFSRootCAG2.pem

- Install the following build dependencies for macOS:
  - Autoconf 2.69 (License GPLv3+/Autoconf: GNU GPL version 3 or later)
  - CMake 3.7 or 3.8
  - Pkq-Config
  - Flex 2.5.35 Apple (flex-31) or later
  - Bison 2.4 (GNU License)
  - Automake 1.15.1 (GNU License)
  - GNU Libtool (Apple Inc. version cctools-898)
  - xCode (macOS) / clang / gcc (xcode-select version 2347)
  - Java Development Kit (JDK) (for Java JNI compilation)
  - Lib-Pkg
- Install the following build dependencies for Ubuntu (responses to version commands are truncated):
  - Install Git: sudo apt-get install git

```
$ git --version
git version 2.14.1
```

Install CMake: sudo apt-get install cmake

```
$ cmake --version
cmake version 3.9.1
```

• Install Libtool: sudo apt-get install libtool

```
2.4.6-2
```

Install libtool-bin: sudo apt-get install libtool-bin

```
$ libtool --version
libtool (GNU libtool) 2.4.6
Written by Gordon Matzigkeit, 1996
```

• Install GNU Automake: sudo apt-get install automake

```
$ automake --version
automake (GNU automake) 1.15
```

• Install GNU Bison: sudo apt-get install bison

```
$ bison -V
bison (GNU Bison) 3.0.4
```

• Install G++: sudo apt-get install g++

```
g++ --version
g++ (Ubuntu 7.2.0-8ubuntu3) 7.2.0
```

• Install curl: sudo apt-get install curl

```
$ curl --version
curl 7.55.1 (x86_64-pc-linux-gnu) libcurl/7.55.1 OpenSSL/1.0.2g zlib/1.2.11
libidn2/2.0.2 libpsl/0.18.0 (+libidn2/2.0.2) librtmp/2.3
```

• Install pkg-config: sudo apt-get install pkg-config

```
$ pkg-config --version
0.29.1
```

Install Flex: sudo apt-get install flex

```
$ flex --version
flex 2.6.1
```

• Install OpenJDK: sudo apt-get install openjdk-8-jdk

```
$ java -version
openjdk version "1.8.0_171"
```

- Set the JAVA\_HOME environment variable: export JAVA\_HOME=/usr/lib/jvm/java-8-openjdk-amd64/
- Run the build script: ./install-script

### **Next Step**

Step 1: Download and Configure the C++ Producer Library Code

## Step 1: Download and Configure the C++ Producer Library Code

For information about how to download and configure the C++ producer library, see Amazon Kinesis Video Streams CPP Producer, GStreamer Pluqin and JNI.

For prerequisites and more information about this example, see Using the C++ Producer Library.

### **Next Step**

Step 2: Write and Examine the Code (p. 66)

### Step 2: Write and Examine the Code

In this section of the C++ Producer Library procedure, you examine the code in the C++ test harness (tst/ProducerTestFixture.h and other files). You downloaded this code in the previous section.

The **Platform Independent** C++ example shows the following coding pattern:

- Create an instance of Kinesis Video Producer to access Kinesis Video Streams.
- Create an instance of KinesisVideoStream. This creates a Kinesis video stream in your AWS account if a stream of the same name doesn't already exist.
- Call putFrame on the KinesisVideoStream for every frame of data, as it becomes available, to send it to the stream.

The following sections provide more information about this coding pattern.

### Creating an Instance of KinesisVideoProducer

You create the KinesisVideoProducer object by calling the KinesisVideoProducer::createSync method. The following example creates the KinesisVideoProducer in the ProducerTestFixture.h file:

```
kinesis_video_producer_ = KinesisVideoProducer::createSync(move(device_provider_),
    move(client_callback_provider_),
    move(stream_callback_provider_),
    move(credential_provider_),
    defaultRegion_);
```

The createSync method takes the following parameters:

• A DeviceInfoProvider object, which returns a DeviceInfo object containing information about the device or storage configuration.

#### Note

You configure your content store size using the deviceInfo.storageInfo.storageSize parameter. Your content streams share the content store. To determine your storage size requirement, multiply the average frame size by the number of frames stored for the max duration for all the streams. Then multiply by 1.2 to account for defragmentation. For example, suppose that your application has the following configuration:

- · Three streams
- · 3 minutes of maximum duration
- Each stream is 30 frames per second (FPS)
- Each frame is 10,000 KB in size

The content store requirement for this application is 3 (streams) \* 3 (minutes) \* 60 (seconds in a minute) \* 10000 (kb) \* 1.2 (defragmentation allowance) = 194.4 Mb ~ 200Mb.

 A ClientCallbackProvider object, which returns function pointers that report client-specific events.

- A StreamCallbackProvider object, which returns function pointers that are called back when stream-specific events occur.
- A CredentialProvider object, which provides access to AWS credential environment variables.
- The AWS Region ("us-west-2"). The service endpoint is determined from the Region.

## Creating an Instance of KinesisVideoStream

You create the KinesisVideoStream object by calling the KinesisVideoProducer::CreateStream method with a StreamDefinition parameter. The example creates the KinesisVideoStream in the ProducerTestFixture.h file with the track type as video, and with track id as 1:

The StreamDefinition object has the following fields:

- · Stream name.
- · Data retention period.
- Tags for the stream. These tags can be used by consumer applications to find the correct stream, or to get more information about the stream. The tags can also be viewed in the AWS Management Console.
- AWS KMS encryption key for the stream. For more information, see Using Server-Side Encryption with Kinesis Video Streams.
- Streaming type. Currently, the only valid value is STREAMING\_TYPE\_REALTIME.
- · Media content type.
- Media latency. This value is not currently used, and should be set to 0.
- Playback duration of each fragment.
- Media timecode scale.
- Whether the media uses key frame fragmentation.
- · Whether the media uses timecodes.
- · Whether the media uses absolute fragment times.

## Adding an audio track to the Kinesis Video Stream

You can add audio track details to a video track stream definition by using the addTrack method of the StreamDefinition:

```
stream_definition->addTrack(DEFAULT_AUDIO_TRACKID, DEFAULT_AUDIO_TRACK_NAME,
DEFAULT_AUDIO_CODEC_ID, MKV_TRACK_INFO_TYPE_AUDIO);
```

The addTrack method requires the following parameters:

- Track id (as 1 for audio). This should be unique and non-zero value.
- User-defined track name (e.g. "audio" for the audio track).
- Codec id for this track (e.g. for audio track "A\_AAC").
- Track type (e.g. use the enum value of MKV\_TRACK\_INFO\_TYPE\_AUDIO for audio).

If you have codec private data for the audio track, then you can pass it when calling the addTrack function. You can also send the codec private data after creating the KinesisVideoStream object while calling the start method in KinesisVideoStream.

## Putting a Frame into the Kinesis Video Stream

You put media into the Kinesis video stream using KinesisVideoStream::putFrame, passing in a Frame object that contains the header and media data. The example calls putFrame in the ProducerApiTest.cpp file:

#### Note

The preceding C++ Producer example sends a buffer of test data. In a real-world application, you should obtain the frame buffer and size from the frame data from a media source (such as a camera).

The Frame object has the following fields:

- Frame index. This should be a monotonically incrementing value.
- Flags associated with the frame. For example, if the encoder were configured to produce a key frame, this frame would be assigned the FRAME\_FLAG\_KEY\_FRAME flag.
- Decoding time stamp.
- Presentation time stamp.
- Duration of the frame (to 100 ns units).
- · Size of the frame in bytes.
- Frame data.

For more information about the format of the frame, see Kinesis Video Streams Data Model.

# Putting a KinesisVideoFrame into a specific track of KinesisVideoStream

You can use the PutFrameHelper class to put frame data into a specific track. First, call the getFrameDataBuffer to get a pointer to one of the pre-allocated buffers to fill in the KinesisVideoFrame data. Then, you can call the putFrameMultiTrack to send the KinesisVideoFrame along with the boolean value to indicate the type of frame data. Use true if it's a video data or false if the frame contains audio data. The putFrameMultiTrack method uses a queueing mechanism to ensure that the MKV Fragments maintain monotonically increasing frame time stamps and any two fragments do not overlap. For example, MKV timestamp of the first frame of a fragment should always be greater than the MKV timestamp of the last frame of the previous fragment.

The PutFrameHelper has the following fields:

- Maximum number of audio frames in the queue
- Maximum number of video frames in the gueue
- Size to allocate for a single audio frame
- Size to allocate for a single video frame

# **Metrics and Metric Logging**

The C++ Producer SDK includes functionality for metrics and metric logging.

You can use the getKinesisVideoMetrics and getKinesisVideoStreamMetrics API operations to retrieve information about Kinesis Video Streams and your active streams.

The following code is from the kinesis-video-pic/src/client/include/com/amazonaws/kinesis/video/client/Include.h file.

```
/**

* Gets information about the storage availability.

* @param 1 CLIENT_HANDLE - the client object handle.

* @param 2 PKinesisVideoMetrics - OUT - Kinesis Video metrics to be filled.

*

* @return Status of the function call.

*/

PUBLIC_API STATUS getKinesisVideoMetrics(CLIENT_HANDLE, PKinesisVideoMetrics);

/**

* Gets information about the stream content view.

*

* @param 1 STREAM_HANDLE - the stream object handle.

* @param 2 PStreamMetrics - Stream metrics to fill.

*

* @return Status of the function call.

*/

PUBLIC_API STATUS getKinesisVideoStreamMetrics(STREAM_HANDLE, PStreamMetrics);
```

The PClientMetrics object filled by getKinesisVideoMetrics contains the following information:

- **contentStoreSize:** The overall size in bytes of the content store (the memory used to store streaming data).
- contentStoreAvailableSize: The free memory in the content store, in bytes.
- contentStoreAllocatedSize: The allocated memory in the content store.

### Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

- totalContentViewsSize: The total memory used for the content view. (The content view is a series of indices of information in the content store.)
- totalFrameRate: The aggregate number of frames per second across all active streams.
- totalTransferRate: The total bits per second (bps) being sent in all streams.

The PStreamMetrics object filled by getKinesisVideoStreamMetrics contains the following information:

- currentViewDuration: The difference in 100 ns units between the head of the content view (when frames are encoded) and the current position (when frame data is being sent to Kinesis Video Streams).
- overallViewDuration: The difference in 100 ns units between the head of the content view (when
  frames are encoded) to the tail (when frames are flushed from memory, either because the total
  allocated space for the content view is exceeded, or because a PersistedAck message is received
  from Kinesis Video Streams, and frames known to be persisted are flushed).
- **currentViewSize:** The size in bytes of the content view from the head (when frames are encoded) to the current position (when frames are sent to Kinesis Video Streams).
- overallViewSize: The total size in bytes of the content view.
- currentFrameRate: The last measured rate of the stream, in frames per second.
- currentTransferRate: The last measured rate of the stream, in bytes per second.

### **Teardown**

If you want to send the remaining bytes in a buffer and wait for the ACK, you can use stopSync:

```
kinesis_video_stream->stopSync();
```

Or you can call stop to end the streaming:

```
kinesis_video_stream->stop();
```

After stopping the stream, you can free the stream through invoking the following API:

```
kinesis_video_producer_->freeStream(kinesis_video_stream);
```

# Next Step

the section called "Step 3: Run and Verify the Code" (p. 70)

# Step 3: Run and Verify the Code

To run and verify the code for the C++ Producer Library procedure, see the following OS-specific instructions:

Linux

- macOS
- Windows
- Raspberry Pi OS

You can monitor the traffic on your stream by watching the metrics that are associated with your stream in the Amazon CloudWatch console, such as PutMedia.IncomingBytes.

# Using the C++ Producer SDK as a GStreamer Plugin

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams.

For information about using the C++ Producer SDK as a GStreamer plugin, see Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 132).

# Using the C++ Producer SDK as a GStreamer Plugin in a Docker Container

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams.

In addition, using Docker to create the GStreamer pipeline standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

For information about using the C++ Producer SDK as a GStreamer plugin in a Docker container, see Run the GStreamer Element in a Docker Container (p. 135).

# Using Logging with the C++ Producer SDK

You configure logging for C++ Producer SDK applications in the kvs\_log\_configuration file in the kinesis-video-native-build folder.

The following example shows the first line of the default configuration file, which configures the application to write DEBUG-level log entries to the AWS Management Console:

log4cplus.rootLogger=DEBUG, KvsConsoleAppender

You can set the logging level to INFO for less verbose logging.

To configure the application to also write log entries to a log file, update the first line in the file to the following:

 $log 4 cplus.rootLogger = DEBUG, \ Kvs Console Appender, \ Kvs File Appender$ 

This configures the application to write log entries to kvs.log in the kinesis-video-native-build/log folder.

To change the log file location, update the following line with the new path:

log4cplus.appender.KvsFileAppender.File=./log/kvs.log

#### Note

If DEBUG-level logging is written to a file, the log file can use up the available storage space on the device quickly.

# Using the C Producer Library

Amazon Kinesis Video Streams provides the C Producer Library, which you can use to write application code to send media data from a device to a Kinesis video stream.

# Object Model

The Kinesis Video Streams C producer library is based on a common component called Platform Independent Codebase (PIC), which is available on GitHub at <a href="https://github.com/awslabs/amazon-kinesis-video-streams-pic/">https://github.com/awslabs/amazon-kinesis-video-streams-pic/</a>. The PIC contains platform-independent business logic for the low-levels. The Kinesis Video Streams C producer library wraps PIC with additional layer of API that allows scenario- and platform-specific callbacks and events. The Kinesis Video Streams C producer library has the following components built on top of PIC:

- Device info providers Exposes the DeviceInfo structure that can be directly supplied to the PIC API. There is a set of providers that you can configure, including application scenario-optimized provider that can optimize the content store based on the number and types of streams that your application handles and the amount of required buffering configured based on the amount of available RAM.
- Stream info provider Exposes the StreamInfo structure that can be directly supplied to the PIC API. There is a set of easy-to-configure providers which are specific to the application types and the common types of streaming scenarios. These include providers such as video, audio, audio/video multitrack, etc. Each of these scenarios has defaults that you can customize according to your application's requirements.
- Callback provider Exposes the ClientCallbacks structure that can be directly supplied to the PIC API. This includes a set of easy-to-configure callback providers for networking (CURL-based API callbacks), authorization (AWS credentials API), retry streaming on errors callbacks, etc. The Callback Provider API takes a number of arguments to configure, such as the AWS Region and authorization information, by using IoT certificates or by using AWS AccessKeyId, SecretKey, or SessionToken. You can enhance Callback Provider with custom callbacks if your application needs further processing of a particular callback to achieve some application-specific logic.
- FrameOrderCoordinator Helps handle audio and video synchronization for multi-track scenarios. It has default behavior, which you can customize to handle your application's specific logic. It also simplifies the frame metadata packaging in PIC Frame structure before submitting it to the lower-layer PIC API. For non-multitrack scenarios, this component is a pass-through to PIC putFrame API.

The C library provides the following objects to manage sending data to a Kinesis video stream:

- **KinesisVideoClient** Contains information about your device information and maintains callbacks to report on Kinesis Video Streams events.
- **KinesisVideoStream** Represents information about the video stream's parameters, such as name, data retention period, media content type, and so on.

# Putting Media Into the Stream

The C library provides methods (for example, PutKinesisVideoFrame) that you can use to put data into the KinesisVideoStream object. The library then manages the internal state of the data, which can include the following tasks:

- · Performing authentication.
- Watching for network latency. If the latency is too high, the library might choose to drop frames.
- · Tracking status of streaming in progress.

# Procedure: Using the C Producer SDK

This procedure demonstrates how to use the Kinesis Video Streams client and media sources in a C application to send H.264-encoded video frames to your Kinesis video stream.

The procedure includes the following steps:

- Step 1: Download the C Producer Library Code (p. 75)
- Step 2: Write and Examine the Code (p. 75)
- Step 3: Run and Verify the Code (p. 77)

## **Prerequisites**

• Credentials – In the sample code, you provide credentials by specifying a profile that you set up in your AWS credentials profile file. If you haven't already done so, first set up your credentials profile.

For more information, see Set up AWS Credentials and Region for Development.

• Certificate store integration – The Kinesis Video Streams Producer Library must establish trust with the service it calls. This is done through validating the certificate authorities (CAs) in the public certificate store. On Linux-based models, this store is located in the /etc/ss1/ directory.

Download the certificate from the following location to your certificate store:

https://www.amazontrust.com/repository/SFSRootCAG2.pem

- Install the following build dependencies for macOS:
  - Autoconf 2.69 (License GPLv3+/Autoconf: GNU GPL version 3 or later)
  - CMake 3.7 or 3.8
  - Pkg-Config
  - Flex 2.5.35 Apple (flex-31) or later
  - Bison 2.4 (GNU License)
  - Automake 1.15.1 (GNU License)
  - GNU Libtool (Apple Inc. version cctools-898)
  - xCode (macOS) / clang / gcc (xcode-select version 2347)
  - Java Development Kit (JDK) (for Java JNI compilation)
  - · Lib-Pkg
- Install the following build dependencies for Ubuntu (responses to version commands are truncated):
  - Install Git: sudo apt-get install git

```
$ git --version
git version 2.14.1
```

• Install CMake: sudo apt-get install cmake

```
$ cmake --version cmake version 3.9.1
```

• Install Libtool: sudo apt-get install libtool

### Amazon Kinesis Video Streams Developer Guide Procedure: Using the C Producer SDK

```
2.4.6-2
```

• Install libtool-bin: sudo apt-get install libtool-bin

```
$ libtool --version
libtool (GNU libtool) 2.4.6
Written by Gordon Matzigkeit, 1996
```

• Install GNU Automake: sudo apt-get install automake

```
$ automake --version
automake (GNU automake) 1.15
```

• Install GNU Bison: sudo apt-get install bison

```
$ bison -V
bison (GNU Bison) 3.0.4
```

• Install G++: sudo apt-get install g++

```
g++ --version
g++ (Ubuntu 7.2.0-8ubuntu3) 7.2.0
```

• Install curl: sudo apt-get install curl

```
$ curl --version
curl 7.55.1 (x86_64-pc-linux-gnu) libcurl/7.55.1 OpenSSL/1.0.2g zlib/1.2.11
libidn2/2.0.2 libpsl/0.18.0 (+libidn2/2.0.2) librtmp/2.3
```

• Install pkg-config: sudo apt-get install pkg-config

```
$ pkg-config --version
0.29.1
```

• Install Flex: sudo apt-get install flex

```
$ flex --version
flex 2.6.1
```

• Install OpenJDK: sudo apt-get install openjdk-8-jdk

```
$ java -version
openjdk version "1.8.0_171"
```

- Set the JAVA\_HOME environment variable: export JAVA\_HOME=/usr/lib/jvm/java-8-openjdk-amd64/
- Run the build script: ./install-script

## **Next Step**

Step 1: Download the C Producer Library Code (p. 75)

# Step 1: Download the C Producer Library Code

In this section, you download the low-level libraries. For prerequisites and other details about this example, see Using the C Producer Library.

1. Create a directory, and then clone the example source code from the GitHub repository.

git clone --recursive https://github.com/awslabs/amazon-kinesis-video-streams-producer-c.git  $% \left( 1\right) =\left( 1\right) \left( 1\right) \left($ 

#### Note

If you miss running git clone with --recursive, run git submodule update --init in the amazon-kinesis-video-streams-producer-c/open-source directory. You must also install pkg-config, automake, CMake, and a build environment.

For more information, see the README.md in https://github.com/awslabs/amazon-kinesis-video-streams-producer-c.git.

Open the code in the integrated development environment (IDE) of your choice (for example, Eclipse).

## **Next Step**

Step 2: Write and Examine the Code (p. 75)

# Step 2: Write and Examine the Code

In this section, you examine the code of the sample application KvsVideoOnlyStreamingSample.c in the samples folder of the https://github.com/awslabs/amazon-kinesis-video-streams-producer-c repo on GitHub. You downloaded this code in the previous step. This sample demonstrates how to use the C producer library to send H.264-encoded video frames inside the folder samples/h264SampleFrames to your Kinesis video stream.

This sample application has three sections:

- Initialization and configuration:
  - Initializing and configuring the platform-specific media pipeline.
  - Initializing and configuring KinesisVideoClient and KinesisVideoStream for the pipeline, setting the callbacks, integrating scenario-specific authentication, extracting and submitting codec private data, and getting the stream to READY state.
- · Main loop:
  - Getting the frame from the media pipeline with the timestamps and flags.
  - · Submitting the frame to the KinesisVideoStream.
- · Teardown:
  - Stopping (sync) KinesisVideoStream, freeing KinesisVideoStream, freeing KinesisVideoClient.

This sample application completes the following tasks:

• Call the createDefaultDeviceInfo API to create the deviceInfo object that contains information about the device or storage configuration.

### Amazon Kinesis Video Streams Developer Guide Step 2: Write and Examine the Code

```
// default storage size is 128MB. Use setDeviceInfoStorageSize after create to change
storage size.
CHK_STATUS(createDefaultDeviceInfo(&pDeviceInfo));
// adjust members of pDeviceInfo here if needed
    pDeviceInfo->clientInfo.loggerLogLevel = LOG_LEVEL_DEBUG;
```

Call the createRealtimeVideoStreamInfoProvider API to create the StreamInfo object.

```
CHK_STATUS(createRealtimeVideoStreamInfoProvider(streamName, DEFAULT_RETENTION_PERIOD, DEFAULT_BUFFER_DURATION, &pStreamInfo));
// adjust members of pStreamInfo here if needed
```

 Call the createDefaultCallbacksProviderWithAwsCredentials API to create the default callbacks provider based on static AWS credentials.

```
CHK_STATUS(createDefaultCallbacksProviderWithAwsCredentials(accessKey, secretKey, sessionToken, MAX_UINT64, region, cacertPath, NULL, NULL, FALSE, &pClientCallbacks));
```

• Call the createKinesisVideoClient API to create the KinesisVideoClient object that contains information about your device storage and maintains callbacks to report on Kinesis Video Streams events.

```
CHK_STATUS(createKinesisVideoClient(pDeviceInfo, pClientCallbacks, &clientHandle));
```

• Call the createKinesisVideoStreamSync API to create the KinesisVideoStream object.

```
CHK_STATUS(createKinesisVideoStreamSync(clientHandle, pStreamInfo, &streamHandle));
```

• Set up a sample frame and call PutKinesisVideoFrame API to send that frame to the KinesisVideoStream object.

```
// setup sample frame
MEMSET(frameBuffer, 0x00, frameSize);
frame.frameData = frameBuffer;
frame.version = FRAME_CURRENT_VERSION;
frame.trackId = DEFAULT_VIDEO_TRACK_ID;
frame.duration = HUNDREDS_OF_NANOS_IN_A_SECOND / DEFAULT_FPS_VALUE;
frame.decodingTs = defaultGetTime(); // current time
frame.presentationTs = frame.decodingTs;

while(defaultGetTime() > streamStopTime) {
    frame.index = frameIndex;
    frame.flags = fileIndex % DEFAULT_KEY_FRAME_INTERVAL == 0 ?
FRAME_FLAG_KEY_FRAME : FRAME_FLAG_NONE;
```

### Amazon Kinesis Video Streams Developer Guide Step 3: Run and Verify the Code

```
frame.size = SIZEOF(frameBuffer);

CHK_STATUS(readFrameData(&frame, frameFilePath));

CHK_STATUS(putKinesisVideoFrame(streamHandle, &frame));
  defaultThreadSleep(frame.duration);

frame.decodingTs += frame.duration;
  frame.presentationTs = frame.decodingTs;
  frameIndex++;
  fileIndex++;
  fileIndex = fileIndex % NUMBER_OF_FRAME_FILES;
}
```

· Teardown:

```
CHK_STATUS(stopKinesisVideoStreamSync(streamHandle));
CHK_STATUS(freeKinesisVideoStream(&streamHandle));
CHK_STATUS(freeKinesisVideoClient(&clientHandle));
```

## **Next Step**

Step 3: Run and Verify the Code (p. 77)

# Step 3: Run and Verify the Code

To run and verify the code for the Producer Library procedure, do the following:

 Run the following commands to create a build directory in your downloaded C SDK, and execute cmake from it:

```
mkdir -p amazon-kinesis-video-streams-producer-c/build;
cd amazon-kinesis-video-streams-producer-c/build;
cmake ..
```

You can pass the following options to cmake ...

- -DBUILD\_DEPENDENCIES whether or not to build depending libraries from source
- -DBUILD\_TEST=TRUE build unit/integration tests, may be useful for confirm support for your device.
  - ./tst/webrtc\_client\_test
- -DCODE\_COVERAGE -enable coverage reporting
- -DCOMPILER\_WARNINGS enable all compiler warnings
- -DADDRESS\_SANITIZER build with AddressSanitizer
- -DMEMORY\_SANITIZER build with MemorySanitizer
- -DTHREAD\_SANITIZER build with ThreadSanitizer
- -DUNDEFINED\_BEHAVIOR\_SANITIZER build with UndefinedBehaviorSanitizer
- -DALIGNED\_MEMORY\_MODEL build for aligned memory model only devices. Default is OFF.

2. Navigate to the build directory you just created with the step above, and run make to build the WebRTC C SDK and its provided samples.

make

3. The sample application kinesis\_video\_cproducer\_video\_only\_sample sends h.264-encoded video frames inside the folder samples/h264SampleFrames to Kinesis Video Streams. The following command sends the video frames in a loop for ten seconds to Kinesis Video Streams:

```
./kinesis_video_cproducer_video_only_sample YourStreamName 10
```

If you want to send H.264-encoded frames from another folder (for example, MyH264FramesFolder), you can run the sample with the following arguments:

```
./kinesis_video_cproducer_video_only_sample YourStreamName 10 MyH264FramesFolder
```

4. To enable verbose logs, define the HEAP\_DEBUG and LOG\_STREAMING C-defines by uncommenting the appropriate lines in CMakeList.txt.

You can monitor the progress of the test suite in the debug output in your IDE. You can also monitor the traffic on your stream by watching the metrics that are associated with your stream in the Amazon CloudWatch console, such as PutMedia.IncomingBytes.

### Note

The console doesn't display the data as a video stream because the test harness only sends frames of empty bytes.

# **Producer SDK Reference**

This section contains limits, error codes, and other reference information for the Kinesis Video Streams Producer Libraries (p. 53).

### **Topics**

- Producer SDK Limits (p. 78)
- Error Code Reference (p. 80)
- Network Abstraction Layer (NAL) Adaptation Flag Reference (p. 104)
- Producer SDK Structures (p. 104)
- Kinesis Video Stream Structures (p. 106)
- Producer SDK Callbacks (p. 118)

## **Producer SDK Limits**

The following table contains the current limits for values in the Producer Libraries (p. 53).

#### Note

Before setting these values, you must validate your inputs. The SDK doesn't validate these limits, and a runtime error occurs if the limits are exceeded.

## Amazon Kinesis Video Streams Developer Guide Producer SDK Limits

Value	Limit	Notes
Max stream count	128	The maximum number of streams that a producer object can create. This is a soft limit (you can request an increase). It ensures that the producer doesn't accidentally create streams recursively.
Max device name length	128 characters	
Max tag count	50 per stream	
Max stream name length	256 characters	
Min storage size	10 MiB = 10 * 1024 * 1024 bytes	
Max storage size	10 GiB = 10 * 1024 * 1024 * 1024 bytes	
Max root directory path length	4,096 characters	
Max auth info length	10,000 bytes	
Max URI string length	10,000 characters	
Max tag name length	128 characters	
Max tag value length	1,024 characters	
Min security token period	30 seconds	
Security token grace period	40 minutes	If the specified duration is longer, it is limited to this value.
Retention period	0 or greater than one hour	0 indicates no retention.
Min cluster duration	1 second	The value is specified in 100 ns units, which is the SDK standard.
Max cluster duration	30 seconds	The value is specified in 100 ns units, which is the SDK standard. The backend API may enforce a shorter cluster duration.
Max fragment size	50 MB	For more information, see Kinesis Video Streams Limits (p. 168).
Max fragment duration	10 seconds	For more information, see Kinesis Video Streams Limits (p. 168).
Max connection duration	45 minutes	The backend closes the connection after this time. The SDK rotates the token and establishes a new connection within this time.

Value	Limit	Notes
Max ACK segment length	1,024 characters	Maximum segment length of the acknowledgement sent to the ACK parser function.
Max content type string length	128 characters	
Max codec ID string length	32 characters	
Max track name string length	32 characters	
Max codec private data length	1 MiB = 1 * 1024 * 1024 bytes	
Min timecode scale value length	100 ns	The minimum timecode scale value to represent the frame timestamps in the resulting MKV cluster. The value is specified in increments of 100 ns, which is the SDK standard.
Max timecode scale value length	1 second	The maximum timecode scale value to represent the frame timestamps in the resulting MKV cluster. The value is specified in increments of 100 ns, which is the SDK standard.
Min content view item count	10	
Min buffer duration	20 seconds	The value is specified in increments of 100 ns, which is the SDK standard.
Max update version length	128 characters	
Max ARN length	1024 characters	
Max fragment sequence length	128 characters	
Max retention period	10 years	

# **Error Code Reference**

This section contains error and status code information for the Producer Libraries (p. 53).

For information about solutions to common issues, see Troubleshooting Kinesis Video Streams (p. 174).

### **Topics**

- Errors and Status Codes Returned by PutFrame Callbacks Platform Independent Code (PIT) (p. 81)
- Errors and Status Codes Returned by PutFrame Callbacks C Producer Library (p. 102)

# Errors and Status Codes Returned by PutFrame Callbacks - Platform Independent Code (PIT)

The following sections contain error and status information that is returned by callbacks for the PutFrame operation within the Platform Independent Codebase (PIT).

### **Topics**

- Error and Status Codes Returned by the Client Library (p. 81)
- Error and Status Codes Returned by the Duration Library (p. 94)
- Error and Status Codes Returned by the Common Library (p. 94)
- Error and Status Codes Returned by the Heap Library (p. 95)
- Error and Status Codes Returned by the MKVGen Library (p. 96)
- Error and Status Codes Returned by the Trace Library (p. 100)
- Error and Status Codes Returned by the Utils Library (p. 100)
- Error and Status Codes Returned by the View Library (p. 101)

### Error and Status Codes Returned by the Client Library

The following table contains error and status information that is returned by methods in the Kinesis Video Streams Client library.

Code	Message	Description	Recommended Action
0x52000001	STATUS_MAX_STREAM_COUN	IThe maximum stream count was reached.	Specify a larger max stream count in DeviceInfo as specified in Producer SDK Limits (p. 78).
0x52000002	STATUS_MIN_STREAM_COUN	Minimum stream count error.	Specify the max number of streams greater than 0 in DeviceInfo.
0x52000003	STATUS_INVALID_DEVICE_	NAMH <u>id đ</u> ቀሌን đ length.	Refer to the max device name length in characters that is specified in Producer SDK Limits (p. 78).
0x52000004	STATUS_INVALID_DEVICE_	IMFO <u>ic</u> MERSIONInfo structure version.	Specify the correct current version of the structure.
0x52000005	STATUS_MAX_TAG_COUNT	The maximum tag count was reached.	Refer to the current max tag count that is specified in Producer SDK Limits (p. 78).
0x52000006	STATUS_DEVICE_FINGERPF	RINT_LENGTH	
0x52000007	STATUS_INVALID_CALLBAC	Kr <u>Sv</u> al <b>ic</b> RS <b>aDN</b> backs structure version.	Specify the correct current version of the structure.
0x52000008	STATUS_INVALID_STREAM_	IMF01icWFR6420NInfo structure version.	Specify the correct current version of the structure.
0x52000009	STATUS_INVALID_STREAM_	NAME <u>id सम</u> ्बाम name length.	Refer to the max stream name length in characters

Code	Message	Description	Recommended Action
			that is specified in Producer SDK Limits (p. 78).
0x5200000a	STATUS_INVALID_STORAGE	Aள்ம்⊾alid storage size was specified.	The storage size in bytes must be within the limits specified in Producer SDK Limits (p. 78).
0x5200000b	STATUS_INVALID_ROOT_DI	RnEvCaTOORYO <u>o</u> t ENIGETEbry string length.	Refer to the max root directory path length that is specified in Producer SDK Limits (p. 78).
0x5200000c	STATUS_INVALID_SPILL_F	RANTV <b>a0</b> id spill ratio.	Express the spill ratio as a percentage from 0 to 100.
0x5200000d	STATUS_INVALID_STORAGE	Inwid SERSION Info structure version.	Specify the correct current version of the structure.
0x5200000e	STATUS_INVALID_STREAM_	State that doesn't permit the current operation.	Most commonly, this error occurs when the SDK fails to reach the state that it needs to perform the requested operation. For example, it occurs if the GetStreamingEndpoint API call fails, and the client application ignores it and continues putting frames into the stream.
0x5200000f	STATUS_SERVICE_CALL_CA	ATTIMEACTIONS ING structure has missing function entry points for some mandatory functions.	Ensure that the mandatory callbacks are implemented in the client application. This error is exposed only to PIC (Platform Independent Code) clients. C++ and other higher-level wrappers satisfy these calls.
0x52000010	STATUS_SERVICE_CALL_NO	)T <u>lo</u> ct <b>latiflibil</b> atizend_ERROR	Verify the security token/certificate/security token integration/expiration. Ensure that the token has the correct associated rights with it. For the Kinesis Video Streams sample applications, ensure that the environment variable is set correctly.
0x52000011	STATUS_DESCRIBE_STREAM	1 <u>D</u> eAsldr <u>i</u> fbAsDtFr@am API failure.	This error is returned after the DescribeStream API retry failure. The PIC client returns this error after it gives up retrying.

Code	Message	Description	Recommended Action
0x52000012	STATUS_INVALID_DESCRIE	B <b>E</b> n <b>&amp; TRE</b> AM_RESPONSE DescribeStreamResp structure.	The structure that ownsepassed to the DescribeStreamResultEve is either null or contains invalid items like a null Amazon Resource Name (ARN).
0x52000013	STATUS_STREAM_IS_BEING	<u>Tiblelstrædn</u> Erlkeikg deleted.	An API failure was caused by the stream being deleted. Ensure that no other processes are trying to delete the stream while the stream is in use.
0x52000014	STATUS_SERVICE_CALL_IN	NVAVAID_ANGG_MERRESR were specified for the service call.	The backend returns this error when a service call argument is not valid or when the SDK encounters an error that it can't interpret.
0x52000015	STATUS_SERVICE_CALL_DE	WTh@EdeWOŒ_WOЫNDt_ERR found.	Offensure that the device is not deleted while in use.
0x52000016	STATUS_SERVICE_CALL_DE	VTheEdeWoode_พลิเมฟซิธิION provisioned.	EDISEIRR Office the device has been provisioned.
0x52000017	STATUS_SERVICE_CALL_RE	ട്ങൾReciiE rksവ്വrEelukub_E found returned from the service.	RRORerror occurs when the service can't locate the resource (for example, a stream). It might mean different things in different contexts, but the likely cause is the usage of APIs before the stream is created. Using the SDK ensures that the stream is created first.
0x52000018	STATUS_INVALID_AUTH_LE	Nnvalid auth info length.	Refer to the current values that are specified in Producer SDK Limits (p. 78).
0x52000019	STATUS_CREATE_STREAM_C	Alhe (FÆIdIEDStream API call failed.	Refer to the error string for more detailed information about why the operation failed.
0x5200002a	STATUS_GET_STREAMING_T	TOTNEN_CALL_FAILED GetStreamingToken call failed.	Refer to the error string for more detailed information about why the operation failed.

Code	Message	Description	Recommended Action
0x5200002b	STATUS_GET_STREAMING_I		Refer to the error string for mtore detailed information about why the operation failed.
0x5200002c	STATUS_INVALID_URI_LE	NAn invalid URI string length was returned from the GetStreamingEndpot	Refer to the current maximum values that are specified in Producer SDK intrits (p. 78).
0x5200002d	STATUS_PUT_STREAM_CALI	_TheTrumMedia API call failed.	Refer to the error string for more detailed information about why the operation failed.
0x5200002e	STATUS_STORE_OUT_OF_MI	MONEYCONTENT STORE IS OUT OF MEMORY.	The content store is shared between the streams and should have enough capacity to store the maximum durations for all the streams + ~20% (accounting for the defragmentation). It's important to not overflow the storage. Choose values for the maximum duration per stream that correspond to the cumulative storage size and the latency tolerances. It's better to drop the frames as they fall out of the content view window versus just being put (content store memory pressure). This is because dropping the frames initiates the stream pressure notification callbacks. Then the application can adjust the upstream media components (like the encoder) to thin the bitrate, drop frames, or act accordingly.

Code	Message	Description	Recommended Action
0x5200002f	STATUS_NO_MORE_DATA_A\	/ANCLARDIr€ data is available currently for a stream.	This is a potential valid result when the media pipeline produces more slowly than the networking thread consumes the frames to be sent to the service. Higher-level clients (for example, C++, Java, or Android) do not see this warning because it's handled internally.
0x52000030	STATUS_INVALID_TAG_VER	R <b>SrIVœN</b> id Tag structure version.	Specify the correct current version of the structure.
0x52000031	STATUS_SERVICE_CALL_UN	<b>IKNOWN<u>kr</u>ጩጹወ</b> ®r generic error was returned from the networking stack.	See the logs for more detailed information.
0x52000032	STATUS_SERVICE_CALL_RE	<b>570HROF<u>e</u>IN_H8</b> E_ERRO	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000033	STATUS_SERVICE_CALL_CL	_ <b>工班被市<u>t</u> Li面MC</b> T_ERROR	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0×52000034	STATUS_SERVICE_CALL_DE	E <b>VDEO/ficellim/i</b> ET_ERROR	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000035	STATUS_SERVICE_CALL_ST	rseada <u>n</u> a IimiitERROR	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000036	STATUS_SERVICE_CALL_RE	S <b>ൾReso</b> @EesvæsD_ERR deleted or is being deleted.	Returned from the service. For more information, see the Kinesis Video Streams API Reference.
0x52000037	STATUS_SERVICE_CALL_TI	. <b>Mis@LsE<u>r</u>viR&amp;O&amp;</b> ll timed out.	Calling a particular service API resulted in a timeout. Ensure that you have a valid network connection. The PIC will retry the operation automatically.
0x52000038	STATUS_STREAM_READY_CA	AlSitte Active ED notification.	This notification is sent from the PIC to the client indicating that the async stream has been created.

Code	Message	Description	Recommended Action
0x52000039	STATUS_DEVICE_TAGS_COL	J <b>NiTv<u>a</u>NiaNt<u>a</u>ZjERVæ<u>r</u>EAGS_N specified.</b>	Unde tag count is not zero, but the tags are empty. Ensure that the tags are specified or the count is zero.
0x5200003a	STATUS_INVALID_STREAM_	_ <b>DmissiRI</b> IPTION_VERSIO StreamDescription structure version.	
0x5200003b	STATUS_INVALID_TAG_NAM	ባ <b>፤</b> ፫ኒ <b>ሂቭ፤ Ni</b> tag name length.	Refer to the limits for the tag name that are specified in Producer SDK Limits (p. 78).
0x5200003c	STATUS_INVALID_TAG_VAL	. <b>ฟา<u>โช</u>สโซิฟ</b> tag value length.	Refer to the limits for the tag value that are specified in Producer SDK Limits (p. 78).
0x5200003d	STATUS_TAG_STREAM_CALL	_ <b>_Th&amp;III</b> & <b>g</b> Resource API failed.	The TagResource API call failed. Check for a valid network connection. See the logs for more information about the failure.
0x5200003e	STATUS_INVALID_CUSTOM_	_DAMAid custom data calling PIC APIs.	Invalid custom data has been specified in a call to the PIC APIs. This can occur only in the clients that directly use PIC.
0x5200003f	STATUS_INVALID_CREATE_		The structure or its member siælds are invalid (that is, the ARN is null or larger than what's specified in Producer SDK Limits (p. 78)).
0x52000040	STATUS_CLIENT_AUTH_CAL	.C <u>l</u> i <b>eAI</b> blith failed.	The PIC failed to get proper auth information (that is, AccessKeyId or SecretAccessKey) after a number of retries. Check the authentication integration. The sample applications use environment variables to pass in credential information to the C++ Producer Library.
0x52000041	STATUS_GET_CLIENT_TOKE	M <u>etriby t</u> ክልፔድደውity token call failed.	This situation can occur for clients that use PIC directly. After a number of retries, the call fails with this error.

Code	Message	Description	Recommended Action
0x52000042	STATUS_CLIENT_PROVISION	)IP <u>r</u> 6vikilo <u>n</u> fræg e <b>fri</b> ðr.	Provisioning is not implemented.
0x52000043	STATUS_CREATE_CLIENT_C	Falle AC LEED te the producer client.	A generic error returned by the PIC after a number of retries when the client creation fails.
0x52000044	STATUS_CLIENT_READY_CA	AlFa <b>BAd Ko GAT LIED</b> producer client to a READY state.	Returned by the PIC state machine if the PIC fails to move to the READY state. See the logs for more information about the root cause.
0x52000045	STATUS_TAG_CLIENT_CALI	_ <b>TheILag</b> Resource for the producer client failed.	The TagResource API call failed for the producer client. See the logs for more information about the root cause.
0x52000046	STATUS_INVALID_CREATE_	Device#PredirenSE creation failed.	The higher-level SDKs (for example, C++ or Java) don't implement the device/producer creation API yet. Clients that use PIC directly can indicate a failure using the result notification.
0x52000047	STATUS_ACK_TIMESTAMP_N	いの方点型が立くを登場が立めるのであります。 received ACK is not in the view.	This error occurs if the frame corresponding to the received ACK falls out of the content view window. Generally, this occurs if the ACK delivery is slow. It can be interpreted as a warning and an indication that the downlink is slow.
0x52000048	STATUS_INVALID_FRAGMEN	NT <u>n.<b>A.G.M.E.R.G.T.E.O.</b>N</u> tAck structure version.	Specify the correct current version of the FragmentAck structure.
0x52000049	STATUS_INVALID_TOKEN_	Xin TarikiTsia Nirity token expiration.	The security token expiration should have an absolute timestamp in the future that is greater than the current timestamp, with a grace period. For the limits for the grace period, see the Producer SDK Limits (p. 78).

Code	Message	Description	Recommended Action
0x5200004a	STATUS_END_OF_STREAM	End of stream (EOS) indicator.	In the GetStreamData API call, indicates that the current upload handle session has ended. This occurs if the session ends or errors, or if the session token has expired and the session is being rotated.
0x5200004b	STATUS_DUPLICATE_STREA	เท <u>ิบ</u> ท <b>ุฬเซ</b> ิte stream name.	Multiple streams can't have the same stream name. Choose a unique name for the stream.
0x5200004c	STATUS_INVALID_RETENT	On <u>v</u> ඇ ር ር ር ር ር ር ር ር ር ር ር ር ር ር ር ር ር ር	An invalid retention period is specified in the StreamInfo structure. For information about the valid range of values for the retention period, see Producer SDK Limits (p. 78).
0x5200004d	STATUS_INVALID_ACK_KEY	<u>/I</u> sज्ज <b>ारा</b> FragmentAck.	Failed to parse the fragment ACK string. Invalid key start indicator. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.
0x5200004e	STATUS_INVALID_ACK_DUF	P <b>luīvālīt</b> E_KEY_NAME FragmentAck.	Failed to parse the fragment ACK string. Multiple keys have the same name. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.
0x5200004f	STATUS_INVALID_ACK_INV	/ <b>Antvīd)<u>ic</u>VALUE_START</b> FragmentAck.	Failed to parse the fragment ACK string because of an invalid key value start indicator. The fragment ACK string might be damaged. It can self-correct, and this error can be treated as a warning.
0×52000050	STATUS_INVALID_ACK_INV	/ <b>Antvīdi<u>c</u>VALUE_END</b> FragmentAck.	Failed to parse the fragment ACK string because of an invalid key value end indicator. The fragment ACK string might be damaged. It can self-correct and this error can be treated as a warning.

Code	Message	Description	Recommended Action
0x52000051	STATUS_INVALID_PARSED_	ANGW <u>al</u> iCYPE FragmentAck.	Failed to parse the fragment ACK string because an invalid ACK type was specified.
0x52000052	STATUS_STREAM_HAS_BEEN	ง <u>S</u> \$ศิส <b>ภ</b> ศฅโซโอร stopped.	The stream has been stopped, but a frame is still being put into the stream.
0x52000053	STATUS_INVALID_STREAM_	MMTATICS_VERSION StreamMetrics structure version.	Specify the correct current version of the StreamMetrics structure.
0x52000054	STATUS_INVALID_CLIENT_	_MheVਕੇਵੇਪੋCS_VERSION ClientMetrics structure version.	Specify the correct current version of the ClientMetrics structure.
0x52000055	STATUS_INVALID_CLIENT_	<b>RFEADYCeSTAITE</b> alization failed to reach a READY state.	Failed to reach the READY state during the producer client initialization. See the logs for more information.
0x52000056	STATUS_STATE_MACHINE_S	TIATEE <u>n</u> alOTateOUND machine error.	Not a publicly visible error.
0x52000057	STATUS_INVALID_FRAGMEN	NTn_AGM_AGMEype is specified in the FragmentAck structure.	The FragmentAck structure should contain ACK types defined in the public header.
0x52000058	STATUS_INVALID_STREAM	RittADYaState machine transition error.	Not a publicly visible error.
0x52000059	STATUS_CLIENT_FREED_B	HONRESTERNE AND Ject was freed after the producer was freed.	There was an attempt to free a stream object after the producer object was freed. This can only occur in clients that directly use PIC.
0x5200005a	STATUS_ALLOCATION_SIZE	<u>IiSNAADALERo</u> iiak <u>yavei</u> ir <u>oi</u> qu	that the actual allocating that the actual allocation size from the content store is smaller than the size of the packaged frame/fragment.
0x5200005b	STATUS_VIEW_ITEM_SIZE	<u>Grafieat a eige fan fan State a fan fan State a fan S</u>	ATheOstored size of the allocation in the content view is greater than the allocation size in the content store.

Code	Message	Description	Recommended Action
0x5200005c	STATUS_ACK_ERR_STREAM	<u>ISEAGan</u> ERAGORerror ACK.	An error that the ACK returned from the backend indicating a stream read/ parsing error. This generally occurs when the backend fails to retrieve the stream. Auto-restreaming can usually correct this error.
0x5200005d	STATUS_ACK_ERR_FRAGMEN	NT <u>h</u> <b>្ទារថ្មីត្រូវត្រៃអ៊ូអ្នក</b> GHED fragment size was reached.	The max fragment size in bytes is defined in Producer SDK Limits (p. 78). This error indicates that there are either very large frames, or there are no key frames to create manageable size fragments. Check the encoder settings and ensure that key frames are being produced properly. For streams that have very high density, configure the encoder to produce fragments at smaller durations to manage the maximum size.
0x5200005e	STATUS_ACK_ERR_FRAGMEN	NT <u>he</u> URAXIDON <u>n</u> REACHED fragment duration was reached.	The max fragment duration is defined in Producer SDK Limits (p. 78). This error indicates that there are either very low frames per second or there are no key frames to create manageable duration fragments. Check the encoder settings and ensure that key frames are being produced properly at the regular intervals.
0x5200005f	STATUS_ACK_ERR_CONNEC	T <b>រាប់ម</b> ្មា <b>ជមស់ATUIO</b> N_REACH connection duration was reached.	enforces the max connection duration as specified in the Producer SDK Limits (p. 78). The Producer SDK automatically rotates the stream/token before the maximum is reached, and so clients using the SDK should not receive this error.

Code	Message	Description	Recommended Action
0x52000060	STATUS_ACK_ERR_FRAGMEN	NT <u>ir</u> TiPMcdeDar <u>e</u> NOot_MON monotonically increasing.	OTTONE Coducer SDK enforces timestamps, so clients using the SDK should not receive this error.
0x52000061	STATUS_ACK_ERR_MULTI_T	T <b>RAIDKi<u>p</u>NeXt</b> racks in the MKV.	The Producer SDK enforces single track streams, so clients using the SDK should not receive this error.
0x52000062	STATUS_ACK_ERR_INVALID	O <u>l</u> mwak <u>id</u> dwika/data.	The backend MKV parser encountered an error parsing the stream. Clients using the SDK might encounter this error if the stream is corrupted in the transition or if the buffer pressures force the SDK to drop tail frames that are partially transmitted. In the latter case, we recommend that you either reduce the FPS/resolution, increase the compression ratio, or (in the case of a "bursty" network) allow for larger content store and buffer duration to accommodate for the temporary pressures.
0x52000063	STATUS_ACK_ERR_INVALID	<u>I</u> mrandunder <u>u</u> tem ESTAM timestamp.	PThe service returns this error ACK if the producer clock has a large drift into the future. Higher-level SDKs (for example, Java or C++) use some version of the system clock to satisfy the current time callback from PIC. Ensure that the system clock is set properly. Clients using the PIC directly should ensure that their callback functions return the correct timestamp.
0x52000064	STATUS_ACK_ERR_STREAM_	NO∃c <u>t</u> À@Ts <b>I</b> k€am.	A call to a backend API was made while the stream was not in an "Active" state. This occurs when the client creates the stream and immediately continues to push frames into it. The SDK handles this scenario through the state machine and recovery mechanism.

Code	Message	Description	Recommended Action
0x52000065	STATUS_ACK_ERR_KMS_KE	/ <u>AWCS K\$4SS_</u> <b>ĐĒሲ</b> ቅቼĒ D denied error.	Returned when the account has no access to the specified key.
0x52000066	STATUS_ACK_ERR_KMS_KE	∕ <u>A<b>WIS</b>ABM</u> <b>⊊</b> Rey is disabled	The specified key has been disabled.
0x52000067	STATUS_ACK_ERR_KMS_KEY	/ AWAS KDASTROW_ERROR validation error.	Generic validation error. For more information, see the AWS Key Management Service API Reference.
0x52000068	STATUS_ACK_ERR_KMS_KEY	∕ <u>A</u> VM% KATSL k⊕y E unavailable.	The key is unavailable. For more information, see the AWS Key Management Service API Reference.
0x52000069	STATUS_ACK_ERR_KMS_KE	/ <u>Intwal</u> ialuge_d/sava/s KMS key.	The AWS KMS key is not configured to be used in this context. For more information, see the AWS Key Management Service API Reference.
0x5200006a	STATUS_ACK_ERR_KMS_KE	/ <u>AIMS/AIMIS)ir</u> s/TANTE state.	For more information, see the AWS Key Management Service API Reference.
0x5200006b	STATUS_ACK_ERR_KMS_KEY	∕ <u>A</u> ₩ <b>05</b> <u>K</u> ₱ŒJ₩Ðy not found.	The key was not found. For more information, see the AWS Key Management Service API Reference.
0x5200006c	STATUS_ACK_ERR_STREAM_	<b>DibleiSTfda</b> m has been or is being deleted.	The stream is being deleted by another application or through the AWS Management Console.
0x5200006d	STATUS_ACK_ERR_ACK_INT	Eirtead <u>a</u> leatroir	Generic service internal error.
0x5200006e	STATUS_ACK_ERR_FRAGMEN	VF <u>r</u> akgnodelmt√Altc <u>h</u> EvrantOR error.	Returned when the service fails to durably persist and index the fragment. Although it's rare, it can occur for various reasons. By default, the SDK retries sending the fragment.
0x5200006f	STATUS_ACK_ERR_UNKNOWN	∖ <u>L</u> ACK <u>Ó</u> ONRR <b>O</b> ROr.	The service returned an unknown error.
0x52000070	STATUS_MISSING_ERR_ACK	( <u>M</u> īBsing ACK information.	The ACK parser completed parsing, but the FragmentAck information is missing.

Code	Message	Description	Recommended Action
0x52000071	STATUS_INVALID_ACK_SEC	ያ <b>ነነቴ Val</b> L <b>ac</b> K segment length.	An ACK segment string with an invalid length was specified to the ACK parser. For more information, see Producer SDK Limits (p. 78).
0x52000074	STATUS_MAX_FRAGMENT_ME	TIADATIA <u>xi</u> ចលិប្បក់T number of metadata items has been added to a fragment.	A Kinesis video stream can add up to 10 metadata items to a fragment, either by adding a nonpersistent item to a fragment, or by adding a persistent item to the metadata queue. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 15).
0x52000075	STATUS_ACK_ERR_FRAGMEN	IA MinitADATAMUDMIT R metadata count, metadata name length, or metadata value length) has been reached.	the number and size of metadata items. This error does not occur unless the limits in the Producer SDK code are changed. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 15).
0x52000076	STATUS_BLOCKING_PUT_IN	NTEARHAPTEIDI <u>e</u> STEAEAM_T	ERMINATED
0x52000077	STATUS_INVALID_METADAT	ፐ <u>ብ</u> ተቀረብ name is not valid.	The metadata name cannot start with the string "AWS". If this error occurs, the metadata item is not added to the fragment or metadata queue. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 15).
0x52000078	STATUS_END_OF_FRAGMENT	Tific Antic of Nav ALID STA fragment frame is in an invalid state.	The end of fragment should not be sent in a non-key-frame fragmented stream.
0x52000079	STATUS_TRACK_INFO_MISS	STMECk information is missing.	The track number must be greater than 0 and it must match the track id.
0x5200007a	STATUS_MAX_TRACK_COUNT	MEXAGENE Drack count is exceeded.	You can have a maximum of 3 tracks per stream.

Code	Message	Description	Recommended Action
0x5200007b	STATUS_OFFLINE_MODE_W	TIM <u>eZ<b>IFN</b>OL</u> R <b>£ITEANTIFO</b> N mode retention time is set to zero.	The offline streaming mode retention time should not be set to zero.
0x5200007c	STATUS_ACK_ERR_TRACK_I	いけい いっぱい いっぱい いっぱい いっぱい いっぱい いっぱい いっぱい い	
0x5200007d	STATUS_ACK_ERR_FRAMES_	MFI&SAENG <u>ni</u> ESARg F&A&K track.	
0x5200007e	STATUS_ACK_ERR_MORE_TH	IMaximLow Bilo weal CKS_ number of tracks is exceeded.	FOUND
0x5200007f	STATUS_UPLOAD_HANDLE_A	A <b>ይወተσεφ</b> handle is aborted.	
0x52000080	STATUS_INVALID_CERT_PA	ATm <u>va</u> ll <b>ich@Fti</b> ficate path length.	
0x52000081	STATUS_DUPLICATE_TRACE	( <u>DIDL</u> iceteNDrack ID found.	

## Error and Status Codes Returned by the Duration Library

The following table contains error and status information that is returned by methods in the Duration library.

Code	Message
0xffffffffffff	INVALID_DURATION_VALUE

## Error and Status Codes Returned by the Common Library

The following table contains error and status information that is returned by methods in the Common library.

### Note

These error and status information codes are common to many APIs.

Code	Message	Description
0x00000001	STATUS_NULL_ARG	NULL was passed for a mandatory argument.
0x00000002	STATUS_INVALID_ARG	An invalid value was specified for an argument.
0x00000003	STATUS_INVALID_ARG_LEN	An invalid argument length was specified.
0x00000004	STATUS_NOT_ENOUGH_MEMORY	Could not allocate enough memory.

Code	Message	Description
0x0000005	STATUS_BUFFER_T00_SMALL	The specified buffer size is too small.
0x00000006	STATUS_UNEXPECTED_EOF	An unexpected end of file was reached.
0x00000007	STATUS_FORMAT_ERROR	An invalid format was encountered.
0x0000008	STATUS_INVALID_HANDLE_ERRO	Rnvalid handle value.
0x00000009	STATUS_OPEN_FILE_FAILED	Failed to open a file.
0x0000000a	STATUS_READ_FILE_FAILED	Failed to read from a file.
0x000000b	STATUS_WRITE_TO_FILE_FAILE	<b>F</b> ailed to write to a file.
0х0000000с	STATUS_INTERNAL_ERROR	An internal error that normally doesn't occur and might indicate an SDK or service API bug.
0x0000000d	STATUS_INVALID_OPERATION	There was an invalid operation, or the operation is not permitted.
0x0000000e	STATUS_NOT_IMPLEMENTED	The feature is not implemented.
0x000000f	STATUS_OPERATION_TIMED_OUT	The operation timed out.
0x00000010	STATUS_NOT_FOUND	A required resource was not found.

# Error and Status Codes Returned by the Heap Library

The following table contains error and status information that is returned by methods in the Heap library.

Code	Message	Description
0x01000001	STATUS_HEAP_FLAGS_ERROR	An invalid combination of flags was specified.
0x01000002	STATUS_HEAP_NOT_INITIALIZE	DAn operation was attempted before the heap was initialized.
0x01000003	STATUS_HEAP_CORRUPTED	The heap was corrupted or the guard band (in debug mode) was overwritten. A buffer overflow in the client code might lead to a heap corruption.
0x01000004	STATUS_HEAP_VRAM_LIB_MISSI	None VRAM (video RAM) user or kernel mode library cannot be loaded or is missing. Check if the underlying platform supports VRAM allocations.

Code	Message	Description
0x01000005	STATUS_HEAP_VRAM_LIB_REOPE	NFailed to open the VRAM library.
0x01000006	STATUS_HEAP_VRAM_INIT_FUNC	_ <b>፫፮ህ⊭៩ዕ</b> ៤ load the INIT function export.
0x01000007	STATUS_HEAP_VRAM_ALLOC_FUN	I <u>Fa</u> <b>ቯ¥dጩO</b> lload the ALLOC function export.
0x01000008	STATUS_HEAP_VRAM_FREE_FUNC	_ <b>፫፮ዣ⊭ፀ</b> ባዕ load the FREE function export.
0x01000009	STATUS_HEAP_VRAM_LOCK_FUNC	_ <b>፫፮ዣለዘፀ</b> ባኔ load the LOCK function export.
0x0100000a	STATUS_HEAP_VRAM_UNLOCK_FU	በ <b>ፕ</b> ፭ <u>il</u> <b>ፍሄ<b>ሰነፀባ</b>ሴad the UNLOCK function export.</b>
0x0100000b	STATUS_HEAP_VRAM_UNINIT_FU	በ <b>ፕ፭<u>፡l</u>6ህ118ባዕ</b> ad the UNINIT function export.
0х0100000с	STATUS_HEAP_VRAM_GETMAX_FU	በ <b>ፕ፭<u>፡l</u>ዬህሰፄዐዕ</b> ad the GETMAX function export.
0x0100000d	STATUS_HEAP_DIRECT_MEM_INI	Failed to initialize the main heap pool in the hybrid heap.
0x0100000e	STATUS_HEAP_VRAM_INIT_FAIL	Ethe VRAM dynamic initialization failed.
0x0100000f	STATUS_HEAP_LIBRARY_FREE_F	สะวันโยชี to de-allocate and free the VRAM library.
0x01000010	STATUS_HEAP_VRAM_ALLOC_FAI	山油 VRAM allocation failed.
0x01000011	STATUS_HEAP_VRAM_FREE_FAIL	EDne VRAM free failed.
0x01000012	STATUS_HEAP_VRAM_MAP_FAILE	<b>D</b> he VRAM map failed.
0x01000013	STATUS_HEAP_VRAM_UNMAP_FAI	ШЊе VRAM unmap failed.
0x01000014	STATUS_HEAP_VRAM_UNINIT_FA	IIIheDVRAM deinitialization failed.

## Error and Status Codes Returned by the MKVGen Library

The following table contains error and status information that is returned by methods in the MKVGen library.

Code	Message	Description / Recommended Action
0x32000001	STATUS_MKV_INVALID_FRAME_I	DAMMalid members of the Frame data structure. Ensure that the duration, size, and frame data are valid and are within the limits specified in Producer SDK Limits (p. 78).

Code	Message	Description / Recommended Action
0x32000002	STATUS_MKV_INVALID_FRAME_1	INVESTICAMEME timestamp. The calculated PTS (presentation timestamp) and DTS (decoding timestamp) are greater or equal to the timestamp of the start frame of the fragment. This is an indication of a potential media pipeline restart or an encoder stability issue. For troubleshooting information, see Error: "Failed to submit frame to Kinesis Video client" (p. 179)
0x32000003	STATUS_MKV_INVALID_CLUSTER	ADURWALION ragment duration was specified. For more information, see Producer SDK Limits (p. 78).
0x32000004	STATUS_MKV_INVALID_CONTENT	invalid_taintent type string length. For more information, see Producer SDK Limits (p. 78).
0x32000005	STATUS_MKV_NUMBER_TOO_BIG	There was an attempt to encode a number that's too large to be represented in EBML (Extensible Binary Meta Language) format. This should not be exposed to the SDK clients.
0x32000006	STATUS_MKV_INVALID_CODEC_1	DnvalNGdodec ID string length. For more information, see Producer SDK Limits (p. 78).
0x32000007	STATUS_MKV_INVALID_TRACK_N	AMEalle Nath name string length. For more information, see Producer SDK Limits (p. 78).
0x32000008	STATUS_MKV_INVALID_CODEC_F	RāvalīcEcdatAGītiivate data length. For more information, see Producer SDK Limits (p. 78).
0x32000009	STATUS_MKV_CODEC_PRIVATE_N	Nulle codec private data (CPD) is NULL, whereas the CPD size is greater than 0.
0x3200000a	STATUS_MKV_INVALID_TIMECOD	Mn&AAL timecode scale value. For more information, see Producer SDK Limits (p. 78).

Code	Message	Description / Recommended Action
0x3200000b	STATUS_MKV_MAX_FRAME	_TIMECODE frame timecode is greater than the maximum. For more information, see Producer SDK Limits (p. 78).
0x3200000c	STATUS_MKV_LARGE_FRA	ME_TIMETED Enax frame timecode was reached. The MKV format uses signed 16 bits to represent the relative timecode of the frame to the beginning of the cluster. The error is generated if the frame timecode cannot be represented. This error indicates either a bad timecode scale selection or the cluster duration is too long, so representing the frame timecode overflows the signed 16-bit space.
0x3200000d	STATUS_MKV_INVALID_A	NNEXB_NAT_LID_ENIGERTANEE_BATTARt code was encountered. For example, the Annex-B adaptation flag was specified and the code encounters an invalid start sequence of more than three zeroes. A valid Annex-B format should have an "emulation prevention" sequence to escape a sequence of three or more zeroes in the bytestream. For more information, see the MPEG specification. For information about this error on Android, see STATUS_MKV_INVALID_ANNEXB_ (0x32000000d) error on Android (p. 182).
0x3200000e	STATUS_MKV_INVALID_A	VCC_NALID <u>v</u> all <u>M_ARCOEN_ANAI</u> Packaging when the adapting AVCC flag is specified. Ensure that the bytestream is in a valid AVCC format. For more information, see the MPEG specification.
0x3200000f	STATUS_MKV_BOTH_ANNE	XB_AND_ <b>Postb</b> (a <u>c</u> <b>b)PEIOTFAVEOC</b> and Annex- B NALs were specified. Specify either one, or specify none.
0x32000010	STATUS_MKV_INVALID_A	NNEXB NAValid Nn@PD-B format of CPD when the adapting Annex-B flag is specified. Ensure that the CPD is in valid Annex-B format. If it is not, then remove the CPD Annex-B adaptation flag.

Code	Message	Description / Recommended Action
0x32000011	STATUS_MKV_PTS_DTS_ARE_NOT	Kinesis Video Streams enforces the PTS (presentation timestamp) and DTS (decoding timestamp) to be the same for the fragment start frames. These are the key frames that start the fragment.
0x32000012	STATUS_MKV_INVALID_H264_H2	প্র <u>ন্</u> যা <b>িটি</b> parse H264/H265 codec private data.
0x32000013	STATUS_MKV_INVALID_H264_H2	<del>የ፮<u>il</u>§d\$<u>o</u>wጀ<b>ው</b>ፑዜቲ the width from the codec private data.</del>
0x32000014	STATUS_MKV_INVALID_H264_H2	ው <u>፯il</u> ዬ <b>ያ ኗ</b> olቴ <b>፯ ፤/Gkt T</b> the height from codec private data.
0x32000015	STATUS_MKV_INVALID_H264_H2	. <b>65</b> <u>v</u> <b>álR</b> 5 <u>H</u> <b>Ω64</b> ØH265 SPS NALu.
0x32000016	STATUS_MKV_INVALID_BIH_CPD	Invalid bitmap info header format in the codec private data.
0x32000017	STATUS_MKV_INVALID_HEVC_NA	Nubvalល់Unigh Efficiency Video Coding (HEVC) Network Abstraction Layer units (NALU) count.
0x32000018	STATUS_MKV_INVALID_HEVC_FO	RMMailid HEVC format.
0x32000019	STATUS_MKV_HEVC_SPS_NALU_M	I <b>ាវ</b> នៃជា <b>វា</b> ឲ្យ HEVC NALUs in the Sequence Parameter Set (SPS).
0x3200001a	STATUS_MKV_INVALID_HEVC_SF	PS <u>n</u> <b>WalldJ<u>H</u>EVZE</b> SPS NALU size.
0x3200001b	STATUS_MKV_INVALID_HEVC_SF	ŶĠĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸĸ
0x3200001c	STATUS_MKV_INVALID_HEVC_SF	영 <u>n</u> 陳祖8年Ħ포VID reserved SPS.
0x3200001d	STATUS_MKV_MIN_ANNEX_B_CPD	Minimum Annex-b codec private beta value size. For H264, this value must be equal to or greater that 11. For H265, this value must be equal to or greater than 15.
0x3200001e	STATUS_MKV_ANNEXB_CPD_MISS	IMis <u>si</u> NAgLddslec private data in Annex-B NALUs.
0x3200001f	STATUS_MKV_INVALID_ANNEXB_	<b>፲ନ</b> 0a <b>lN</b> At <b>ዕ</b> ይec private beta in Annex-B NALUs.
0x32000020	STATUS_MKV_INVALID_TAG_NAM	ዘ <u>በ</u> ሂ <b>ፈዘለ</b> ርቲa <b>ቲ</b> name length. Valid value is greater than zero and less than 128.

Code	Message	Description / Recommended Action
0x32000021	STATUS_MKV_INVALID_TAG_VAL	U <u>fiv</u> alជាជាថ្នាសalue length. valid value is greater than zero and less than 256.
0x32000022	STATUS_MKV_INVALID_GENERAT	OR <u>v</u> alīcAge <u>n</u> eīr <b>a€s</b> r state tags.
0x32000023	STATUS_MKV_INVALID_AAC_CPD	<u>լ</u> ճ <b>AMRLANG_©RIEQ WENG Ye_d MDE</b> X sampling frequency index.
0x32000024	STATUS_MKV_INVALID_AAC_CPD	<u>L ( COMET</u> Grivate data channel configuration.
0x32000025	STATUS_MKV_INVALID_AAC_CPD	Invalid AAC codec private data.
0x32000026	STATUS_MKV_TRACK_INFO_NOT_	_ <b>Hobakl</b> Dinformation not found.
0x32000027	STATUS_MKV_INVALID_SEGMENT	_lbWall0d segment UUID.
0x32000028	STATUS_MKV_INVALID_TRACK_U	I <b>10</b> valid track UID.

## Error and Status Codes Returned by the Trace Library

The following table contains error and status information that is returned by methods in the Trace library.

Code	Message
0×10100001	STATUS_MIN_PROFILER_BUFFER

## Error and Status Codes Returned by the Utils Library

The following table contains error and status information that is returned by methods in the Utils library.

Code	Message
0x40000001	STATUS_INVALID_BASE64_ENCODE
0x40000002	STATUS_INVALID_BASE
0x40000003	STATUS_INVALID_DIGIT
0x40000004	STATUS_INT_OVERFLOW
0x40000005	STATUS_EMPTY_STRING
0×40000006	STATUS_DIRECTORY_OPEN_FAILED
0x40000007	STATUS_PATH_TOO_LONG
0x40000008	STATUS_UNKNOWN_DIR_ENTRY_TYPE
0x40000009	STATUS_REMOVE_DIRECTORY_FAILED

Code	Message
0x4000000a	STATUS_REMOVE_FILE_FAILED
0x4000000b	STATUS_REMOVE_LINK_FAILED
0x4000000c	STATUS_DIRECTORY_ACCESS_DENIED
0x4000000d	STATUS_DIRECTORY_MISSING_PATH
0x4000000e	STATUS_DIRECTORY_ENTRY_STAT_ERROR

# Error and Status Codes Returned by the View Library

The following table contains error and status information that is returned by methods in the View library.

Code	Message	Description
0x30000001	STATUS_MIN_CONTENT_VIEW_IT	EMSinvalid content view item count was specified. For more information, see Producer SDK Limits (p. 78).
0x30000002	STATUS_INVALID_CONTENT_VIE	W <u>r</u> D <b>ሁየ</b> A lid @ ntent view duration was specified. For more information, see Producer SDK Limits (p. 78).
0x30000003	STATUS_CONTENT_VIEW_NO_MOR	R <u>ሉ</u> ፲ <b>፲፻፱</b> ፱6፡pt was made to get past the head position.
0x30000004	STATUS_CONTENT_VIEW_INVAL	DAnī NiDrākid index is specified.
0x30000005	STATUS_CONTENT_VIEW_INVALI	timestamp or a timestamp overlap. The frame decoding timestamp should be greater or equal to the previous frame timestamp, plus the previous frame duration:  `DTS(n) >= DTS(n-1) +  Duration(n-1)`. This error often indicates an "unstable" encoder. The encoder produces a burst of encoded frames, and their timestamps are smaller than the intra-frame durations. Or the stream is configured to use SDK timestamps, and the frames are sent faster than the frame durations. To help with some "jitter" in the encoder, specify a smaller frame duration in the StreamInfo.StreamCaps structure. For example, if the

Code	Message	Description
		stream is 25FPS, each frame's duration is 40 ms. However, to handle the encoder jitter, we recommend that you use half of that frame duration (20 ms). Some streams require more precise control over the timing for error detection.
0x30000006	STATUS_INVALID_CONTENT_VIEW	/_AuEMGālid content view item data length was specified.

# Errors and Status Codes Returned by PutFrame Callbacks - C Producer Library

The following section contains error and status information that is returned by callbacks for the PutFrame operation within the C producer library.

Code	Message	Description	Recommended Action
0×15000001	STATUS_STOP_CALLBACK_	CHAENtallback chain has stopped.	
0x15000002	STATUS_MAX_CALLBACK_C	HATNé maximum callback chain was reached.	
0x15000003	STATUS_INVALID_PLATFO		NSpecify the correct current version of the structure.
0x15000004	STATUS_INVALID_PRODUC		NSpecify the correct current version of the structure.
0x15000005	STATUS_INVALID_STREAM	CONVALIBIACKS_VERSION StreamCallbacks structure version.	Specify the correct current version of the structure.
0×15000006	STATUS_INVALID_AUTH_CA	AllhwaAicKS_VERSION AuthCallbacks structure version.	Specify the correct current version of the structure.
0x15000007	STATUS_INVALID_API_CA	பிக்கில் _VERSION ApiCallbacks structure version.	Specify the correct current version of the structure.
0x15000008	STATUS_INVALID_AWS_CR	EDNEWATUEALS_VERSION AwsCredentials structure version.	Specify the correct current version of the structure.
0x15000009	STATUS_MAX_REQUEST_HE	A <b>DER_roexikT</b> um request header count was reached.	

#### Amazon Kinesis Video Streams Developer Guide Error Code Reference

Code	Message	Description	Recommended Action
0x1500000a	STATUS_MAX_REQUEST_HEA	A <b>Մեռ լ Ի A XI ե</b> ղև <b>r</b> եN request header name length was reached.	
0x1500000b	STATUS_MAX_REQUEST_HEA	A <b>បាក់ខ ្មៅAkidច</b> ឬក់EN request header value length was reached.	
0x1500000c	STATUS_INVALID_API_CAL	.ll <u>n</u> vætitUrætu <u>r</u> 76. <b>03</b> 0N for an API call.	
0x1500000d	STATUS_CURL_INIT_FAILE	Curl initialization failed.	
0x1500000e	STATUS_CURL_LIBRARY_IN	N <b>C</b> U <u>r</u> FMU iriitialization failed.	
0x1500000f	STATUS_INVALID_DESCRIE	B <b>En នៅREAMUREJS QN</b> _JS for DescribeStream.	ON
0×15000010	STATUS_HMAC_GENERATION	l <b>_ਜ਼ਾਪੈੈੈਂਪੈ</b> Rgeneration error.	
0×15000011	STATUS_IOT_FAILED	IOT authorization failed.	
0x15000012	STATUS_MAX_ROLE_ALIAS_	_ <b>ITEN ្ចែងលិចជាបិត</b> Drole alias length was reached.	Specify a shorter alias length.
0x15000013	STATUS_MAX_USER_AGENT_	_ <b>NAME</b> ក្មា <b>នជាតាក្រៅបង្សៀមការ</b> _E name postfix length was reached.	XCEEDED
0x15000014	STATUS_MAX_CUSTOM_USER	R <u>T</u> <b>คัด</b> Eท <b>า</b> สั <u>xi</u> b <b>น</b> ิท <u>า</u> EXCEEDE customer user agent length was reached.	D
0×15000015	STATUS_INVALID_USER_AG	EINMa <u>l</u> idENKEFHagent length.	
0×15000016	STATUS_INVALID_ENDPOIN	NT <u>n</u> va <b>រicHថ្មាស់ក្រ្</b> ថាចិRIOD caching period.	Specify a caching period that is less than 24 hours.
0x15000017	STATUS_IOT_EXPIRATION_	_ <b>00ፒሬቋ</b> ጵ <u>βir</u> ፮ህ <u>o</u> ₱AST timestamp occurs in the past.	
0×15000018	STATUS_IOT_EXPIRATION_	FFARESION C <u>ex</u> PATALLIGID parsing has failed.	

## Network Abstraction Layer (NAL) Adaptation Flag Reference

This section contains information about available flags for the StreamInfo.NalAdaptationFlags enumeration.

The elementary stream in an application can be in either **Annex-B** or **AVCC** format:

- The **Annex-B** format delimits NALUs (Network Abstraction Layer units) with two bytes of zeroes, followed by one or three bytes of zeroes, followed by the number 1 (called a **start code**, for example, 0000001).
- The AVCC format also wraps NALUs, but each NALU is preceded by a value that indicates the size of the NALU (usually four bytes).

Many encoders produce the Annex-B bitstream format. Some higher-level bitstream processors (such as a playback engine or the Media Source Extensions (MSE) player in the AWS Management Console) use the AVCC format for their frames.

The codec private data (CPD), which is SPS/PPS (Sequence Parameter Set/Picture Parameter Set) for the H.264 codec, can also be in Annex-B or AVCC format. However, for the CPD, the formats are different from those described previously.

The flags tell the SDK to adapt the NALUs to AVCC or Annex-B for frame data and CPD as follows:

Flag	Adaptation	
NAL_ADAPTATION_FLAG_NONE	No adaptation	
NAL_ADAPTATION_ANNEXB_NALS	Adapt Annex-B NALUs to AVCC NALUs	
NAL_ADAPTATION_AVCC_NALS	Adapt AVCC NALUs to Annex-B NALUs	
NAL_ADAPTATION_ANNEXB_CPD_	NXdapt Annex-B NALUs for the codec private data to AVCC format NALUs	
NAL_ADAPTATION_ANNEXB_CPD_	AND DEFRICATION NAME AND ALUS FOR the codec and frame private data to AVCC format NALUS	

For more information about NALU types, see **Section 1.3: Network Abstraction Layer Unit Types** in RFC 3984.

## **Producer SDK Structures**

This section includes information about structures that you can use to provide data to the Kinesis Video Streams Producer object.

#### **Topics**

- DeviceInfo/DefaultDeviceInfoProvider (p. 105)
- StorageInfo (p. 105)

### DeviceInfo/DefaultDeviceInfoProvider

The **DeviceInfo** and **DefaultDeviceInfoProvider** objects control the behavior of the Kinesis Video Streams Producer object.

#### **Member Fields**

- version: An integer value used to ensure that the correct version of the structure is used
  with the current version of the code base. The current version is specified using the
  DEVICE\_INFO\_CURRENT\_VERSION macro.
- name: The human-readable name for the device.
- tagCount/tags: Not currently used.
- streamCount: The maximum number of streams that the device can handle. This pre-allocates the storage for pointers to the stream objects initially, but the actual stream objects are created later. The default is 16 streams, but you can change this number in the DefaultDeviceInfoProvider.cpp file
- **storageInfo**: An object that describes the main storage configuration. For more information, see StorageInfo (p. 105).

## StorageInfo

Specifies the configuration of the main storage for Kinesis Video Streams.

The default implementation is based on a low-fragmentation fast heap implementation, which is optimized for streaming. It uses the MEMALLOC allocator, which can be overwritten on a given platform. Some platforms have virtual memory allocation without backing the allocation with physical pages. As the memory is used, the virtual pages are backed by the physical pages. This results in low-memory pressure on the overall system when storage is underused.

Calculate the default storage size based on the following formula. The DefragmentationFactor should be set to 1.2 (20 percent).

```
Size = NumberOfStreams * AverageFrameSize * FramesPerSecond * BufferDurationInSeconds * DefragmentationFactor
```

In the following example, a device has audio and video streams. The audio stream has 512 samples per second, with an average sample of 100 bytes. The video stream has 25 frames per second, with an average of 10,000 bytes. Each stream has 3 minutes of buffer duration.

```
Size = (512 * 100 * (3 * 60) + 25 * 10000 * (3 * 60)) * 1.2 = (9216000 + 45000000) * 1.2 = 65059200 = ~ 66MB.
```

If the device has more available memory, it is recommended that you add more memory to storage to avoid severe fragmentation.

Ensure that the storage size is adequate to accommodate the full buffers for all streams at high encoding complexity (when the frame size is larger due to high motion) or when the bandwidth is low. If the producer hits memory pressure, it emits storage overflow pressure callbacks (StorageOverflowPressureFunc). However, when no memory is available in the content store, it drops the frame that's being pushed into Kinesis Video Streams with an error (STATUS\_STORE\_OUT\_OF\_MEMORY = 0x5200002e). For more information, see Error and Status Codes Returned by the Client Library (p. 81). This can also happen if the application acknowledgements (ACKs) are not available, or the persisted ACKs are delayed. In this case, the buffers fill to the "buffer duration" capacity before the older frames start dropping out.

#### Member Fields

- version: An integer value used to ensure that the correct version of the structure is used with the current version of the code base.
- storageType: A DEVICE\_STORAGE\_TYPE enumeration that specifies the underlying backing/implementation of the storage. Currently the only supported value is DEVICE\_STORAGE\_TYPE\_IN\_MEM. A future implementation will support DEVICE\_STORAGE\_TYPE\_HYBRID\_FILE, indicating that storage falls back to the file-backed content store.
- storageSize: The storage size in bytes to preallocate. The minimum allocation is 10 MB, and the
  maximum allocation is 10 GB. (This will change with the future implementation of the file-backed
  content store.)
- **spillRatio**: An integer value that represents the percentage of the storage to be allocated from the direct memory storage type (RAM), as opposed to the secondary overflow storage (file storage). Not currently used.
- rootDirectory: The path to the directory where the file-backed content store is located. Not currently
  used.

### Kinesis Video Stream Structures

You can use the following structures to provide data to an instance of a Kinesis video stream.

#### **Topics**

- StreamDefinition/ StreamInfo (p. 106)
- ClientMetrics (p. 116)
- StreamMetrics (p. 117)

## StreamDefinition/StreamInfo

The StreamDefinition object in the C++ layer wraps the StreamInfo object in the platform-independent code, and provides some default values in the constructor.

#### Member Fields

Field	Data Type	Description	Default Value
stream_name	string	An optional stream name. For more information about the length of the stream name, see Producer SDK Limits (p. 78) . Each stream should have a unique name.	If no name is specified, a name is generated randomly.
retention_period	<pre>duration<uint64_t, ratio<3600="">&gt;</uint64_t,></pre>	The retention period for the stream, in seconds. Specifying <b>0</b> indicates no retention.	3600 (One hour)
tags	<pre>const map<string, string="">*</string,></pre>	A map of key-value pairs that contain user information. If the	No tags

Field	Data Type	Description	Default Value
		stream already has a set of tags, the new tags are appended to the existing set of tags.	
kms_key_id	string	The AWS KMS key ID to be used for encrypting the stream. For more information, see Data Protection in Kinesis Video Streams (p. 37).	The default KMS key (aws/kinesis-video.)
streaming_type	STREAMING_TYPE enumeration	The only supported value is STREAMING_TYPE_REAL	TIME.
content_type	string	The content format of the stream. The Kinesis Video Streams console can play back content in the video/h264 format.	video/h264
max_latency	duration <uint64_t, milli=""></uint64_t,>	The maximum latency in milliseconds for the stream. The stream latency pressure callback (if specified) is called when the buffer duration exceeds this amount of time. Specifying 0 indicates that no stream latency pressure callback will be called.	milliseconds::zero(

Field	Data Type	Description	Default Value
fragment_duration	duration <uint64_t></uint64_t>	The fragment duration that you want, in seconds. This value is used in combination with the key_frame_fragmenta value. If this value is false, Kinesis Video Streams generates fragments on a key frame after this duration elapses. For example, an Advanced Audio Coding (AAC) audio stream has each frame as a key frame. Specifying key_frame_fragmenta = false causes fragmentation to happen on a key frame after this duration expires, resulting in 2-second fragments.	

Field	Data Type	Description	Default Value
timecode_scale	<pre>duration<uint64_t, milli=""></uint64_t,></pre>	The MKV timecode scale in milliseconds, which specifies the granularity of the timecodes for the frames within the MKV cluster. The MKV frame timecode is always relative to the start of the cluster. MKV uses a signed 16-bit value (0-32767) to represent the timecode within the cluster (fragment). Therefore, you should ensure that the frame timecode can be represented with the given timecode scale. The default timecode scale value of 1 ms ensures that the largest frame that can be represented is 32767 ms ~= 32 seconds. This is over the maximum fragment duration that is specified in Kinesis Video Streams Limits (p. 168), which is 10 seconds.	1
key_frame_fragmentation	pribool	Whether to produce fragments on a key frame. If true, the SDK produces a start of the fragment every time there is a key frame. If false, Kinesis Video Streams waits for at least fragment_duration and produces a new fragment on the key frame following it.	true

Field	Data Type	Description	Default Value
frame_timecodes	bool	Whether to use frame timecodes or generate timestamps using the current time callback. Many encoders don't produce timestamps with the frames. So specifying false for this parameter ensures that the frames are timestamped as they are put into Kinesis Video Streams.	true
absolute_fragment_time	esbool	Kinesis Video Streams uses MKV as its underlying packaging mechanism. The MKV specification is strict about frame timecodes being relative to the beginning of the cluster (fragment). However, the cluster timecodes can be either absolute or relative to the starting time for the stream. If the timestamps are relative, the PutMedia service API call uses the optional stream start timestamp and adjust the cluster timestamps. The service always stores the fragments with their absolute timestamps.	true
fragment_acks	bool	Whether to receive application level fragment ACKs (acknowledgements) or not.	true, meaning that the SDK will receive the ACKs and act accordingly.
restart_on_error	bool	Whether to restart on specific errors.	true, meaning that the SDK tries to restart the streaming if any errors occur.

Field	Data Type	Description	Default Value
recalculate_metrics	bool	Whether to recalculate the metrics. Each call to retrieve the metrics can recalculate those to get the latest "running" value, which might create a small CPU impact. You might need to set this to false on extremely low-power/footprint devices to spare the CPU cycles. Otherwise, it's not advised to use false for this value.	true

Field	Data Type	Description	Default Value
nal_adaptation_flags	uint32_t	Specifies the Network Abstraction Layer unit (NALU) adaptation flags. If the bitstream is H.264 encoded, it can then be processed as raw or packaged in NALUs. Those are either in the Annex-B or AVCC format. Most of the elementary stream producers/ consumers (read encoders/decoders) use the Annex-B format because it has some advantages, such as error recovery. Higherlevel systems use the AVCC format, which is the default format for MPEG, HLS, DASH, and so on. The console playback uses the browser's MSE (media source extensions) to decode and play back the stream that uses the AVCC format. For H.264 (and for M-JPEG and H.265), the SDK provides adaptation capabilities.  Many elementary streams are in the following format. In this example, Ab is the Annex-B start code (001 or 0001).  Ab(Sps)Ab(Pps)Ab(I-frame)Ab(P/B-frame)Ab(P/B-frame)Ab(P/B-frame) Ab(P/B-frame)	The default is to adapt Annex-B format to AVCC format for both the frame data and for the codec private data.

Field	Data Type	Description	Default Value
		be adapted to the AVCC format. Unless the media pipeline gives the CPD separately, the application can extract the CPD from the frame. It can do this by looking for the first IDR frame (which should contain the SPS/PPS), extract the two NALUs (which are Ab(Sps)Ab(Pps)), and set it in the CPD in StreamDefinition.  For more information, see NAL Adaptation Flags (p. 104).	
frame_rate	uint32_t	The expected frame rate. This value is used to better calculate buffering needs.	25
avg_bandwidth_bps	uint32_t	The expected average bandwidth for the stream. This value is used to better calculate buffering needs.	4 * 1024 * 1024

Field	Data Type	Description	Default Value
buffer_duration	duration <uint64_t></uint64_t>	The stream buffer duration, in seconds. The SDK keeps the frames in the content store for up to the buffer_duration, after which the older frames are dropped as the window moves forward. If the frame that is being dropped has not been sent to the backend, the dropped frame callback is called. If the current buffer duration is greater than max_latency, then the stream latency pressure callback is called. The buffer is trimmed to the next fragment start when the fragment persisted ACK is received. This indicates that the content has been durably persisted in the cloud, so storing the content on the local device is no longer needed.	120

Field	Data Type	Description	Default Value
replay_duration	duration <uint64_t></uint64_t>	The duration to roll the current reader backward to replay during an error if restarting is enabled, in seconds. The rollback stops at the buffer start (in case it has just started streaming or the persisted ACK has come along). The rollback tries to land on a key frame that indicates a fragment start. If the error that is causing the restart is not indicative of a dead host (that is, the host is still alive and contains the frame data in its internal buffers), the rollback stops at the last received ACK frame. It then rolls forward to the next key frame, because the entire fragment is already stored in the host memory.	40
connection_staleness	<pre>duration<uint64_t></uint64_t></pre>	The time, in seconds, after which the stream staleness callback is called if the SDK does not receive the buffering ACK. It indicates that the frames are being sent from the device, but the backend is not acknowledging them. This condition indicates a severed connection at the intermediate hop or at the load balancer.	30
codec_id	string	The codec ID for the MKV track.	V_MPEG4/ISO/AVC
track_name	string	The MKV track name.	kinesis_video

Field	Data Type	Description	Default Value
codecPrivateData	unsigned char*	The codec private data (CPD) buffer. If the media pipeline has the information about the CPD before the stream starts, it can be set in StreamDefinition.co The bits are copied, and the buffer can be reused or freed after the call to create the stream. However, if the data is not available when the stream is created, it can be set in one of the overloads of the KinesisVideoStream. function.	
codecPrivateDataSize	uint32_t	The codec private data buffer size.	0

## ClientMetrics

The  ${\bf ClientMetrics}$  object is filled by calling getKinesisVideoMetrics.

### **Member Fields**

Field	Data Type	Description	
version	UINT32	The version of the structure, defined in the CLIENT_METRICS_CURRENT_VER macro.	
contentStoreSize	UINT64	The overall content store size in bytes. This is the value specified in DeviceInfo.StorageInfo.sto	
contentStoreAvailableSize	UINT64	Currently available storage size in bytes.	
contentStoreAllocatedSize	UINT64	Currently allocated size. The allocated plus the available sizes should be slightly smaller than the overall storage size, due to the internal bookkeeping and the implementation of the content store.	
totalContentViewsSize	UINT64	The size of the memory allocated for all content views	

Field	Data Type	Description
		for all streams. This is not counted against the storage size. This memory is allocated using the MEMALLOC macro, which can be overwritten to provide a custom allocator.
totalFrameRate	UINT64	The total observed frame rate across all the streams.
totalTransferRate	UINT64	The total observed stream rate in bytes per second across all the streams.

## **StreamMetrics**

The **StreamMetrics** object is filled by calling getKinesisVideoMetrics.

#### **Member Fields**

Field	Data Type	Description	
version	UINT32	The version of the structure, defined in the STREAM_METRICS_CURRENT_VERS macro.	
currentViewDuration	UINT64	The duration of the accumulated frames. In the fast networking case, this duration is either 0 or the frame duration (as the frame is being transmitted). If the duration becomes longer than the max_latency specified in the StreamDefinition, the stream latency callback is called if it is specified. The duration is specified in 100 ns units, which is the default time unit for the PIC layer.	
overallViewDuration	UINT64	The overall view duration. If the stream is configured with no ACKs or persistence, this value grows as the frames are put into the Kinesis video stream and becomes equal to the buffer_duration in the StreamDefinition. When ACKs are enabled and the persisted ACK is received, the buffer is trimmed to the next key frame, because the ACK timestamp indicates	

Field	Data Type	Description	
		the beginning of the entire fragment. The duration is specified in 100-ns units, which is the default time unit for the PIC layer.	
currentViewSize	UINT64	The size in bytes of the current buffer.	
overallViewSize	UINT64	The overall view size in bytes.	
currentFrameRate	UINT64	The observed frame rate for the current stream.	
currentTransferRate	UINT64	The observed transfer rate in bytes per second for the current stream.	


### **Producer SDK Callbacks**

The classes and methods in the Amazon Kinesis Video Streams Producer SDK do not maintain their own processes. Instead, they use the incoming function calls and events to schedule callbacks to communicate with the application.

There are two callback patterns that the application can use to interact with the SDK:

- CallbackProvider: This object exposes every callback from the platform-independent code (PIC) component to the application. This pattern allows full functionality, but it also means that the implementation must handle all of the public API methods and signatures in the C++ layer.
- StreamCallbackProvider (p. 119) and ClientCallbackProvider (p. 119): These objects expose the stream-specific and client-specific callbacks, and the C++ layer of the SDK exposes the rest of the callbacks. This is the preferred callback pattern for interacting with the Producer SDK.

The following diagram illustrates the object model of the callback objects:



In the preceding diagram, DefaultCallbackProvider derives from CallbackProvider (which exposes all of the callbacks in the PIC) and contains StreamCallbackProvider and ClientCallbackProvider.

#### This topic contains the following sections:

- ClientCallbackProvider (p. 119)
- StreamCallbackProvider (p. 119)

- ClientCallbacks Structure (p. 119)
- Callback Implementations to Retry Streaming (p. 122)

#### ClientCallbackProvider

The ClientCallbackProvider object exposes client-level callback functions. The details of the functions are described in the ClientCallbacks (p. 119) section.

#### Callback methods:

- getClientReadyCallback: Reports a ready state for the client.
- getStorageOverflowPressureCallback: Reports storage overflow or pressure. This callback is called when the storage utilization drops below the STORAGE\_PRESSURE\_NOTIFICATION\_THRESHOLD value, which is 5 percent of the overall storage size. For more information, see StorageInfo (p. 105).

#### StreamCallbackProvider

The StreamCallbackProvider object exposes stream-level callback functions.

#### Callback methods:

- getDroppedFragmentReportCallback: Reports a dropped fragment.
- getDroppedFrameReportCallback: Reports a dropped frame.
- getFragmentAckReceivedCallback: Reports that a fragment ACK is received for the stream.
- getStreamClosedCallback: Reports a stream closed condition.
- getStreamConnectionStaleCallback: Reports a stale connection condition. In this condition, the producer is sending data to the service but is not receiving acknowledgements.
- getStreamDataAvailableCallback: Reports that data is available in the stream.
- getStreamErrorReportCallback: Reports a stream error condition.
- getStreamLatencyPressureCallback: Reports a stream latency condition, which is when the accumulated buffer size is larger than the max\_latency value. For more information, see StreamDefinition/ StreamInfo (p. 106).
- getStreamReadyCallback: Reports a stream ready condition.
- getStreamUnderflowReportCallback: Reports a stream underflow condition. This function is not currently used and is reserved for future use.

For the source code for StreamCallbackProvider, see StreamCallbackProvider.h.

#### ClientCallbacks Structure

The ClientCallbacks structure contains the callback function entry points that the PIC calls when specific events occur. The structure also contains version information in the CALLBACKS\_CURRENT\_VERSION field, and a customData field for user-defined data that is returned with the individual callback functions.

The client application can use a this pointer for the custom\_data field to map member functions to the static ClientCallback functions at runtime, as shown in the following code example:

```
STATUS TestStreamCallbackProvider::streamClosedHandler(UINT64 custom_data, STREAM_HANDLE
    stream_handle, UINT64 stream_upload_handle) {
      LOG_INFO("Reporting stream stopped.");
```

TestStreamCallbackProvider\* streamCallbackProvider =
 reinterpret\_cast<TestStreamCallbackProvider\*> (custom\_data);
streamCallbackProvider->streamClosedHandler(...);

#### **Events**

Function	Description	Туре
CreateDeviceFunc	Not currently implemented on the backend. This call fails when called from Java or C++. Other clients perform platform- specific initialization.	Backend API
CreateStreamFunc	Called when the stream is created.	Backend API
DescribeStreamFunc	Called when DescribeStream is called.	Backend API
GetStreamingEndpointFunc	Called when GetStreamingEndpoint is called.	Backend API
GetStreamingTokenFunc	Called when GetStreamingToken is called.	Backend API
PutStreamFunc	Called when PutStream is called.	Backend API
TagResourceFunc	Called when TagResource is called.	Backend API
CreateMutexFunc	Creates a synchronization mutex.	Synchronization
FreeMutexFunc	Frees the mutex.	Synchronization
LockMutexFunc	Locks the synchronization mutex.	Synchronization
TryLockMutexFunc	Tries to lock the mutex. Not currently implemented.	Synchronization
UnlockMutexFunc	Unlocks the mutex.	Synchronization
ClientReadyFunc	Called when the client enters a ready state.	Notification
DroppedFrameReportFunc	Reports when a frame is dropped.	Notification
DroppedFragmentReportFunc	Reports when a fragment is dropped. This function is not currently used and is reserved for future use.	Notification

Function	Description	Туре
FragmentAckReceivedFunc	Called when a fragment ACK (buffering, received, persisted, and error) is received.	Notification
StorageOverflowPressureFur	Called when the storage utilization drops below the STORAGE_PRESSURE_NOTIFICAT value, which is defined as 5 percent of the overall storage size.	Notification TION_THRESHOLD
StreamClosedFunc	Called when the last bits of the remaining frames are streamed.	Notification
StreamConnectionStaleFunc	Called when the stream enters a stale connection state. In this condition, the producer is sending data to the service but is not receiving acknowledgements.	Notification
StreamDataAvailableFunc	Called when stream data is available.	Notification
StreamErrorReportFunc	Called when a stream error occurs. The PIC automatically closes the stream under this condition.	Notification
StreamLatencyPressureFunc	Called when the stream enters a latency condition, which is when the accumulated buffer size is larger than the max_latency value. For more information, see StreamDefinition/StreamInfo (p. 106).	Notification
StreamReadyFunc	Called when the stream enters the ready state.	Notification
StreamUnderflowReportFunc	This function is not currently used and is reserved for future use.	Notification
DeviceCertToTokenFunc	Returns the connection	Platform integration
	certificate as a token.	
GetCurrentTimeFunc	Returns the current time.	Platform integration
GetDeviceCertificateFunc	Returns the device certificate. This function is not currently used and is reserved for future use.	Platform integration

Function	Description	Туре
GetDeviceFingerprintFunc	Returns the device fingerprint. This function is not currently used and is reserved for future use.	Platform integration
GetRandomNumberFunc	Returns a random number between 0 and RAND_MAX.	Platform integration
GetSecurityTokenFunc	Returns the security token that is passed to the functions that communicate with the backend API. The implementation can specify the serialized AccessKeyId, SecretKeyId, and the session token.	Platform integration
LogPrintFunc	Logs a line of text with the tag and the log level. For more information, see PlatformUtils.h.	Platform integration

For the platform integration functions in the preceding table, the last parameter is a ServiceCallContext structure, which has the following fields:

- version: The version of the struct.
- callAfter: An absolute time after which to call the function.
- timeout: The timeout of the operation in 100 nanosecond units.
- customData: A user-defined value to be passed back to the client.
- pAuthInfo: The credentials for the call. For more information, see the following (\_\_AuthInfo) structure.

The authorization information is provided using the \_\_AuthInfo structure, which can be either serialized credentials or a provider-specific authentication token. This structure has the following fields:

- version: The version of the \_\_AuthInfo structure.
- type: An AUTH\_INFO\_TYPE value defining the type of the credential (certificate or security token).
- data: A byte array containing the authentication information.
- size: The size of the data parameter.
- expiration: The expiration of the credentials in 100 nanosecond units.

## Callback Implementations to Retry Streaming

The Kinesis Video Producer SDK provides the status of streaming through callback functions. It is recommended that you implement the following callback mechanisms to recover from any momentary network issues encountered during streaming.

• Stream latency pressure callback - this callback mechanism gets initiated when the SDK encounters a stream latency condition. This happens when the accumulated buffer size is larger than the MAX\_LATENCY value. When the stream is created, the streaming application sets MAX\_LATENCY to the default value of 60 seconds. The typical implementation for this callback is to reset the connection. You can use the sample implementation at <a href="https://github.com/awslabs/amazon-">https://github.com/awslabs/amazon-</a>

kinesis-video-streams-producer-sdk-cpp/blob/master/kinesis-video-c-producer/src/source/ StreamLatencyStateMachine.c as needed. Note that there is no option to store the frames undelivered due to network outage into a secondary storage for back-fill.

- Stream staleness callback this callback gets initiated when the producer can send data to the Amazon Kinesis Data Streams service (uplink) but it's not able to get the acknowledgements (buffered ACK) back in time (default is 60 seconds). Depending on the network settings, either the stream latency pressure callback or the stream staleness callback, or both can get initiated. Similar to the stream latency pressure callback retry implementation, the typical implementation is to reset the connection and start a new connection for streaming. You can use the sample implementation at <a href="https://github.com/awslabs/amazon-kinesis-video-streams-producer-c/blob/master/src/source/ConnectionStaleStateMachine.c">https://github.com/awslabs/amazon-kinesis-video-streams-producer-c/blob/master/src/source/ConnectionStaleStateMachine.c</a> as needed.
- Stream error callback this callback gets initiated when the SDK encounters a timeout on the network connection or other errors during the call to the KVS API service calls.
- **Dropped frame callback** this callback gets initiated when the storage size is full either because of slow network speed or a stream error. If the network speed results in dropped frames, then you can either increase the storage size, reduce the video frame size or frame rate to match the network speed.

## Kinesis Video Stream Parser Library

The Kinesis Video Stream Parser Library is an easy-to-use set of tools you can use in Java applications to consume the MKV data in a Kinesis video stream.

The library includes the following tools:

- StreamingMkvReader (p. 125): This class reads specified MKV elements from a video stream.
- FragmentMetadataVisitor (p. 126): This class retrieves metadata for fragments (media elements) and tracks (individual data streams containing media information, such as audio or subtitles).
- OutputSegmentMerger (p. 127): This class merges consecutive fragments or chunks in a video stream.
- KinesisVideoExample (p. 128): This is a sample application that shows how to use the Kinesis Video Stream Parser Library.

The library also includes tests that show how the tools are used.

## Procedure: Using the Kinesis Video Stream Parser Library

This procedure includes the following steps:

- the section called "Step 1: Download and Configure the Code" (p. 125)
- the section called "Step 2: Write and Examine the Code" (p. 125)
- the section called "Step 3: Run and Verify the Code" (p. 130)

## **Prerequisites**

You must have the following to examine and use the Kinesis Video Stream Parser Library:

- An Amazon Web Services (AWS) account. If you don't already have an AWS account, do the following:
  - Open https://aws.amazon.com/, and then choose Create an AWS Account.

#### Note

This might be unavailable in your browser if you previously signed in to the AWS Management Console. In that case, choose **Sign In to the Console**, and then choose **Create a new AWS account**.

· Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a PIN using the phone keypad.

Note your AWS account ID because you need it for configuring programmatic access to Kinesis video streams.

• A Java integrated development environment (IDE), such as Eclipse Java Neon or JetBrains IntelliJ Idea.

## Step 1: Download and Configure the Code

In this section, you download the Java library and test code, and import the project into your Java IDE.

For prerequisites and other details about this procedure, see Stream Parser Library (p. 124).

1. Create a directory and clone the library source code from the GitHub repository (https://github.com/aws/amazon-kinesis-video-streams-parser-library).

```
$ git clone https://github.com/aws/amazon-kinesis-video-streams-parser-library
```

- 2. Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA) and import the Apache Maven project that you downloaded:
  - In Eclipse: Choose File, Import, Maven, Existing Maven Projects, and navigate to the kinesis-video-streams-parser-lib folder.
  - In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

For more information, see the related IDE documentation.

## **Next Step**

the section called "Step 2: Write and Examine the Code" (p. 125)

## Step 2: Write and Examine the Code

In this section, you examine the Java library and test code, and learn how to use the tools from the library in your own code.

The Kinesis Video Stream Parser Library contains the following tools:

- StreamingMkvReader (p. 125)
- FragmentMetadataVisitor (p. 126)
- OutputSegmentMerger (p. 127)
- KinesisVideoExample (p. 128)

## StreamingMkvReader

This class reads specified MKV elements from a stream in a non-blocking way.

The following code example (from FragmentMetadataVisitorTest) shows how to create and use a Streaming MkvReader to retrieve MkvElement objects from an input stream called inputStream:

```
while (mkvStreamReader.mightHaveNext()) {
    Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
    if (mkvElement.isPresent()) {
        mkvElement.get().accept(fragmentVisitor);
        ...
     }
    }
}
```

## FragmentMetadataVisitor

This class retrieves metadata for fragments (media elements) and tracks (individual data streams containing media information, such as codec private data, pixel width, or pixel height).

The following code example (from the FragmentMetadataVisitorTest file) shows how to use FragmentMetadataVisitor to retrieve data from a MkvElement object:

```
FragmentMetadataVisitor fragmentVisitor = FragmentMetadataVisitor.create();
       StreamingMkvReader mkvStreamReader =
                StreamingMkvReader.createDefault(new InputStreamParserByteSource(in));
        int segmentCount = 0;
       while(mkvStreamReader.mightHaveNext()) {
            Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
            if (mkvElement.isPresent()) {
                mkvElement.get().accept(fragmentVisitor);
(MkvTypeInfos.SIMPLEBLOCK.equals(mkvElement.get().getElementMetaData().getTypeInfo())) {
                    MkvDataElement dataElement = (MkvDataElement) mkvElement.get();
                    Frame frame = ((MkvValue<Frame>)dataElement.getValueCopy()).getVal();
                    MkvTrackMetadata trackMetadata =
fragmentVisitor.getMkvTrackMetadata(frame.getTrackNumber());
                    assertTrackAndFragmentInfo(fragmentVisitor, frame, trackMetadata);
                if
(MkvTypeInfos.SEGMENT.equals(mkvElement.get().getElementMetaData().getTypeInfo())) {
                    if (mkvElement.get() instanceof MkvEndMasterElement) {
                        if (segmentCount < continuationTokens.size()) {</pre>
                            Optional<String> continuationToken =
fragmentVisitor.getContinuationToken();
                            Assert.assertTrue(continuationToken.isPresent());
                            Assert.assertEquals(continuationTokens.get(segmentCount),
continuationToken.get());
                        segmentCount++;
                }
            }
       }
```

The preceding example shows the following coding pattern:

- Create a FragmentMetadataVisitor to parse the data, and a StreamingMkvReader (p. 125) to provide the data.
- For each MkvElement in the stream, test if its metadata is of type SIMPLEBLOCK.
- If it is, retrieve the MkvDataElement from the MkvElement.
- Retrieve the Frame (media data) from the MkvDataElement.
- Retrieve the MkvTrackMetadata for the Frame from the FragmentMetadataVisitor.
- Retrieve and verify the following data from the Frame and MkvTrackMetadata objects:

#### Amazon Kinesis Video Streams Developer Guide OutputSegmentMerger

- · The track number.
- The frame's pixel height.
- · The frame's pixel width.
- The codec ID for the codec used to encode the frame.
- That this frame arrived in order. That is, verify that the track number of the previous frame, if
  present, is less than that of the current frame.

To use FragmentMetadataVisitor in your project, pass MkvElement objects to the visitor using their accept method:

```
mkvElement.get().accept(fragmentVisitor);
```

## OutputSegmentMerger

This class merges metadata from different tracks in the stream into a stream with a single segment.

The following code example (from the FragmentMetadataVisitorTest file) shows how to use OutputSegmentMerger to merge track metadata from a byte array called inputBytes:

```
FragmentMetadataVisitor fragmentVisitor = FragmentMetadataVisitor.create();
ByteArrayOutputStream outputStream = new ByteArrayOutputStream();
OutputSegmentMerger outputSegmentMerger =
    OutputSegmentMerger.createDefault(outputStream);
CompositeMkvElementVisitor compositeVisitor =
    new TestCompositeVisitor(fragmentVisitor, outputSegmentMerger);
final InputStream in = TestResourceUtil.getTestInputStream("output_get_media.mkv");
StreamingMkvReader mkvStreamReader =
    StreamingMkvReader.createDefault(new InputStreamParserByteSource(in));
while (mkvStreamReader.mightHaveNext()) {
    Optional<MkvElement> mkvElement = mkvStreamReader.nextIfAvailable();
    if (mkvElement.isPresent()) {
        mkvElement.get().accept(compositeVisitor);
 (MkvTypeInfos.SIMPLEBLOCK.equals(mkvElement.get().getElementMetaData().getTypeInfo())) {
        MkvDataElement dataElement = (MkvDataElement) mkvElement.get();
        Frame frame = ((MkvValue<Frame>) dataElement.getValueCopy()).getVal();
        Assert.assertTrue(frame.getFrameData().limit() > 0);
        MkvTrackMetadata trackMetadata =
 fragmentVisitor.getMkvTrackMetadata(frame.getTrackNumber());
        assertTrackAndFragmentInfo(fragmentVisitor, frame, trackMetadata);
    }
}
```

The preceding example shows the following coding pattern:

- Create a FragmentMetadataVisitor (p. 126)to retrieve the metadata from the stream.
- Create an output stream to receive the merged metadata.
- Create an OutputSegmentMerger, passing in the ByteArrayOutputStream.
- Create a CompositeMkvElementVisitor that contains the two visitors.
- Create an InputStream that points to the specified file.

· Merge each element in the input data into the output stream.

## KinesisVideoExample

This is a sample application that shows how to use the Kinesis Video Stream Parser Library.

This class performs the following operations:

- Creates a Kinesis video stream. If a stream with the given name already exists, the stream is deleted and recreated.
- Calls PutMedia to stream video fragments to the Kinesis video stream.
- Calls GetMedia to stream video fragments out of the Kinesis video stream.
- Uses a StreamingMkvReader (p. 125) to parse the returned fragments on the stream, and uses a FragmentMetadataVisitor (p. 126) to log the fragments.

#### Delete and recreate the stream

The following code example (from the StreamOps.java file) deletes a given Kinesis video stream:

```
//Delete the stream
amazonKinesisVideo.deleteStream(new
DeleteStreamRequest().withStreamARN(streamInfo.get().getStreamARN()));
```

The following code example (from the StreamOps.java file) creates a Kinesis video stream with the specified name:

```
amazonKinesisVideo.createStream(new CreateStreamRequest().withStreamName(streamName)
.withDataRetentionInHours(DATA_RETENTION_IN_HOURS)
.withMediaType("video/h264"));
```

#### Call PutMedia

The following code example (from the PutMediaWorker. java file) calls PutMedia on the stream:

```
putMedia.putMedia(new PutMediaRequest().withStreamName(streamName)
.withFragmentTimecodeType(FragmentTimecodeType.RELATIVE)
.withProducerStartTimestamp(new Date())
.withPayload(inputStream), new PutMediaAckResponseHandler() {
...
});
```

#### Call GetMedia

The following code example (from the GetMediaWorker. java file) calls GetMedia on the stream:

```
GetMediaResult result = videoMedia.getMedia(new
GetMediaRequest().withStreamName(streamName).withStartSelector(startSelector));
```

#### Parse the GetMedia result

This section describes how to use StreamingMkvReader (p. 125), FragmentMetadataVisitor (p. 126) and CompositeMkvElementVisitor to parse, save to file, and log the data returned from GetMedia.

#### Read the output of GetMedia with StreamingMkvReader

The following code example (from the GetMediaWorker.java file) creates a StreamingMkyReader (p. 125) and uses it to parse the result from the GetMedia operation:

```
StreamingMkvReader mkvStreamReader = StreamingMkvReader.createDefault(new
InputStreamParserByteSource(result.getPayload()));
log.info("StreamingMkvReader created for stream {} ", streamName);
try {
    mkvStreamReader.apply(this.elementVisitor);
} catch (MkvElementVisitException e) {
    log.error("Exception while accepting visitor {}", e);
}
```

In the preceding code example, the StreamingMkvReader (p. 125) retrieves MKVElement objects from the payload of the GetMedia result. In the next section, the elements are passed to a FragmentMetadataVisitor (p. 126).

#### Retrieve Fragments with FragmentMetadataVisitor

The following code examples (from the KinesisVideoExample.java and StreamingMkvReader.java files) create a FragmentMetadataVisitor (p. 126). The MkvElement objects iterated by the StreamingMkvReader (p. 125) are then passed to the visitor using the accept method.

from KinesisVideoExample.java:

```
FragmentMetadataVisitor fragmentMetadataVisitor = FragmentMetadataVisitor.create();
```

from StreamingMkvReader.java:

```
if (mkvElementOptional.isPresent()) {
   //Apply the MkvElement to the visitor
   mkvElementOptional.get().accept(elementVisitor);
   }
```

#### Log the elements and write them to a file

The following code example (from the KinesisVideoExample.java file) creates the following objects and returns them as part of the return value of the GetMediaProcessingArguments function:

- A LogVisitor (an extension of MkvElementVisitor) that writes to the system log.
- An OutputStream that writes the incoming data to an MKV file.
- A BufferedOutputStream that buffers data bound for the OutputStream.
- An the section called "OutputSegmentMerger" (p. 127) that merges consecutive elements in the GetMedia result with the same track and EBML data.
- A CompositeMkvElementVisitor that composes the FragmentMetadataVisitor (p. 126), the section called "OutputSegmentMerger" (p. 127), and LogVisitor into a single element visitor

```
//A visitor used to log as the GetMedia stream is processed.
LogVisitor logVisitor = new LogVisitor(fragmentMetadataVisitor);
```

#### Amazon Kinesis Video Streams Developer Guide Next Step

The media processing arguments are then passed into the GetMediaWorker, which is in turn passed to the ExecutorService which executes the worker on a separate thread:

## **Next Step**

the section called "Step 3: Run and Verify the Code" (p. 130)

## Step 3: Run and Verify the Code

The Kinesis Video Stream Parser Library contains tools that are intended for you to use in your own projects. The project contains unit tests for the tools that you can run to verify your installation.

The following unit tests are included in the library:

- mkv
  - ElementSizeAndOffsetVisitorTest
  - MkvValueTest
  - StreamingMkvReaderTest
- utilities
  - FragmentMetadataVisitorTest
  - OutputSegmentMergerTest

# Amazon Kinesis Video Streams Examples

The following code examples demonstrate how to work with the Kinesis Video Streams API:

## **Examples: Sending Data to Kinesis Video Streams**

- Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 132): Shows how to build the Kinesis Video Streams Producer SDK to use as a GStreamer destination.
- Run the GStreamer Element in a Docker Container (p. 135): Shows how to use a pre-built Docker image for sending RTSP video from an IP camera to Kinesis Video Streams.
- Example: Streaming from an RTSP Source (p. 143): Shows how to build your own Docker image and send RTSP video from an IP camera to Kinesis Video Streams.
- Example: Sending Data to Kinesis Video Streams Using the PutMedia API (p. 140): Shows how to use the Using the Java Producer Library (p. 54) to send data to Kinesis Video Streams that is already in a container format (MKV) using the PutMedia API.

## Examples: Retrieving Data from Kinesis Video Streams

- KinesisVideoExample (p. 128): Shows how to parse and log video fragments using the Kinesis Video Streams Parser Library.
- Example: Parsing and Rendering Kinesis Video Streams Fragments (p. 145): Shows how to parse and render Kinesis video stream fragments using JCodec and JFrame.
- the section called "SageMaker" (p. 147): Demonstrates a solution that uses SageMaker to determine when certain objects appear in a video stream.

## **Examples: Playing Back Video Data**

• Example: Using HLS in HTML and JavaScript (p. 10): Shows how to retrieve an HLS streaming session for a Kinesis video stream and play it back in a webpage.

## **Prerequisites**

- In the sample code, you provide credentials by specifying a profile that you set in your AWS
  credentials profile file, or by providing credentials in the Java system properties of your integrated
  development environment (IDE). So if you haven't already done so, first set up your credentials. For
  more information, see Set up AWS Credentials and Region for Development.
- We recommend that you use a Java IDE to view and run the code, such as one of the following:
  - Eclipse Java Neon

· JetBrains IntelliJ IDEA

## Example: Kinesis Video Streams Producer SDK GStreamer Plugin

This topic shows how to build the Amazon Kinesis Video Streams Producer SDK to use as a GStreamer plugin.

#### **Topics**


- Download, Build, and Configure the GStreamer Element (p. 133)
- Run the GStreamer Element (p. 133)
- Example GStreamer Launch Commands (p. 133)
- Run the GStreamer Element in a Docker Container (p. 135)
- GStreamer Element Parameter Reference (p. 137)

GStreamer is a popular media framework used by a multitude of cameras and video sources to create custom media pipelines by combining modular plugins. The Kinesis Video Streams GStreamer plugin greatly simplifies the integration of your existing GStreamer media pipeline with Kinesis Video Streams. After integrating GStreamer, you can get started with streaming video from a webcam or RTSP (Real Time Streaming Protocol) camera to Kinesis Video Streams for real-time or later playback, storage, and further analysis.

The GStreamer plugin automatically manages the transfer of your video stream to Kinesis Video Streams by encapsulating the functionality provided by the Kinesis Video Streams Producer SDK in a GStreamer sink element, kvssink. The GStreamer framework provides a standard managed environment for constructing media flow from a device such as a camera or other video source for further processing, rendering, or storage.

The GStreamer pipeline typically consists of the link between a source (video camera) and the sink element (either a player to render the video, or storage for offline retrieval). In this example, you use the Producer SDK element as a *sink*, or media destination, for your video source (webcam or IP camera). The plugin element that encapsulates the SDK then manages sending the video stream to Kinesis Video Streams.

This topic shows how to construct a GStreamer media pipeline capable of streaming video from a video source, such as a web camera or RTSP stream, typically connected through intermediate encoding stages (using H.264 encoding) to Kinesis Video Streams. When your video stream is available as a Kinesis video stream, you can use the Kinesis Video Stream Parser Library for further processing, playback, storage, or analysis of your video stream.



## Download, Build, and Configure the GStreamer Flement

The GStreamer Plugin example is included with the Kinesis Video Streams C++ Producer SDK. For information about SDK prerequisites and downloading, see Step 1: Download and Configure the C++ Producer Library Code (p. 65).

You can build the Producer SDK GStreamer sink as a dynamic library on macOS, Ubuntu, Raspberry Pi, or Windows. The GStreamer plugin is located in your build directory. To load this plugin, it needs to be in your GST\_PLUGIN\_PATH. Run the following command:

export GST\_PLUGIN\_PATH=`pwd`/build

### Run the GStreamer Element

To run GStreamer with the Kinesis Video Streams Producer SDK element as a sink, execute the gst-launch-1.0 command. Use settings that are appropriate for the GStreamer plugin to use. For example, v4l2src for v4l2 devices on Linux systems, or rtspsrc for RTSP devices. Specify kvssink as the sink (final destination of the pipeline) to send video to the Producer SDK.

The kvssink element has the following required parameters:

- stream-name: The name of the destination Kinesis video stream.
- storage-size: The storage size of the device in kilobytes. For information about configuring device storage, see StorageInfo (p. 105).
- access-key: The AWS access key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- secret-key: The AWS secret key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- credential-path: A path to a file containing your credentials for accessing Kinesis Video Streams. For more information on rotating credentials, see Managing Access Keys for IAM Users. You must provide either this parameter or access-key and secret-key.

For information about kvssink optional parameters, see GStreamer Element Parameter Reference (p. 137).

For the latest information about GStreamer plugins and parameters, see GStreamer Plugins, or execute the following command to list options:

gst-inspect-1.0 kvssink

If the build failed or GST\_PLUGIN\_PATH is not properly set, your output looks similar to this:

No such element or plugin 'kvssink'

## **Example GStreamer Launch Commands**

These examples demonstrate how to use a GStreamer plugin to stream video from different types of devices.

### Example 1: Stream Video from an RTSP Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that streams from a network RTSP camera, using the rtspsrc GStreamer plugin:

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
  rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

## Example 2: Encode and Stream Video from a USB Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that encodes the stream from a USB camera in H.264 format, and streams it to Kinesis Video Streams. This example uses the v4l2src GStreamer plugin.

```
$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/
x-raw,format=I420,width=640,height=480,framerate=30/1 ! x264enc bframes=0 key-int-
max=45 bitrate=500 ! video/x-h264,stream-format=avc,alignment=au,profile=baseline !
kvssink stream-name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

## Example 3: Stream Pre-Encoded Video from a USB Camera on Ubuntu

The following command creates a GStreamer pipeline on Ubuntu that streams video that the camera has already encoded in H.264 format to Kinesis Video Streams. This example uses the v4l2src GStreamer plugin.

```
$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! h264parse ! video/x-
h264,stream-format=avc,alignment=au ! kvssink stream-name="plugin" storage-size=512 access-
key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"
```

### Example 4: Stream Video from a Network Camera on macOS

The following command creates a GStreamer pipeline on macOS that streams video to Kinesis Video Streams from a network camera. This example uses the <a href="rtspsrc">rtspsrc</a> GStreamer plugin.

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
  rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

## Example 5: Stream Video from a Network Camera on Windows

The following command creates a GStreamer pipeline on Windows that streams video to Kinesis Video Streams from a network camera. This example uses the rtspsrc GStreamer plugin.

```
$ gst-launch-1.0 rtspsrc location="rtsp://YourCameraRtspUrl" short-header=TRUE !
rtph264depay ! video/x-h264, format=avc,alignment=au ! kvssink stream-
name="YourStreamName" storage-size=512 access-key="YourAccessKey" secret-
key="YourSecretKey" aws-region="YourAWSRegion"
```

### Example 6: Stream Video from a Camera on Raspberry Pi

The following command creates a GStreamer pipeline on Raspberry Pi that streams video to Kinesis Video Streams. This example uses the v4l2src GStreamer plugin.

\$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/x-raw,format=I420,width=640,height=480,framerate=30/1 ! omxh264enc control-rate=1 target-bitrate=5120000 periodicity-idr=45 inline-header=FALSE ! h264parse ! video/x-h264,stream-format=avc,alignment=au,width=640,height=480,framerate=30/1,profile=baseline ! kvssink stream-name="YourStreamName" access-key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"

## Example 7: Stream Video from a Camera on Raspberry Pi and Specify Region

The following command creates a GStreamer pipeline on Raspberry Pi that streams video to Kinesis Video Streams in the US East (N. Virginia) region. This example uses the v4l2src GStreamer plugin.

\$ gst-launch-1.0 v4l2src do-timestamp=TRUE device=/dev/video0 ! videoconvert ! video/x-raw,format=I420,width=640,height=480,framerate=30/1 ! omxh264enc control-rate=1 target-bitrate=5120000 periodicity-idr=45 inline-header=FALSE ! h264parse ! video/x-h264,stream-format=avc,alignment=au,width=640,height=480,framerate=30/1,profile=baseline ! kvssink stream-name="YourStreamName" access-key="YourAccessKey" secret-key="YourSecretKey" aws-region="YourAWSRegion"

## Example 8: Stream both audio and video in Raspberry-PI and Ubuntu

See how to run the gst-launch-1.0 command to start streaming both audio and video in Raspberry-PI and Ubuntu.

## Example 9: Stream both audio and video in MacOS

See how to run the gst-launch-1.0 command to start streaming both audio and video in MacOS.

## Example 10: Upload MKV file that contains both audio and video

See how to run the gst-launch-1.0 command to upload MKV file that contains both audio and video.

## Run the GStreamer Element in a Docker Container

Docker is a platform for developing, deploying, and running applications using containers. Using Docker to create the GStreamer pipeline standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

To install and configure Docker, see the following:

- Docker download instructions
- · Getting started with Docker

After installing Docker, you can download the Kinesis Video Streams C++ Producer SDK (and GStreamer plugin) from Amazon Elastic Container Registry using the docker pull command.

To run GStreamer with the Kinesis Video Streams Producer SDK element as a sink in a Docker container, do the following:

#### **Topics**

- Authenticate your Docker Client (p. 136)
- Download the Docker Image for Ubuntu, macOS, Windows, or Raspberry Pi (p. 136)
- Run the Docker Image (p. 137)

### Authenticate your Docker Client

Authenticate your Docker client to the Amazon ECR registry that you intend to pull your image from. You must get authentication tokens for each registry used, and the tokens are valid for 12 hours. For more information, see Registry Authentication in the Amazon Elastic Container Registry User Guide.

#### **Example: Authenticate with Amazon ECR**

```
aws ecr get-login-password --region us-west-2 | docker login -u AWS --password-stdin https://546150905175.dkr.ecr.us-west-2.amazonaws.com
```

If successful, the output prints Login Succeeded.

## Download the Docker Image for Ubuntu, macOS, Windows, or Raspberry Pi

Download the Docker image to your Docker environment using one the following commands, depending on your operating system:

#### Download the Docker Image for Ubuntu

 $\verb|sudo| docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-linux:latest| \\$ 

#### Download the Docker Image for macOS

sudo docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-linux:latest

#### Download the Docker Image for Windows

docker pull 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-windows:latest

#### Download the Docker Image for Raspberry Pi

 $sudo \ docker \ pull \ 546150905175. dkr.ecr.us-west-2. amazonaws.com/kinesis-video-producer-sdk-cpp-raspberry-pi:latest\\$ 

To verify that the image was successfully added, use the following command:

docker images

### Run the Docker Image

Use one of the following commands to run the Docker image, depending on your operating system:

#### Run the Docker Image on Ubuntu

```
sudo docker run -it --network="host" --device=/dev/video0 546150905175
.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-linux /bin/bash
```

#### Run the Docker Image on macOS

 $sudo\ docker\ run\ -it\ --network="host"\ 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-amazon-linux\ /bin/bash$ 

#### Run the Docker Image on Windows

docker run -it 546150905175.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cppwindows <AWS\_ACCESS\_KEY\_ID> <AWS\_SECRET\_ACCESS\_KEY> <RTSP\_URL> <STREAM\_NAME>

#### Run the Docker Image on Raspberry Pi

```
sudo docker run -it --device=/dev/video0 --device=/dev/vchiq -v /opt/vc:/opt/vc
546150905175
.dkr.ecr.us-west-2.amazonaws.com/kinesis-video-producer-sdk-cpp-raspberry-pi /bin/bash
```

Docker launches the container, and presents you with a command prompt for executing commands within the container.

In the container, set the environment variables using the following command:

```
export LD_LIBRARY_PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build/downloads/local/lib:$LD_LIBRARY_PATH
export PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build/downloads/local/bin:$PATH
export GST_PLUGIN_PATH=/opt/awssdk/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build/downloads/local/lib:$GST_PLUGIN_PATH
```

Start streaming from the camera using the gst-launch-1.0 command that is appropriate for your device.

#### Note

On macOS, you can only stream video from a network camera when running GStreamer in a Docker container. Streaming video from a USB camera on macOS in a Docker container is not supported.

For examples of using the gst-launch-1.0 command to connect to a local web camera or a network RTSP camera, see Launch Commands (p. 133).

## **GStreamer Element Parameter Reference**

To send video to the Amazon Kinesis Video Streams Producer SDK, you specify kvssink as the *sink*, or final destination of the pipeline. This reference provides information about kvssink required and optional parameters. For more information, see the section called "GStreamer" (p. 132).

The kyssink element has the following required parameters:

#### Amazon Kinesis Video Streams Developer Guide Parameter Reference

• stream-name: The name of the destination Kinesis video stream.

#### Note

When using IoT authorization, the value of stream-name must be identical to the value of iot-thingname (in IoT provisioning). For more information, see "Invalid thing name passed" error when using IoT authorization (p. 182).

- storage-size: The storage size of the device in megabytes. For information about configuring device storage, see StorageInfo (p. 105).
- access-key: The AWS access key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- secret-key: The AWS secret key that is used to access Kinesis Video Streams. You must provide either this parameter or credential-path.
- credential-path: A path to a file containing your credentials for accessing Kinesis Video Streams. You must provide either this parameter or access-key and secret-key.

The kvssink element has the following optional parameters. For more information about these parameters, see Kinesis Video Stream Structures (p. 106).

Parameter	Description	Unit/ Type	Default
absolute-fragment- times	Whether to use absolute fragment times.	Boolean	true
avg-bandwidth-bps	The expected average bandwidth for the stream.	Bytes per second	4194304
aws-region	The AWS region to use.	String	us-west-2
buffer-duration	The stream buffer duration.	Seconds	180
codec-id	The codec ID of the stream.	String	"V_MPEG4/ISO/AVC"
connection- staleness	The time after which the stream staleness callback is called.	Seconds	60
content-type	The content type of the stream.	String	"video/h264"
fragment-acks	Whether to use fragment ACKs.	Boolean	true
fragment-duration	The fragment duration that you want.	Milliseconds	2000
framerate	The expected frame rate.	Frames per second	25
frame-timecodes	Whether to use frame timecodes or generate timestamps using the current time callback.	Boolean	true

## Amazon Kinesis Video Streams Developer Guide Parameter Reference

Parameter	Description	Unit/ Type	Default
key-frame- fragmentation	Whether to produce fragments on a key frame.	Boolean	true
log-config	The log configuration path.	String	"./ kvs_log_configuration
max-latency	The maximum latency for the stream.	Seconds	60
recalculate- metrics	Whether to recalculate the metrics.	Boolean	true
replay-duration	The duration to roll the current reader backward to replay during an error if restarting is enabled.	Seconds	40
restart-on-error	Whether to restart when an error occurs.	Boolean	true
retention-period	The length of time the stream is preserved.	Hours	2
rotation-period	The key rotation period. For more information, see Rotating Customer Master Keys.	Seconds	2400
streaming-type	The streaming type. Valid values include:  O: real time 1: near real time (not currently supported) 2: offline	Enum GstKvsSinkStreaming	0: real time Type
timecode-scale	The MKV timecode scale.	Milliseconds	1
track-name	The MKV track name.	String	"kinesis_video"

Parameter	Description	Unit/ Type	Default
iot-certificate	IoT credentials to be used in the kvssink element. Accepts the following keys and values:	String	None
	<ul> <li>endpoint=iotcredential</li> </ul>	sproviderendpoint	
	<ul> <li>cert-path=/ localdirectorypath / to/certificate</li> </ul>		
	<ul> <li>key-path=/ localdirectorypath / to/private/key</li> </ul>		
	• ca-path=/ localdirectorypath/ to/ca-cert		
	• role-aliases=role- aliases		

## Example: Sending Data to Kinesis Video Streams Using the PutMedia API

This example demonstrates how to use the PutMedia API. It shows how to send data that is already in a container format (MKV). If your data needs to be assembled into a container format before sending (for example, if you are assembling camera video data into frames), see Kinesis Video Streams Producer Libraries (p. 53).

### Note

The PutMedia operation is available only in the C++ and Java SDKs, due to the full-duplex management of connections, data flow, and acknowledgements. It is not supported in other languages.

### This example includes the following steps:

- Step 1: Download and Configure the Code (p. 140)
- Step 2: Write and Examine the Code (p. 141)
- Step 3: Run and Verify the Code (p. 143)

## Step 1: Download and Configure the Code

In this section, you download the Java example code, import the project into your Java IDE, configure the library locations, and configure the code to use your AWS credentials.

1. Create a directory and clone the example source code from the GitHub repository. The PutMedia example is part of the Java Producer Library (p. 54).

\$ git clone https://github.com/awslabs/amazon-kinesis-video-streams-producer-sdk-java

2. Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA), and import the Apache Maven project that you downloaded:

- In Eclipse: Choose File, Import, Maven, Existing Maven Projects, and navigate to the root of the downloaded package. Select the pom.xml file.
- In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

For more information, see the related IDE documentation.

- 3. Update the project so that the IDE can find the libraries that you imported.
  - For IntelliJ IDEA, do the following:
    - a. Open the context (right-click) menu for the project's lib directory, and choose Add as library.
    - b. Choose File, Project Structure.
    - c. Under Project Settings, choose Modules.
    - In the Sources tab, set Language Level to 7 or higher.
  - For Eclipse, do the following:
    - a. Open the context (right-click) menu for the project, and choose **Properties**, **Java Build Path**, **Source**. Then do the following:
      - 1. On the **Source** tab, double-click **Native library location**.
      - 2. In the Native Library Folder Configuration wizard, choose Workspace.
      - 3. In the Native Library Folder selection, choose the lib directory in the project.
    - b. Open the context (right-click) menu for the project, and choose **Properties**. Then do the following:
      - 1. On the Libraries tab, choose Add Jars.
      - 2. In the **JAR selection** wizard, choose all the .jars in the project's lib directory.

## Step 2: Write and Examine the Code

The PutMedia API example (PutMediaDemo) shows the following coding pattern:

#### **Topics**

- Create the PutMediaClient (p. 141)
- Stream Media and Pause the Thread (p. 142)

The code examples in this section are from the PutMediaDemo class.

## Create the PutMediaClient

Creating the PutMediaClient object takes the following parameters:

- The URI for the PutMedia endpoint.
- An InputStream pointing to the MKV file to stream.
- The stream name. This example uses the stream that was created in the Using the Java Producer Library (p. 54) (my-stream). To use a different stream, change the following parameter:

private static final String STREAM\_NAME="my-stream";

#### Note

The PutMedia API example does not create a stream. You must create a stream either by using the test application for the Using the Java Producer Library (p. 54), by using the Kinesis Video Streams console, or by using the AWS CLI.

- The current timestamp.
- The time code type. The example uses RELATIVE, indicating that the timestamp is relative to the start of the container.
- An AWSKinesisVideoV4Signer object that verifies that the received packets were sent by the authorized sender.
- The maximum upstream bandwidth in Kbps.
- An AckConsumer object to receive packet received acknowledgements.

The following code creates the PutMediaClient object:

```
/* actually URI to send PutMedia request */
final URI uri = URI.create(KINESIS_VIDEO_DATA_ENDPOINT + PUT_MEDIA_API);
/* input stream for sample MKV file */
final InputStream inputStream = new FileInputStream(MKV_FILE_PATH);
/* use a latch for main thread to wait for response to complete */
final CountDownLatch latch = new CountDownLatch(1);
/* a consumer for PutMedia ACK events */
final AckConsumer ackConsumer = new AckConsumer(latch);
/* client configuration used for AWS SigV4 signer */
final ClientConfiguration configuration = getClientConfiguration(uri);
/* PutMedia client */
final PutMediaClient client = PutMediaClient.builder()
        .putMediaDestinationUri(uri)
        .mkvStream(inputStream)
        .streamName(STREAM_NAME)
        .timestamp(System.currentTimeMillis())
        .fragmentTimeCodeType("RELATIVE")
        .signWith(getKinesisVideoSigner(configuration))
        .upstreamKbps(MAX_BANDWIDTH_KBPS)
        .receiveAcks(ackConsumer)
        .build();
```

## Stream Media and Pause the Thread

After the client is created, the sample starts asynchronous streaming with putMediaInBackground. The main thread is then paused with latch.await until the AckConsumer returns, at which point the client is closed.

```
/* start streaming video in a background thread */
    client.putMediaInBackground();

    /* wait for request/response to complete */
    latch.await();

    /* close the client */
    client.close();
```

## Step 3: Run and Verify the Code

To run the PutMedia API example, do the following:

- Create a stream named my-stream in the Kinesis Video Streams console or by using the AWS CLI.
- 2. Change your working directory to the Java producer SDK directory:

3. Compile the Java SDK and demo application:

```
mvn package
```

4. Create a temporary filename in the /tmp directory:

```
$ jar_files=$(mktemp)
```

5. Create a classpath string of dependencies from the local repository to a file:

```
$ mvn -Dmdep.outputFile=$jar_files dependency:build-classpath
```

6. Set the value of the LD\_LIBRARY\_PATH environment variable as follows:

```
$ export LD_LIBRARY_PATH=/<YOUR_FOLDER_PATH_WHERE_SDK_IS_DOWNLOADED>/amazon-kinesis-
video-streams-producer-sdk-cpp/kinesis-video-native-build/downloads/local/lib:
$LD_LIBRARY_PATH
$ classpath_values=$(cat $jar_files)
```

7. Run the demo from the command line as follows, providing your AWS credentials:

```
$ java -classpath target/kinesisvideo-java-demo-1.0-SNAPSHOT.jar:$classpath_values
-Daws.accessKeyId=${ACCESS_KEY} -Daws.secretKey=${SECRET_KEY} -Djava.library.path=/
opt/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-video-native-build
com.amazonaws.kinesisvideo.demoapp.DemoAppMain
```

8. Open the Kinesis Video Streams console at https://console.aws.amazon.com/kinesisvideo/, and choose your stream on the Manage Streams page. The video plays in the Video Preview pane.

## Example: Streaming from an RTSP Source

The C++ Producer Library (p. 63) contains a definition for a Docker container that connects to an RTSP (Real Time Streaming Protocol) network camera. Using Docker standardizes the operating environment for Kinesis Video Streams, which greatly simplifies building and executing the application.

To use the RTSP demo application, first install and build the C++ Producer Library (p. 63).

The following procedure demonstrates how to set up and use the RTSP demo application.

#### **Topics**

- Prerequisites (p. 144)
- Build the Docker Image (p. 144)
- Run the RTSP Example Application (p. 144)

## **Prerequisites**

To run the Kinesis Video Streams RTSP example application, you must have the following:

- Docker: For information about installing and using Docker, see the following links:
  - Docker download instructions
  - · Getting started with Docker
- RTSP network camera source: For information about recommended cameras, see System Requirements (p. 3).

## **Build the Docker Image**

First, you build the Docker image that the demo application will run inside.

- Create a new directory and copy the following files from the docker\_native\_scripts directory to the new directory:
  - Dockerfile
  - start\_rtsp\_in\_docker.sh
- 2. Change to the directory that you created in the previous step.
- 3. Build the Docker image using the following command. This command creates the image and tags it as rtspdockertest.

```
docker build -t rtspdockertest .
```

4. Record the image ID that was returned in the previous step (for example, 54f0d65f69b2).

## Run the RTSP Example Application

Start the Kinesis Video Streams Docker container using the following command. Provide the image ID from the previous step, your AWS credentials, the URL of your RTSP network camera, and the name of the Kinesis video stream to send the data.

```
$ docker run -
it <IMAGE_ID> <AWS_ACCESS_KEY_ID> <AWS_SECRET_ACCESS_KEY> <RTSP_URL> <STREAM_NAME>
```

To customize the application, comment or remove the ENTRYPOINT command in Dockerfile, and launch the container using the following command:

```
docker run -it <IMAGE_ID> bash
```

You are then prompted inside the Docker container to customize the sample application and start streaming.

## Example: Parsing and Rendering Kinesis Video Streams Fragments

The Stream Parser Library (p. 124) contains a demo application named KinesisVideoRendererExample that demonstrates parsing and rendering Amazon Kinesis video stream fragments. The example uses JCodec to decode the H.264 encoded frames that are ingested using the Example: Kinesis Video Streams Producer SDK GStreamer Plugin (p. 132) application. After the frame is decoded using JCodec, the visible image is rendered using JFrame.

This example shows how to do the following:

- Retrieve frames from a Kinesis video stream using the GetMedia API and render the stream for viewing.
- View the video content of streams in a custom application instead of using the Kinesis Video Streams console.

You can also use the classes in this example to view Kinesis video stream content that isn't encoded as H.264, such as a stream of JPEG files that don't require decoding before being displayed.

The following procedure demonstrates how to set up and use the Renderer demo application.

## **Prerequisites**

To examine and use the Renderer example library, you must have the following:

- An Amazon Web Services (AWS) account. If you don't already have an AWS account, see Getting Started with Kinesis Video Streams.
- A Java integrated development environment (IDE), such as Eclipse Java Neon or JetBrains IntelliJ Idea.

## Running the Renderer Example

1. Create a directory, and then clone the example source code from the GitHub repository.

\$ git clone https://github.com/aws/amazon-kinesis-video-streams-parser-library

- Open the Java IDE that you are using (for example, Eclipse or IntelliJ IDEA), and import the Apache Maven project that you downloaded:
  - In Eclipse: Choose File, Import, Maven, Existing Maven Projects. Navigate to the kinesisvideo-streams-parser-lib directory.
  - In IntelliJ Idea: Choose Import. Navigate to the pom.xml file in the root of the downloaded package.

#### Note

If IntelliJ can't find your dependencies, you might have to do the following:

- Build clean: Choose File, Settings, Build, Execution, Deployment, Compiler. Ensure that Clear output directory on rebuild is selected, and then choose Build, Build Project.
- Reimport the project: Open the context (right-click) menu for the project, and choose Maven, Reimport.

For more information, see the related IDE documentation.

#### Amazon Kinesis Video Streams Developer Guide How It Works

- From your Java IDE, open src/test/java/com.amazonaws.kinesisvideo.parser/ examples/KinesisVideoRendererExampleTest.
- 4. Remove the @Ignore directive from the file.
- 5. Update the .stream parameter with the name of your Kinesis video stream.
- 6. Run the KinesisVideoRendererExample test.

## **How It Works**

The example application demonstrates the following:

- Sending MKV data (p. 146)
- Parsing MKV Fragments into Frames (p. 146)
- Decoding and Displaying the Frame (p. 146)

## Sending MKV data

The example sends sample MKV data from the rendering\_example\_video.mkv file, using PutMedia to send video data to a stream named render-example-stream.

The application creates a PutMediaWorker:

```
PutMediaWorker putMediaWorker = PutMediaWorker.create(getRegion(),
   getCredentialsProvider(),
   getStreamName(),
   inputStream,
   streamOps.amazonKinesisVideo);
executorService.submit(putMediaWorker);
```

For information about the PutMediaWorker class, see Call PutMedia (p. 128) in the Stream Parser Library (p. 124) documentation.

## Parsing MKV Fragments into Frames

The example then retrieves and parses the MKV fragments from the stream using a GetMediaWorker:

```
GetMediaWorker getMediaWorker = GetMediaWorker.create(getRegion(),
    getCredentialsProvider(),
    getStreamName(),
    new StartSelector().withStartSelectorType(StartSelectorType.EARLIEST),
    streamOps.amazonKinesisVideo,
    getMediaProcessingArgumentsLocal.getFrameVisitor());
executorService.submit(getMediaWorker);
```

For more information about the GetMediaWorker class, see Call GetMedia (p. 128) in the Stream Parser Library (p. 124) documentation.

## Decoding and Displaying the Frame

The example then decodes and displays the frame using JFrame.

The following code example is from the KinesisVideoFrameViewer class, which extends JFrame:

```
public void setImage(BufferedImage bufferedImage) {
```

#### Amazon Kinesis Video Streams Developer Guide SageMaker

```
image = bufferedImage;
  repaint();
}
```

The image is displayed as an instance of java.awt.image.BufferedImage. For examples that show how to work with BufferedImage, see Reading/Loading an Image.

## Example: Identifying Objects in Video Streams Using SageMaker

This example demonstrates how to create a solution that uses SageMaker to identify when certain objects appear in an Amazon Kinesis video stream. SageMaker is the managed platform for developers and data scientists to build, train, and deploy machine learning models quickly and easily.

The example consists of a Docker container that includes the application functionality, and an AWS CloudFormation template that automates the deployment of the application's AWS resources.

The AWS CloudFormation template creates the following resources:

- An Amazon Elastic Container Service (Amazon ECS) cluster that uses the AWS Fargate compute engine that runs the library software.
- An Amazon DynamoDB table that maintains checkpoints and related state across workers that run on Fargate tasks.
- A Kinesis data stream that captures the inference outputs generated from SageMaker.
- An AWS Lambda function that parses the output from SageMaker.
- AWS Identity and Access Management (IAM) resources for providing access across services.
- Amazon CloudWatch resources for monitoring the application.

The application is compatible with any SageMaker endpoint that processes data. This example contains instructions for creating a SageMaker endpoint that uses a sample object identification algorithm template. You can modify or replace the algorithm based on your application's use cases and requirements.

#### Topics

- Prerequisites (p. 147)
- Creating the Application (p. 148)
- Monitoring the Application (p. 149)
- Extending the Application (p. 151)
- Cleaning up the Application (p. 151)

## **Prerequisites**

The example application has the following prerequisites:

- SageMaker (p. 148)
- Kinesis Video Stream (p. 148)
- Service-Linked Role (p. 148)

## SageMaker

This example requires a SageMaker notebook. For information about creating a notebook, see Creating a Notebook Instance in the Amazon SageMaker Developer Guide. Note the following when creating your notebook:

- Add the Amazon\_JumpStart\_Object\_Detection.ipynb example (from the Introduction to Amazon Algorithms section in the SageMaker Examples tab of the Jupyter console) to the notebook.
- Create an Amazon Simple Storage Service (Amazon S3) bucket, and provide its name in the **Prerequisites** step when adding the example.
- After you create the notebook, choose **Endpoint configuration** on the SageMaker console, and make a note of the **Endpoint name**.

## Kinesis Video Stream

This example requires one or more Kinesis video streams that have live video data. For information about creating a Kinesis video stream and sending data to it from a camera, see GStreamer (p. 132). Make a note of your Kinesis video stream name.

## Service-Linked Role

This example requires that your account have a service-linked role for AWS Fargate operation. New AWS accounts have this role enabled by default. If you see the following error when creating the application, you must enable the service-linked role:

Unable to assume the service linked role. Please verify that the ECS service linked role exists

To enable the service-linked role, run the following command:

aws iam create-service-linked-role --aws-service-name ecs.amazonaws.com

## **Creating the Application**

To create the sample application, you use AWS CloudFormation and the templates that are provided.

#### To use AWS CloudFormation to create the application

- 1. Sign in to the AWS Management Console and open the AWS CloudFormation console using one of the following links for your AWS Region. The link launches the correct stack for your Region:
  - Launch in Asia Pacific (Sydney) Region (ap-southeast-2)
  - Launch in Asia Pacific (Tokyo) Region (ap-northeast-1)
  - Launch in Europe (Frankfurt) Region (eu-central-1)
  - Launch in Europe (Ireland) Region (eu-west-1)
  - Launch in US East (N. Virginia) Region (us-east-1)
  - Launch in US West (Oregon) Region (us-west-2)
- 2. On the Create Stack page, provide the following values:
  - Give the stack a unique name (for example, username-KVS-SageMaker).
  - Provide the SageMaker endpoint name (not the endpoint ARN) that you created in the previous section.

#### Amazon Kinesis Video Streams Developer Guide Monitoring the Application

- Provide the name of your Kinesis video stream. If you have more than one Kinesis video stream, provide the stream names in quotation marks and separated by commas.
- Keep the rest of the settings as they are.

Choose Next.

- 3. On the **Options** page, keep the settings as they are.
- Select the I acknowledge that AWS CloudFormation might create IAM resources check box. Choose Next.

AWS CloudFormation creates the application.

The following table lists several parameters used by the Docker container when you create a stack using this AWS CloudFormation template. Their values are predefined in the SSM resource in the template, but you can customize them as needed.

Resource name	Default value	Description
inferenceInterval	6	The sampling ratio for video frames that are sout of every 6 I-Frames is sent to the SageMa
sageMakerTaskQueueSize	5000	The size of the queue that maintains the pend 'sageMakerTaskTimeoutInMilli'. If SageMaker
sage Maker Task Thread Pool Size	20	Number of threads that is used to concurrent
sage Maker Task Time out In Milli	20000	The maximum duration allowed for a single r
sageMakerTaskThreadPoolName	SageMakerThreadPoo %d	l- The name of the threadpool that is sending re

To customize the values of these parameters, download the AWS CloudFormation template by choosing the template URL on the **Create stack** page, and then locate these parameters in the Params section of the template that looks like this:

## Monitoring the Application

The application created by the AWS CloudFormation template includes an Amazon CloudWatch dashboard and a CloudWatch log stream that you use to monitor application metrics and events.

## **Application Dashboard**

The application includes a CloudWatch dashboard for monitoring application metrics. To view the application dashboard, open the CloudWatch console at <a href="https://console.aws.amazon.com/cloudwatch/">https://console.aws.amazon.com/cloudwatch/</a> and choose **Dashboards** in the left navigation bar.

Choose the **KVS-SageMaker-Driver-KvsSageMakerIntegration-**aws-region dashboard. The dashboard shows the following information:

- Frame Metrics: Metrics for processing the video stream, sending frames to the SageMaker endpoint, and writing to the Kinesis data stream that connects the SageMaker notebook with the AWS Lambda function that processes SageMaker inference output results.
- IngestToProcessLatency: The time difference between when a video frame is ingested into the Kinesis Video Streams service and when the application receives the frame.
- **Current Lease Total:** The application is granted permissions to read from the Kinesis video stream using a lease. This metric shows the number of active leases. The application uses one lease per Kinesis video stream, and one lease for synchronization between streams.
- Lease Sync Metrics: The frequency and duration of permission lease synchronization.
- LeaseCount per Worker: The distribution of leases among the SageMaker worker threads.
- **Number of Workers:** The number of SageMaker workers processing streams. Each task in an Amazon ECS cluster has one worker running. One worker can process more than one stream.
- ECS Service Utilization: Usage metrics for the Amazon ECS cluster.
- KinesisDataStream: Usage metrics of the Kinesis data stream.
- SageMaker: Operations performed by the SageMaker notebook.
- Lambda: Number and duration of the Lambda function that processes the output from the SageMaker notebook.

If any of the information in these graphs indicates an operational issue (such as a value steadily increasing rather than being stable), see the following section about how to read the application logs to determine the issue.

## CloudWatch Logs

The application includes two CloudWatch logs:

### **Topics**

- The Application Log (p. 150)
- The Lambda Function Log (p. 151)

## The Application Log

You can use the application log to monitor application events and error conditions. This log is helpful if you need to contact product support with an issue.

### To read the Application Log

- 1. Open the Amazon ECS console at https://console.aws.amazon.com/ecs.
- Choose the KVS-Sagemaker-Driver cluster.
- 3. Choose the **stack-name-SageMakerDriverService** service in the **Services** tab.
- 4. Choose the **Logs** tab.

The application log shows events such as initialization, configuration, and lease activity.

## The Lambda Function Log

You can use the Lambda function log to track successful object identifications.

#### To read the Lambda log

- 1. Open the AWS Lambda console at https://console.aws.amazon.com/lambda.
- Choose the Lambda function for your application. The Lambda function name is in the following format:

```
stack-name-LambdaFunction-A1B2C3D4E5F6G
```

- 3. Choose the Monitoring panel.
- 4. Choose View logs in CloudWatch.

The CloudWatch log for the application shows successful identifications of objects in the Kinesis video stream and other application events.

## **Extending the Application**

You can add custom functionality to your application by modifying the values that you provide in the AWS CloudFormation template window as follows:

- EndPointAcceptContentType: You can change this value if your SageMaker endpoint does not accept frames in JPG format. The following formats are supported:
  - image/jpeg
  - image/png
  - image/bmp
  - image/gif
  - application/x-image
- LambdaFunctionBucket, LambdaFunctionKey: The provided settings use an AWS Lambda function that processes the SageMaker output and writes it to CloudWatch Logs. If you want to send the SageMaker output elsewhere, you can provide your own Lambda function.
- Tag Filters: If you have streams that are tagged using the the section called "TagStream" (p. 234) action, you can specify the tags of streams that you want to process. For example, if you have two streams that have the Location key with the values Front and Parking, you would filter to only use those streams using the following entry:

```
{"key":"Location", "values":["Front", "Parking"]}
```

## Cleaning up the Application

After you've finished with the application that you created for this tutorial, we recommend that you delete any resources that you don't want to keep, to avoid incurring any ongoing charges.

- 1. **SageMaker endpoint:** If you created the SageMaker endpoint for this tutorial rather than using an existing endpoint, delete the endpoint. In the SageMaker control panel, choose **Endpoint configurations**. Choose the endpoint you created, and choose **Actions**, **Delete**. Confirm the deletion.
- 2. **SageMaker notebook:** On the SageMaker console, choose **Notebook instances**. Choose the notebook that you created, and choose **Actions**, **Stop**. When the notebook shows that its **Status** is **Stopped**, choose **Actions**, **Delete**. Confirm the deletion.

### Amazon Kinesis Video Streams Developer Guide Cleaning up the Application

#### Note

For more information on cleaning up SageMaker resources, see Clean up in the SageMaker developer guide.

3. **SageMaker execution policy:** On the IAM console, in the navigation pane, choose **Policies**. Choose the policy that you created for this tutorial. The name of the policy is similar to the following: AmazonSageMaker-ExecutionPolicy-timestamp

Choose **Policy actions**, **Delete.** Confirm the deletion.

4. **SageMaker execution role:** On the IAM console, in the navigation pane, choose **Roles**. Choose the role that you created for this tutorial. The name of the role is similar to the following: AmazonSageMaker-ExecutionRole-*timestamp* 

Choose **Delete role**. Confirm the deletion.

- 5. **AWS CloudFormation stack:** On the AWS CloudFormation console, choose the stack that you created for this tutorial. Choose **Actions, Delete Stack**. Confirm the deletion.
- 6. **Amazon S3 bucket:** On the Amazon S3 console, choose the bucket that you created to store the SageMaker assets. Choose **Delete**. Enter the name of the bucket and choose **Confirm** to confirm deletion.
- 7. **Kinesis video stream:** On the Kinesis Video Streams console, choose the video stream that you created for the application. Choose **Delete**. Confirm the deletion.

## Monitoring Kinesis Video Streams

Monitoring is an important part of maintaining the reliability, availability, and performance of Kinesis Video Streams and your AWS solutions. You should collect monitoring data from all of the parts of your AWS solution so that you can more easily debug a multi-point failure if one occurs. Before you start monitoring Kinesis Video Streams, however, you should create a monitoring plan that includes answers to the following questions:

- · What are your monitoring goals?
- · What resources will you monitor?
- · How often will you monitor these resources?
- What monitoring tools will you use?
- Who will perform the monitoring tasks?
- Who should be notified when something goes wrong?

After you have defined your monitoring goals and have created your monitoring plan, the next step is to establish a baseline for normal Kinesis Video Streams performance in your environment. You should measure Kinesis Video Streams performance at various times and under different load conditions. As you monitor Kinesis Video Streams, you should store a history of monitoring data that you've collected. You can compare current Kinesis Video Streams performance to this historical data to help you to identify normal performance patterns and performance anomalies, and devise methods to address issues that may arise.

#### **Topics**

- Monitoring Kinesis Video Streams Metrics with CloudWatch (p. 153)
- Logging Kinesis Video Streams API Calls with AWS CloudTrail (p. 164)

## Monitoring Kinesis Video Streams Metrics with CloudWatch

You can monitor a Kinesis video stream using Amazon CloudWatch, which collects and processes raw data from Kinesis Video Streams into readable, near real-time metrics. These statistics are recorded for a period of 15 months, so that you can access historical information and gain a better perspective on how your web application or service is performing.

In the Kinesis Video Streams Management Console, you can view CloudWatch metrics for a Kinesis video stream in two ways:

- In the Dashboard page, choose the Video streams tab in the Account-level metrics for Current Region section.
- Choose the **Monitoring** tab in the video stream's details page.

Kinesis Video Streams provides the following metrics:

Metric	Description
ArchivedFragmentsConsumed.Media	Number of fragment media quota points that were consumed by all of the APIs. For an explanation

Metric	Description
	of the concept of quota points, see the section called "Fragment-metadata and fragment-media quotas" (p. 171).
	Units: Count
ArchivedFragmentsConsumed.Metadata	Number of fragments metadata quota points that were consumed by all of the APIs. For an explanation of the concept of quota points, see the section called "Fragment-metadata and fragment-media quotas" (p. 171).
	Units: Count
PutMedia.Requests	Number of PutMedia API requests for a given stream.
	Units: Count
PutMedia.IncomingBytes	Number of bytes received as part of PutMedia for the stream.
	Units: Bytes
PutMedia.IncomingFragments	Number of complete fragments received as part of PutMedia for the stream.
	Units: Count
PutMedia.IncomingFrames	Number of complete frames received as part of PutMedia for the stream.
	Units: Count
PutMedia.ActiveConnections	The total number of connections to the service host.
	Units: Count
PutMedia.ConnectionErrors	Errors while establishing PutMedia connection for the stream.
	Units: Count
PutMedia.FragmentIngestionLatency	Time difference between when the first and last bytes of a fragment are received by Kinesis Video Streams.
	Units: Milliseconds
PutMedia.FragmentPersistLatency	Time taken from when the complete fragment data is received and archived.
	Units: Count
PutMedia.Latency	Time difference between the request and the HTTP response from InletService while establishing the connection.
	Units: Count

Metric	Description
PutMedia.BufferingAckLatency	Time difference between when the first byte of a new fragment is received by Kinesis Video Streams and when the Buffering ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.ReceivedAckLatency	Time difference between when the last byte of a new fragment is received by Kinesis Video Streams and when the Received ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.PersistedAckLatency	Time difference between when the last byte of a new fragment is received by Kinesis Video Streams and when the Persisted ACK is sent for the fragment.
	Units: Milliseconds
PutMedia.ErrorAckCount	Number of Error ACKs sent while doing PutMedia for the stream.
	Units: Count
PutMedia.Success	1 for each fragment successfully written; 0 for every failed fragment. The average value of this metric indicates how many complete, valid fragments are sent.
	Units: Count
GetMedia.Requests	Number of GetMedia API requests for a given stream.
	Units: Count
GetMedia.OutgoingBytes	Total number of bytes sent out from the service as part of the GetMedia API for a given stream.
	Units: Bytes
GetMedia.OutgoingFragments	Number of fragments sent while doing GetMedia for the stream.
	Units: Count
GetMedia.OutgoingFrames	Number of frames sent during GetMedia on the given stream.
	Units: Count
GetMedia.MillisBehindNow	Time difference between the current server timestamp and the server timestamp of the last fragment sent.
	Units: Milliseconds
GetMedia.ConnectionErrors	The number of connections that were not successfully established.
	Units: Count

Metric	Description
GetMedia.Success	1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success.
	Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.
	Units: Count
GetMediaForFragmentList.OutgoingBy	tđstal number of bytes sent out from the service as part of the GetMediaForFragmentList API for a given stream.
	Units: Bytes
GetMediaForFragmentList.OutgoingFr	agiotaltrumber of fragments sent out from the service as part of the GetMediaForFragmentList API for a given stream.
	Units: Count
GetMediaForFragmentList.OutgoingFr	ametal number of frames sent out from the service as part of the GetMediaForFragmentList API for a given stream.
	Units: Count
GetMediaForFragmentList.Requests	Number of GetMediaForFragmentList API requests for a given stream.
	Units: Count
GetMediaForFragmentList.Success	1 for every fragment successfully sent; 0 for every failure. The average value indicates the rate of success.
	Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.
	Units: Count
ListFragments.Latency	Latency of the ListFragments API calls for the given stream name.
	Units: Milliseconds
ListFragments.Requests	Number of ListFragments API requests for a given stream.
	Units: Count

Metric	Description
ListFragments.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetHLSStreamingSessionURL.Latency	Latency of the GetHLSStreamingSessionURL API calls for the given stream name.  Units: Milliseconds
GetHLSStreamingSessionURL.Requests	Number of GetHLSStreamingSessionURL API requests for a given stream.  Units: Count
GetHLSStreamingSessionURL.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetHLSMasterPlaylist.Latency	Latency of the GetHLSMasterPlaylist API calls for the given stream name.  Units: Milliseconds
GetHLSMasterPlaylist.Requests	Number of GetHLSMasterPlaylist API requests for a given stream.  Units: Count
GetHLSMasterPlaylist.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count

Metric	Description
GetHLSMediaPlaylist.Latency	Latency of the GetHLSMediaPlaylist API calls for the given stream name.
	Units: Milliseconds
GetHLSMediaPlaylist.Requests	Number of GetHLSMediaPlaylist API requests for a given stream.
	Units: Count
GetHLSMediaPlaylist.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetMP4InitFragment.Latency	Latency of the GetMP4InitFragment API calls for the given stream name.  Units: Milliseconds
GetMP4InitFragment.Requests	Number of GetMP4InitFragment API requests for a given stream.  Units: Count
GetMP4InitFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetMP4MediaFragment.Latency	Latency of the GetMP4MediaFragment API calls for the given stream name.  Units: Milliseconds
GetMP4MediaFragment.Requests	Number of GetMP4MediaFragment API requests for a given stream.  Units: Count

Metric	Description
GetMP4MediaFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetMP4MediaFragment.OutgoingBytes	Total number of bytes sent out from the service as part of the GetMP4MediaFragment API for a given stream.  Units: Bytes
GetTSFragment.Latency	Latency of the GetTSFragment API calls for the given stream name.  Units: Milliseconds
GetTSFragment.Requests	Number of GetTSFragment API requests for a given stream.  Units: Count
GetTSFragment.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetTSFragment.OutgoingBytes	Total number of bytes sent out from the service as part of the GetTSFragment API for a given stream.  Units: Bytes
GetDASHStreamingSessionURL.Latency	Latency of the GetDASHStreamingSessionURL API calls for the given stream name.  Units: Milliseconds
GetDASHStreamingSessionURL.Requests	s Number of GetDASHStreamingSessionURL API requests for a given stream.  Units: Count

Metric	Description
GetDASHStreamingSessionURL.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetDASHManifest.Latency	Latency of the GetDASHManifest API calls for the given stream name.  Units: Milliseconds
GetDASHManifest.Requests	Number of GetDASHManifest API requests for a given stream.  Units: Count
GetDASHManifest.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count
GetClip.Latency	Latency of the GetClip API calls for the given video stream name.  Units: Miliseconds
GetClip.Requests	Number of GetClip API requests for a given video stream.  Units: Count
GetClip.Success	1 for every successful request; 0 for every failure. The average value indicates the rate of success.  Note Failures include both 400 (user) errors and 500 (system) errors. For more information about enabling a summary of requests and responses, including AWS request IDs, see Request/Response Summary Logging.  Units: Count

#### Amazon Kinesis Video Streams Developer Guide CloudWatch Metrics Guidance

Metric	Description
GetClip.OutgoingBytes	Total number of bytes sent out from the service as part of the GetClip API for a given video stream.
	Units: Bytes

## CloudWatch Metrics Guidance

CloudWatch metrics can be useful for finding answers to the following questions:

#### **Topics**

- Is data reaching the Kinesis Video Streams service? (p. 161)
- Why is data not being successfully ingested by the Kinesis Video Streams service? (p. 161)
- Why can't the data be read from the Kinesis Video Streams service at the same rate as it's being sent from the producer? (p. 162)
- Why is there no video in the console, or why is the video being played with a delay? (p. 162)
- What is the delay in reading real-time data, and why is the client lagging behind the head of the stream? (p. 162)
- Is the client reading data out of the Kinesis video stream, and at what rate? (p. 163)
- Why can't the client read data out of the Kinesis video stream? (p. 163)

## Is data reaching the Kinesis Video Streams service?

#### **Relevant metrics:**

- PutMedia.IncomingBytes
- PutMedia.IncomingFragments
- PutMedia.IncomingFrames

### **Action items:**

- If there is a drop in these metrics, check if your application is still sending data to the service.
- Check the network bandwidth. If your network bandwidth is insufficient, it could be slowing down the rate the service is receiving the data.

## Why is data not being successfully ingested by the Kinesis Video Streams service?

#### **Relevant metrics:**

- PutMedia.Requests
- PutMedia.ConnectionErrors
- PutMedia.Success
- PutMedia.ErrorAckCount

#### **Action items:**

#### Amazon Kinesis Video Streams Developer Guide CloudWatch Metrics Guidance

- If there is an increase in PutMedia. ConnectionErrors, look at the HTTP response/error codes received by the producer client to see what errors are occurring while establishing the connection.
- If there is a drop in PutMedia. Success or increase in PutMedia. ErrorAckCount, look at the ack
  error code in the ack responses sent by the service to see why ingestion of data is failing. For more
  information, see AckErrorCode.Values.

## Why can't the data be read from the Kinesis Video Streams service at the same rate as it's being sent from the producer?

#### **Relevant metrics:**

- PutMedia.FragmentIngestionLatency
- PutMedia.IncomingBytes

#### **Action items:**

• If there is a drop in these metrics, check the network bandwidth of your connections. Low-bandwidth connections could cause the data to reach the service at a lower rate.

## Why is there no video in the console, or why is the video being played with a delay?

#### **Relevant metrics:**

- PutMedia.FragmentIngestionLatency
- PutMedia.FragmentPersistLatency
- PutMedia.Success
- ListFragments.Latency
- PutMedia.IncomingFragments

#### **Action items:**

- If there is an increase in PutMedia.FragmentIngestionLatency or a drop in PutMedia.IncomingFragments, check the network bandwidth and whether the data is still being sent.
- If there is a drop in PutMedia. Success, check the ack error codes. For more information, see AckErrorCode.Values.
- If there is an increase in PutMedia.FragmentPersistLatency or ListFragments.Latency, you are most likely experiencing a service issue. If the condition persists for an extended period of time, check with your customer service contact to see if there is an issue with your service.

## What is the delay in reading real-time data, and why is the client lagging behind the head of the stream?

### **Relevant metrics:**

- GetMedia.MillisBehindNow
- GetMedia.ConnectionErrors

• GetMedia.Success

#### **Action items:**

- If there is an increase in GetMedia. ConnectionErrors, then the consumer might be falling behind in reading the stream, due to frequent attempts to re-connect to the stream. Look at the HTTP response/error codes returned for the GetMedia request.
- If there is a drop in GetMedia. Success, then it's likely due to the service being unable to send the data to the consumer, which would result in dropped connection, and reconnects from consumers, which would result in the consumer lagging behind the head of the stream.
- If there is an increase in GetMedia.MillisBehindNow, look at your bandwidth limits to see if you are receiving the data at a slower rate because of lower bandwidth.

## Is the client reading data out of the Kinesis video stream, and at what rate?

#### **Relevant metrics:**

- GetMedia.OutgoingBytes
- GetMedia.OutgoingFragments
- GetMedia.OutgoingFrames
- GetMediaForFragmentList.OutgoingBytes
- GetMediaForFragmentList.OutgoingFragments
- GetMediaForFragmentList.OutgoingFrames

### **Action items:**

• These metrics indicate what rate real-time and archived data is being read.

## Why can't the client read data out of the Kinesis video stream?

#### **Relevant metrics:**

- GetMedia.ConnectionErrors
- GetMedia.Success
- GetMediaForFragmentList.Success
- PutMedia.IncomingBytes

#### **Action items:**

- If there is an increase in GetMedia. ConnectionErrors, look at the HTTP response/error codes returned by the GetMedia request. For more information, see AckErrorCode.Values.
- If you are trying to read the latest/live data, check PutMedia.IncomingBytes to see if there is data coming into the stream for the service to send to the consumers.
- If there is a drop in GetMedia. Success or GetMediaForFragmentList. Success, it's likely due to the service being unable to send the data to the consumer. If the condition persists for an extended period of time, check with your customer service contact to see if there is an issue with your service.

## Logging Kinesis Video Streams API Calls with AWS CloudTrail

Amazon Kinesis Video Streams is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon Kinesis Video Streams. CloudTrail captures all API calls for Amazon Kinesis Video Streams as events. The calls captured include calls from the Amazon Kinesis Video Streams console and code calls to the Amazon Kinesis Video Streams API operations. If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon Kinesis Video Streams. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon Kinesis Video Streams, the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, including how to configure and enable it, see the AWS CloudTrail User Guide.

## Kinesis Video Streams and CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When supported event activity occurs in Amazon Kinesis Video Streams, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see Viewing Events with CloudTrail Event History.

For an ongoing record of events in your AWS account, including events for Amazon Kinesis Video Streams, create a trail. A *trail* enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all Regions in the AWS partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following:

- · Overview for Creating a Trail
- CloudTrail Supported Services and Integrations
- Configuring Amazon SNS Notifications for CloudTrail
- Receiving CloudTrail Log Files from Multiple Regions and Receiving CloudTrail Log Files from Multiple Accounts

Amazon Kinesis Video Streams supports logging the following actions as events in CloudTrail log files:

- CreateStream
- DeleteStream
- DescribeStream
- GetDataEndpoint
- ListStreams
- ListTagsForStream
- TagStream
- UntagStream
- UpdateDataRetention
- UpdateStream

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or AWS Identity and Access Management (IAM) user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another AWS service.

For more information, see the CloudTrail userIdentity Element.

## Example: Amazon Kinesis Video Streams Log File Entries

A trail is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. CloudTrail log files contain one or more log entries. An event represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order.

The following example shows a CloudTrail log entry that demonstrates the CreateStream action.

```
{
    "Records": [
        {
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012"
                "accessKeyId": "EXAMPLE_KEY_ID",
                "userName": "Alice"
            "eventTime": "2018-05-25T00:16:31Z",
            "eventSource": " kinesisvideo.amazonaws.com",
            "eventName": "CreateStream",
            "awsRegion": "us-east-1",
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                 "streamName": "VideoStream",
                "dataRetentionInHours": 2,
                "mediaType": "mediaType",
                "kmsKeyId": "arn:aws:kms::us-east-1:123456789012:alias",
  "deviceName": "my-device"
        },
            "responseElements": {
  "streamARN":arn:aws:kinesisvideo:us-east-1:123456789012:stream/VideoStream/12345"
            "requestID": "db6c59f8-c757-11e3-bc3b-57923b443c1c",
            "eventID": "b7acfcd0-6ca9-4ee1-a3d7-c4e8d420d99b"
            "eventVersion": "1.05",
            "userIdentity": {
    "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012",
                "accessKevId": "EXAMPLE KEY ID",
                "userName": "Alice"
            "eventTime": "2018-05-25:17:06Z",
```

```
"eventSource": " kinesisvideo.amazonaws.com",
            "eventName": "DeleteStream",
            "awsRegion": "us-east-1",
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                "streamARN": "arn:aws:kinesisvideo:us-east-1:012345678910:stream/
VideoStream/12345",
                "currentVersion": "keqrjeqkj9"
            "responseElements": null,
            "requestID": "f0944d86-c757-11e3-b4ae-25654b1d3136",
            "eventID": "0b2f1396-88af-4561-b16f-398f8eaea596"
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012",
"accessKeyId": "EXAMPLE_KEY_ID",
                "userName": "Alice"
            },
            "eventTime": "2014-04-19T00:15:02Z",
            "eventSource": " kinesisvideo.amazonaws.com",
            "eventName": "DescribeStream",
            "awsRegion": "us-east-1"
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                "streamName": "VideoStream"
            "responseElements": null,
            "requestID": "a68541ca-c757-11e3-901b-cbcfe5b3677a".
            "eventID": "22a5fb8f-4e61-4bee-a8ad-3b72046b4c4d"
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
                "principalId": "EX_PRINCIPAL_ID",
                "arn": "arn:aws:iam::123456789012:user/Alice",
                "accountId": "123456789012"
                "accessKeyId": "EXAMPLE_KEY_ID",
                "userName": "Alice"
            "eventTime": "2014-04-19T00:15:03Z",
            "eventSource": "kinesisvideo.amazonaws.com",
            "eventName": "GetDataEndpoint",
            "awsRegion": "us-east-1"
            "sourceIPAddress": "127.0.0.1",
            "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
            "requestParameters": {
                "streamName": "VideoStream",
                "aPIName": "LIST_FRAGMENTS"
11
            "responseElements": null,
            "requestID": "a6e6e9cd-c757-11e3-901b-cbcfe5b3677a",
            "eventID": "dcd2126f-c8d2-4186-b32a-192dd48d7e33"
            "eventVersion": "1.05",
            "userIdentity": {
                "type": "IAMUser",
```

```
"principalId": "EX_PRINCIPAL_ID",
                 "arn": "arn:aws:iam::123456789012:user/Alice",
                 "accountId": "123456789012",
                 "accessKeyId": "EXAMPLE_KEY_ID",
                 "userName": "Alice"
             },
"eventTime": "2018-05-25T00:16:56Z",
" "!incoisvideo.amazonal
             "eventSource": "kinesisvideo.amazonaws.com",
             "eventName": "ListStreams",
"awsRegion": "us-east-1",
             "sourceIPAddress": "127.0.0.1",
             "userAgent": "aws-sdk-java/unknown-version Linux/x.xx",
             "requestParameters": {
                 "maxResults": 100,
                 "streamNameCondition": {"comparisonValue":"MyVideoStream"
 comparisonOperator":"BEGINS_WITH"}}
             },
             "responseElements": null,
             "requestID": "e9f9c8eb-c757-11e3-bf1d-6948db3cd570",
             "eventID": "77cf0d06-ce90-42da-9576-71986fec411f"
        }
    ]
}
```

## **Kinesis Video Streams Limits**

Kinesis Video Streams has the following limits:

The limits below are either soft [s], which can be upgraded by submitting a support ticket, or hard [h], which can't be increased.

## Control-plane API limits

The following section describes limits for Control Plane APIs. TPS stands for transactions per second.

When an account-level or resource-level Request limit is reached, a ClientLimitExceededException is thrown.

#### **Control Plane API limits**

API	Account Limit: Request	Account Limit: Streams	Stream-level limit	Relevant Exceptions and Notes
CreateStream	50 TPS [s]	10000 streams per account [s] in US East (N. Virginia) and US West (Oregon) regions. 5000 streams per account [s] in all other supported regions.		Devices, CLIs, SDK-driven access, and the console can all invoke this API. Only one API call succeeds if the stream doesn't already exist.
		Note This limit can be increased up to 100,000 (or more) streams per account [s]. Sign in to the AWS Managemer Console at https:// console.aws and	nt .amazon.com/	

API	Account Limit: Request	Account Limit: Streams	Stream-level limit	Relevant Exceptions and Notes
		submit a service limit increase case for Kinesis Video Streams to request an increase of this limit.		
DescribeStream	300 TPS [h]	N/A	5 TPS [h]	
UpdateStream	50 TPS [h]	N/A	5 TPS [h]	
ListStreams	50 TPS [h]	N/A		
DeleteStream	50 TPS [h]	N/A	5 TPS [h]	
GetDataEndpoin	ൻ00 TPS [h]	N/A	5 TPS [h]	Called every 45 minutes to refresh the streaming token for most PutMedia/GetMedia use cases. Caching data endpoints is safe if the application reloads them on failure.
UpdateDataRete	e <b>n5t0oTr</b> PS [h]	N/A	5 TPS [h]	
TagStream	50 TPS [h]	N/A	5 TPS [h]	
UntagStream	50 TPS [h]	N/A	5 TPS [h]	
ListTagsForStrea	a <b>5</b> 0 TPS [h]	N/A	5 TPS [h]	
DescribelmageG	e50eiTaHSo[hn⊈onfig	u <b>Ne/tAon</b>	5 TPS [h]	
UpdateImageGe	ทธิยาสิโหิSr[โจ้pnfigu	ra <b>t</b> i/øn	5 TPS [h]	
DescribeNotifica	າ <b>ເຮັດ</b> ກ່ <b>ັ</b> ເຕີຍກ <b>ູ້</b> figuratio	nN/A	5 TPS [h]	
UpdateNotificat	i <b>60C</b> CR <b>filg</b> u]ration	N/A	5 TPS [h]	

## Media and archived-media API limits

The following section describes limits for Media and Archived Media APIs.

When an account-level or resource-level Request limit is reached, a ClientLimitExceededException is thrown.

When a connection-level limit is reached, a ConnectionLimitExceededException is thrown.

### Amazon Kinesis Video Streams Developer Guide Media and archived-media API limits

The following errors or acks are thrown when a fragment-level limit is reached:

- A MIN\_FRAGMENT\_DURATION\_REACHED ack is returned for a fragment below the minimum duration.
- A MAX\_FRAGMENT\_DURATION\_REACHED ack is returned for a fragment above the maximum duration.
- A MAX\_FRAGMENT\_SIZE ack is returned for a fragment above the maximum data size.
- A FragmentLimitExceeded exception is thrown if a fragment limit is reached in a GetMediaForFragmentList operation.

### **Data Plane API limits**

API	Stream- level limit	Connection- level limit	Bandwidth limit	Fragment- level limit	Relevant Exceptions and Notes
PutMedia	5 TPS [h]	1 [s]	12.5 MB/ second, or 100 Mbps [s]	<ul> <li>Minimum fragment duration: 1 second [h]</li> <li>Maximum fragment duration: 20 seconds [h]</li> <li>Maximum fragment size: 50 MB [h]</li> <li>Maximum number of tracks: 3 [s]</li> </ul>	A typical PutMedia request contains data for several seconds, resulting in a lower TPS per stream. In the case of multiple concurrent connections that exceed limits, the last connection is accepted.
GetHLSStream	m2n5gTSieSs[ilo]nUR	LN/A	N/A	N/A	
GetDASHStre	ลชิษีเ <b>ที่∲S</b> e∯s]onし	J <b>rl</b> /A	N/A	N/A	
GetMedia	5 TPS [h]	3 [s]	25 MB/s or 200 Mbps [s]	N/A	Only three clients can concurrently receive content from the media stream at any moment of time. Further client connections are rejected. A unique consuming client shouldn't need more than 2 or 3 TPS because after the connection is established, we anticipate that the application will read continuously.  If a typical fragment is approximately 5 MB, this limit means ~75 MB/ sec per Kinesis video stream. Such a stream would have

API	Stream- level limit	Connection- level limit	Bandwidth limit	Fragment- level limit	Relevant Exceptions and Notes
					an outgoing bitrate of 2x the streams' maximum incoming bitrate.
GetMediaFor	Frkilg/InentList	5 [s]	25 MB/s or 200 Mbps [s]	Maximum number of fragments: 1000 [h]	Five fragment-based consuming applications can concurrently get media. Further connections are rejected.
GetClip	N/A	N/A	100 MB size limit [h]	Maximum number of fragments: 200 [h]	
GetImages	N/A	N/A	100 MB [h]	N/A	Maximum number of Images per request is 100 [h]

## Video Playback Protocol API limits

API	Session-level limit	Fragment-level limit
GetDASHManifestPlaylist	5 TPS [h]	Maximum number of fragments per playlist: 5000 [h]
GetHLSMasterPlaylist	5 TPS [h]	N/A
GetHLSMediaPlaylist	5 TPS [h]	Maximum number of fragments per playlist: 5000 [h]
GetMP4InitFragment	5 TPS [h]	N/A
GetMP4MediaFragment	20 TPS [h]	N/A
GetTSFragment	20 TPS [h]	N/A

## Fragment-metadata and fragment-media quotas

Kinesis Video Streams APIs for accessing archived media are throttled based on the number of fragments requested rather than the number of API calls. APIs are rate-limited by both the number of fragment metadata and the number of fragment media that is requested. The fragment metadata and fragment media quotas are applied per stream. In other words, requests for fragment metadata or media in one stream don't apply to the quotas of another stream. However, within a given stream, each quota is shared across multiple APIs. This means that, for a given stream, requests for fragments across different APIs consume from the same quota. When either the fragment metadata or fragment media quota for a stream is exceeded, the API returns a ClientLimitExceededException. The following tables show how the APIs consume from each of the two types of quota. For the second column in these tables, assume that if a stream has a quota of N, that means the APIs have N points to consume from that quota type for that stream. The GetClip API appears in both tables.

### Fragment metadata quota consumption

API	Number of quota points consumed per request
ListFragments	Value of the MaxResults parameter
GetClip	Number of fragments in the resulting clip
GetHLSMediaPlaylist	Value of the MaxMediaPlaylistFragmentResults parameter
GetDASHManifest	Value of the MaxManifestFragmentResults parameter
GetImages	Value of 400 + Max Number of Images requested

### Fragment media quota consumption

API	Number of quota points consumed per request	
GetMediaForFragmentList	Number of fragments in the Fragments parameter	
GetClip	Number of fragments in the resulting clip	
GetMP4MediaFragment	1	
GetTSFragment	1	
GetImages	Max Number of Images Requested	

For example, with a quota of 500 fragment media per second, the following call patterns for a particular stream are supported:

- 5 requests per second to GetClip with 100 fragments in each clip.
- 100 requests per second to GetClip with 5 fragments in each clip.
- 2 requests per second to GetClip with 100 fragments in each clip and 3 requests per second to GetMediaForFragmentList in each clip.
- 400 requests per second to GetMP4MediaFragment and 100 requests per second to GetTSFragment.

These quotas have an important implication regarding the number of HLS and MPEG-DASH sessions that can be supported per stream. There is no limit to the number of HLS and DASH sessions that can be in use by media players at a given time. Therefore, it is important that the playback application not allow too many sessions to be in use concurrently. The following are two examples of how to determine the number of concurrent playback sessions that can be supported:

## Example 1: Live Streaming

In a live streaming scenario with HLS with 1 second duration fragments, an audio and video track, and MaxMediaPlaylistFragmentResults set to 5, a media player typically makes 2 calls to GetHLSMediaPlaylist per second: one call for the latest video metadata and another for the corresponding audio metadata. The two calls consume 5 fragment metadata quota points each. It also makes 2 calls to GetMP4MediaFragment per second: one call for the latest video and another for the corresponding audio. These two calls consume a total of 2 fragment media quota points. In this scenario, up to 125 concurrent playback sessions can be supported. With 250 sessions, this scenario consumes

2,500 fragment metadata quota points per second (well below the 10,000 quota) and 500 fragment media quota points per second.

### Example 2: On-Demand Playback

In an on-demand playback scenario of a past event with MPEG-DASH, an audio and video track and MaxManifestFragmentResults set to 1,000, a media player typically calls GetDASHManifest once at the start of the session (consuming 1,000 fragment metadata quota points) and it calls GetMP4MediaFragment at a rate of up to 5 times per second (consuming 5 fragment media quota points) until all fragments are loaded. In this scenario, up to 10 new sessions can be started per second (right at the 10,000 fragment metadata per second quota), and up to 100 sessions can be actively loading fragment media at a rate of 5 per second (right at the 500 fragment media per second quota).

You can use ArchivedFragmentsConsumed.Metadata and ArchivedFragmentsConsumed.Media to monitor the consumption of fragment metadata and fragment media quota points, respectively. For information about monitoring, see *Monitoring* (p. 153).

# Troubleshooting Kinesis Video Streams

Use the following information to troubleshoot common issues encountered with Amazon Kinesis Video Streams.

### **Topics**

- Troubleshooting General Issues (p. 174)
- Troubleshooting API Issues (p. 174)
- Troubleshooting HLS Issues (p. 176)
- Troubleshooting Java Issues (p. 177)
- Troubleshooting Producer Library Issues (p. 178)
- Troubleshooting Stream Parser Library Issues (p. 183)

## **Troubleshooting General Issues**

This section describes general issues that you might encounter when working with Kinesis Video Streams.

#### Issues

· Latency too high (p. 174)

## Latency too high

Latency might be caused by the duration of fragments that are sent to the Kinesis Video Streams service. One way to reduce the latency between the producer and the service is to configure the media pipeline to produce shorter fragment durations.

To reduce the number of frames sent in each fragment, and thus reduce the amount of time for each fragment, reduce the following value in kinesis\_video\_gstreamer\_sample\_app.cpp:

```
g_object_set(G_OBJECT (data.encoder), "bframes", 0, "key-int-max", 45, "bitrate", 512,
NULL);
```

### Note

Latencies are higher in the Mozilla Firefox browser due to the internal implementation of video rendering.

## **Troubleshooting API Issues**

This section describes API issues that you might encounter when working with Kinesis Video Streams.

#### Issues

- Error: "Unknown options" (p. 175)
- Error: "Unable to determine service/operation name to be authorized" (p. 175)
- Error: "Failed to put a frame in the stream" (p. 175)

# Amazon Kinesis Video Streams Developer Guide Error: "Unknown options"

- Error: "Service closed connection before final AckEvent was received" (p. 175)
- Error: "STATUS\_STORE\_OUT\_OF\_MEMORY" (p. 176)

### Error: "Unknown options"

GetMedia and GetMediaForFragmentList can fail with the following error:

```
Unknown options: <filename>.mkv
```

This error occurs if you configured the AWS CLI with an output type of json. Reconfigure the AWS CLI with the default output type (none). For information about configuring the AWS CLI, see configure in the AWS CLI Command Reference.

# Error: "Unable to determine service/operation name to be authorized"

GetMedia can fail with the following error:

```
Unable to determine service/operation name to be authorized
```

This error might occur if the endpoint is not properly specified. When you are getting the endpoint, be sure to include the following parameter in the GetDataEndpoint call, depending on the API to be called:

```
--api-name GET_MEDIA
--api-name PUT_MEDIA
--api-name GET_MEDIA_FOR_FRAGMENT_LIST
--api-name LIST_FRAGMENTS
```

### Error: "Failed to put a frame in the stream"

PutMedia can fail with the following error:

```
Failed to put a frame in the stream
```

This error might occur if connectivity or permissions are not available to the service. Run the following in the AWS CLI, and verify that the stream information can be retrieved:

```
aws kinesisvideo describe-stream --stream-name StreamName --endpoint https://
ServiceEndpoint.kinesisvideo.region.amazonaws.com
```

If the call fails, see Troubleshooting AWS CLI Errors for more information.

# Error: "Service closed connection before final AckEvent was received"

PutMedia can fail with the following error:

com.amazonaws.SdkClientException: Service closed connection before final AckEvent was received This error might occur if PushbackInputStream is improperly implemented. Ensure that the unread() methods are correctly implemented.

### Error: "STATUS\_STORE\_OUT\_OF\_MEMORY"

PutMedia can fail with the following error:

The content store is out of memory.

This error occurs when the content store is not allocated with sufficient size. To increase the size of the content store, increase the value of StorageInfo.storageSize. For more information, see StorageInfo (p. 105).

# **Troubleshooting HLS Issues**

This section describes issues that you might encounter when using HTTP Live Streaming (HLS) with Kinesis Video Streams.

#### **Issues**

- Retrieving HLS streaming session URL succeeds, but playback fails in video player (p. 176)
- Latency too high between producer and player (p. 177)

# Retrieving HLS streaming session URL succeeds, but playback fails in video player

This situation occurs when you can successfully retrieve an HLS streaming session URL using GetHLSStreamingSessionURL, but the video fails to play back when the URL is provided to a video player.

To troubleshoot this situation, try the following:

- Determine whether the video stream plays back in the Kinesis Video Streams console. Consider any errors that the console shows.
- If the fragment duration is less than one second, increase it to one second. If the fragment duration is too short, the service might throttle the player because it is making requests for video fragments too frequently.
- Verify that each HLS streaming session URL is being used by only one player. If more than one player
  is using a single HLS streaming session URL, the service might receive too many requests and throttle
  them.
- Verify that your player supports all of the options that you are specifying for the HLS streaming session. Try different combinations of values for the following parameters:
  - ContainerFormat
  - PlaybackMode
  - FragmentSelectorType
  - DiscontinuityMode
  - MaxMediaPlaylistFragmentResults

Some media players (like HTML5 and mobile players) typically only support HLS with the fMP4 container format. Other media players (like Flash and custom players) may only support HLS with the

- MPEG TS container format. Experimenting with the ContainerFormat parameter is a good place to start troubleshooting.
- Verify that each fragment has a consistent number of tracks. Verify that fragments in the stream are not changing between having both an audio and video track and just a video track. Also verify that the encoder settings (resolution, frame rate, etc) are not changing between fragments in each track.

# Latency too high between producer and player

This situation occurs when the latency is too high from when the video is captured to when it is played in the video player.

Video is played back through HLS on a per-fragment basis. Therefore, latency can't be less than fragment duration. Latency also includes the time needed for buffering and transferring data. If your solution requires latency of less than one second, consider using the GetMedia API instead.

You can adjust the following parameters to reduce the overall latency, but adjusting these parameters might also reduce the video quality or increase the rebuffering rate.

- Fragment duration: The fragment duration is the amount of video between divisions in the stream as controlled by the frequency of keyframes generated by the video encoder. The recommended value is one second. Having a shorter fragment duration means that less time is spent waiting for the fragment to complete before transmitting the video data to the service. Shorter fragments are also faster for the service to process. However, if the fragment duration is too short, the probability increases that the player will run out of content and have to stop and buffer content. If the fragment duration is less than 500 milliseconds, the producer might create too many requests, causing the service to throttle them.
- **Bitrate**: A video stream with a lower bitrate takes less time to read, write, and transmit. However, a video stream with a lower bitrate usually has a lower video quality.
- Fragment count in media playlists: A latency-sensitive player should only load the newest fragments in a media playlist. Most players start at the oldest fragment instead. By reducing the number of fragments in the playlist, you reduce the time separation between the old and new fragments. With a smaller playlist size, it is possible for a fragment to be skipped during playback, if there is a delay in adding new fragments to the playlist, or if there is a delay in the player getting an updated playlist. We recommend using 3–5 fragments, and to use a player that is configured to load only the newest fragments from a playlist.
- Player buffer size: Most video players have a configurable minimum buffer duration, usually with a 10-second default. For the lowest latency, you can set this value to 0 seconds. However, doing so means that the player rebuffers if there is any delay producing fragments because the player will have no buffer for absorbing the delay.
- Player "catch up": Video players typically don't automatically catch playback up to the front of the video buffer if the buffer fills up, such as when a delayed fragment causes a backlog of fragments to play. A custom player can avoid this by either dropping frames, or increasing the playback speed (for example, to 1.1x) to catch up to the front of the buffer. This causes playback to be choppy or increase in speed as the player catches up, and rebuffering might be more frequent as the buffer size is kept short.

# **Troubleshooting Java Issues**

This section describes how to troubleshoot common Java issues encountered when working with Kinesis Video Streams.

#### Issues

• Enabling Java logs (p. 178)

# **Enabling Java logs**

To troubleshoot issues with Java samples and libraries, it is helpful to enable and examine the debug logs. To enable debug logs, do the following:

1. Add log4j to the pom.xml file, in the dependencies node:

```
<dependency>
    <groupId>log4j</groupId>
    <artifactId>log4j</artifactId>
    <version>1.2.17</version>
</dependency>
```

In the target/classes directory, create a file named log4j.properties with the following contents:

```
# Root logger option
log4j.rootLogger=DEBUG, stdout

# Redirect log messages to console
log4j.appender.stdout=org.apache.log4j.ConsoleAppender
log4j.appender.stdout.Target=System.out
log4j.appender.stdout.layout=org.apache.log4j.PatternLayout
log4j.appender.stdout.layout.ConversionPattern=%d{yyyy-MM-dd HH:mm:ss} %-5p %c{1}:%L -
%m%n
log4j.logger.org.apache.http.wire=DEBUG
```

The debug logs then print to the IDE console.

# Troubleshooting Producer Library Issues

This section describes issues that you might encounter when using the Producer Libraries (p. 53).

#### Issues

- Cannot compile the Producer SDK (p. 179)
- Video stream does not appear in the console (p. 179)
- Error: "Security token included in the request is invalid" when streaming data using the GStreamer demo application (p. 179)
- Error: "Failed to submit frame to Kinesis Video client" (p. 179)
- GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS X (p. 180)
- Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on Raspberry Pi (p. 180)
- Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi (p. 180)
- Camera fails to load on Raspberry Pi (p. 180)
- Camera can't be found on macOS High Sierra (p. 181)
- jni.h file not found when compiling on macOS High Sierra (p. 181)
- Curl errors when running the GStreamer demo application (p. 181)
- Timestamp/range assertion at runtime on Raspberry Pi (p. 181)
- Assertion on gst\_value\_set\_fraction\_range\_full on Raspberry Pi (p. 182)
- STATUS\_MKV\_INVALID\_ANNEXB\_NALU\_IN\_FRAME\_DATA (0x3200000d) error on Android (p. 182)

- Maximum Fragment Duration Was Reached Error (p. 182)
- "Invalid thing name passed" error when using IoT authorization (p. 182)

### Cannot compile the Producer SDK

Verify that the required libraries are in your path. To verify this, use the following command:

```
$ env | grep LD_LIBRARY_PATH
LD_LIBRARY_PATH=/home/local/awslabs/amazon-kinesis-video-streams-producer-sdk-cpp/kinesis-
video-native-build/downloads/local/lib
```

### Video stream does not appear in the console

To display your video stream in the console, it must be encoded using H.264 in AvCC format. If your stream is not displayed, verify the following:

- Your NAL Adaptation Flags (p. 104) are set to NAL\_ADAPTATION\_ANNEXB\_NALS | NAL\_ADAPTATION\_ANNEXB\_CPD\_NALS if the original stream is in Annex-B format. This is the default value in the StreamDefinition constructor.
- You are providing the codec private data correctly. For H.264, this is the sequence parameter set (SPS) and picture parameter set (PPS). Depending on your media source, this data may be retrieved from the media source separately or encoded into the frame.

Many elementary streams are in the following format, where Ab is the Annex-B start code (001 or 0001):

The CPD (Codec Private Data) which in the case of H.264 is in the stream as SPS and PPS, can be adapted to the AvCC format. Unless the media pipeline gives the CPD separately, the application can extract the CPD from the frame by looking for the first Idr frame (which should contain the SPS/PPS), extract the two NALUs [which will be Ab(Sps)Ab(Pps)] and set it in the CPD in StreamDefinition.

# Error: "Security token included in the request is invalid" when streaming data using the GStreamer demo application

If this error occurs, there is an issue with your credentials. Verify the following:

- If you are using temporary credentials, you must specify the session token.
- Verify that your temporary credentials are not expired.
- · Verify that you have the proper rights set up.
- On macOS, verify that you do not have credentials cached in Keychain.

# Error: "Failed to submit frame to Kinesis Video client"

If this error occurs, the timestamps are not properly set in the source stream. Try the following:

- Use the latest SDK sample, which might have an update that fixes your issue.
- Set the high-quality stream to a higher bit rate, and fix any jitter in the source stream if the camera supports doing so.

# GStreamer application stops with "streaming stopped, reason not-negotiated" message on OS X

Streaming may stop on OS X with the following message:

```
Debugging information: gstbasesrc.c(2939): void gst_base_src_loop(GstPad *) (): / GstPipeline:test-pipeline/GstAutoVideoSrc:source/GstAVFVideoSrc:source-actual-src-avfvide: streaming stopped, reason not-negotiated (-4)
```

A possible workaround for this is to remove the framerate parameters from the gst\_caps\_new\_simple call in kinesis video gstreamer sample app.cpp:

# Error: "Failed to allocate heap" when creating Kinesis Video Client in GStreamer demo on Raspberry Pi

The GStreamer sample application tries to allocate 512 MB of RAM, which might not be available on your system. You can reduce this allocation by reducing the following value in KinesisVideoProducer.cpp:

```
device_info.storageInfo.storageSize = 512 * 1024 * 1024;
```

# Error: "Illegal Instruction" when running GStreamer demo on Raspberry Pi

If you encounter the following error when executing the GStreamer demo, ensure that you have compiled the application for the correct version of your device. (For example, ensure that you are not compiling for Raspberry Pi 3 when you are running on Raspberry Pi 2.)

```
INFO - Initializing curl.
Illegal instruction
```

# Camera fails to load on Raspberry Pi

To check whether the camera is loaded, run the following:

\$ ls /dev/video\*

If nothing is found, run the following:

\$ vcgencmd get\_camera

The output should look similar to the following:

supported=1 detected=1

If the driver does not detect the camera, do the following:

- 1. Check the physical camera setup and verify that it's connected properly.
- 2. Run the following to upgrade the firmware:

\$ sudo rpi-update

- 3. Restart the device.
- 4. Run the following to load the driver:

\$ sudo modprobe bcm2835-v412

5. Verify that the camera was detected:

\$ ls /dev/video\*

## Camera can't be found on macOS High Sierra

On macOS High Sierra, the demo application can't find the camera if more than one camera is available.

# jni.h file not found when compiling on macOS High Sierra

To resolve this error, update your installation of Xcode to the latest version.

# Curl errors when running the GStreamer demo application

To resolve curl errors when you run the GStreamer demo application, copy this certificate file to /etc/ssl/cert.pem.

# Timestamp/range assertion at runtime on Raspberry Pi

If a timestamp range assertion occurs at runtime, update the firmware and restart the device:

```
$ sudo rpi-update
$ sudo reboot
```

# Assertion on gst\_value\_set\_fraction\_range\_full on Raspberry Pi

The following assertion appears if the uv41 service is running:

```
\label{lem:gst_util_fraction_compare} $$ gst_util_fraction_compare (numerator_start, denominator_start, numerator_end, denominator_end) < 0' failed
```

If this occurs, stop the uv41 service and restart the application.

# STATUS\_MKV\_INVALID\_ANNEXB\_NALU\_IN\_FRAME\_DATA (0x3200000d) error on Android

The following error appears if the NAL Adaptation Flags (p. 104) are incorrect for the media stream:

```
putKinesisVideoFrame(): Failed to put a frame with status code 0x3200000d
```

If this error occurs, provide the correct .withNalAdaptationFlags flag for your media (for example, NAL\_ADAPTATION\_ANNEXB\_CPD\_NALS). Provide this flag in the following line of the Android Producer Library (p. 58):

https://github.com/awslabs/aws-sdk-android-samples/blob/master/AmazonKinesisVideoDemoApp/src/main/java/com/amazonaws/kinesisvideo/demoapp/fragment/StreamConfigurationFragment.java#L169

## Maximum Fragment Duration Was Reached Error

This error occurs when a media fragment in a stream exceeds the maximum fragment duration limit. By default, Kinesis Video Streams sets a stream's maximum fragment duration to 10 seconds.

To resolve this issue, try the following:

- If you are using a webcam/USB camera, do one of the following:
  - If the you are using key frame-based fragmentation, then set the encoder to provide key frames within 10 seconds.
  - If you are not using key frame-based fragmentation, then when defining the stream in Step 2: Write and Examine the Code (p. 66), set the maximum fragment duration limit to a value that's less than 10 seconds.
  - If you are using software encoders (like x264) in the GStreamer pipeline, you can set the key-int-max attribute to a value within 10 seconds (for example, set key-int-max to 60, with fps set to 30, to enable key frames every 2 seconds).
- If you are using an RPI camera, set the keyframe-interval attribute to be less than 10 seconds.
- If you are using an IP (RTSP) camera, set the GOP size to 60.

# "Invalid thing name passed" error when using IoT authorization

To avoid this error (HTTP Error 403: Response: {"message":"Invalid thing name passed"}) when you're using IoT credentials for authorization, make sure that the value of streamname (a required parameter of the kvssink element) is identital to the value of iot-thingname. For more information, see GStreamer Element Parameter Reference (p. 137).

# Troubleshooting Stream Parser Library Issues

This section describes issues that you might encounter when using the Stream Parser Library (p. 124).

#### Issues

- Cannot access a single frame from the stream (p. 183)
- Fragment decoding error (p. 183)

# Cannot access a single frame from the stream

To access a single frame from a streaming source in your consumer application, ensure that your stream contains the correct codec private data. For information about the format of the data in a stream, see Data Model (p. 18).

To learn how to use codec private data to access a frame, see the following test file on the GitHub website: KinesisVideoRendererExampleTest.java

# Fragment decoding error

If your fragments are not properly encoded in an H.264 format and level that the browser supports, you might see the following error when playing your stream in the console:

Fragment Decoding Error

There was an error decoding the video data. Verify that the stream contains valid H.264 content

If this occurs, verify the following:

- The resolution of the frames matches the resolution specified in the Codec Private Data.
- The H.264 profile and level of the encoded frames matches the profile and level specified in the Codec Private Data.
- The browser supports the profile/level combination. Most current browsers support all profile and level combinations.
- The timestamps are accurate and in the correct order, and no duplicate timestamps are being created.
- Your application is encoding the frame data using the H.264 format.

# Document History for Amazon Kinesis Video Streams

The following table describes the important changes to the documentation since the last release of Amazon Kinesis Video Streams.

• Latest API version: 2017-11-29

• Latest documentation update: January 21, 2019

Change	Description	Date
Getting Started: Send Data to a Kinesis video stream	Basic tutorial for sending media data from a camera to a Kinesis video stream. For more information, see Step 3: Send Data to a Kinesis Video Stream (p. 26).	January 21, 2019
Library template for integration with SageMaker	Sample application for Kinesis Video Streams that uses SageMaker to identify when certain objects appear in an Amazon Kinesis video stream. For more information, see SageMaker (p. 147).	November 19, 2018
Streaming metadata	You can use the Producer SDK to embed metadata in a Kinesis video stream. For more information, see Using Streaming Metadata with Kinesis Video Streams (p. 15).	September 28, 2018
C++ Producer SDK logging	You can configure logging for C ++ Producer SDK applications. For more information, see Using Logging with the C++ Producer SDK (p. 71).	July 18, 2018
HLS video streaming	You can now view a Kinesis video stream using HTTP Live Streaming. For more information, see Kinesis Video Streams Playback (p. 9).	July 13, 2018
Streaming from an RTSP source	Sample application for Kinesis Video Streams that runs in a Docker container and streams video from an RTSP source. For more information, see RTSP and Docker (p. 143).	June 20, 2018

Change	Description	Date
C++ Producer SDK GStreamer Plugin	Shows how to build the C++ Producer Library (p. 63) to use as a GStreamer destination. For more information, see GStreamer (p. 132).	June 15, 2018
Producer SDK callbacks reference documentation	Reference documentation for the callbacks used by the Kinesis Video Streams Producer Libraries (p. 53). For more information, see Producer SDK Callbacks (p. 118).	June 12, 2018
System requirements	Documentation for memory and storage requirements for producer devices and SDK. For more information, see Kinesis Video Streams System Requirements (p. 3).	May 30, 2018
CloudTrail support	Documentation for using CloudTrail to monitor API usage. For more information, see Logging Kinesis Video Streams API Calls with AWS CloudTrail (p. 164).	May 24, 2018
Producer SDK structures reference documentation	Reference documentation for the structures used by the Kinesis Video Streams Producer Libraries (p. 53). For more information, see Producer SDK Structures (p. 104) and Kinesis Video Stream Structures (p. 106).	May 7, 2018
Renderer example documentation	Documentation for the Renderer example application, which shows how to decode and display frames from a Kinesis video stream. For more information, see Example: Parsing and Rendering Kinesis Video Streams Fragments (p. 145).	March 15, 2018
Producer SDK Limits reference documentation	Information about limits for operations in the C++ Producer Library (p. 63). For more information, see Producer SDK Limits (p. 78).	March 13, 2018

Change	Description	Date
Monitoring	Information about monitoring Kinesis Video Streams metrics and API calls using Amazon CloudWatch and AWS CloudTrail. For more information, see Monitoring Kinesis Video Streams (p. 153).	February 5, 2018
Network Abstraction Layer (NAL) adaptation flag reference	Information about setting NAL adaptation flags when consuming streaming video. For more information, see NAL Adaptation Flags (p. 104).	January 15, 2018
Android support for streaming video	Kinesis Video Streams now supports streaming video from Android devices. For more information, see Android Producer Library (p. 58).	January 12, 2018
Kinesis Video example documentation	Documentation for the Kinesis Video example application, which shows how to use the Kinesis Video Stream Parser Library (p. 124) in an application. For more information, see Kinesis Video Example (p. 128).	January 9, 2018
Kinesis Video Streams documentation released	This is the initial release of the Amazon Kinesis Video Streams Developer Guide.	November 29, 2017

# **API Reference**

The sections under this node contain the API Reference documentation. Use the table of contents in the left pane to go to the different API reference sections.

### **Actions**

The following actions are supported by Amazon Kinesis Video Streams:

- CreateSignalingChannel (p. 189)
- CreateStream (p. 192)
- DeleteSignalingChannel (p. 196)
- DeleteStream (p. 199)
- DescribeImageGenerationConfiguration (p. 202)
- DescribeNotificationConfiguration (p. 205)
- DescribeSignalingChannel (p. 208)
- DescribeStream (p. 211)
- GetDataEndpoint (p. 214)
- GetSignalingChannelEndpoint (p. 217)
- ListSignalingChannels (p. 220)
- ListStreams (p. 223)
- ListTagsForResource (p. 226)
- ListTagsForStream (p. 229)
- TagResource (p. 232)
- TagStream (p. 234)
- UntagResource (p. 237)
- UntagStream (p. 239)
- UpdateDataRetention (p. 242)
- UpdateImageGenerationConfiguration (p. 245)
- UpdateNotificationConfiguration (p. 248)
- UpdateSignalingChannel (p. 251)
- UpdateStream (p. 254)

The following actions are supported by Amazon Kinesis Video Streams Media:

- GetMedia (p. 258)
- PutMedia (p. 262)

The following actions are supported by Amazon Kinesis Video Streams Archived Media:

- GetClip (p. 269)
- GetDASHStreamingSessionURL (p. 273)
- GetHLSStreamingSessionURL (p. 280)
- GetImages (p. 288)

- GetMediaForFragmentList (p. 293)
- ListFragments (p. 296)

The following actions are supported by Amazon Kinesis Video Signaling Channels:

- GetIceServerConfig (p. 300)
- SendAlexaOfferToMaster (p. 303)

### Amazon Kinesis Video Streams

The following actions are supported by Amazon Kinesis Video Streams:

- CreateSignalingChannel (p. 189)
- CreateStream (p. 192)
- DeleteSignalingChannel (p. 196)
- DeleteStream (p. 199)
- DescribeImageGenerationConfiguration (p. 202)
- DescribeNotificationConfiguration (p. 205)
- DescribeSignalingChannel (p. 208)
- DescribeStream (p. 211)
- GetDataEndpoint (p. 214)
- GetSignalingChannelEndpoint (p. 217)
- ListSignalingChannels (p. 220)
- ListStreams (p. 223)
- ListTagsForResource (p. 226)
- ListTagsForStream (p. 229)
- TagResource (p. 232)
- TagStream (p. 234)
- UntagResource (p. 237)
- UntagStream (p. 239)
- UpdateDataRetention (p. 242)
- UpdateImageGenerationConfiguration (p. 245)
- UpdateNotificationConfiguration (p. 248)
- UpdateSignalingChannel (p. 251)
- UpdateStream (p. 254)

### CreateSignalingChannel

Service: Amazon Kinesis Video Streams

Creates a signaling channel.

CreateSignalingChannel is an asynchronous operation.

#### Request Syntax

```
POST /createSignalingChannel HTTP/1.1
Content-type: application/json

{
    "ChannelName": "string",
    "ChannelType": "string",
    "SingleMasterConfiguration": {
        "MessageTtlSeconds": number
    },
    "Tags": [
        {
            "Key": "string",
            "Value": "string"
        }
    ]
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### ChannelName (p. 189)

A name for the signaling channel that you are creating. It must be unique for each AWS account and AWS Region.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: Yes

#### ChannelType (p. 189)

A type of the signaling channel that you are creating. Currently, SINGLE\_MASTER is the only supported channel type.

```
Type: String
```

Valid Values: SINGLE\_MASTER | FULL\_MESH

Required: No

#### SingleMasterConfiguration (p. 189)

A structure containing the configuration for the SINGLE\_MASTER channel type.

Type: SingleMasterConfiguration (p. 317) object

Required: No Tags (p. 189)

A set of tags (key-value pairs) that you want to associate with this channel.

Type: Array of Tag (p. 321) objects

Array Members: Minimum number of 0 items. Maximum number of 50 items.

Required: No

#### Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "ChannelARN": "string"
}
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### ChannelARN (p. 190)

The Amazon Resource Name (ARN) of the created channel.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### AccountChannelLimitExceededException

You have reached the maximum limit of active signaling channels for this AWS account in this region.

HTTP Status Code: 400

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

#### HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, <code>DescribeStream</code> for video streams.

HTTP Status Code: 400

#### TagsPerResourceExceededLimitException

You have exceeded the limit of tags that you can associate with the resource. A Kinesis video stream can support up to 50 tags.

HTTP Status Code: 400

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V3

#### CreateStream

Service: Amazon Kinesis Video Streams

Creates a new Kinesis video stream.

When you create a new stream, Kinesis Video Streams assigns it a version number. When you change the stream's metadata, Kinesis Video Streams updates the version.

CreateStream is an asynchronous operation.

For information about how the service works, see How it Works.

You must have permissions for the KinesisVideo:CreateStream action.

#### Request Syntax

```
POST /createStream HTTP/1.1
Content-type: application/json

{
    "DataRetentionInHours": number,
    "DeviceName": "string",
    "KmsKeyId": "string",
    "MediaType": "string",
    "StreamName": "string",
    "Tags": {
        "string" : "string"
    }
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### Request Body

The request accepts the following data in JSON format.

#### DataRetentionInHours (p. 192)

The number of hours that you want to retain the data in the stream. Kinesis Video Streams retains the data in a data store that is associated with the stream.

The default value is 0, indicating that the stream does not persist data.

When the DataRetentionInHours value is 0, consumers can still consume the fragments that remain in the service host buffer, which has a retention time limit of 5 minutes and a retention memory limit of 200 MB. Fragments are removed from the buffer when either limit is reached.

Type: Integer

Valid Range: Minimum value of 0.

Required: No

#### DeviceName (p. 192)

The name of the device that is writing to the stream.

#### Note

In the current implementation, Kinesis Video Streams does not use this name.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9\_.-]+

Required: No KmsKeyId (p. 192)

The ID of the AWS Key Management Service (AWS KMS) key that you want Kinesis Video Streams to use to encrypt stream data.

If no key ID is specified, the default, Kinesis Video-managed key (aws/kinesisvideo) is used.

For more information, see DescribeKey.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 2048.

Pattern: .+

Required: No MediaType (p. 192)

The media type of the stream. Consumers of the stream can use this information when processing the stream. For more information about media types, see Media Types. If you choose to specify the MediaType, see Naming Requirements for guidelines.

Example valid values include "video/h264" and "video/h264,audio/aac".

This parameter is optional; the default value is null (or empty in JSON).

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [\w\-\.\+]+/[\w\-\.\+]+(, [\w\-\.\+]+/[\w\-\.\+]+)\*

Required: No

StreamName (p. 192)

A name for the stream that you are creating.

The stream name is an identifier for the stream, and must be unique for each account and region.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: Yes

Tags (p. 192)

A list of tags to associate with the specified stream. Each tag is a key-value pair (the value is optional).

Type: String to string map

Map Entries: Maximum number of 50 items.

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Key Pattern:  $^([\p{L}\p{Z}\p{N}_.:/=+\-@]*)$ 

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Value Pattern:  $[\p{L}\p{N}_.:/=+\-@]*$ 

Required: No

#### Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "StreamARN": "string"
}
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### StreamARN (p. 194)

The Amazon Resource Name (ARN) of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccountStreamLimitExceededException

The number of streams created for the account is too high.

HTTP Status Code: 400

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### ${\bf Device Stream Limit Exceeded Exception}$

Not implemented.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400 InvalidDeviceException

Not implemented.

HTTP Status Code: 400 ResourceInUseException

# The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, DescribeStream for video streams.

HTTP Status Code: 400

#### Tags Per Resource Exceeded Limit Exception

You have exceeded the limit of tags that you can associate with the resource. A Kinesis video stream can support up to 50 tags.

HTTP Status Code: 400

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

### DeleteSignalingChannel

Service: Amazon Kinesis Video Streams

Deletes a specified signaling channel. DeleteSignalingChannel is an asynchronous operation. If you don't specify the channel's current version, the most recent version is deleted.

#### Request Syntax

```
POST /deleteSignalingChannel HTTP/1.1
Content-type: application/json
{
    "ChannelARN": "string",
    "CurrentVersion": "string"
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### ChannelARN (p. 196)

The Amazon Resource Name (ARN) of the signaling channel that you want to delete.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+: kinesis video: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: Yes

#### **CurrentVersion (p. 196)**

The current version of the signaling channel that you want to delete. You can obtain the current version by invoking the DescribeSignalingChannel or ListSignalingChannels API operations.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: No

#### Response Syntax

```
HTTP/1.1 200
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400 ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, <code>DescribeStream</code> for video streams.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams	
	_

#### DeleteStream

Service: Amazon Kinesis Video Streams

Deletes a Kinesis video stream and the data contained in the stream.

This method marks the stream for deletion, and makes the data in the stream inaccessible immediately.

To ensure that you have the latest version of the stream before deleting it, you can specify the stream version. Kinesis Video Streams assigns a version to each stream. When you update a stream, Kinesis Video Streams assigns a new version number. To get the latest stream version, use the DescribeStream API.

This operation requires permission for the KinesisVideo:DeleteStream action.

#### Request Syntax

```
POST /deleteStream HTTP/1.1
Content-type: application/json

{
    "CurrentVersion": "string",
    "StreamARN": "string"
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### CurrentVersion (p. 199)

Optional: The version of the stream that you want to delete.

Specify the version as a safeguard to ensure that your are deleting the correct stream. To get the stream version, use the DescribeStream API.

If not specified, only the CreationTime is checked before deleting the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

```
Pattern: [a-zA-Z0-9]+
```

Required: No StreamARN (p. 199)

The Amazon Resource Name (ARN) of the stream that you want to delete.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: Yes

#### Response Syntax

HTTP/1.1 200

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### Invalid Argument Exception

The value for this input parameter is invalid.

HTTP Status Code: 400 **NotAuthorizedException** 

The caller is not authorized to perform this operation.

HTTP Status Code: 401 ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, DescribeStream for video streams.

HTTP Status Code: 400

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

### DescribelmageGenerationConfiguration

Service: Amazon Kinesis Video Streams

Gets the ImageGenerationConfiguration for a given Kinesis video stream.

#### **Request Syntax**

```
POST /describeImageGenerationConfiguration HTTP/1.1
Content-type: application/json
{
    "StreamARN": "string",
    "StreamName": "string"
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### StreamARN (p. 202)

The Amazon Resource Name (ARN) of the Kinesis video stream from which to retrieve the image generation configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn:[a-z\d-]+:kinesisvideo:[a-z0-9-]+:[0-9]+:[a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### StreamName (p. 202)

The name of the stream from which to retrieve the image generation configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

#### Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "ImageGenerationConfiguration": {
        "DestinationConfig": {
            "DestinationRegion": "string",
```

```
"Uri": "string"
},
"Format": "string",
"FormatConfig": {
    "string" : "string"
},
"HeightPixels": number,
"ImageSelectorType": "string",
"SamplingInterval": number,
"Status": "string",
"WidthPixels": number
}
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### ImageGenerationConfiguration (p. 202)

The structure that contains the information required for the Kinesis video stream (KVS) images delivery. If this structure is null, the configuration will be deleted from the stream.

Type: ImageGenerationConfiguration (p. 310) object

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

AWS Command Line Interface

- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

### DescribeNotificationConfiguration

Service: Amazon Kinesis Video Streams

Gets the NotificationConfiguration for a given Kinesis video stream.

#### **Request Syntax**

```
POST /describeNotificationConfiguration HTTP/1.1
Content-type: application/json
{
    "StreamARN": "string",
    "StreamName": "string"
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### StreamARN (p. 205)

The Amazon Resource Name (ARN) of the Kinesis video stream from where you want to retrieve the notification configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### StreamName (p. 205)

The name of the stream from which to retrieve the notification configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

#### Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "NotificationConfiguration": {
        "DestinationConfig": {
            "Uri": "string"
}
```

```
},
    "Status": "string"
}
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### NotificationConfiguration (p. 205)

The structure that contains the information required for notifications. If the structure is null, the configuration will be deleted from the stream.

Type: NotificationConfiguration (p. 313) object

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NET
- · AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python

•	AWS SDK for Ruby V3

### DescribeSignalingChannel

Service: Amazon Kinesis Video Streams

Returns the most current information about the signaling channel. You must specify either the name or the Amazon Resource Name (ARN) of the channel that you want to describe.

#### Request Syntax

```
POST /describeSignalingChannel HTTP/1.1
Content-type: application/json

{
    "ChannelARN": "string",
    "ChannelName": "string"
}
```

#### **URI Request Parameters**

The request does not use any URI parameters.

#### **Request Body**

The request accepts the following data in JSON format.

#### ChannelARN (p. 208)

The ARN of the signaling channel that you want to describe.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### ChannelName (p. 208)

The name of the signaling channel that you want to describe.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

#### Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "ChannelInfo": {
        "ChannelARN": "string",
        "ChannelName": "string",
        "ChannelStatus": "string",
```

```
"ChannelType": "string",
    "CreationTime": number,
    "SingleMasterConfiguration": {
        "MessageTtlSeconds": number
    },
        "Version": "string"
}
```

#### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### Channelinfo (p. 208)

A structure that encapsulates the specified signaling channel's metadata and properties.

Type: ChannelInfo (p. 307) object

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- · AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript

- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# DescribeStream

Service: Amazon Kinesis Video Streams

Returns the most current information about the specified stream. You must specify either the StreamName or the StreamARN.

### Request Syntax

```
POST /describeStream HTTP/1.1
Content-type: application/json
{
    "StreamARN": "string",
    "StreamName": "string"
}
```

### **URI Request Parameters**

The request does not use any URI parameters.

### **Request Body**

The request accepts the following data in JSON format.

```
StreamARN (p. 211)
```

The Amazon Resource Name (ARN) of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### StreamName (p. 211)

The name of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

### Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "StreamInfo": {
        "CreationTime": number,
        "DataRetentionInHours": number,
        "DeviceName": "string",
```

```
"KmsKeyId": "string",
   "MediaType": "string",
   "Status": "string",
   "StreamARN": "string",
   "StreamName": "string",
   "Version": "string"
}
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### StreamInfo (p. 211)

An object that describes the stream.

Type: StreamInfo (p. 318) object

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

#### NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

### See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript

- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# GetDataEndpoint

Service: Amazon Kinesis Video Streams

Gets an endpoint for a specified stream for either reading or writing. Use this endpoint in your application to read from the specified stream (using the GetMedia or GetMediaForFragmentList operations) or write to it (using the PutMedia operation).

#### Note

The returned endpoint does not have the API name appended. The client needs to add the API name to the returned endpoint.

In the request, specify the stream either by StreamName or StreamARN.

## Request Syntax

```
POST /getDataEndpoint HTTP/1.1
Content-type: application/json

{
    "APIName": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

#### APIName (p. 214)

The name of the API action for which to get an endpoint.

```
Type: String

Valid Values: PUT_MEDIA | GET_MEDIA | LIST_FRAGMENTS |
GET_MEDIA_FOR_FRAGMENT_LIST | GET_HLS_STREAMING_SESSION_URL |
GET_DASH_STREAMING_SESSION_URL | GET_CLIP | GET_IMAGES

Required: Yes
```

### StreamARN (p. 214)

The Amazon Resource Name (ARN) of the stream that you want to get the endpoint for. You must specify either this parameter or a StreamName in the request.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### StreamName (p. 214)

The name of the stream that you want to get the endpoint for. You must specify either this parameter or a StreamARN in the request.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

### Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "DataEndpoint": "string"
}
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### DataEndpoint (p. 215)

The endpoint value. To read data from the stream or to write data to it, specify this endpoint in your application.

Type: String

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

# **InvalidArgumentException**

The value for this input parameter is invalid.

HTTP Status Code: 400

## NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# GetSignalingChannelEndpoint

Service: Amazon Kinesis Video Streams

Provides an endpoint for the specified signaling channel to send and receive messages. This API uses the SingleMasterChannelEndpointConfiguration input parameter, which consists of the Protocols and Role properties.

Protocols is used to determine the communication mechanism. For example, if you specify WSS as the protocol, this API produces a secure websocket endpoint. If you specify HTTPS as the protocol, this API generates an HTTPS endpoint.

Role determines the messaging permissions. A MASTER role results in this API generating an endpoint that a client can use to communicate with any of the viewers on the channel. A VIEWER role results in this API generating an endpoint that a client can use to communicate only with a MASTER.

### Request Syntax

```
POST /getSignalingChannelEndpoint HTTP/1.1
Content-type: application/json

{
    "ChannelARN": "string",
    "SingleMasterChannelEndpointConfiguration": {
        "Protocols": [ "string" ],
        "Role": "string"
    }
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

#### ChannelARN (p. 217)

The Amazon Resource Name (ARN) of the signalling channel for which you want to get an endpoint.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: Yes

### SingleMasterChannelEndpointConfiguration (p. 217)

A structure containing the endpoint configuration for the SINGLE\_MASTER channel type.

Type: SingleMasterChannelEndpointConfiguration (p. 316) object

Required: No

### Response Syntax

```
HTTP/1.1 200
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### ResourceEndpointList (p. 217)

A list of endpoints for the specified signaling channel.

Type: Array of ResourceEndpointListItem (p. 315) objects

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

### ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, <code>DescribeStream</code> for video streams.

HTTP Status Code: 400

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# ListSignalingChannels

Service: Amazon Kinesis Video Streams

Returns an array of ChannelInfo objects. Each object describes a signaling channel. To retrieve only those channels that satisfy a specific condition, you can specify a ChannelNameCondition.

### Request Syntax

```
POST /listSignalingChannels HTTP/1.1
Content-type: application/json

{
    "ChannelNameCondition": {
        "ComparisonOperator": "string",
        "ComparisonValue": "string"
},
    "MaxResults": number,
    "NextToken": "string"
}
```

### **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

#### ChannelNameCondition (p. 220)

Optional: Returns only the channels that satisfy a specific condition.

Type: ChannelNameCondition (p. 309) object

Required: No

MaxResults (p. 220)

The maximum number of channels to return in the response. The default is 500.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 10000.

Required: No NextToken (p. 220)

If you specify this parameter, when the result of a ListSignalingChannels operation is truncated, the call returns the NextToken in the response. To get another batch of channels, provide this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Pattern: [a-zA-Z0-9+/=]\*

Required: No

# Response Syntax

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### ChannelInfoList (p. 221)

An array of Channel Info objects.

Type: Array of ChannelInfo (p. 307) objects

### NextToken (p. 221)

If the response is truncated, the call returns this element with a token. To get the next batch of streams, use this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

```
Pattern: [a-zA-Z0-9+/=]*
```

# **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

# InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

### See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

### ListStreams

Service: Amazon Kinesis Video Streams

Returns an array of StreamInfo objects. Each object describes a stream. To retrieve only streams that satisfy a specific condition, you can specify a StreamNameCondition.

### Request Syntax

```
POST /listStreams HTTP/1.1
Content-type: application/json

{
    "MaxResults": number,
    "NextToken": "string",
    "StreamNameCondition": {
        "ComparisonOperator": "string",
        "ComparisonValue": "string"
    }
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

### Request Body

The request accepts the following data in JSON format.

#### MaxResults (p. 223)

The maximum number of streams to return in the response. The default is 10,000.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 10000.

Required: No

#### NextToken (p. 223)

If you specify this parameter, when the result of a ListStreams operation is truncated, the call returns the NextToken in the response. To get another batch of streams, provide this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Pattern: [a-zA-Z0-9+/=]\*

Required: No

### StreamNameCondition (p. 223)

Optional: Returns only streams that satisfy a specific condition. Currently, you can specify only the prefix of a stream name as a condition.

Type: StreamNameCondition (p. 320) object

Required: No

# Response Syntax

```
HTTP/1.1 200
Content-type: application/json
   "NextToken": "string",
   "StreamInfoList": [
      {
          "CreationTime": number,
          "DataRetentionInHours": number,
          "DeviceName": "string",
          "KmsKeyId": "string"
          "MediaType": "string",
          "Status": "string",
          "StreamARN": "string",
"StreamName": "string",
          "Version": "string"
      }
   ]
}
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### NextToken (p. 224)

If the response is truncated, the call returns this element with a token. To get the next batch of streams, use this token in your next request.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

```
Pattern: [a-zA-Z0-9+/=]*
```

### StreamInfoList (p. 224)

An array of StreamInfo objects.

Type: Array of StreamInfo (p. 318) objects

## **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# ListTagsForResource

Service: Amazon Kinesis Video Streams

Returns a list of tags associated with the specified signaling channel.

### Request Syntax

```
POST /ListTagsForResource HTTP/1.1
Content-type: application/json

{
    "NextToken": "string",
    "ResourceARN": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

### **Request Body**

The request accepts the following data in JSON format.

#### NextToken (p. 226)

If you specify this parameter and the result of a ListTagsForResource call is truncated, the response includes a token that you can use in the next request to fetch the next batch of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Pattern: [a-zA-Z0-9+/=]\*

Required: No

### ResourceARN (p. 226)

The Amazon Resource Name (ARN) of the signaling channel for which you want to list tags.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+: kinesis video: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: Yes

### Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "NextToken": "string",
    "Tags": {
        "string" : "string"
    }
```

}

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### NextToken (p. 226)

If you specify this parameter and the result of a ListTagsForResource call is truncated, the response includes a token that you can use in the next request to fetch the next set of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

Pattern: [a-zA-Z0-9+/=]\*

Tags (p. 226)

A map of tag keys and values associated with the specified signaling channel.

Type: String to string map

Map Entries: Maximum number of 50 items.

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Key Pattern:  $^([\p{L}\p{X}\p{N}_.:/=+\-@]*)$ 

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Value Pattern:  $[\p{L}\p{N}_.:/=+\-@]*$ 

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# ListTagsForStream

Service: Amazon Kinesis Video Streams

Returns a list of tags associated with the specified stream.

In the request, you must specify either the StreamName or the StreamARN.

### Request Syntax

```
POST /listTagsForStream HTTP/1.1
Content-type: application/json

{
    "NextToken": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

```
NextToken (p. 229)
```

If you specify this parameter and the result of a ListTagsForStream call is truncated, the response includes a token that you can use in the next request to fetch the next batch of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

```
Pattern: [a-zA-Z0-9+/=]*
```

Required: No StreamARN (p. 229)

The Amazon Resource Name (ARN) of the stream that you want to list tags for.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: No

### StreamName (p. 229)

The name of the stream that you want to list tags for.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

#### Required: No

# **Response Syntax**

```
HTTP/1.1 200
Content-type: application/json

{
    "NextToken": "string",
    "Tags": {
        "string" : "string"
    }
}
```

### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

#### NextToken (p. 230)

If you specify this parameter and the result of a ListTags call is truncated, the response includes a token that you can use in the next request to fetch the next set of tags.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 512.

```
Pattern: [a-zA-Z0-9+/=]*
```

## Tags (p. 230)

A map of tag keys and values associated with the specified stream.

Type: String to string map

Map Entries: Maximum number of 50 items.

Key Length Constraints: Minimum length of 1. Maximum length of 128.

```
Key Pattern: ^([\p{L}\p{Z}\p{N}_.:/=+\-@]*)
```

Value Length Constraints: Minimum length of 0. Maximum length of 256.

```
Value Pattern: [\p{L}\p{Z}\p{N}_.:/=+\-@]*
```

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

```
HTTP Status Code: 400
```

### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

### InvalidResourceFormatException

The format of the StreamARN is invalid.

HTTP Status Code: 400 **NotAuthorizedException** 

The caller is not authorized to perform this operation.

HTTP Status Code: 401
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

### See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **TagResource**

Service: Amazon Kinesis Video Streams

Adds one or more tags to a signaling channel. A *tag* is a key-value pair (the value is optional) that you can define and assign to AWS resources. If you specify a tag that already exists, the tag value is replaced with the value that you specify in the request. For more information, see Using Cost Allocation Tags in the AWS Billing and Cost Management and Cost Management User Guide.

### Request Syntax

### **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

# ResourceARN (p. 232)

The Amazon Resource Name (ARN) of the signaling channel to which you want to add tags.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: Yes

### Tags (p. 232)

A list of tags to associate with the specified signaling channel. Each tag is a key-value pair.

```
Type: Array of Tag (p. 321) objects
```

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Required: Yes

### Response Syntax

```
HTTP/1.1 200
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401
ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

#### TagsPerResourceExceededLimitException

You have exceeded the limit of tags that you can associate with the resource. A Kinesis video stream can support up to 50 tags.

HTTP Status Code: 400

### See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **TagStream**

Service: Amazon Kinesis Video Streams

Adds one or more tags to a stream. A *tag* is a key-value pair (the value is optional) that you can define and assign to AWS resources. If you specify a tag that already exists, the tag value is replaced with the value that you specify in the request. For more information, see Using Cost Allocation Tags in the AWS Billing and Cost Management and Cost Management User Guide.

You must provide either the StreamName or the StreamARN.

This operation requires permission for the KinesisVideo: TagStream action.

A Kinesis video stream can support up to 50 tags.

# Request Syntax

```
POST /tagStream HTTP/1.1
Content-type: application/json

{
    "StreamARN": "string",
    "StreamName": "string",
    "Tags": {
        "string" : "string"
    }
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

### StreamARN (p. 234)

The Amazon Resource Name (ARN) of the resource that you want to add the tag or tags to.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

# StreamName (p. 234)

The name of the stream that you want to add the tag or tags to.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

### Tags (p. 234)

A list of tags to associate with the specified stream. Each tag is a key-value pair (the value is optional).

Type: String to string map

Map Entries: Maximum number of 50 items.

Key Length Constraints: Minimum length of 1. Maximum length of 128.

Key Pattern:  $([\p{L}\p{Z}\p{N}_.:/=+\-@]*)$ 

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Value Pattern:  $[\p{L}\p{Z}\p{N}_.:/=+\-@]*$ 

Required: Yes

# Response Syntax

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

#### InvalidResourceFormatException

The format of the StreamARN is invalid.

HTTP Status Code: 400

#### NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

### Tags Per Resource Exceeded Limit Exception

You have exceeded the limit of tags that you can associate with the resource. A Kinesis video stream can support up to 50 tags.

HTTP Status Code: 400

### See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **UntagResource**

Service: Amazon Kinesis Video Streams

Removes one or more tags from a signaling channel. In the request, specify only a tag key or keys; don't specify the value. If you specify a tag key that does not exist, it's ignored.

### Request Syntax

```
POST /UntagResource HTTP/1.1
Content-type: application/json

{
    "ResourceARN": "string",
    "TagKeyList": [ "string" ]
}
```

### **URI Request Parameters**

The request does not use any URI parameters.

### Request Body

The request accepts the following data in JSON format.

### ResourceARN (p. 237)

The Amazon Resource Name (ARN) of the signaling channel from which you want to remove tags.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: Yes

### TagKeyList (p. 237)

A list of the keys of the tags that you want to remove.

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

```
Pattern: ^([\p{L}\p{X}\p{N}_.:/=+\-@]*)
```

Required: Yes

### Response Syntax

```
HTTP/1.1 200
```

### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401
ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

### See Also

- AWS Command Line Interface
- AWS SDK for .NET
- · AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **UntagStream**

Service: Amazon Kinesis Video Streams

Removes one or more tags from a stream. In the request, specify only a tag key or keys; don't specify the value. If you specify a tag key that does not exist, it's ignored.

In the request, you must provide the StreamName or StreamARN.

# **Request Syntax**

```
POST /untagStream HTTP/1.1
Content-type: application/json

{
    "StreamARN": "string",
    "StreamName": "string",
    "TagKeyList": [ "string" ]
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

```
StreamARN (p. 239)
```

The Amazon Resource Name (ARN) of the stream that you want to remove tags from.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: No

#### StreamName (p. 239)

The name of the stream that you want to remove tags from.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

#### TagKeyList (p. 239)

A list of the keys of the tags that you want to remove.

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern:  $^([\p{L}\p{Z}\p{N}_.:/=+\-@]*)$ 

Required: Yes

# **Response Syntax**

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

### InvalidResourceFormatException

The format of the StreamARN is invalid.

HTTP Status Code: 400

#### NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

#### ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

### See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- · AWS SDK for PHP V3

- AWS SDK for Python
- AWS SDK for Ruby V3

# **UpdateDataRetention**

Service: Amazon Kinesis Video Streams

Increases or decreases the stream's data retention period by the value that you specify. To indicate whether you want to increase or decrease the data retention period, specify the Operation parameter in the request body. In the request, you must specify either the StreamName or the StreamARN.

#### Note

The retention period that you specify replaces the current value.

This operation requires permission for the KinesisVideo:UpdateDataRetention action.

Changing the data retention period affects the data in the stream as follows:

- If the data retention period is increased, existing data is retained for the new retention period. For example, if the data retention period is increased from one hour to seven hours, all existing data is retained for seven hours.
- If the data retention period is decreased, existing data is retained for the new retention period. For example, if the data retention period is decreased from seven hours to one hour, all existing data is retained for one hour, and any data older than one hour is deleted immediately.

# Request Syntax

```
POST /updateDataRetention HTTP/1.1
Content-type: application/json

{
    "CurrentVersion": "string",
    "DataRetentionChangeInHours": number,
    "Operation": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

### Request Body

The request accepts the following data in JSON format.

#### CurrentVersion (p. 242)

The version of the stream whose retention period you want to change. To get the version, call either the DescribeStream or the ListStreams API.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 64.

```
Pattern: [a-zA-Z0-9]+
```

Required: Yes

#### DataRetentionChangeInHours (p. 242)

The retention period, in hours. The value you specify replaces the current value. The maximum value for this parameter is 87600 (ten years).

Type: Integer

Valid Range: Minimum value of 1.

Required: Yes Operation (p. 242)

Indicates whether you want to increase or decrease the retention period.

Type: String

Valid Values: INCREASE\_DATA\_RETENTION | DECREASE\_DATA\_RETENTION

Required: Yes StreamARN (p. 242)

The Amazon Resource Name (ARN) of the stream whose retention period you want to change.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No

StreamName (p. 242)

The name of the stream whose retention period you want to change.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Response Syntax

HTTP/1.1 200

### **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401
ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, <code>DescribeStream</code> for video streams.

HTTP Status Code: 400

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

## See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# UpdateImageGenerationConfiguration

Service: Amazon Kinesis Video Streams

Updates the StreamInfo and ImageProcessingConfiguration fields.

### Request Syntax

```
POST /updateImageGenerationConfiguration HTTP/1.1
Content-type: application/json
   "ImageGenerationConfiguration": {
      "DestinationConfig": {
          "DestinationRegion": "string",
          "Uri": "string"
      "Format": "string",
      "FormatConfig": {
    "string": "string"
      },
"HeightPixels": number,
"Type": "s
      "ImageSelectorType": "string",
      "SamplingInterval": number,
      "Status": "string",
      "WidthPixels": number
   },
   "StreamARN": "string",
   "StreamName": "string"
```

### **URI Request Parameters**

The request does not use any URI parameters.

### Request Body

The request accepts the following data in JSON format.

### ImageGenerationConfiguration (p. 245)

The structure that contains the information required for the KVS images delivery. If the structure is null, the configuration will be deleted from the stream.

Type: ImageGenerationConfiguration (p. 310) object

Required: No

#### StreamARN (p. 245)

The Amazon Resource Name (ARN) of the Kinesis video stream from where you want to update the image generation configuration. You must specify either the StreamName or the StreamARN.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

#### StreamName (p. 245)

The name of the stream from which to update the image generation configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Response Syntax

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
NoDataRetentionException

The Stream data retention in hours is equal to zero.

HTTP Status Code: 400

# ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, DescribeStream for video streams.

HTTP Status Code: 400

### Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

# ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# UpdateNotificationConfiguration

Service: Amazon Kinesis Video Streams

Updates the notification information for a stream.

# Request Syntax

```
POST /updateNotificationConfiguration HTTP/1.1
Content-type: application/json

{
    "NotificationConfiguration": {
        "DestinationConfig": {
            "Uri": "string"
        },
        "Status": "string"
      },
      "StreamARN": "string",
      "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

### NotificationConfiguration (p. 248)

The structure containing the information required for notifications. If the structure is null, the configuration will be deleted from the stream.

Type: NotificationConfiguration (p. 313) object

Required: No

#### StreamARN (p. 248)

The Amazon Resource Name (ARN) of the Kinesis video stream from where you want to update the notification configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

### StreamName (p. 248)

The name of the stream from which to update the notification configuration. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# **Response Syntax**

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401
ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

NoDataRetentionException

The Stream data retention in hours is equal to zero.

HTTP Status Code: 400 ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, <code>DescribeStream</code> for video streams.

HTTP Status Code: 400

ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404

# See Also

# Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **UpdateSignalingChannel**

Service: Amazon Kinesis Video Streams

Updates the existing signaling channel. This is an asynchronous operation and takes time to complete.

If the MessageTtlSeconds value is updated (either increased or reduced), it only applies to new messages sent via this channel after it's been updated. Existing messages are still expired as per the previous MessageTtlSeconds value.

# **Request Syntax**

```
POST /updateSignalingChannel HTTP/1.1
Content-type: application/json

{
    "ChannelARN": "string",
    "CurrentVersion": "string",
    "SingleMasterConfiguration": {
        "MessageTtlSeconds": number
    }
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

# ChannelARN (p. 251)

The Amazon Resource Name (ARN) of the signaling channel that you want to update.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: Yes

# **CurrentVersion (p. 251)**

The current version of the signaling channel that you want to update.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

```
Pattern: [a-zA-Z0-9]+
```

Required: Yes

# SingleMasterConfiguration (p. 251)

The structure containing the configuration for the SINGLE\_MASTER type of the signaling channel that you want to update.

Type: SingleMasterConfiguration (p. 317) object

Required: No

# Response Syntax

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### AccessDeniedException

You do not have required permissions to perform this operation.

HTTP Status Code: 401
ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400 ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, DescribeStream for video streams.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

### See Also

# Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# **UpdateStream**

Service: Amazon Kinesis Video Streams

Updates stream metadata, such as the device name and media type.

You must provide the stream name or the Amazon Resource Name (ARN) of the stream.

To make sure that you have the latest version of the stream before updating it, you can specify the stream version. Kinesis Video Streams assigns a version to each stream. When you update a stream, Kinesis Video Streams assigns a new version number. To get the latest stream version, use the DescribeStream API.

UpdateStream is an asynchronous operation, and takes time to complete.

# Request Syntax

```
POST /updateStream HTTP/1.1
Content-type: application/json

{
    "CurrentVersion": "string",
    "DeviceName": "string",
    "MediaType": "string",
    "StreamARN": "string",
    "StreamName": "string",
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

### **CurrentVersion (p. 254)**

The version of the stream whose metadata you want to update.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: Yes

DeviceName (p. 254)

The name of the device that is writing to the stream.

#### Note

In the current implementation, Kinesis Video Streams does not use this name.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

### MediaType (p. 254)

The stream's media type. Use MediaType to specify the type of content that the stream contains to the consumers of the stream. For more information about media types, see Media Types. If you choose to specify the MediaType, see Naming Requirements.

To play video on the console, you must specify the correct video type. For example, if the video in the stream is H.264, specify video/h264 as the MediaType.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [\w\-\.\+]+/[\w\-\.\+]+(, [\w\-\.\+]+/[\w\-\.\+]+)\*

Required: No StreamARN (p. 254)

The ARN of the stream whose metadata you want to update.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No StreamName (p. 254)

The name of the stream whose metadata you want to update.

The stream name is an identifier for the stream, and must be unique for each account and region.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# **Response Syntax**

HTTP/1.1 200

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

# **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

# HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401
ResourceInUseException

The resource is currently not available for this operation. New resources cannot be created with the same name as existing resources. Also, resources cannot be updated or deleted unless they are in an ACTIVE state.

If this exception is returned, do not use it to determine whether the requested resource already exists. Instead, it is recommended you use the resource-specific describe API, for example, DescribeStream for video streams.

HTTP Status Code: 400
ResourceNotFoundException

Amazon Kinesis Video Streams can't find the stream that you specified.

HTTP Status Code: 404 VersionMismatchException

The stream version that you specified is not the latest version. To get the latest version, use the DescribeStream API.

HTTP Status Code: 400

### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- AWS SDK for .NFT.
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V3

# Amazon Kinesis Video Streams Media

The following actions are supported by Amazon Kinesis Video Streams Media:

- GetMedia (p. 258)
- PutMedia (p. 262)

Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams Media

# GetMedia

Service: Amazon Kinesis Video Streams Media

Use this API to retrieve media content from a Kinesis video stream. In the request, you identify the stream name or stream Amazon Resource Name (ARN), and the starting chunk. Kinesis Video Streams then returns a stream of chunks in order by fragment number.

#### Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the GetMedia requests to this endpoint using the --endpoint-url parameter.

When you put media data (fragments) on a stream, Kinesis Video Streams stores each incoming fragment and related metadata in what is called a "chunk." For more information, see <a href="PutMedia">PutMedia</a>. The GetMedia API returns a stream of these chunks starting from the chunk that you specify in the request.

The following limits apply when using the GetMedia API:

- A client can call GetMedia up to five times per second per stream.
- Kinesis Video Streams sends media data at a rate of up to 25 megabytes per second (or 200 megabits per second) during a GetMedia session.

#### Note

If an error is thrown after invoking a Kinesis Video Streams media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

- x-amz-ErrorType HTTP header contains a more specific error type in addition to what the HTTP status code provides.
- x-amz-RequestId HTTP header if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

# Request Syntax

```
POST /getMedia HTTP/1.1
Content-type: application/json

{
    "StartSelector": {
        "AfterFragmentNumber": "string",
        "ContinuationToken": "string",
        "StartSelectorType": "string",
        "StartTimestamp": number
    },
    "StreamARN": "string",
    "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

# StartSelector (p. 258)

Identifies the starting chunk to get from the specified stream.

Type: StartSelector (p. 322) object

Required: Yes StreamARN (p. 258)

The ARN of the stream from where you want to get the media content. If you don't specify the streamARN, you must specify the streamName.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No

# StreamName (p. 258)

The Kinesis video stream name from where you want to get the media content. If you don't specify the streamName, you must specify the streamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Response Syntax

```
HTTP/1.1 200
Content-Type: ContentType
Payload
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following HTTP headers.

### ContentType (p. 259)

The content type of the requested media.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[a-zA-Z0-9\_\.\-]+\$

The response returns the following as the HTTP body.

### Payload (p. 259)

The payload Kinesis Video Streams returns is a sequence of chunks from the specified stream. For more information about the chunks, see PutMedia. The chunks that Kinesis Video Streams returns in the GetMedia call also include the following additional Matroska (MKV) tags:

- AWS\_KINESISVIDEO\_CONTINUATION\_TOKEN (UTF-8 string) In the event your GetMedia call
  terminates, you can use this continuation token in your next request to get the next chunk where
  the last request terminated.
- AWS\_KINESISVIDEO\_MILLIS\_BEHIND\_NOW (UTF-8 string) Client applications can use this tag
  value to determine how far behind the chunk returned in the response is from the latest chunk on
  the stream.
- AWS\_KINESISVIDEO\_FRAGMENT\_NUMBER Fragment number returned in the chunk.
- AWS\_KINESISVIDEO\_SERVER\_TIMESTAMP Server timestamp of the fragment.
- AWS\_KINESISVIDEO\_PRODUCER\_TIMESTAMP Producer timestamp of the fragment.

The following tags will be present if an error occurs:

- AWS\_KINESISVIDEO\_ERROR\_CODE String description of an error that caused GetMedia to stop.
- AWS\_KINESISVIDEO\_ERROR\_ID: Integer code of the error.

The error codes are as follows:

- 3002 Error writing to the stream
- · 4000 Requested fragment is not found
- 4500 Access denied for the stream's KMS key
- 4501 Stream's KMS key is disabled
- · 4502 Validation error on the stream's KMS key
- 4503 KMS key specified in the stream is unavailable
- · 4504 Invalid usage of the KMS key specified in the stream
- 4505 Invalid state of the KMS key specified in the stream
- 4506 Unable to find the KMS key specified in the stream
- 5000 Internal error

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

# ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

### ConnectionLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client connections.

HTTP Status Code: 400

### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

### InvalidEndpointException

Caller used wrong endpoint to write data to a stream. On receiving such an exception, the user must call GetDataEndpoint with APIName set to PUT\_MEDIA and use the endpoint from response to invoke the next PutMedia call.

HTTP Status Code: 400 **NotAuthorizedException** 

The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401
ResourceNotFoundException

Status Code: 404, The stream with the given name does not exist.

HTTP Status Code: 404

# See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V3

# PutMedia

Service: Amazon Kinesis Video Streams Media

Use this API to send media data to a Kinesis video stream.

#### Note

Before using this API, you must call the GetDataEndpoint API to get an endpoint. You then specify the endpoint in your PutMedia request.

In the request, you use the HTTP headers to provide parameter information, for example, stream name, timestamp, and whether the timestamp value is absolute or relative to when the producer started recording. You use the request body to send the media data. Kinesis Video Streams supports only the Matroska (MKV) container format for sending media data using this API.

You have the following options for sending data using this API:

- Send media data in real time: For example, a security camera can send frames in real time as it generates them. This approach minimizes the latency between the video recording and data sent on the wire. This is referred to as a continuous producer. In this case, a consumer application can read the stream in real time or when needed.
- Send media data offline (in batches): For example, a body camera might record video for hours and store it on the device. Later, when you connect the camera to the docking port, the camera can start a PutMedia session to send data to a Kinesis video stream. In this scenario, latency is not an issue.

When using this API, note the following considerations:

- You must specify either streamName or streamARN, but not both.
- To be able to play the media on the console or via HLS, track 1 of each fragment should contain h.264 encoded video, the CodecID in the fragment metadata should be "V\_MPEG/ISO/AVC", and the fragment metadata should include AVCC formatted h.264 codec private data. Optionally, track 2 of each fragment should contain AAC encoded audio, the CodecID in the fragment metadata should be "A\_AAC", and the fragment metadata should include AAC codec private data.
- You might find it easier to use a single long-running PutMedia session and send a large number of
  media data fragments in the payload. For each fragment received, Kinesis Video Streams sends one
  or more acknowledgements. Potential network considerations might cause you to not get all these
  acknowledgements as they are generated.
- You might choose multiple consecutive PutMedia sessions, each with fewer fragments to ensure that you get all acknowledgements from the service in real time.

#### Note

If you send data to the same stream on multiple simultaneous PutMedia sessions, the media fragments get interleaved on the stream. You should make sure that this is OK in your application scenario.

The following limits apply when using the PutMedia API:

- A client can call PutMedia up to five times per second per stream.
- A client can send up to five fragments per second per stream.
- Kinesis Video Streams reads media data at a rate of up to 12.5 MB/second, or 100 Mbps during a PutMedia session.

Note the following constraints. In these cases, Kinesis Video Streams sends the Error acknowledgement in the response.

### Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams Media

- Fragments that have time codes spanning longer than 10 seconds and that contain more than 50 MB of data are not allowed.
- Fragments containing more than three tracks are not allowed. Each frame in every fragment must have the same track number as one of the tracks defined in the fragment header. Additionally, every fragment must contain at least one frame for each track defined in the fragment header.
- Each fragment must contain at least one frame for each track defined in the fragment metadata.
- The earliest frame timestamp in a fragment must be after the latest frame timestamp in the previous fragment.
- An MKV stream containing more than one MKV segment or containing disallowed MKV elements (like track\*) also results in the Error acknowledgement.

Kinesis Video Streams stores each incoming fragment and related metadata in what is called a "chunk." The fragment metadata includes the following:

- The MKV headers provided at the start of the PutMedia request
- The following Kinesis Video Streams-specific metadata for the fragment:
  - server\_timestamp Timestamp when Kinesis Video Streams started receiving the fragment.
  - producer\_timestamp Timestamp, when the producer started recording the fragment. Kinesis Video Streams uses three pieces of information received in the request to calculate this value.
    - The fragment timecode value received in the request body along with the fragment.
    - Two request headers: producerStartTimestamp (when the producer started recording) and fragmentTimeCodeType (whether the fragment timecode in the payload is absolute or relative).

Kinesis Video Streams then computes the producer timestamp for the fragment as follows:

If fragmentTimeCodeType is relative, then

producer\_timestamp = producerStartTimeStamp + fragment timecode

If fragmentTimeCodeType is absolute, then

producer\_timestamp = fragment timecode (converted to milliseconds)

Unique fragment number assigned by Kinesis Video Streams.

#### Note

When you make the GetMedia request, Kinesis Video Streams returns a stream of these chunks. The client can process the metadata as needed.

#### Note

This operation is only available for the AWS SDK for Java. It is not supported in AWS SDKs for other languages.

#### Note

Kinesis Video Streams does not parse and validate the codec private data during ingestion and archival via the PutMedia API. KVS extracts and validates the necessary information from the codec private data for MPEG-TS and MP4 fragment packaging when consuming the stream via the HLS APIs.

#### Note

If an error is thrown after invoking a Kinesis Video Streams media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

 x-amz-ErrorType HTTP header – contains a more specific error type in addition to what the HTTP status code provides. • x-amz-RequestId HTTP header – if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

# Request Syntax

```
POST /putMedia HTTP/1.1
x-amzn-stream-name: StreamName
x-amzn-stream-arn: StreamARN
x-amzn-fragment-timecode-type: FragmentTimecodeType
x-amzn-producer-start-timestamp: ProducerStartTimestamp

Payload
```

# **URI Request Parameters**

The request uses the following URI parameters.

### FragmentTimecodeType (p. 264)

You pass this value as the x-amzn-fragment-timecode-type HTTP header.

Indicates whether timecodes in the fragments (payload, HTTP request body) are absolute or relative to producerStartTimestamp. Kinesis Video Streams uses this information to compute the producer\_timestamp for the fragment received in the request, as described in the API overview.

```
Valid Values: ABSOLUTE | RELATIVE
```

Required: Yes

# ProducerStartTimestamp (p. 264)

You pass this value as the x-amzn-producer-start-timestamp HTTP header.

This is the producer timestamp at which the producer started recording the media (not the timestamp of the specific fragments in the request).

#### StreamARN (p. 264)

You pass this value as the x-amzn-stream-arn HTTP header.

Amazon Resource Name (ARN) of the Kinesis video stream where you want to write the media content. If you don't specify the streamARN, you must specify the streamName.

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

### StreamName (p. 264)

You pass this value as the x-amzn-stream-name HTTP header.

Name of the Kinesis video stream where you want to write the media content. If you don't specify the streamName, you must specify the streamARN.

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

# **Request Body**

The request accepts the following binary data.

### Payload (p. 264)

The media content to write to the Kinesis video stream. In the current implementation, Kinesis Video Streams supports only the Matroska (MKV) container format with a single MKV segment. A segment can contain one or more clusters.

#### Note

Each MKV cluster maps to a Kinesis video stream fragment. Whatever cluster duration you choose becomes the fragment duration.

# Response Syntax

HTTP/1.1 200

Payload

# Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following as the HTTP body.

# Payload (p. 265)

After Kinesis Video Streams successfully receives a PutMedia request, the service validates the request headers. The service then starts reading the payload and first sends an HTTP 200 response.

The service then returns a stream containing a series of JSON objects (Acknowledgement objects) separated by newlines. The acknowledgements are received on the same connection on which the media data is sent. There can be many acknowledgements for a PutMedia request. Each Acknowledgement consists of the following key-value pairs:

- AckEventType Event type the acknowledgement represents.
  - **Buffering:** Kinesis Video Streams has started receiving the fragment. Kinesis Video Streams sends the first Buffering acknowledgement when the first byte of fragment data is received.
  - **Received:** Kinesis Video Streams received the entire fragment. If you did not configure the stream to persist the data, the producer can stop buffering the fragment upon receiving this acknowledgement.
  - **Persisted:** Kinesis Video Streams has persisted the fragment (for example, to Amazon S3). You get this acknowledgement if you configured the stream to persist the data. After you receive this acknowledgement, the producer can stop buffering the fragment.
  - **Error:** Kinesis Video Streams ran into an error while processing the fragment. You can review the error code and determine the next course of action.
  - Idle: The PutMedia session is in-progress. However, Kinesis Video Streams is currently not receiving data. Kinesis Video Streams sends this acknowledgement periodically for up to 30 seconds after the last received data. If no data is received within the 30 seconds, Kinesis Video Streams closes the request.

### Note

This acknowledgement can help a producer determine if the PutMedia connection is alive, even if it is not sending any data.

• FragmentTimeCode - Fragment timecode for which acknowledgement is sent.

The element can be missing if the AckEventType is **Idle**.

- FragmentNumber Kinesis Video Streams-generated fragment number for which the acknowledgement is sent.
- ErrorId and ErrorCode If the AckEventType is ErrorId, this field provides corresponding error code. The following is the list of error IDs and their corresponding error codes and error messages:
  - 4000 STREAM\_READ\_ERROR Error reading the data stream.
  - 4001 MAX\_FRAGMENT\_SIZE\_REACHED Fragment size is greater than maximum limit, 50 MB, allowed.
  - 4002 MAX\_FRAGMENT\_DURATION\_REACHED Fragment duration is greater than maximum limit, 10 seconds, allowed.
  - 4003 MAX\_CONNECTION\_DURATION\_REACHED Connection duration is greater than maximum allowed threshold.
  - 4004 FRAGMENT\_TIMECODE\_LESSER\_THAN\_PREVIOUS Fragment timecode is less than the timecode previous time code (within a PutMedia call, you cannot send fragments out of order).
  - 4005 MORE\_THAN\_ALLOWED\_TRACKS\_FOUND More than one track is found in MKV. (deprecated)
  - 4006 INVALID\_MKV\_DATA Failed to parse the input stream as valid MKV format.
  - 4007 INVALID\_PRODUCER\_TIMESTAMP Invalid producer timestamp.
  - 4008 STREAM\_NOT\_ACTIVE Stream no longer exists (deleted).
  - 4009 FRAGMENT\_METADATA\_LIMIT\_REACHED Fragment metadata limit reached.
  - 4010 TRACK\_NUMBER\_MISMATCH The track number in an MKV frame did not match the tracks in the MKV header.
  - 4011 FRAMES\_MISSING\_FOR\_TRACK The fragment did not contain any frames for at least one of the tracks in the MKV header.
  - 4500 KMS\_KEY\_ACCESS\_DENIED Access to the stream's specified KMS key is denied.
  - 4501 KMS\_KEY\_DISABLED The stream's specified KMS key is disabled.
  - 4502 KMS\_KEY\_VALIDATION\_ERROR The stream's specified KMS key failed validation.
  - 4503 KMS\_KEY\_UNAVAILABLE The stream's specified KMS key is unavailable.
  - 4504 KMS\_KEY\_INVALID\_USAGE Invalid usage of the stream's specified KMS key.
  - 4505 KMS\_KEY\_INVALID\_STATE The stream's specified KMS key is in an invalid state.
  - 4506 KMS\_KEY\_NOT\_FOUND The stream's specified KMS key is not found.
  - 5000 INTERNAL\_ERROR Internal service error
  - 5001 ARCHIVAL\_ERROR Kinesis Video Streams failed to persist fragments to the data store.

#### Note

The producer, while sending the payload for a long running PutMedia request, should read the response for acknowledgements. A producer might receive chunks of acknowledgements at the same time, due to buffering on an intermediate proxy server. A producer that wants to receive timely acknowledgements can send fewer fragments in each PutMedia request.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

### ConnectionLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded the limit of allowed client connections.

HTTP Status Code: 400
InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
InvalidEndpointException

Caller used wrong endpoint to write data to a stream. On receiving such an exception, the user must call GetDataEndpoint with APIName set to PUT\_MEDIA and use the endpoint from response to invoke the next PutMedia call.

HTTP Status Code: 400 **NotAuthorizedException** 

The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

ResourceNotFoundException

Status Code: 404, The stream with the given name does not exist.

HTTP Status Code: 404

# **Examples**

# Acknowledgement Format

The format of the acknowledgement is as follows:

```
{
    Acknowledgement : {
        "EventType": enum
        "FragmentTimecode": Long,
        "FragmentNumber": Long,
        "ErrorId" : String
}
```

### See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2

- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# Amazon Kinesis Video Streams Archived Media

The following actions are supported by Amazon Kinesis Video Streams Archived Media:

- GetClip (p. 269)
- GetDASHStreamingSessionURL (p. 273)
- GetHLSStreamingSessionURL (p. 280)
- GetImages (p. 288)
- GetMediaForFragmentList (p. 293)
- ListFragments (p. 296)

# GetClip

Service: Amazon Kinesis Video Streams Archived Media

Downloads an MP4 file (clip) containing the archived, on-demand media from the specified video stream over the specified time range.

Both the StreamName and the StreamARN parameters are optional, but you must specify either the StreamName or the StreamARN when invoking this API operation.

As a prerequisite to using GetCLip API, you must obtain an endpoint using GetDataEndpoint, specifying GET\_CLIP for the APIName parameter.

An Amazon Kinesis video stream has the following requirements for providing data through MP4:

- The media must contain h.264 or h.265 encoded video and, optionally, AAC or G.711 encoded audio.
   Specifically, the codec ID of track 1 should be V\_MPEG/ISO/AVC (for h.264) or V\_MPEGH/ISO/HEVC (for H.265). Optionally, the codec ID of track 2 should be A\_AAC (for AAC) or A\_MS/ACM (for G.711).
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format and HEVC for H.265 format. For more information, see MPEG-4 specification ISO/IEC 14496-15. For information about adapting stream data to a given format, see NAL Adaptation Flags.
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7) or the MS Wave format.

You can monitor the amount of outgoing data by monitoring the GetClip.OutgoingBytes Amazon CloudWatch metric. For information about using CloudWatch to monitor Kinesis Video Streams, see Monitoring Kinesis Video Streams. For pricing information, see Amazon Kinesis Video Streams Pricing and AWS Pricing. Charges for outgoing AWS data apply.

# Request Syntax

```
POST /getClip HTTP/1.1
Content-type: application/json

{
    "ClipFragmentSelector": {
        "FragmentSelectorType": "string",
        "TimestampRange": {
            "EndTimestamp": number,
            "StartTimestamp": number
        }
    },
    "StreamARN": "string",
    "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# Request Body

The request accepts the following data in JSON format.

### ClipFragmentSelector (p. 269)

The time range of the requested clip and the source of the timestamps.

Type: ClipFragmentSelector (p. 324) object

Required: Yes StreamARN (p. 269)

The Amazon Resource Name (ARN) of the stream for which to retrieve the media clip.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No StreamName (p. 269)

The name of the stream for which to retrieve the media clip.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Response Syntax

```
HTTP/1.1 200
Content-Type: ContentType

Payload
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following HTTP headers.

# ContentType (p. 270)

The content type of the media in the requested clip.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern:  $^[a-zA-Z0-9]\.\-]+$ \$

The response returns the following as the HTTP body.

### Payload (p. 270)

Traditional MP4 file that contains the media clip from the specified video stream. The output will contain the first 100 MB or the first 200 fragments from the specified start timestamp. For more information, see Kinesis Video Streams Limits.

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

# HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

### InvalidCodecPrivateDataException

The codec private data in at least one of the tracks of the video stream is not valid for this operation.

HTTP Status Code: 400
InvalidMediaFrameException

One or more frames in the requested clip could not be parsed based on the specified codec.

HTTP Status Code: 400

### MissingCodecPrivateDataException

No codec private data was found in at least one of tracks of the video stream.

HTTP Status Code: 400
NoDataRetentionException

A streaming session was requested for a stream that does not retain data (that is, has a DataRetentionInHours of 0).

HTTP Status Code: 400 **NotAuthorizedException** 

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL and GetDASHStreamingSessionURL throw this error if a session with a PlaybackMode of ON\_DEMAND or LIVE\_REPLAYis requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

# UnsupportedStreamMediaTypeException

The type of the media (for example, h.264 or h.265 video or ACC or G.711 audio) could not be determined from the codec IDs of the tracks in the first fragment for a playback session. The codec ID for track 1 should be V\_MPEG/ISO/AVC and, optionally, the codec ID for track 2 should be A\_AAC.

HTTP Status Code: 400

# See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# GetDASHStreamingSessionURL

Service: Amazon Kinesis Video Streams Archived Media

Retrieves an MPEG Dynamic Adaptive Streaming over HTTP (DASH) URL for the stream. You can then open the URL in a media player to view the stream contents.

Both the StreamName and the StreamARN parameters are optional, but you must specify either the StreamName or the StreamARN when invoking this API operation.

An Amazon Kinesis video stream has the following requirements for providing data through MPEG-DASH:

- The media must contain h.264 or h.265 encoded video and, optionally, AAC or G.711 encoded audio.
   Specifically, the codec ID of track 1 should be V\_MPEG/ISO/AVC (for h.264) or V\_MPEGH/ISO/HEVC (for H.265). Optionally, the codec ID of track 2 should be A\_AAC (for AAC) or A\_MS/ACM (for G.711).
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format and HEVC for H.265 format. For more information, see MPEG-4 specification ISO/IEC 14496-15. For information about adapting stream data to a given format, see NAL Adaptation Flags.
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7) or the MS Wave format.

The following procedure shows how to use MPEG-DASH with Kinesis Video Streams:

- Get an endpoint using GetDataEndpoint, specifying GET\_DASH\_STREAMING\_SESSION\_URL for the APIName parameter.
- Retrieve the MPEG-DASH URL using GetDASHStreamingSessionURL. Kinesis Video Streams creates
  an MPEG-DASH streaming session to be used for accessing content in a stream using the MPEG-DASH
  protocol. GetDASHStreamingSessionURL returns an authenticated URL (that includes an encrypted
  session token) for the session's MPEG-DASH manifest (the root resource needed for streaming with
  MPEG-DASH).

#### Note

Don't share or store this token where an unauthorized entity can access it. The token provides access to the content of the stream. Safeguard the token with the same measures that you use with your AWS credentials.

The media that is made available through the manifest consists only of the requested stream, time range, and format. No other media data (such as frames outside the requested window or alternate bitrates) is made available.

- 3. Provide the URL (containing the encrypted session token) for the MPEG-DASH manifest to a media player that supports the MPEG-DASH protocol. Kinesis Video Streams makes the initialization fragment and media fragments available through the manifest URL. The initialization fragment contains the codec private data for the stream, and other data needed to set up the video or audio decoder and renderer. The media fragments contain encoded video frames or encoded audio samples.
- 4. The media player receives the authenticated URL and requests stream metadata and media data normally. When the media player requests data, it calls the following actions:
  - **GetDASHManifest:** Retrieves an MPEG DASH manifest, which contains the metadata for the media that you want to playback.
  - **GetMP4InitFragment:** Retrieves the MP4 initialization fragment. The media player typically loads the initialization fragment before loading any media fragments. This fragment contains the "fytp" and "moov" MP4 atoms, and the child atoms that are needed to initialize the media player decoder.

The initialization fragment does not correspond to a fragment in a Kinesis video stream. It contains only the codec private data for the stream and respective track, which the media player needs to decode the media frames.

GetMP4MediaFragment: Retrieves MP4 media fragments. These fragments contain the "moof" and
"mdat" MP4 atoms and their child atoms, containing the encoded fragment's media frames and
their timestamps.

#### Note

After the first media fragment is made available in a streaming session, any fragments that don't contain the same codec private data cause an error to be returned when those different media fragments are loaded. Therefore, the codec private data should not change between fragments in a session. This also means that the session fails if the fragments in a stream change from having only video to having both audio and video.

Data retrieved with this action is billable. See Pricing for details.

#### Note

For restrictions that apply to MPEG-DASH sessions, see Kinesis Video Streams Limits.

You can monitor the amount of data that the media player consumes by monitoring the GetMP4MediaFragment.OutgoingBytes Amazon CloudWatch metric. For information about using CloudWatch to monitor Kinesis Video Streams, see Monitoring Kinesis Video Streams. For pricing information, see Amazon Kinesis Video Streams Pricing and AWS Pricing. Charges for both HLS sessions and outgoing AWS data apply.

For more information about HLS, see HTTP Live Streaming on the Apple Developer site.

#### **Important**

If an error is thrown after invoking a Kinesis Video Streams archived media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

- x-amz-ErrorType HTTP header contains a more specific error type in addition to what the HTTP status code provides.
- x-amz-RequestId HTTP header if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

# Request Syntax

```
POST /getDASHStreamingSessionURL HTTP/1.1
Content-type: application/json

{
    "DASHFragmentSelector": {
        "FragmentSelectorType": "string",
        "TimestampRange": {
            "EndTimestamp": number,
            "StartTimestamp": number
        }
    },
    "DisplayFragmentNumber": "string",
    "DisplayFragmentTimestamp": "string",
    "Expires": number,
    "MaxManifestFragmentResults": number,
    "PlaybackMode": "string",
    "StreamARN": "string",
```

```
"StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

# DASHFragmentSelector (p. 274)

The time range of the requested fragment and the source of the timestamps.

This parameter is required if PlaybackMode is ON\_DEMAND or LIVE\_REPLAY. This parameter is optional if PlaybackMode is LIVE. If PlaybackMode is LIVE, the FragmentSelectorType can be set, but the TimestampRange should not be set. If PlaybackMode is ON\_DEMAND or LIVE\_REPLAY, both FragmentSelectorType and TimestampRange must be set.

Type: DASHFragmentSelector (p. 326) object

Required: No

# DisplayFragmentNumber (p. 274)

Fragments are identified in the manifest file based on their sequence number in the session. If DisplayFragmentNumber is set to ALWAYS, the Kinesis Video Streams fragment number is added to each S element in the manifest file with the attribute name "kvs:fn". These fragment numbers can be used for logging or for use with other APIs (e.g. GetMedia and GetMediaForFragmentList). A custom MPEG-DASH media player is necessary to leverage these this custom attribute.

The default value is NEVER.

Type: String

Valid Values: ALWAYS | NEVER

Required: No

# DisplayFragmentTimestamp (p. 274)

Per the MPEG-DASH specification, the wall-clock time of fragments in the manifest file can be derived using attributes in the manifest itself. However, typically, MPEG-DASH compatible media players do not properly handle gaps in the media timeline. Kinesis Video Streams adjusts the media timeline in the manifest file to enable playback of media with discontinuities. Therefore, the wall-clock time derived from the manifest file may be inaccurate. If DisplayFragmentTimestamp is set to ALWAYS, the accurate fragment timestamp is added to each S element in the manifest file with the attribute name "kvs:ts". A custom MPEG-DASH media player is necessary to leverage this custom attribute.

The default value is NEVER. When DASHFragmentSelector (p. 326) is SERVER\_TIMESTAMP, the timestamps will be the server start timestamps. Similarly, when DASHFragmentSelector (p. 326) is PRODUCER\_TIMESTAMP, the timestamps will be the producer start timestamps.

Type: String

Valid Values: ALWAYS | NEVER

Required: No

### **Expires (p. 274)**

The time in seconds until the requested session expires. This value can be between 300 (5 minutes) and 43200 (12 hours).

When a session expires, no new calls to GetDashManifest, GetMP4InitFragment, or GetMP4MediaFragment can be made for that session.

The default is 300 (5 minutes).

Type: Integer

Valid Range: Minimum value of 300. Maximum value of 43200.

Required: No

### MaxManifestFragmentResults (p. 274)

The maximum number of fragments that are returned in the MPEG-DASH manifest.

When the PlaybackMode is LIVE, the most recent fragments are returned up to this value. When the PlaybackMode is ON\_DEMAND, the oldest fragments are returned, up to this maximum number.

When there are a higher number of fragments available in a live MPEG-DASH manifest, video players often buffer content before starting playback. Increasing the buffer size increases the playback latency, but it decreases the likelihood that rebuffering will occur during playback. We recommend that a live MPEG-DASH manifest have a minimum of 3 fragments and a maximum of 10 fragments.

The default is 5 fragments if PlaybackMode is LIVE or LIVE\_REPLAY, and 1,000 if PlaybackMode is ON\_DEMAND.

The maximum value of 1,000 fragments corresponds to more than 16 minutes of video on streams with 1-second fragments, and more than 2 1/2 hours of video on streams with 10-second fragments.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 5000.

Required: No

### PlaybackMode (p. 274)

Whether to retrieve live, live replay, or archived, on-demand data.

Features of the three types of sessions include the following:

• LIVE: For sessions of this type, the MPEG-DASH manifest is continually updated with the latest fragments as they become available. We recommend that the media player retrieve a new manifest on a one-second interval. When this type of session is played in a media player, the user interface typically displays a "live" notification, with no scrubber control for choosing the position in the playback window to display.

### Note

In LIVE mode, the newest available fragments are included in an MPEG-DASH manifest, even if there is a gap between fragments (that is, if a fragment is missing). A gap like this might cause a media player to halt or cause a jump in playback. In this mode, fragments are not added to the MPEG-DASH manifest if they are older than the newest fragment in the playlist. If the missing fragment becomes available after a subsequent fragment is added to the manifest, the older fragment is not added, and the gap is not filled.

• LIVE\_REPLAY: For sessions of this type, the MPEG-DASH manifest is updated similarly to how it is updated for LIVE mode except that it starts by including fragments from a given start time.

Instead of fragments being added as they are ingested, fragments are added as the duration of the next fragment elapses. For example, if the fragments in the session are two seconds long, then a new fragment is added to the manifest every two seconds. This mode is useful to be able to start playback from when an event is detected and continue live streaming media that has not yet been ingested as of the time of the session creation. This mode is also useful to stream previously archived media without being limited by the 1,000 fragment limit in the ON\_DEMAND mode.

• ON\_DEMAND: For sessions of this type, the MPEG-DASH manifest contains all the fragments for the session, up to the number that is specified in MaxManifestFragmentResults. The manifest must be retrieved only once for each session. When this type of session is played in a media player, the user interface typically displays a scrubber control for choosing the position in the playback window to display.

In all playback modes, if FragmentSelectorType is PRODUCER\_TIMESTAMP, and if there are multiple fragments with the same start timestamp, the fragment that has the larger fragment number (that is, the newer fragment) is included in the MPEG-DASH manifest. The other fragments are not included. Fragments that have different timestamps but have overlapping durations are still included in the MPEG-DASH manifest. This can lead to unexpected behavior in the media player.

The default is LIVE.

Type: String

Valid Values: LIVE | LIVE\_REPLAY | ON\_DEMAND

Required: No StreamARN (p. 274)

The Amazon Resource Name (ARN) of the stream for which to retrieve the MPEG-DASH manifest URL.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No **StreamName (p. 274)** 

The name of the stream for which to retrieve the MPEG-DASH manifest URL.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Response Syntax

```
HTTP/1.1 200 Content-type: application/json
```

```
{
    "DASHStreamingSessionURL": "string"
}
```

# **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

### DASHStreamingSessionURL (p. 277)

The URL (containing the session token) that a media player can use to retrieve the MPEG-DASH manifest.

Type: String

### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

# HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

#### InvalidCodecPrivateDataException

The codec private data in at least one of the tracks of the video stream is not valid for this operation.

HTTP Status Code: 400

# MissingCodecPrivateDataException

No codec private data was found in at least one of tracks of the video stream.

HTTP Status Code: 400
NoDataRetentionException

A streaming session was requested for a stream that does not retain data (that is, has a DataRetentionInHours of 0).

HTTP Status Code: 400

### NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

### ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL and GetDASHStreamingSessionURL throw this error if a session with a PlaybackMode of ON\_DEMAND or LIVE\_REPLAYis requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

## UnsupportedStreamMediaTypeException

The type of the media (for example, h.264 or h.265 video or ACC or G.711 audio) could not be determined from the codec IDs of the tracks in the first fragment for a playback session. The codec ID for track 1 should be V\_MPEG/ISO/AVC and, optionally, the codec ID for track 2 should be A\_AAC.

HTTP Status Code: 400

# See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# GetHLSStreamingSessionURL

Service: Amazon Kinesis Video Streams Archived Media

Retrieves an HTTP Live Streaming (HLS) URL for the stream. You can then open the URL in a browser or media player to view the stream contents.

Both the StreamName and the StreamARN parameters are optional, but you must specify either the StreamName or the StreamARN when invoking this API operation.

An Amazon Kinesis video stream has the following requirements for providing data through HLS:

- For streaming video, the media must contain H.264 or H.265 encoded video and, optionally, AAC encoded audio. Specifically, the codec ID of track 1 should be V\_MPEG/ISO/AVC (for H.264) or V\_MPEG/ISO/HEVC (for H.265). Optionally, the codec ID of track 2 should be A\_AAC. For audio only streaming, the codec ID of track 1 should be A\_AAC.
- Data retention must be greater than 0.
- The video track of each fragment must contain codec private data in the Advanced Video Coding (AVC) for H.264 format or HEVC for H.265 format (MPEG-4 specification ISO/IEC 14496-15). For information about adapting stream data to a given format, see NAL Adaptation Flags.
- The audio track (if present) of each fragment must contain codec private data in the AAC format (AAC specification ISO/IEC 13818-7).

Kinesis Video Streams HLS sessions contain fragments in the fragmented MPEG-4 form (also called fMP4 or CMAF) or the MPEG-2 form (also called TS chunks, which the HLS specification also supports). For more information about HLS fragment types, see the HLS specification.

The following procedure shows how to use HLS with Kinesis Video Streams:

- 1. Get an endpoint using GetDataEndpoint, specifying GET\_HLS\_STREAMING\_SESSION\_URL for the APIName parameter.
- 2. Retrieve the HLS URL using GetHLSStreamingSessionURL. Kinesis Video Streams creates an HLS streaming session to be used for accessing content in a stream using the HLS protocol. GetHLSStreamingSessionURL returns an authenticated URL (that includes an encrypted session token) for the session's HLS master playlist (the root resource needed for streaming with HLS).

### Note

Don't share or store this token where an unauthorized entity could access it. The token provides access to the content of the stream. Safeguard the token with the same measures that you would use with your AWS credentials.

The media that is made available through the playlist consists only of the requested stream, time range, and format. No other media data (such as frames outside the requested window or alternate bitrates) is made available.

- 3. Provide the URL (containing the encrypted session token) for the HLS master playlist to a media player that supports the HLS protocol. Kinesis Video Streams makes the HLS media playlist, initialization fragment, and media fragments available through the master playlist URL. The initialization fragment contains the codec private data for the stream, and other data needed to set up the video or audio decoder and renderer. The media fragments contain H.264-encoded video frames or AAC-encoded audio samples.
- 4. The media player receives the authenticated URL and requests stream metadata and media data normally. When the media player requests data, it calls the following actions:
  - **GetHLSMasterPlaylist:** Retrieves an HLS master playlist, which contains a URL for the GetHLSMediaPlaylist action for each track, and additional metadata for the media player, including estimated bitrate and resolution.
  - **GetHLSMediaPlaylist:** Retrieves an HLS media playlist, which contains a URL to access the MP4 initialization fragment with the GetMP4InitFragment action, and URLs to access the MP4

media fragments with the GetMP4MediaFragment actions. The HLS media playlist also contains metadata about the stream that the player needs to play it, such as whether the PlaybackMode is LIVE or ON\_DEMAND. The HLS media playlist is typically static for sessions with a PlaybackType of ON\_DEMAND. The HLS media playlist is continually updated with new fragments for sessions with a PlaybackType of LIVE. There is a distinct HLS media playlist for the video track and the audio track (if applicable) that contains MP4 media URLs for the specific track.

GetMP4InitFragment: Retrieves the MP4 initialization fragment. The media player typically loads
the initialization fragment before loading any media fragments. This fragment contains the "fytp"
and "moov" MP4 atoms, and the child atoms that are needed to initialize the media player decoder.

The initialization fragment does not correspond to a fragment in a Kinesis video stream. It contains only the codec private data for the stream and respective track, which the media player needs to decode the media frames.

• **GetMP4MediaFragment:** Retrieves MP4 media fragments. These fragments contain the "moof" and "mdat" MP4 atoms and their child atoms, containing the encoded fragment's media frames and their timestamps.

#### Note

For the HLS streaming session, in-track codec private data (CPD) changes are supported. After the first media fragment is made available in a streaming session, fragments can contain CPD changes for each track. Therefore, the fragments in a session can have a different resolution, bit rate, or other information in the CPD without interrupting playback. However, any change made in the track number or track codec format can return an error when those different media fragments are loaded. For example, streaming will fail if the fragments in the stream change from having only video to having both audio and video, or if an AAC audio track is changed to an ALAW audio track. For each streaming session, only 500 CPD changes are allowed.

Data retrieved with this action is billable. For information, see Pricing.

• **GetTSFragment:** Retrieves MPEG TS fragments containing both initialization and media data for all tracks in the stream.

#### Note

If the ContainerFormat is MPEG\_TS, this API is used instead of GetMP4InitFragment and GetMP4MediaFragment to retrieve stream media.

Data retrieved with this action is billable. For more information, see Kinesis Video Streams pricing.

A streaming session URL must not be shared between players. The service might throttle a session if multiple media players are sharing it. For connection limits, see Kinesis Video Streams Limits.

You can monitor the amount of data that the media player consumes by monitoring the GetMP4MediaFragment.OutgoingBytes Amazon CloudWatch metric. For information about using CloudWatch to monitor Kinesis Video Streams, see Monitoring Kinesis Video Streams. For pricing information, see Amazon Kinesis Video Streams Pricing and AWS Pricing. Charges for both HLS sessions and outgoing AWS data apply.

For more information about HLS, see HTTP Live Streaming on the Apple Developer site.

### **Important**

If an error is thrown after invoking a Kinesis Video Streams archived media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

- x-amz-ErrorType HTTP header contains a more specific error type in addition to what the HTTP status code provides.
- x-amz-RequestId HTTP header if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

# Request Syntax

```
POST /getHLSStreamingSessionURL HTTP/1.1
Content-type: application/json
   "ContainerFormat": "string",
   "DiscontinuityMode": "string",
   "DisplayFragmentTimestamp": "string",
   "Expires": number,
   "HLSFragmentSelector": {
      "FragmentSelectorType": "string",
      "TimestampRange": {
         "EndTimestamp": number,
         "StartTimestamp": number
      }
   },
   "MaxMediaPlaylistFragmentResults": number,
   "PlaybackMode": "string",
   "StreamARN": "string",
   "StreamName": "string"
}
```

# **URI Request Parameters**

The request does not use any URI parameters.

# **Request Body**

The request accepts the following data in JSON format.

### ContainerFormat (p. 282)

DiscontinuityMode (p. 282)

Specifies which format should be used for packaging the media. Specifying the FRAGMENTED\_MP4 container format packages the media into MP4 fragments (fMP4 or CMAF). This is the recommended packaging because there is minimal packaging overhead. The other container format option is MPEG\_TS. HLS has supported MPEG TS chunks since it was released and is sometimes the only supported packaging on older HLS players. MPEG TS typically has a 5-25 percent packaging overhead. This means MPEG TS typically requires 5-25 percent more bandwidth and cost than fMP4.

The default is FRAGMENTED\_MP4.

```
Type: String

Valid Values: FRAGMENTED_MP4 | MPEG_TS

Required: No
```

Specifies when flags marking discontinuities between fragments are added to the media playlists.

Media players typically build a timeline of media content to play, based on the timestamps of each fragment. This means that if there is any overlap or gap between fragments (as is typical if

HLSFragmentSelector (p. 330) is set to SERVER\_TIMESTAMP), the media player timeline will also have small gaps between fragments in some places, and will overwrite frames in other places. Gaps in the media player timeline can cause playback to stall and overlaps can cause playback to be jittery. When there are discontinuity flags between fragments, the media player is expected to reset the timeline, resulting in the next fragment being played immediately after the previous fragment.

The following modes are supported:

- ALWAYS: a discontinuity marker is placed between every fragment in the HLS media playlist. It is recommended to use a value of ALWAYS if the fragment timestamps are not accurate.
- NEVER: no discontinuity markers are placed anywhere. It is recommended to use a value of NEVER to ensure the media player timeline most accurately maps to the producer timestamps.
- ON\_DISCONTINUITY: a discontinuity marker is placed between fragments that have a gap or overlap of more than 50 milliseconds. For most playback scenarios, it is recommended to use a value of ON\_DISCONTINUITY so that the media player timeline is only reset when there is a significant issue with the media timeline (e.g. a missing fragment).

The default is ALWAYS when HLSFragmentSelector (p. 330) is set to SERVER\_TIMESTAMP, and NEVER when it is set to PRODUCER\_TIMESTAMP.

Type: String

Valid Values: ALWAYS | NEVER | ON\_DISCONTINUITY

Required: No

#### DisplayFragmentTimestamp (p. 282)

Specifies when the fragment start timestamps should be included in the HLS media playlist. Typically, media players report the playhead position as a time relative to the start of the first fragment in the playback session. However, when the start timestamps are included in the HLS media playlist, some media players might report the current playhead as an absolute time based on the fragment timestamps. This can be useful for creating a playback experience that shows viewers the wall-clock time of the media.

The default is NEVER. When HLSFragmentSelector (p. 330) is SERVER\_TIMESTAMP, the timestamps will be the server start timestamps. Similarly, when HLSFragmentSelector (p. 330) is PRODUCER\_TIMESTAMP, the timestamps will be the producer start timestamps.

Type: String

Valid Values: ALWAYS | NEVER

Required: No Expires (p. 282)

The time in seconds until the requested session expires. This value can be between 300 (5 minutes) and 43200 (12 hours).

When a session expires, no new calls to GetHLSMasterPlaylist, GetHLSMediaPlaylist, GetMP4InitFragment, GetMP4MediaFragment, or GetTSFragment can be made for that session.

The default is 300 (5 minutes).

Type: Integer

Valid Range: Minimum value of 300. Maximum value of 43200.

Required: No

## **HLSFragmentSelector (p. 282)**

The time range of the requested fragment and the source of the timestamps.

This parameter is required if PlaybackMode is ON\_DEMAND or LIVE\_REPLAY. This parameter is optional if PlaybackMode is LIVE. If PlaybackMode is LIVE, the FragmentSelectorType can be set, but the TimestampRange should not be set. If PlaybackMode is ON\_DEMAND or LIVE\_REPLAY, both FragmentSelectorType and TimestampRange must be set.

Type: HLSFragmentSelector (p. 330) object

Required: No

#### MaxMediaPlaylistFragmentResults (p. 282)

The maximum number of fragments that are returned in the HLS media playlists.

When the PlaybackMode is LIVE, the most recent fragments are returned up to this value. When the PlaybackMode is ON\_DEMAND, the oldest fragments are returned, up to this maximum number.

When there are a higher number of fragments available in a live HLS media playlist, video players often buffer content before starting playback. Increasing the buffer size increases the playback latency, but it decreases the likelihood that rebuffering will occur during playback. We recommend that a live HLS media playlist have a minimum of 3 fragments and a maximum of 10 fragments.

The default is 5 fragments if PlaybackMode is LIVE or LIVE\_REPLAY, and 1,000 if PlaybackMode is ON\_DEMAND.

The maximum value of 5,000 fragments corresponds to more than 80 minutes of video on streams with 1-second fragments, and more than 13 hours of video on streams with 10-second fragments.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 5000.

Required: No

#### PlaybackMode (p. 282)

Whether to retrieve live, live replay, or archived, on-demand data.

Features of the three types of sessions include the following:

• LIVE: For sessions of this type, the HLS media playlist is continually updated with the latest fragments as they become available. We recommend that the media player retrieve a new playlist on a one-second interval. When this type of session is played in a media player, the user interface typically displays a "live" notification, with no scrubber control for choosing the position in the playback window to display.

#### Note

In LIVE mode, the newest available fragments are included in an HLS media playlist, even if there is a gap between fragments (that is, if a fragment is missing). A gap like this might cause a media player to halt or cause a jump in playback. In this mode, fragments are not added to the HLS media playlist if they are older than the newest fragment in the playlist. If the missing fragment becomes available after a subsequent fragment is added to the playlist, the older fragment is not added, and the gap is not filled.

• LIVE\_REPLAY: For sessions of this type, the HLS media playlist is updated similarly to how it is updated for LIVE mode except that it starts by including fragments from a given start time. Instead of fragments being added as they are ingested, fragments are added as the duration of the next fragment elapses. For example, if the fragments in the session are two seconds long, then a new fragment is added to the media playlist every two seconds. This mode is useful to be able to

start playback from when an event is detected and continue live streaming media that has not yet been ingested as of the time of the session creation. This mode is also useful to stream previously archived media without being limited by the 1,000 fragment limit in the ON\_DEMAND mode.

• ON\_DEMAND: For sessions of this type, the HLS media playlist contains all the fragments for the session, up to the number that is specified in MaxMediaPlaylistFragmentResults. The playlist must be retrieved only once for each session. When this type of session is played in a media player, the user interface typically displays a scrubber control for choosing the position in the playback window to display.

In all playback modes, if FragmentSelectorType is PRODUCER\_TIMESTAMP, and if there are multiple fragments with the same start timestamp, the fragment that has the largest fragment number (that is, the newest fragment) is included in the HLS media playlist. The other fragments are not included. Fragments that have different timestamps but have overlapping durations are still included in the HLS media playlist. This can lead to unexpected behavior in the media player.

```
The default is LIVE.
```

```
Type: String
```

Valid Values: LIVE | LIVE\_REPLAY | ON\_DEMAND

# Required: No StreamARN (p. 282)

The Amazon Resource Name (ARN) of the stream for which to retrieve the HLS master playlist URL.

You must specify either the StreamName or the StreamARN.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: No

## StreamName (p. 282)

The name of the stream for which to retrieve the HLS master playlist URL.

You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

## Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "HLSStreamingSessionURL": "string"
}
```

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

## **HLSStreamingSessionURL (p. 285)**

The URL (containing the session token) that a media player can use to retrieve the HLS master playlist.

Type: String

## **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

## ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

#### InvalidCodecPrivateDataException

The codec private data in at least one of the tracks of the video stream is not valid for this operation.

HTTP Status Code: 400

#### MissingCodecPrivateDataException

No codec private data was found in at least one of tracks of the video stream.

HTTP Status Code: 400

NoDataRetentionException

A streaming session was requested for a stream that does not retain data (that is, has a DataRetentionInHours of 0).

HTTP Status Code: 400

#### NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

## ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

 $\label{lem:general-section} GetHLSStreamingSessionURL \ and \ GetDASHStreamingSessionURL \ throw \ this \ error \ if \ as session \ with \ a \ PlaybackMode \ of \ ON_DEMAND \ or \ LIVE\_REPLAY is \ requested \ for \ a \ stream \ that \ has \ an all \ and \ before \ a \ description \ of \ one \ of \ one \ of \ one \$ 

no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

## UnsupportedStreamMediaTypeException

The type of the media (for example, h.264 or h.265 video or ACC or G.711 audio) could not be determined from the codec IDs of the tracks in the first fragment for a playback session. The codec ID for track 1 should be V\_MPEG/ISO/AVC and, optionally, the codec ID for track 2 should be A\_AAC.

HTTP Status Code: 400

## See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

## GetImages

Service: Amazon Kinesis Video Streams Archived Media

Retrieves a list of Images corresponding to each timestamp for a given time range, sampling interval, and image format configuration.

## **Request Syntax**

```
POST /getImages HTTP/1.1
Content-type: application/json

{
    "EndTimestamp": number,
    "Format": "string",
    "FormatConfig": {
        "string" : "string"
    },
    "HeightPixels": number,
    "ImageSelectorType": "string",
    "MaxResults": number,
    "NextToken": "string",
    "SamplingInterval": number,
    "StreamARN": "string",
    "StreamARN": "string",
    "StreamName": "string",
    "WidthPixels": number
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

## Request Body

The request accepts the following data in JSON format.

#### EndTimestamp (p. 288)

The end timestamp for the range of images to be generated.

```
Type: Timestamp

Required: Yes

Format (p. 288)
```

The format that will be used to encode the image.

```
Type: String

Valid Values: JPEG | PNG

Required: Yes

FormatConfig (p. 288)
```

The list of a key-value pair structure that contains extra parameters that can be applied when the image is generated. The FormatConfig key is the JPEGQuality, which indicates the JPEG quality key to be used to generate the image. The FormatConfig value accepts ints from 1 to 100. If the value is 1, the image will be generated with less quality and the best compression. If the value is 100, the image will be generated with the best quality and less compression. If no value is provided, the default value of the JPEGQuality key will be set to 80.

Type: String to string map

Map Entries: Maximum number of 1 item.

Valid Keys: JPEGQuality

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Value Pattern: ^[a-zA-Z\_0-9]+

Required: No HeightPixels (p. 288)

The height of the output image that is used in conjunction with the WidthPixels parameter. When both HeightPixels and WidthPixels parameters are provided, the image will be stretched to fit the specified aspect ratio. If only the HeightPixels parameter is provided, its original aspect ratio will be used to calculate the WidthPixels ratio. If neither parameter is provided, the original image size will be returned.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 2160.

Required: No

ImageSelectorType (p. 288)

The origin of the Server or Producer timestamps to use to generate the images.

Type: String

Valid Values: PRODUCER\_TIMESTAMP | SERVER\_TIMESTAMP

Required: Yes

MaxResults (p. 288)

The maximum number of images to be returned by the API.

Note

The default limit is 100 images per API response. The additional results will be paginated.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 100.

Required: No NextToken (p. 288)

A token that specifies where to start paginating the next set of Images. This is the GetImages: NextToken from a previously truncated response.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 4096.

Pattern:  $[a-zA-Z0-9+/]+=\{0,2\}$ 

Required: No

SamplingInterval (p. 288)

The time interval in milliseconds (ms) at which the images need to be generated from the stream. The minimum value that can be provided is 3000 ms. If the timestamp range is less than the sampling interval, the Image from the startTimestamp will be returned if available.

Type: Integer

Valid Range: Minimum value of 3000. Maximum value of 20000.

Required: Yes

## StartTimestamp (p. 288)

The starting point from which the images should be generated. This StartTimestamp must be within an inclusive range of timestamps for an image to be returned.

Type: Timestamp

Required: Yes StreamARN (p. 288)

The Amazon Resource Name (ARN) of the stream from which to retrieve the images. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+: kinesis video: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: No

StreamName (p. 288)

The name of the stream from which to retrieve the images. You must specify either the StreamName or the StreamARN.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No WidthPixels (p. 288)

The width of the output image that is used in conjunction with the HeightPixels parameter. When both WidthPixels and HeightPixels parameters are provided, the image will be stretched to fit the specified aspect ratio. If only the WidthPixels parameter is provided or if only the HeightPixels is provided, a ValidationException will be thrown. If neither parameter is provided, the original image size from the stream will be returned.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 3840.

Required: No

## **Response Syntax**

```
HTTP/1.1 200
Content-type: application/json
{
```

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

## Images (p. 290)

The list of images generated from the video stream. If there is no media available for the given timestamp, the NO\_MEDIA error will be listed in the output. If an error occurs while the image is being generated, the MEDIA\_ERROR will be listed in the output as the cause of the missing image.

```
Type: Array of Image (p. 332) objects
```

## NextToken (p. 290)

The encrypted token that was used in the request to get more images.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 4096.

```
Pattern: [a-zA-Z0-9+/]+=\{0,2\}
```

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

## HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

## NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

#### ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL and GetDASHStreamingSessionURL throw this error if a session with a PlaybackMode of ON\_DEMAND or LIVE\_REPLAYis requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

## See Also

- AWS Command Line Interface
- AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# GetMediaForFragmentList

Service: Amazon Kinesis Video Streams Archived Media

Gets media for a list of fragments (specified by fragment number) from the archived data in an Amazon Kinesis video stream.

#### Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the GetMediaForFragmentList requests to this endpoint using the --endpoint-url parameter.

For limits, see Kinesis Video Streams Limits.

#### **Important**

If an error is thrown after invoking a Kinesis Video Streams archived media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

- x-amz-ErrorType HTTP header contains a more specific error type in addition to what the HTTP status code provides.
- x-amz-RequestId HTTP header if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

## Request Syntax

```
POST /getMediaForFragmentList HTTP/1.1
Content-type: application/json

{
    "Fragments": [ "string" ],
    "StreamARN": "string",
    "StreamName": "string"
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

## Request Body

The request accepts the following data in JSON format.

## Fragments (p. 293)

A list of the numbers of fragments for which to retrieve media. You retrieve these values with ListFragments (p. 296).

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 1000 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[0-9]+\$

## Required: Yes

### StreamARN (p. 293)

The Amazon Resource Name (ARN) of the stream from which to retrieve fragment media. Specify either this parameter or the StreamName parameter.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/ [0-9]+

Required: No

## StreamName (p. 293)

The name of the stream from which to retrieve fragment media. Specify either this parameter or the StreamARN parameter.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## Response Syntax

```
HTTP/1.1 200
Content-Type: ContentType
```

Payload

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The response returns the following HTTP headers.

#### ContentType (p. 294)

The content type of the requested media.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[a-zA-Z0-9\_\.\-]+\$

The response returns the following as the HTTP body.

## Payload (p. 294)

The payload that Kinesis Video Streams returns is a sequence of chunks from the specified stream. For information about the chunks, see PutMedia. The chunks that Kinesis Video Streams returns in the GetMediaForFragmentList call also include the following additional Matroska (MKV) tags:

- AWS\_KINESISVIDEO\_FRAGMENT\_NUMBER Fragment number returned in the chunk.
- AWS\_KINESISVIDEO\_SERVER\_SIDE\_TIMESTAMP Server-side timestamp of the fragment.

AWS\_KINESISVIDEO\_PRODUCER\_SIDE\_TIMESTAMP - Producer-side timestamp of the fragment.

The following tags will be included if an exception occurs:

- AWS\_KINESISVIDEO\_FRAGMENT\_NUMBER The number of the fragment that threw the exception
- AWS\_KINESISVIDEO\_EXCEPTION\_ERROR\_CODE The integer code of the
- AWS\_KINESISVIDEO\_EXCEPTION\_MESSAGE A text description of the exception

#### **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

HTTP Status Code: 400 InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400 **NotAuthorizedException** 

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL and GetDASHStreamingSessionURL throw this error if a session with a PlaybackMode of ON\_DEMAND or LIVE\_REPLAYis requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

## See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# ListFragments

Service: Amazon Kinesis Video Streams Archived Media

Returns a list of Fragment (p. 328) objects from the specified stream and timestamp range within the archived data.

Listing fragments is eventually consistent. This means that even if the producer receives an acknowledgment that a fragment is persisted, the result might not be returned immediately from a request to ListFragments. However, results are typically available in less than one second.

#### Note

You must first call the GetDataEndpoint API to get an endpoint. Then send the ListFragments requests to this endpoint using the --endpoint-url parameter.

#### Important

If an error is thrown after invoking a Kinesis Video Streams archived media API, in addition to the HTTP status code and the response body, it includes the following pieces of information:

- x-amz-ErrorType HTTP header contains a more specific error type in addition to what the HTTP status code provides.
- x-amz-RequestId HTTP header if you want to report an issue to AWS, the support team can better diagnose the problem if given the Request Id.

Both the HTTP status code and the ErrorType header can be utilized to make programmatic decisions about whether errors are retry-able and under what conditions, as well as provide information on what actions the client programmer might need to take in order to successfully try again.

For more information, see the **Errors** section at the bottom of this topic, as well as Common Errors.

## Request Syntax

```
POST /listFragments HTTP/1.1
Content-type: application/json

{
    "FragmentSelector": {
        "FragmentSelectorType": "string",
        "TimestampRange": {
            "EndTimestamp": number,
            "StartTimestamp": number
        }
    },
    "MaxResults": number,
    "NextToken": "string",
    "StreamARN": "string",
    "StreamName": "string"
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

#### Request Body

The request accepts the following data in JSON format.

#### FragmentSelector (p. 296)

Describes the timestamp range and timestamp origin for the range of fragments to return.

Type: FragmentSelector (p. 329) object

# Required: No MaxResults (p. 296)

The total number of fragments to return. If the total number of fragments available is more than the value specified in max-results, then a ListFragments:NextToken (p. 298) is provided in the output that you can use to resume pagination.

Type: Long

Valid Range: Minimum value of 1. Maximum value of 1000.

Required: No

## NextToken (p. 296)

A token to specify where to start paginating. This is the ListFragments:NextToken (p. 298) from a previously truncated response.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 4096.

Pattern:  $[a-zA-Z0-9+/]+=\{0,2\}$ 

Required: No StreamARN (p. 296)

The Amazon Resource Name (ARN) of the stream from which to retrieve a fragment list. Specify either this parameter or the StreamName parameter.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9\_.-]+/[0-9]+

Required: No

#### StreamName (p. 296)

The name of the stream from which to retrieve a fragment list. Specify either this parameter or the StreamARN parameter.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "Fragments": [
```

```
{
    "FragmentLengthInMilliseconds": number,
    "FragmentNumber": "string",
    "FragmentSizeInBytes": number,
    "ProducerTimestamp": number,
    "ServerTimestamp": number
}
],
"NextToken": "string"
}
```

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

## Fragments (p. 297)

A list of archived Fragment (p. 328) objects from the stream that meet the selector criteria. Results are in no specific order, even across pages.

Type: Array of Fragment (p. 328) objects

#### NextToken (p. 297)

If the returned list is truncated, the operation returns this token to use to retrieve the next page of results. This value is null when there are no more results to return.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 4096.

Pattern:  $[a-zA-Z0-9+/]+=\{0,2\}$ 

## **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

## ClientLimitExceededException

Kinesis Video Streams has throttled the request because you have exceeded a limit. Try making the call later. For information about limits, see Kinesis Video Streams Limits.

HTTP Status Code: 400

## InvalidArgumentException

A specified parameter exceeds its restrictions, is not supported, or can't be used.

HTTP Status Code: 400

#### NotAuthorizedException

Status Code: 403, The caller is not authorized to perform an operation on the given stream, or the token has expired.

HTTP Status Code: 401

#### ResourceNotFoundException

GetImages will throw this error when Kinesis Video Streams can't find the stream that you specified.

GetHLSStreamingSessionURL and GetDASHStreamingSessionURL throw this error if a session with a PlaybackMode of ON\_DEMAND or LIVE\_REPLAYis requested for a stream that has no fragments within the requested time range, or if a session with a PlaybackMode of LIVE is requested for a stream that has no fragments within the last 30 seconds.

HTTP Status Code: 404

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

# Amazon Kinesis Video Signaling Channels

The following actions are supported by Amazon Kinesis Video Signaling Channels:

- GetIceServerConfig (p. 300)
- SendAlexaOfferToMaster (p. 303)

# GetIceServerConfig

Service: Amazon Kinesis Video Signaling Channels

#### Note

Before using this API, you must call the GetSignalingChannelEndpoint API to get an endpoint. You then specify the endpoint and region in your GetIceServerConfig API request.

Gets the Interactive Connectivity Establishment (ICE) server configuration information, including URIs, user name, and password which can be used to configure the WebRTC connection. The ICE component uses this configuration information to set up the WebRTC connection, including authenticating with the Traversal Using Relays around NAT (TURN) relay server.

TURN is a protocol that is used to improve the connectivity of peer-to-peer applications. By providing a cloud-based relay service, TURN ensures that a connection can be established even when one or more peers are incapable of a direct peer-to-peer connection. For more information, see A REST API For Access To TURN Services.

You can invoke this API to establish a fallback mechanism in case either of the peers is unable to establish a direct peer-to-peer connection over a signaling channel. You must specify the Amazon Resource Name (ARN) of your signaling channel in order to invoke this API.

## Request Syntax

```
POST /v1/get-ice-server-config HTTP/1.1
Content-type: application/json

{
    "ChannelARN": "string",
    "ClientId": "string",
    "Service": "string",
    "Username": "string"
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

## Request Body

The request accepts the following data in JSON format.

## ChannelARN (p. 300)

The ARN of the signaling channel to be used for the peer-to-peer connection between configured peers.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+
```

Required: Yes ClientId (p. 300)

Unique identifier for the viewer. Must be unique within the signaling channel.

Type: String

```
Length Constraints: Minimum length of 1. Maximum length of 256.
```

```
Pattern: [a-zA-Z0-9_.-]+
```

Required: No

## Service (p. 300)

Specifies the desired service. Currently, TURN is the only valid value.

Type: String

Valid Values: TURN

Required: No

## Username (p. 300)

An optional user ID to be associated with the credentials.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## Response Syntax

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

## IceServerList (p. 301)

The list of ICE server information objects.

Type: Array of IceServer (p. 334) objects

## **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

#### ClientLimitExceededException

Your request was throttled because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400 InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400
InvalidClientException

The specified client is invalid.

HTTP Status Code: 400

NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

ResourceNotFoundException

The specified resource is not found.

HTTP Status Code: 404 **SessionExpiredException** 

If the client session is expired. Once the client is connected, the session is valid for 45 minutes. Client should reconnect to the channel to continue sending/receiving messages.

HTTP Status Code: 400

## See Also

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- AWS SDK for Python
- AWS SDK for Ruby V3

## SendAlexaOfferToMaster

Service: Amazon Kinesis Video Signaling Channels

#### Note

Before using this API, you must call the GetSignalingChannelEndpoint API to get an endpoint. You then specify the endpoint and region in your SendAlexaOfferToMaster API request.

This API allows you to connect WebRTC-enabled devices with Alexa display devices. When invoked, it sends the Alexa Session Description Protocol (SDP) offer to the master peer. The offer is delivered as soon as the master is connected to the specified signaling channel. This API returns the SDP answer from the connected master. If the master is not connected to the signaling channel, redelivery requests are made until the message expires.

## Request Syntax

```
POST /v1/send-alexa-offer-to-master HTTP/1.1
Content-type: application/json

{
    "ChannelARN": "string",
    "MessagePayload": "string",
    "SenderClientId": "string"
}
```

## **URI Request Parameters**

The request does not use any URI parameters.

## **Request Body**

The request accepts the following data in JSON format.

## ChannelARN (p. 303)

The Amazon Resource Name (ARN) of the signaling channel by which Alexa and the master peer communicate.

```
Type: String
```

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: Yes

## MessagePayload (p. 303)

The base64-encoded SDP offer content.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 10000.

```
Pattern: [a-zA-Z0-9+/=]+
```

Required: Yes

## SenderClientId (p. 303)

The unique identifier for the sender client.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: Yes

## Response Syntax

```
HTTP/1.1 200
Content-type: application/json
{
    "Answer": "string"
}
```

## **Response Elements**

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

## Answer (p. 304)

The base64-encoded SDP answer content.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 10000.

## **Errors**

For information about the errors that are common to all actions, see Common Errors (p. 335).

## ClientLimitExceededException

Your request was throttled because you have exceeded the limit of allowed client calls. Try making the call later.

HTTP Status Code: 400

#### InvalidArgumentException

The value for this input parameter is invalid.

HTTP Status Code: 400

## NotAuthorizedException

The caller is not authorized to perform this operation.

HTTP Status Code: 401

## Resource Not Found Exception

The specified resource is not found.

HTTP Status Code: 404

#### See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS Command Line Interface
- · AWS SDK for .NET
- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for JavaScript
- AWS SDK for PHP V3
- · AWS SDK for Python
- AWS SDK for Ruby V3

# **Data Types**

The following data types are supported by Amazon Kinesis Video Streams:

- ChannelInfo (p. 307)
- ChannelNameCondition (p. 309)
- ImageGenerationConfiguration (p. 310)
- ImageGenerationDestinationConfig (p. 312)
- NotificationConfiguration (p. 313)
- NotificationDestinationConfig (p. 314)
- ResourceEndpointListItem (p. 315)
- SingleMasterChannelEndpointConfiguration (p. 316)
- SingleMasterConfiguration (p. 317)
- StreamInfo (p. 318)
- StreamNameCondition (p. 320)
- Tag (p. 321)

The following data types are supported by Amazon Kinesis Video Streams Media:

• StartSelector (p. 322)

The following data types are supported by Amazon Kinesis Video Streams Archived Media:

- ClipFragmentSelector (p. 324)
- ClipTimestampRange (p. 325)
- DASHFragmentSelector (p. 326)
- DASHTimestampRange (p. 327)
- Fragment (p. 328)
- FragmentSelector (p. 329)
- HLSFragmentSelector (p. 330)
- HLSTimestampRange (p. 331)
- Image (p. 332)
- TimestampRange (p. 333)

The following data types are supported by Amazon Kinesis Video Signaling Channels:

• IceServer (p. 334)

# Amazon Kinesis Video Streams

The following data types are supported by Amazon Kinesis Video Streams:

- ChannelInfo (p. 307)
- ChannelNameCondition (p. 309)
- ImageGenerationConfiguration (p. 310)
- ImageGenerationDestinationConfig (p. 312)
- NotificationConfiguration (p. 313)
- NotificationDestinationConfig (p. 314)
- ResourceEndpointListItem (p. 315)
- SingleMasterChannelEndpointConfiguration (p. 316)
- SingleMasterConfiguration (p. 317)
- StreamInfo (p. 318)
- StreamNameCondition (p. 320)
- Tag (p. 321)

## ChannelInfo

Service: Amazon Kinesis Video Streams

A structure that encapsulates a signaling channel's metadata and properties.

## **Contents**

#### ChannelARN

```
The Amazon Resource Name (ARN) of the signaling channel.
```

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

```
Pattern: arn: [a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/ [0-9]+
```

Required: No

## ChannelName

The name of the signaling channel.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## ChannelStatus

Current status of the signaling channel.

Type: String

Valid Values: CREATING | ACTIVE | UPDATING | DELETING

Required: No

#### ChannelType

The type of the signaling channel.

Type: String

Valid Values: SINGLE\_MASTER | FULL\_MESH

Required: No

#### CreationTime

The time at which the signaling channel was created.

Type: Timestamp

Required: No

## ${\bf Single Master Configuration}$

A structure that contains the configuration for the SINGLE\_MASTER channel type.

Type: SingleMasterConfiguration (p. 317) object

## Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

Required: No

## Version

The current version of the signaling channel.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: No

## See Also

- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

## ChannelNameCondition

Service: Amazon Kinesis Video Streams

An optional input parameter for the ListSignalingChannels API. When this parameter is specified while invoking ListSignalingChannels, the API returns only the channels that satisfy a condition specified in ChannelNameCondition.

## **Contents**

## ComparisonOperator

A comparison operator. Currently, you can only specify the BEGINS\_WITH operator, which finds signaling channels whose names begin with a given prefix.

Type: String

Valid Values: BEGINS\_WITH

Required: No **ComparisonValue** 

A value to compare.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# ImageGenerationConfiguration

Service: Amazon Kinesis Video Streams

The structure that contains the information required for the KVS images delivery. If null, the configuration will be deleted from the stream.

#### Contents

## DestinationConfig

The structure that contains the information required to deliver images to a customer.

Type: ImageGenerationDestinationConfig (p. 312) object

Required: Yes

#### **Format**

The accepted image format.

Type: String

Valid Values: JPEG | PNG

Required: Yes

## **FormatConfig**

The list of a key-value pair structure that contains extra parameters that can be applied when the image is generated. The FormatConfig key is the JPEGQuality, which indicates the JPEG quality key to be used to generate the image. The FormatConfig value accepts ints from 1 to 100. If the value is 1, the image will be generated with less quality and the best compression. If the value is 100, the image will be generated with the best quality and less compression. If no value is provided, the default value of the JPEGQuality key will be set to 80.

Type: String to string map

Map Entries: Maximum number of 1 item.

Valid Keys: JPEGQuality

Value Length Constraints: Minimum length of 0. Maximum length of 256.

Value Pattern: ^[a-zA-Z\_0-9]+

Required: No

## HeightPixels

The height of the output image that is used in conjunction with the WidthPixels parameter. When both HeightPixels and WidthPixels parameters are provided, the image will be stretched to fit the specified aspect ratio. If only the HeightPixels parameter is provided, its original aspect ratio will be used to calculate the WidthPixels ratio. If neither parameter is provided, the original image size will be returned.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 2160.

Required: No ImageSelectorType

The origin of the Server or Producer timestamps to use to generate the images.

#### Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

Type: String

Valid Values: SERVER\_TIMESTAMP | PRODUCER\_TIMESTAMP

Required: Yes **SamplingInterval** 

The time interval in milliseconds (ms) at which the images need to be generated from the stream. The minimum value that can be provided is 33 ms, because a camera that generates content at 30 FPS would create a frame every 33.3 ms. If the timestamp range is less than the sampling interval, the Image from the StartTimestamp will be returned if available.

Type: Integer

Valid Range: Minimum value of 3000. Maximum value of 20000.

Required: Yes

#### Status

Indicates whether the Continuous ImageGenerationConfigurations API is enabled or disabled.

Type: String

Valid Values: ENABLED | DISABLED

Required: Yes

#### WidthPixels

The width of the output image that is used in conjunction with the HeightPixels parameter. When both WidthPixels and HeightPixels parameters are provided, the image will be stretched to fit the specified aspect ratio. If only the WidthPixels parameter is provided, its original aspect ratio will be used to calculate the HeightPixels ratio. If neither parameter is provided, the original image size will be returned.

Type: Integer

Valid Range: Minimum value of 1. Maximum value of 3840.

Required: No

## See Also

- AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# ImageGenerationDestinationConfig

Service: Amazon Kinesis Video Streams

The structure that contains the information required to deliver images to a customer.

## Contents

## DestinationRegion

The AWS Region of the S3 bucket where images will be delivered. This DestinationRegion must match the Region where the stream is located.

Type: String

Length Constraints: Minimum length of 9. Maximum length of 14.

Pattern: ^[a-z]+(-[a-z]+)?-[a-z]+-[0-9]\$

Required: Yes

Uri

The Uniform Resource Identifier (URI) that identifies where the images will be delivered.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 255.

Pattern: ^[a-zA-Z\_0-9]+:(//)?([^/]+)/?([^\*]\*)\$

Required: Yes

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# NotificationConfiguration

Service: Amazon Kinesis Video Streams

The structure that contains the notification information for the KVS images delivery. If this parameter is null, the configuration will be deleted from the stream.

## Contents

## DestinationConfig

The destination information required to deliver a notification to a customer.

Type: NotificationDestinationConfig (p. 314) object

Required: Yes

#### Status

Indicates if a notification configuration is enabled or disabled.

Type: String

Valid Values: ENABLED | DISABLED

Required: Yes

## See Also

- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# NotificationDestinationConfig

Service: Amazon Kinesis Video Streams

The structure that contains the information required to deliver a notification to a customer.

## **Contents**

## Uri

The Uniform Resource Identifier (URI) that identifies where the images will be delivered.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 255.

Pattern: ^[a-zA-Z\_0-9]+:(//)?([^/]+)/?([^\*]\*)\$

Required: Yes

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Resource Endpoint List Item

Service: Amazon Kinesis Video Streams

An object that describes the endpoint of the signaling channel returned by the GetSignalingChannelEndpoint API.

## Contents

#### **Protocol**

The protocol of the signaling channel returned by the GetSignalingChannelEndpoint API.

Type: String

Valid Values: WSS | HTTPS

Required: No ResourceEndpoint

The endpoint of the signaling channel returned by the GetSignalingChannelEndpoint API.

Type: String Required: No

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# SingleMasterChannelEndpointConfiguration

Service: Amazon Kinesis Video Streams

An object that contains the endpoint configuration for the SINGLE\_MASTER channel type.

## **Contents**

#### **Protocols**

This property is used to determine the nature of communication over this SINGLE\_MASTER signaling channel. If WSS is specified, this API returns a websocket endpoint. If HTTPS is specified, this API returns an HTTPS endpoint.

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 5 items.

Valid Values: WSS | HTTPS

Required: No

#### Role

This property is used to determine messaging permissions in this SINGLE\_MASTER signaling channel. If MASTER is specified, this API returns an endpoint that a client can use to receive offers from and send answers to any of the viewers on this signaling channel. If VIEWER is specified, this API returns an endpoint that a client can use only to send offers to another MASTER client on this signaling channel.

Type: String

Valid Values: MASTER | VIEWER

Required: No

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# SingleMasterConfiguration

Service: Amazon Kinesis Video Streams

A structure that contains the configuration for the SINGLE\_MASTER channel type.

## **Contents**

## MessageTtlSeconds

The period of time a signaling channel retains undelivered messages before they are discarded.

Type: Integer

Valid Range: Minimum value of 5. Maximum value of 120.

Required: No

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

## StreamInfo

Service: Amazon Kinesis Video Streams

An object describing a Kinesis video stream.

## **Contents**

#### CreationTime

A time stamp that indicates when the stream was created.

Type: Timestamp

Required: No

#### DataRetentionInHours

How long the stream retains data, in hours.

Type: Integer

Valid Range: Minimum value of 0.

Required: No

#### **DeviceName**

The name of the device that is associated with the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

## KmsKeyId

The ID of the AWS Key Management Service (AWS KMS) key that Kinesis Video Streams uses to encrypt data on the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 2048.

Pattern: .+

Required: No

## MediaType

The MediaType of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: [\w\-\.\+]+/[\w\-\.\+]+/[\w\-\.\+]+/

Required: No

## Status

The status of the stream.

## Amazon Kinesis Video Streams Developer Guide Amazon Kinesis Video Streams

Type: String

Valid Values: CREATING | ACTIVE | UPDATING | DELETING

Required: No

# StreamARN

The Amazon Resource Name (ARN) of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 1024.

Pattern: arn:  $[a-z\d-]+:kinesisvideo: [a-z0-9-]+: [0-9]+: [a-z]+/[a-zA-Z0-9_.-]+/[0-9]+$ 

Required: No

#### StreamName

The name of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# Version

The version of the stream.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: [a-zA-Z0-9]+

Required: No

# See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **StreamNameCondition**

Service: Amazon Kinesis Video Streams

Specifies the condition that streams must satisfy to be returned when you list streams (see the ListStreams API). A condition has a comparison operation and a value. Currently, you can specify only the BEGINS\_WITH operator, which finds streams whose names start with a given prefix.

#### Contents

## ComparisonOperator

A comparison operator. Currently, you can specify only the BEGINS\_WITH operator, which finds streams whose names start with a given prefix.

Type: String

Valid Values: BEGINS\_WITH

Required: No **ComparisonValue** 

A value to compare.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Tag

Service: Amazon Kinesis Video Streams

A key and value pair that is associated with the specified signaling channel.

#### Contents

#### Key

The key of the tag that is associated with the specified signaling channel.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern:  $^([\p{L}\p{Z}\p{N}_.:/=+\-@]*)$ 

Required: Yes

## Value

The value of the tag that is associated with the specified signaling channel.

Type: String

Length Constraints: Minimum length of 0. Maximum length of 256.

Pattern:  $[\p{L}\p{Z}\p{N}_.:/=+\-@]*$ 

Required: Yes

# See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Amazon Kinesis Video Streams Media

The following data types are supported by Amazon Kinesis Video Streams Media:

• StartSelector (p. 322)

# StartSelector

Service: Amazon Kinesis Video Streams Media

Identifies the chunk on the Kinesis video stream where you want the GetMedia API to start returning media data. You have the following options to identify the starting chunk:

- · Choose the latest (or oldest) chunk.
- Identify a specific chunk. You can identify a specific chunk either by providing a fragment number or timestamp (server or producer).
- Each chunk's metadata includes a continuation token as a Matroska (MKV) tag
   (AWS\_KINESISVIDEO\_CONTINUATION\_TOKEN). If your previous GetMedia request terminated, you
   can use this tag value in your next GetMedia request. The API then starts returning chunks starting
   where the last API ended.

#### Contents

## AfterFragmentNumber

Specifies the fragment number from where you want the GetMedia API to start returning the fragments.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[0-9]+\$

Required: No ContinuationToken

Continuation token that Kinesis Video Streams returned in the previous GetMedia response. The GetMedia API then starts with the chunk identified by the continuation token.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[a-zA-Z0-9\_\.\-]+\$

Required: No

#### StartSelectorType

Identifies the fragment on the Kinesis video stream where you want to start getting the data from.

- · NOW Start with the latest chunk on the stream.
- EARLIEST Start with earliest available chunk on the stream.
- FRAGMENT\_NUMBER Start with the chunk after a specific fragment. You must also specify the AfterFragmentNumber parameter.
- PRODUCER\_TIMESTAMP or SERVER\_TIMESTAMP Start with the chunk containing a fragment with the specified producer or server timestamp. You specify the timestamp by adding StartTimestamp.
- CONTINUATION\_TOKEN Read using the specified continuation token.

#### Note

If you choose the NOW, EARLIEST, or CONTINUATION\_TOKEN as the startSelectorType, you don't provide any additional information in the startSelector.

Type: String

Valid Values: FRAGMENT\_NUMBER | SERVER\_TIMESTAMP | PRODUCER\_TIMESTAMP | NOW | EARLIEST | CONTINUATION\_TOKEN

Required: Yes **StartTimestamp** 

A timestamp value. This value is required if you choose the PRODUCER\_TIMESTAMP or the SERVER\_TIMESTAMP as the startSelectorType. The GetMedia API then starts with the chunk containing the fragment that has the specified timestamp.

Type: Timestamp

Required: No

# See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Amazon Kinesis Video Streams Archived Media

The following data types are supported by Amazon Kinesis Video Streams Archived Media:

- ClipFragmentSelector (p. 324)
- ClipTimestampRange (p. 325)
- DASHFragmentSelector (p. 326)
- DASHTimestampRange (p. 327)
- Fragment (p. 328)
- FragmentSelector (p. 329)
- HLSFragmentSelector (p. 330)
- HLSTimestampRange (p. 331)
- Image (p. 332)
- TimestampRange (p. 333)

# ClipFragmentSelector

Service: Amazon Kinesis Video Streams Archived Media

Describes the timestamp range and timestamp origin of a range of fragments.

Fragments that have duplicate producer timestamps are deduplicated. This means that if producers are producing a stream of fragments with producer timestamps that are approximately equal to the true clock time, the clip will contain all of the fragments within the requested timestamp range. If some fragments are ingested within the same time range and very different points in time, only the oldest ingested collection of fragments are returned.

# **Contents**

# FragmentSelectorType

The origin of the timestamps to use (Server or Producer).

Type: String

Valid Values: PRODUCER\_TIMESTAMP | SERVER\_TIMESTAMP

Required: Yes TimestampRange

The range of timestamps to return.

Type: ClipTimestampRange (p. 325) object

Required: Yes

## See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# ClipTimestampRange

Service: Amazon Kinesis Video Streams Archived Media

The range of timestamps for which to return fragments.

#### Contents

#### **EndTimestamp**

The end of the timestamp range for the requested media.

This value must be within 24 hours of the specified StartTimestamp, and it must be later than the StartTimestamp value. If FragmentSelectorType for the request is SERVER\_TIMESTAMP, this value must be in the past.

This value is inclusive. The EndTimestamp is compared to the (starting) timestamp of the fragment. Fragments that start before the EndTimestamp value and continue past it are included in the session.

Type: Timestamp

Required: Yes **StartTimestamp** 

The starting timestamp in the range of timestamps for which to return fragments.

Only fragments that start exactly at or after StartTimestamp are included in the session. Fragments that start before StartTimestamp and continue past it aren't included in the session. If FragmentSelectorType is SERVER\_TIMESTAMP, the StartTimestamp must be later than the stream head.

Type: Timestamp

Required: Yes

# See Also

- · AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# DASHFragmentSelector

Service: Amazon Kinesis Video Streams Archived Media

Contains the range of timestamps for the requested media, and the source of the timestamps.

## Contents

#### FragmentSelectorType

The source of the timestamps for the requested media.

When FragmentSelectorType is set to PRODUCER\_TIMESTAMP and GetDASHStreamingSessionURL:PlaybackMode (p. 276) is ON\_DEMAND or LIVE\_REPLAY, the first fragment ingested with a producer timestamp within the specified FragmentSelector:TimestampRange (p. 329) is included in the media playlist. In addition, the fragments with producer timestamps within the TimestampRange ingested immediately following the first fragment (up to the GetDASHStreamingSessionURL:MaxManifestFragmentResults (p. 276) value) are included.

Fragments that have duplicate producer timestamps are deduplicated. This means that if producers are producing a stream of fragments with producer timestamps that are approximately equal to the true clock time, the MPEG-DASH manifest will contain all of the fragments within the requested timestamp range. If some fragments are ingested within the same time range and very different points in time, only the oldest ingested collection of fragments are returned.

When FragmentSelectorType is set to PRODUCER\_TIMESTAMP and GetDASHStreamingSessionURL:PlaybackMode (p. 276) is LIVE, the producer timestamps are used in the MP4 fragments and for deduplication. But the most recently ingested fragments based on server timestamps are included in the MPEG-DASH manifest. This means that even if fragments ingested in the past have producer timestamps with values now, they are not included in the HLS media playlist.

The default is SERVER\_TIMESTAMP.

Type: String

Valid Values: PRODUCER\_TIMESTAMP | SERVER\_TIMESTAMP

Required: No **TimestampRange** 

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

Type: DASHTimestampRange (p. 327) object

Required: No

#### See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- · AWS SDK for Ruby V3

# DASHTimestampRange

Service: Amazon Kinesis Video Streams Archived Media

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

The values in DASHimestampRange are inclusive. Fragments that start exactly at or after the start time are included in the session. Fragments that start before the start time and continue past it are not included in the session.

#### Contents

#### EndTimestamp

The end of the timestamp range for the requested media. This value must be within 24 hours of the specified StartTimestamp, and it must be later than the StartTimestamp value.

If FragmentSelectorType for the request is SERVER\_TIMESTAMP, this value must be in the past.

The EndTimestamp value is required for ON\_DEMAND mode, but optional for LIVE\_REPLAY mode. If the EndTimestamp is not set for LIVE\_REPLAY mode then the session will continue to include newly ingested fragments until the session expires.

#### Note

This value is inclusive. The EndTimestamp is compared to the (starting) timestamp of the fragment. Fragments that start before the EndTimestamp value and continue past it are included in the session.

Type: Timestamp

Required: No

#### StartTimestamp

The start of the timestamp range for the requested media.

If the DASHTimestampRange value is specified, the StartTimestamp value is required.

Only fragments that start exactly at or after StartTimestamp are included in the session. Fragments that start before StartTimestamp and continue past it aren't included in the session. If FragmentSelectorType is SERVER\_TIMESTAMP, the StartTimestamp must be later than the stream head.

Type: Timestamp

Required: No

# See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Fragment

Service: Amazon Kinesis Video Streams Archived Media

Represents a segment of video or other time-delimited data.

# **Contents**

# FragmentLengthInMilliseconds

The playback duration or other time value associated with the fragment.

Type: Long
Required: No

# FragmentNumber

The unique identifier of the fragment. This value monotonically increases based on the ingestion order.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^[0-9]+\$

Required: No

# FragmentSizeInBytes

The total fragment size, including information about the fragment and contained media data.

Type: Long

Required: No

# ProducerTimestamp

The timestamp from the producer corresponding to the fragment.

Type: Timestamp

Required: No

## ServerTimestamp

The timestamp from the AWS server corresponding to the fragment.

Type: Timestamp

Required: No

#### See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# FragmentSelector

Service: Amazon Kinesis Video Streams Archived Media

Describes the timestamp range and timestamp origin of a range of fragments.

Only fragments with a start timestamp greater than or equal to the given start time and less than or equal to the end time are returned. For example, if a stream contains fragments with the following start timestamps:

- 00:00:00
- 00:00:02
- 00:00:04
- 00:00:06

A fragment selector range with a start time of 00:00:01 and end time of 00:00:04 would return the fragments with start times of 00:00:02 and 00:00:04.

# **Contents**

# FragmentSelectorType

The origin of the timestamps to use (Server or Producer).

Type: String

Valid Values: PRODUCER\_TIMESTAMP | SERVER\_TIMESTAMP

Required: Yes TimestampRange

The range of timestamps to return.

Type: TimestampRange (p. 333) object

Required: Yes

#### See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **HLSFragmentSelector**

Service: Amazon Kinesis Video Streams Archived Media

Contains the range of timestamps for the requested media, and the source of the timestamps.

# **Contents**

#### FragmentSelectorType

The source of the timestamps for the requested media.

When FragmentSelectorType is set to PRODUCER\_TIMESTAMP and GetHLSStreamingSessionURL:PlaybackMode (p. 284) is ON\_DEMAND or LIVE\_REPLAY, the first fragment ingested with a producer timestamp within the specified FragmentSelector:TimestampRange (p. 329) is included in the media playlist. In addition, the fragments with producer timestamps within the TimestampRange ingested immediately following the first fragment (up to the GetHLSStreamingSessionURL:MaxMediaPlaylistFragmentResults (p. 284) value) are included.

Fragments that have duplicate producer timestamps are deduplicated. This means that if producers are producing a stream of fragments with producer timestamps that are approximately equal to the true clock time, the HLS media playlists will contain all of the fragments within the requested timestamp range. If some fragments are ingested within the same time range and very different points in time, only the oldest ingested collection of fragments are returned.

When FragmentSelectorType is set to PRODUCER\_TIMESTAMP and GetHLSStreamingSessionURL:PlaybackMode (p. 284) is LIVE, the producer timestamps are used in the MP4 fragments and for deduplication. But the most recently ingested fragments based on server timestamps are included in the HLS media playlist. This means that even if fragments ingested in the past have producer timestamps with values now, they are not included in the HLS media playlist.

The default is SERVER\_TIMESTAMP.

Type: String

Valid Values: PRODUCER\_TIMESTAMP | SERVER\_TIMESTAMP

Required: No **TimestampRange** 

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

Type: HLSTimestampRange (p. 331) object

Required: No

#### See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **HLSTimestampRange**

Service: Amazon Kinesis Video Streams Archived Media

The start and end of the timestamp range for the requested media.

This value should not be present if PlaybackType is LIVE.

#### Contents

# **EndTimestamp**

The end of the timestamp range for the requested media. This value must be within 24 hours of the specified StartTimestamp, and it must be later than the StartTimestamp value.

If FragmentSelectorType for the request is SERVER\_TIMESTAMP, this value must be in the past.

The EndTimestamp value is required for ON\_DEMAND mode, but optional for LIVE\_REPLAY mode. If the EndTimestamp is not set for LIVE\_REPLAY mode then the session will continue to include newly ingested fragments until the session expires.

#### Note

This value is inclusive. The EndTimestamp is compared to the (starting) timestamp of the fragment. Fragments that start before the EndTimestamp value and continue past it are included in the session.

Type: Timestamp

Required: No

#### StartTimestamp

The start of the timestamp range for the requested media.

If the HLSTimestampRange value is specified, the StartTimestamp value is required.

Only fragments that start exactly at or after StartTimestamp are included in the session. Fragments that start before StartTimestamp and continue past it aren't included in the session. If FragmentSelectorType is SERVER\_TIMESTAMP, the StartTimestamp must be later than the stream head.

Type: Timestamp

Required: No

# See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **Image**

Service: Amazon Kinesis Video Streams Archived Media

A structure that contains the Timestamp, Error, and ImageContent.

#### Contents

#### **Error**

The error message shown when the image for the provided timestamp was not extracted due to a non-tryable error. An error will be returned if:

- There is no media that exists for the specified Timestamp.
- The media for the specified time does not allow an image to be extracted. In this case the media is audio only, or the incorrect media has been ingested.

Type: String

Valid Values: NO\_MEDIA | MEDIA\_ERROR

Required: No ImageContent

An attribute of the Image object that is Base64 encoded.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 6291456.

Required: No

#### **TimeStamp**

An attribute of the Image object that is used to extract an image from the video stream. This field is used to manage gaps on images or to better understand the pagination window.

Type: Timestamp

Required: No

# See Also

- · AWS SDK for C++
- AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **TimestampRange**

Service: Amazon Kinesis Video Streams Archived Media

The range of timestamps for which to return fragments.

# **Contents**

#### **EndTimestamp**

The ending timestamp in the range of timestamps for which to return fragments.

Type: Timestamp

# Required: Yes **StartTimestamp**

The starting timestamp in the range of timestamps for which to return fragments.

Type: Timestamp

Required: Yes

# See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# Amazon Kinesis Video Signaling Channels

The following data types are supported by Amazon Kinesis Video Signaling Channels:

• IceServer (p. 334)

# **IceServer**

Service: Amazon Kinesis Video Signaling Channels

A structure for the ICE server connection data.

#### Contents

#### **Password**

A password to login to the ICE server.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

Ttl

The period of time, in seconds, during which the user name and password are valid.

Type: Integer

Valid Range: Minimum value of 30. Maximum value of 86400.

Required: No

Uris

An array of URIs, in the form specified in the I-D.petithuguenin-behave-turn-uris spec. These URIs provide the different addresses and/or protocols that can be used to reach the TURN server.

Type: Array of strings

Length Constraints: Minimum length of 1. Maximum length of 256.

Required: No

# Username

A user name to login to the ICE server.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 256.

Pattern: [a-zA-Z0-9\_.-]+

Required: No

# See Also

- AWS SDK for C++
- · AWS SDK for Go
- AWS SDK for Java V2
- AWS SDK for Ruby V3

# **Common Errors**

This section lists the errors common to the API actions of all AWS services. For errors specific to an API action for this service, see the topic for that API action.

#### AccessDeniedException

You do not have sufficient access to perform this action.

HTTP Status Code: 400

#### **IncompleteSignature**

The request signature does not conform to AWS standards.

HTTP Status Code: 400

#### InternalFailure

The request processing has failed because of an unknown error, exception or failure.

HTTP Status Code: 500

#### InvalidAction

The action or operation requested is invalid. Verify that the action is typed correctly.

HTTP Status Code: 400

#### InvalidClientTokenId

The X.509 certificate or AWS access key ID provided does not exist in our records.

HTTP Status Code: 403

#### InvalidParameterCombination

Parameters that must not be used together were used together.

HTTP Status Code: 400

#### **InvalidParameterValue**

An invalid or out-of-range value was supplied for the input parameter.

HTTP Status Code: 400

#### InvalidQueryParameter

The AWS query string is malformed or does not adhere to AWS standards.

HTTP Status Code: 400

#### MalformedQueryString

The query string contains a syntax error.

HTTP Status Code: 404

# MissingAction

The request is missing an action or a required parameter.

HTTP Status Code: 400

# MissingAuthenticationToken

The request must contain either a valid (registered) AWS access key ID or X.509 certificate.

#### Amazon Kinesis Video Streams Developer Guide Common Parameters

HTTP Status Code: 403

#### MissingParameter

A required parameter for the specified action is not supplied.

HTTP Status Code: 400

#### **NotAuthorized**

You do not have permission to perform this action.

HTTP Status Code: 400

# OptInRequired

The AWS access key ID needs a subscription for the service.

HTTP Status Code: 403

#### RequestExpired

The request reached the service more than 15 minutes after the date stamp on the request or more than 15 minutes after the request expiration date (such as for pre-signed URLs), or the date stamp on the request is more than 15 minutes in the future.

HTTP Status Code: 400

#### ServiceUnavailable

The request has failed due to a temporary failure of the server.

HTTP Status Code: 503

#### **ThrottlingException**

The request was denied due to request throttling.

HTTP Status Code: 400

#### ValidationError

The input fails to satisfy the constraints specified by an AWS service.

HTTP Status Code: 400

# **Common Parameters**

The following list contains the parameters that all actions use for signing Signature Version 4 requests with a query string. Any action-specific parameters are listed in the topic for that action. For more information about Signature Version 4, see Signature Version 4 Signing Process in the Amazon Web Services General Reference.

#### Action

The action to be performed.

Type: string

Required: Yes

## Version

The API version that the request is written for, expressed in the format YYYY-MM-DD.

Type: string

#### Amazon Kinesis Video Streams Developer Guide Common Parameters

# Required: Yes

# X-Amz-Algorithm

The hash algorithm that you used to create the request signature.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Valid Values: AWS4-HMAC-SHA256

Required: Conditional

#### X-Amz-Credential

The credential scope value, which is a string that includes your access key, the date, the region you are targeting, the service you are requesting, and a termination string ("aws4\_request"). The value is expressed in the following format: access\_key/YYYYMMDD/region/service/aws4\_request.

For more information, see Task 2: Create a String to Sign for Signature Version 4 in the Amazon Web Services General Reference.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Required: Conditional

#### X-Amz-Date

The date that is used to create the signature. The format must be ISO 8601 basic format (YYYYMMDD'T'HHMMSS'Z'). For example, the following date time is a valid X-Amz-Date value: 20120325T120000Z.

Condition: X-Amz-Date is optional for all requests; it can be used to override the date used for signing requests. If the Date header is specified in the ISO 8601 basic format, X-Amz-Date is not required. When X-Amz-Date is used, it always overrides the value of the Date header. For more information, see Handling Dates in Signature Version 4 in the Amazon Web Services General Reference.

Type: string

. string

Required: Conditional

## X-Amz-Security-Token

The temporary security token that was obtained through a call to AWS Security Token Service (AWS STS). For a list of services that support temporary security credentials from AWS Security Token Service, go to AWS Services That Work with IAM in the IAM User Guide.

Condition: If you're using temporary security credentials from the AWS Security Token Service, you must include the security token.

Type: string

Required: Conditional

#### X-Amz-Signature

Specifies the hex-encoded signature that was calculated from the string to sign and the derived signing key.

# Amazon Kinesis Video Streams Developer Guide Common Parameters

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Required: Conditional

# X-Amz-SignedHeaders

Specifies all the HTTP headers that were included as part of the canonical request. For more information about specifying signed headers, see Task 1: Create a Canonical Request For Signature Version 4 in the Amazon Web Services General Reference.

Condition: Specify this parameter when you include authentication information in a query string instead of in the HTTP authorization header.

Type: string

Required: Conditional