(#K)

Ask Al 🗱

```
RUN g++ -o /binary source.cpp
Differences between legacy builder and BuildKit
```

The legacy Docker Engine builder processes all stages of a Dockerfile leading up to the selected --target. It will build a stage even if the selected target doesn't depend on that stage.

BuildKit only builds the stages that the target stage depends on.

```
For example, given the following Dockerfile:
```

There is no dependency on stage1, so it's skipped.

Cookies Settings

```
# syntax=docker/dockerfile:1
 FROM ubuntu AS base
 RUN echo "base"
 FROM base AS stage1
 RUN echo "stage1"
 FROM base AS stage2
 RUN echo "stage2"
With BuildKit enabled, building the stage2 target in this Dockerfile means only base and stage2 are processed.
```

\$ DOCKER_BUILDKIT=1 docker build --no-cache -f Dockerfile --target stage2 .

```
[+] Building 0.4s (7/7) FINISHED
  => [internal] load build definition from Dockerfile
  => => transferring dockerfile: 36B
  => [internal] load .dockerignore
  => => transferring context: 2B
  => [internal] load metadata for docker.io/library/ubuntu:latest
  => CACHED [base 1/2] FROM docker.io/library/ubuntu
  => [base 2/2] RUN echo "base"
  => [stage2 1/1] RUN echo "stage2"
  => exporting to image
  => => exporting layers
  => => writing image sha256:f55003b607cef37614f607f0728e6fd4d113a4bf7ef12210da338c716f2cfd15
On the other hand, building the same target without BuildKit results in all stages being processed:
```

```
$ DOCKER_BUILDKIT=0 docker build --no-cache -f Dockerfile --target stage2 .
 Sending build context to Docker daemon 219.1kB
 Step 1/6 : FROM ubuntu AS base
  ---> a7870fd478f4
 Step 2/6 : RUN echo "base"
  ---> Running in e850d0e42eca
 base
 Removing intermediate container e850d0e42eca
  ---> d9f69f23cac8
 Step 3/6 : FROM base AS stage1
  ---> d9f69f23cac8
 Step 4/6 : RUN echo "stage1"
  ---> Running in 758ba6c1a9a3
 stage1
 Removing intermediate container 758ba6c1a9a3
  ---> 396baa55b8c3
 Step 5/6 : FROM base AS stage2
  ---> d9f69f23cac8
 Step 6/6 : RUN echo "stage2"
  ---> Running in bbc025b93175
 stage2
 Removing intermediate container bbc025b93175
  ---> 09fc3770a9c4
 Successfully built 09fc3770a9c4
The legacy builder processes stage1, even if stage2 doesn't depend on it.
```

Product offerings Pricing About us Support Contribute Copyright © 2013-2024 Docker Inc. All Terms of Service Status Legal rights reserved.