




4.1 Vertical Rhythm

4.2 Baseline Setup

4.3 Size + Leading




Grids

1. Horizontal



Susy - http://susy.oddbird.net





4.1 Vertical Rhythm

Grids

1. Horizontal

2. Vertical (Baseline)



High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

We'll be adding rhythm to this snippet of HTML:

index.html

```
<h1>Rivets, Welds, and You</h1>
High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.
<br/>
<blockquote>Assembly is, and will always be, in the details.</blockquote>
Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.
```

4.1 Vertical Rhythm



Eyeballing tends to result in magic numbers and guesses:

application.sass

```
body
  font-size: 18px
  line-height: 1.66667
h1
  border-bottom: 2px solid #333
  font-size: 30px
 margin-bottom: 30px
blockquote
  background: #ccc
  line-height: 3.33333
  text-align: center
p
 margin: 18px 0
```

4.1 Vertical Rhythm



High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

High-quality welding work is a necessity where promotion
ligh-quality welding work is a necessity where promotion
consideration is concerned. One who neglects the smallest detail
annot be put in charge of the whole.
Assembly is, and will always be, in the details. Rivets don't merely give metalwork character - they serve a vital
unction in joining pieces with strong cohesion. Use liberally where
ecessary, and always with care.

Feel the Rhythm, Feel the Rhyme

- We'll add a baseline grid and allow it to manage spacing, line heights, and margins
- Starting with just a reset:



Rivets, Welds, and You High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.
Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

Begin with Compass global variables and establish-baseline:

application.sass

```
@import "compass"

$base-font-size: 18px
$base-line-height: 30px
+establish-baseline
```

application.css

```
html {
  font-size: 112.5%;
  line-height: 1.667em;
}
```

4.2 Baseline Setup


Rivets, Welds, and You
High-quality welding work is a necessity where promotion
consideration is concerned. One who neglects the smallest detail
cannot be put in charge of the whole.
Assembly is, and will always be, in the details.
Rivets don't merely give metalwork character - they serve a vital
function in joining pieces with strong cohesion. Use liberally where

@import "compass"

\$base-font-size: 18px
\$base-line-height: 30px

+establish-baseline

- 4.1 Vertical Rhythm
- 4.2 Baseline Setup
- 4.3 Size + Leading
- 4.4 Margin, Padding, + Borders



adjust-font-size-to keeps size alterations from disrupting the grid:

```
application.sass
```

```
@import "compass"
h1
  +adjust-font-size-to(50px)
```

application.css

```
h1 {
  font-size: 2.778em;
  line-height: 1.2em;
}
```

4.3 Size + Leading

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

@import "compass"

• • •

h 1

+adjust-font-size-to(50px)

Typography Corner

Leading (distance between baselines) originates from typesetting by hand - strips of lead separated lines of text



adjust-leading-to tweaks the amount of vertical space occupied:

```
application.sass
```

```
@import "compass"
blockquote
  +adjust-leading-to(2)
  background: #ccc
```

application.css

```
blockquote {
  line-height: 3.333em;
  background: #ccccc;
}
```

4.3 Size + Leading

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

@import "compass"

• • •

blockquote

+adjust-leading-to(2)
background: #ccc

Rhythm mixins need to be notified of font size adjustments:

```
application.sass
@import "compass"
blockquote
  +adjust-font-size-to(20px)
  +adjust-leading-to(2)
  background: #ccc
```

application.css

```
blockquote {
  font-size: 1.111em;
  line-height: 1.5em;
  line-height: 3.333em;
  background: #cccccc;
}
```

4.3 Size + Leading

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

@import "compass"

• • •

blockquote

+adjust-font-size-to(20px)

+adjust-leading-to(2)

background: #ccc

Rhythm mixins need to be notified of font size adjustments:

```
application.sass
@import "compass"
blockquote
  +adjust-font-size-to(20px)
  +adjust-leading-to(2, 20px)
  background: #ccc
```

application.css

```
blockquote {
  font-size: 1.111em;
  line-height: 1.5em;
  line-height: 3em;
  background: #ccccc;
```

4.3 Size + Leading

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

@import "compass"

• • •

blockquote

+adjust-font-size-to(20px)

+adjust-leading-to(2, 20px)

background: #ccc

Always be wary of the CSS generated by your Sass file:

application.sass

```
@import "compass"
blockquote
  +adjust-font-size-to(20px)
 +adjust-leading-to(2, 20px)
  background: #ccc
```

application.css

```
blockquote {
  font-size: 1.111em;
  line-height: 1.5em;
  line-height: 3em;
  background: #cccccc;
}
```

4.3 Size + Leading

Assembly Tip

Use Vertical Rhythm carefully - misuse or overuse can cause bloat



- 4.1 Vertical Rhythm
- 4.2 Baseline Setup
- 4.3 Size + Leading





leader and trailer are used to add margin:

```
application.sass
```

```
@import "compass"
 +leader(1)
 +trailer(1)
```

application.css

```
p {
  margin-top: 1.667em;
  margin-bottom: 1.667em;
}
```

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

```
@import "compass"
...
```

+leader(1) +trailer(1)

Reminder - notify rhythm mixins of font size adjustments:

application.sass

```
@import "compass"
h1
  +adjust-font-size-to(50px)
  +trailer(2, 50px)
```

application.css

```
h1 {
  font-size: 2.778em;
  line-height: 1.2em;
  margin-bottom: 1.2em;
}
```

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

@import "compass"

• • •

h1

+adjust-font-size-to(50px)
+trailer(2, 50px)

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

Other Spacing Mixins

- padding-leader
- padding-trailer
- rhythm





Standard borders throw off our grid:

```
application.sass
@import "compass"
h1
  +adjust-font-size-to(50px
  +trailer(2, 50px)
  border-bottom: 10px solid #000
```

application.css

```
h1 {
  font-size: 2.778em;
  line-height: 1.2em;
  margin-bottom: 1.2em;
  border-bottom: 10px solid #000;
}
```

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

vets don't merely give metalwork character - they serve a vital inction in joining pieces with strong cohesion. Use liberally where ecessary, and always with care.

```
@import "compass"
```

• • •

h1

+adjust-font-size-to(50px

+trailer(2, 50px)

border-bottom: 10px solid #000

leading-border and trailing-border are grid-friendly alternatives:

```
application.sass
@import "compass"
h1
  +adjust-font-size-to(50px
  +trailer(2, 50px)
  +trailing-border(10px, 1, 50px)
   border width
                           font size,
      units of padding
                           if necessary
```

application.css

```
h1 {
  font-size: 2.778em;
  line-height: 1.2em;
 margin-bottom: 1.2em;
  border-bottom-style: solid;
  border-bottom-width: 0.2em;
  padding-bottom: 0.4em;
```

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

@import "compass"

• • •

h1

+adjust-font-size-to(50px

+trailer(2, 50px)

+trailing-border(10px, 1, 50px)

ssembly is, and will always be, in the details.

vets don't merely give metalwork character - they serve a vital nction in joining pieces with strong cohesion. Use liberally where ecessary, and always with care.

rhythm-borders adds border and uniform whitespace:

application.sass

```
@import "compass"

...

blockquote
    +adjust-font-size-to(20px)
    +rhythm-borders(2px, 1, 20px)
```

application.css

```
blockquote {
  font-size: 1.111em;
  line-height: 1.5em;
  border-style: solid;
  border-width: 0.1em;
  padding: 1.4em;
}
```

High-quality welding work is a necessity where promotion consideration is concerned. One who neglects the smallest detail cannot be put in charge of the whole.

Assembly is, and will always be, in the details.

Rivets don't merely give metalwork character - they serve a vital function in joining pieces with strong cohesion. Use liberally where necessary, and always with care.

@import "compass"

• • •

blockquote

+adjust-font-size-to(20px)

+rhythm-borders(2px, 1, 20px)

application.sass

```
@import "compass"
$base-font-size: 18px
$base-line-height: 30px
+establish-baseline
h1
  +adjust-font-size-to(50px)
  +trailer(2, 50px)
  +trailing-border(10px, 1, 50px)
blockquote
  +adjust-font-size-to(20px)
  +rhythm-borders(2px, 1, 20px)
p
  +leader(1)
  +trailer(1)
```



Assembly Tip

Baseline grids are difficult on the web: use when appropriate

