

MySQL NDB Cluster API Developer Guide

This is the *MySQL NDB Cluster API Developer Guide*, which provides information about developing applications using NDB Cluster as a data store. Application interfaces covered in this Guide include the low-level C++-language NDB API (see MySQL NDB Cluster API Developer Guide), the C-language MGM API for communicating with and controlling NDB Cluster management servers (see Chapter 3, *The MGM API*), and the MySQL NDB Cluster Connector for Java, which is a collection of Java APIs for writing applications against NDB Cluster, including JDBC, JPA, and ClusterJ (see Chapter 4, *MySQL NDB Cluster Connector for Java*).

NDB Cluster also provides support for the Memcache API; for more information, see Chapter 6, *ndbmemcache—Memcache API for NDB Cluster (NO LONGER SUPPORTED)*.

NDB Cluster also provides support for applications written using Node.js. See Chapter 5, MySQL NoSQL Connector for JavaScript, for more information.

This Guide includes concepts, terminology, class and function references, practical examples, common problems, and tips for using these APIs in applications.

For information about NDB internals that may be of interest to developers working with NDB, see MySQL NDB Cluster Internals Manual.

The information presented in this guide is current for recent releases of NDB Cluster up to and including NDB Cluster 8.0.24. Due to significant functional and other changes in NDB Cluster and its underlying APIs, you should not expect this information to apply to versions of the NDB Cluster software prior to NDB Cluster 7.3. Users of older NDB Cluster releases should upgrade to the latest available release of NDB Cluster 8.0, currently the most recent GA release series.

For more information about NDB 8.0, see What is New in NDB Cluster.

For legal information, see the Legal Notices.

For help with using MySQL, please visit the MySQL Forums, where you can discuss your issues with other MySQL users.

Licensing information—NDB APIs. If you are using the NDB APIs with a *Commercial* release of MySQL NDB Cluster, see the MySQL NDB Cluster 7.6 Commercial Release License Information User Manual for licensing information, including licensing information relating to third-party software that may be included in this Commercial release. If you are using the NDB APIs with a *Community* release of MySQL NDB Cluster, see the MySQL NDB Cluster 8.0 Community Release License Information User Manual for licensing information, including licensing information relating to third-party software that may be included in this Community release.

Document generated on: 2021-01-28 (revision: 68612)

Table of Contents

Preface and Legal Notices	VII
1 NDB Cluster APIs: Overview and Concepts	1
1.1 NDB Cluster API Overview: Introduction	1
1.1.1 NDB Cluster API Overview: The NDB API	1
1.1.2 NDB Cluster API Overview: The MGM API	2
1.2 NDB Cluster API Overview: Version Compatibility	
1.3 NDB Cluster API Overview: Terminology	
1.4 The NDB Transaction and Scanning API	
1.4.1 Core NDB API Classes	
1.4.2 Application Program Basics	
1.4.3 Review of NDB Cluster Concepts	
1.4.4 The Adaptive Send Algorithm	
1.5 Application-level partitioning	
1.6 Using NdbInterpretedCode	
2 The NDB API	
2.1 Getting Started with the NDB API	
2.1.1 Compiling and Linking NDB API Programs	
2.1.2 Connecting to the Cluster	
2.1.3 Mapping MySQL Database Object Names and Types to NDB	
2.2 The NDB API Class Hierarachy	
2.3 NDB API Classes, Interfaces, and Structures	
2.3.1 The Column Class	
2.3.2 The Datafile Class	
2.3.3 The Dictionary Class	
2.3.4 The Element Structure	
2.3.5 The Event Class	
2.3.6 The ForeignKey Class	
2.3.7 The HashMap Class	. 94
2.3.8 The Index Class	. 97
2.3.9 The LogfileGroup Class	104
2.3.10 The List Class	108
2.3.11 The Ndb Class	108
2.3.12 The Ndb_cluster_connection Class	132
2.3.13 The NdbBlob Class	143
2.3.14 The NdbDictionary Class	
2.3.15 The NdbError Structure	
2.3.16 The NdbEventOperation Class	
2.3.17 The NdbIndexOperation Class	
2.3.18 The NdbIndexScanOperation Class	
2.3.19 The NdbInterpretedCode Class	
2.3.20 The NdbOperation Class	
2.3.21 The NdbRecAttr Class	
2.3.22 The NdbRecord Interface	
2.3.23 The NdbScanFilter Class	
2.3.24 The NdbScanOperation Class	
2.3.25 The NdbScanOperation Class	
2.3.26 The Object Class	
•	
2.3.27 The Table Class	
2.3.28 The Tablespace Class	
2.3.29 The Undofile Class	
2.4 NDB API Errors and Error Handling	314

2.4.1 Handling NDB API Errors	
2.4.2 NDB Error Codes: by Type	
2.4.3 NDB Error Codes: Single Listing	
2.4.4 NDB Error Classifications	
2.5 NDB API Examples	
2.5.1 NDB API Example Using Synchronous Transactions	468
2.5.2 NDB API Example Using Synchronous Transactions and Multiple Clusters	472
2.5.3 NDB API Example: Handling Errors and Retrying Transactions	
2.5.4 NDB API Basic Scanning Example	
2.5.5 NDB API Example: Using Secondary Indexes in Scans	
2.5.6 NDB API Example: Using NdbRecord with Hash Indexes	
2.5.7 NDB API Example Comparing RecAttr and NdbRecord	
2.5.8 NDB API Event Handling Example	
2.5.9 NDB API Example: Basic BLOB Handling	
2.5.10 NDB API Example: Handling BLOB Columns and Values Using NdbRecord	
2.5.11 NDB API Simple Array Example	
2.5.12 NDB API Simple Array Example Using Adapter	
2.5.13 Timestamp2 Example	
2.5.13 Timestampe Example	
3 The MGM API	
3.1 MGM API Concepts	
3.2 MGM API Function Listing	
3.2.1 Log Event Functions	
3.2.2 MGM API Error Handling Functions	
3.2.3 Management Server Handle Functions	
3.2.4 Management Server Connection Functions	
3.2.5 Cluster Status Functions	
3.2.6 Functions for Starting & Stopping Nodes	
3.2.7 Cluster Log Functions	
3.2.8 Backup Functions	
3.2.9 Single-User Mode Functions	627
3.3 MGM API Data Types	
3.4 MGM API Data Structures	636
3.5 MGM API Errors	643
3.6 MGM API Examples	645
3.6.1 Basic MGM API Event Logging Example	645
3.6.2 MGM API Event Handling with Multiple Clusters	
4 MySQL NDB Cluster Connector for Java	
4.1 MySQL NDB Cluster Connector for Java: Overview	
4.1.1 MySQL NDB Cluster Connector for Java Architecture	
4.1.2 Java and NDB Cluster	
4.1.3 The ClusterJ API and Data Object Model	
4.2 Using MySQL NDB Cluster Connector for Java	
4.2.1 Getting, Installing, and Setting Up MySQL NDB Cluster Connector for Java	
4.2.2 Using ClusterJ	
4.2.3 Using Connector/J with NDB Cluster	868
4.2.3 Osing Connector/3 with NDB Cluster 4.3 ClusterJ API Reference	
4.3.1 com.mysql.clusterj	
4.3.2 com.mysql.clusterj.annotation	
4.3.3 com.mysql.clusterj.query	
4.3.4 Constant field values	
4.4 MySQL NDB Cluster Connector for Java: Limitations and Known Issues	
5 MySQL NoSQL Connector for JavaScript	/35
5.1 MySQL NoSQL Connector for JavaScript Overview	735

MySQL NDB Cluster API Developer Guide

5.2 Installing the JavaScript Connector	736
5.3 Connector for JavaScript API Documentation	737
5.3.1 Batch	737
5.3.2 Context	737
5.3.3 Converter	740
5.3.4 Errors	740
5.3.5 Mynode	741
5.3.6 Session	743
5.3.7 SessionFactory	744
5.3.8 TableMapping and FieldMapping	745
5.3.9 TableMetadata	746
5.3.10 Transaction	747
5.4 Using the MySQL JavaScript Connector: Examples	748
5.4.1 Requirements for the Examples	748
5.4.2 Example: Finding Rows	752
5.4.3 Inserting Rows	754
5.4.4 Deleting Rows	756
6 ndbmemcache—Memcache API for NDB Cluster (NO LONGER SUPPORTED)	759
6.1 Overview	759
6.2 Compiling NDB Cluster with Memcache Support	
6.3 memcached command line options	
6.4 NDB Engine Configuration	
6.5 Memcache protocol commands	
6.6 The memcached log file	
6.7 Known Issues and Limitations of ndbmemcache	770
Indox	772

Preface and Legal Notices

This is the *MySQL NDB Cluster API Developer Guide*, which provides information about developing applications using NDB Cluster as a data store. Application interfaces covered in this Guide include the low-level C++-language NDB API (see MySQL NDB Cluster API Developer Guide), the C-language MGM API for communicating with and controlling NDB Cluster management servers (see Chapter 3, *The MGM API*), and the MySQL NDB Cluster Connector for Java, which is a collection of Java APIs for writing applications against NDB Cluster, including JDBC, JPA, and ClusterJ (see Chapter 4, *MySQL NDB Cluster Connector for Java*).

NDB Cluster also provides support for the Memcache API; for more information, see Chapter 6, ndbmemcache—Memcache API for NDB Cluster (NO LONGER SUPPORTED).

NDB Cluster also provides support for applications written using Node.js. See Chapter 5, *MySQL NoSQL Connector for JavaScript*, for more information.

This Guide includes concepts, terminology, class and function references, practical examples, common problems, and tips for using these APIs in applications. It also contains information about NDB internals that may be of interest to developers working with NDB, such as communication protocols employed between nodes, file systems used by management nodes and data nodes, error messages, and debugging (DUMP) commands in the management client.

The information presented in this guide is current for recent releases of NDB Cluster up to and including NDB Cluster 8.0.24. Due to significant functional and other changes in NDB Cluster and its underlying APIs, you should not expect this information to apply to previous releases of the NDB Cluster software prior to NDB Cluster 7.3. Users of older NDB Cluster releases should upgrade to the latest available release of NDB Cluster 8.0, which is the most recent GA release series.

For more information about NDB 8.0, see What is New in NDB Cluster.

For legal information, see the Legal Notices.

Licensing information—MySQL NDB Cluster 8.0. This product may include third-party software, used under license. If you are using a *Commercial* release of MySQL NDB Cluster 8.0, see the MySQL NDB Cluster 8.0 Commercial Release License Information User Manual for licensing information, including licensing information relating to third-party software that may be included in this Commercial release. If you are using a *Community* release of MySQL NDB Cluster 8.0, see the MySQL NDB Cluster 8.0 Community Release License Information User Manual for licensing information, including licensing information relating to third-party software that may be included in this Community release.

Legal Notices

Copyright © 1997, 2021, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

This documentation is NOT distributed under a GPL license. Use of this documentation is subject to the following terms:

You may create a printed copy of this documentation solely for your own personal use. Conversion to other formats is allowed as long as the actual content is not altered or edited in any way. You shall not publish or distribute this documentation in any form or on any media, except if you distribute the documentation in a manner similar to how Oracle disseminates it (that is, electronically for download on a Web site with the software) or on a CD-ROM or similar medium, provided however that the documentation is disseminated together with the software on the same medium. Any other use, such as any dissemination of printed copies or use of this documentation, in whole or in part, in another publication, requires the prior written consent from an authorized representative of Oracle. Oracle and/or its affiliates reserve any and all rights to this documentation not expressly granted above.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

https://www.oracle.com/corporate/accessibility/.

Access to Oracle Support for Accessibility

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

https://www.oracle.com/corporate/accessibility/learning-support.html#support-tab.

Chapter 1 NDB Cluster APIs: Overview and Concepts

Table of Contents

1.1 NDB Cluster API Overview: Introduction	1
1.1.1 NDB Cluster API Overview: The NDB API	1
1.1.2 NDB Cluster API Overview: The MGM API	2
1.2 NDB Cluster API Overview: Version Compatibility	2
1.3 NDB Cluster API Overview: Terminology	
1.4 The NDB Transaction and Scanning API	4
1.4.1 Core NDB API Classes	
1.4.2 Application Program Basics	5
1.4.3 Review of NDB Cluster Concepts	13
1.4.4 The Adaptive Send Algorithm	
1.5 Application-level partitioning	
1.6 Using NdbInterpretedCode	

This chapter provides a general overview of essential NDB Cluster, NDB API, and MGM API concepts, terminology, and programming constructs.

For an overview of Java APIs that can be used with NDB Cluster, see Section 4.1, "MySQL NDB Cluster Connector for Java: Overview".

For information about using Memcache with NDB Cluster, see Chapter 6, *ndbmemcache—Memcache API for NDB Cluster (NO LONGER SUPPORTED)*.

For information about writing JavaScript applications using Node.js with MySQL, see Chapter 5, MySQL NoSQL Connector for JavaScript.

1.1 NDB Cluster API Overview: Introduction

This section introduces the NDB Transaction and Scanning APIs as well as the NDB Management (MGM) API for use in building applications to run on NDB Cluster. It also discusses the general theory and principles involved in developing such applications.

1.1.1 NDB Cluster API Overview: The NDB API

The *NDB API* is an object-oriented application programming interface for NDB Cluster that implements indexes, scans, transactions, and event handling. NDB transactions are ACID-compliant in that they provide a means to group operations in such a way that they succeed (commit) or fail as a unit (rollback). It is also possible to perform operations in a "no-commit" or deferred mode, to be committed at a later time.

NDB scans are conceptually rather similar to the SQL cursors implemented in MySQL 5.0 and other common enterprise-level database management systems. These provide high-speed row processing for record retrieval purposes. (NDB Cluster naturally supports set processing just as does MySQL in its non-Cluster distributions. This can be accomplished through the usual MySQL APIs discussed in the MySQL Manual and elsewhere.) The NDB API supports both table scans and row scans; the latter can be performed using either unique or ordered indexes. Event detection and handling is discussed in Section 2.3.16, "The NdbEventOperation Class", as well as Section 2.5.8, "NDB API Event Handling Example".

In addition, the NDB API provides object-oriented error-handling facilities in order to provide a means of recovering gracefully from failed operations and other problems. (See Section 2.5.3, "NDB API Example: Handling Errors and Retrying Transactions", for a detailed example.)

The NDB API provides a number of classes implementing the functionality described above. The most important of these include the Ndb, Ndb_cluster_connection, NdbTransaction, and NdbOperation classes. These model (respectively) database connections, cluster connections, transactions, and operations. These classes and their subclasses are listed in Section 2.3, "NDB API Classes, Interfaces, and Structures". Error conditions in the NDB API are handled using NdbError.



Note

NDB API applications access the NDB Cluster's data store directly, without requiring a MySQL Server as an intermediary. This means that such applications are not bound by the MySQL privilege system; any NDB API application has read and write access to any NDB table stored in the same NDB Cluster at any time without restriction.

1.1.2 NDB Cluster API Overview: The MGM API

The NDB Cluster Management API, also known as the MGM API, is a C-language programming interface intended to provide administrative services for the cluster. These include starting and stopping NDB Cluster nodes, handling NDB Cluster logging, backups, and restoration from backups, as well as various other management tasks. A conceptual overview of the MGM API and its uses can be found in Chapter 3, The MGM API.

The MGM API's principal structures model the states of individual modes (ndb_mgm_node_state), the state of the NDB Cluster as a whole (ndb_mgm_cluster_state), and management server response messages (ndb_mgm_reply). See Section 3.4, "MGM API Data Structures", for detailed descriptions of these.

1.2 NDB Cluster API Overview: Version Compatibility

The NDB API is now fairly mature, and has undergone few major changes in recent releases. Where they have occurred, such changes are indicated in the documentation of the affected objects and methods.

The API version of an NDB API application is determined by the version of <code>libndbclient</code> the application uses to provide NDB API functionality. Because it is necessary to support rolling upgrades, we perform basic testing across a number of versions (7.3, 7.4, 7.5, 7.6, 8.0) with regard to both older API versions connecting to data nodes of newer versions, and newer API versions connecting to data nodes of older versions. We no longer perform such testing with releases prior to NDB 7.3, since these are no longer maintained or supported in production.

In addition, in NDB 8.0, some compatibility has been dropped with API versions prior to 7.4, but is retained with versions 7.4, 7.5, and 7.6.

When new a new feature is added to NDB, this is generally done in such a way that the new functionality includes checking that the data nodes which are currently connected are running versions which support the feature. This is done to guard against accidental use of the new feature during a rolling upgrade before the cluster is fully upgraded to the version adding support for it.

In the event that an application employing a newer version of the NDB API is run against an older cluster which does not support a newer feature used by the application, the application raises error code 4003 Function not implemented yet when trying to make use of the feature. Other errors are possible depending on the new functionality involved (see Section 2.4.2, "NDB Error Codes: by Type").

When an application using an older version of libndbclient connects to a cluster running a newer version of NDB, the data nodes should support older API calls, but there other considerations as well. In particular, if the schema on the cluster makes use of newer features not supported by the older API

version does not support, it is possible that operations may be less than optimal or give rise to errors. Some examples are listed here:

- There are tables in the cluster using the JSON data type, which is unknown to NDB prior to version 7.5.1
- The cluster uses one or more fully replicated tables, which are not supported in NDB prior to version 7.5.2
- The cluster includes tables using generated columns, which are unsupported in NDB prior to version 7.5.3

When upgrading a cluster online (that is, by using a rolling restart), existing table schemas are preserved, thus avoiding activation of new schema features too early. This is not the case when the upgrad recreates the schema and restores all data, when the new version may by default use new schema features. For this reason, it is best practice to test with specific schemas, operations, and versions prior upgrading a production system to catch any problems that may arise when connecting an older application or SQL node to a cluster running a newer version of NDB.

1.3 NDB Cluster API Overview: Terminology

This section provides a glossary of terms which are unique to the NDB and MGM APIs, or that have a specialized meaning when applied in the context of either or both of these APIs.

The terms in the following list are useful to an understanding of NDB Cluster, the NDB API, or have a specialized meaning when used in one of these:

Backup. A complete copy of all NDB Cluster data, transactions and logs, saved to disk.

Restore. Return the cluster to a previous state, as stored in a backup.

Checkpoint. Generally speaking, when data is saved to disk, it is said that a checkpoint has been reached. When working with the NDB storage engine, there are two sorts of checkpoints which work together in order to ensure that a consistent view of the cluster's data is maintained. These two types, *local checkpoints* and *global checkpoints*, are described in the next few paragraphs:

Local checkpoint (LCP). This is a checkpoint that is specific to a single node; however, LCPs take place for all nodes in the cluster more or less concurrently. An LCP involves saving all of a node's data to disk, and so usually occurs every few minutes, depending upon the amount of data stored by the node.

More detailed information about LCPs and their behavior can be found in the MySQL Manual; see in particular Defining NDB Cluster Data Nodes.

Global checkpoint (GCP). A GCP occurs every few seconds, when transactions for all nodes are synchronized and the REDO log is flushed to disk.

A related term is *GCI*, which stands for "Global Checkpoint ID". This marks the point in the REDO log where a GCP took place.

Node. A component of NDB Cluster. 3 node types are supported:

- A management (MGM) node is an instance of ndb_mgmd, the NDB Cluster management server daemon.
- A data node an instance of ndbd, the NDB Cluster data storage daemon, and stores NDB Cluster data. This may also be an instance of ndbmtd, a multithreaded version of ndbd.
- An API node an application that accesses NDB Cluster data. SQL node refers to a mysqld (MySQL Server) process that is connected to the NDB Cluster as an API node.

For more information about these node types, please refer to Section 1.4.3, "Review of NDB Cluster Concepts", or to NDB Cluster Programs, in the *MySQL Manual*.

Node failure. An NDB Cluster is not solely dependent upon the functioning of any single node making up the cluster, which can continue to run even when one node fails.

Node restart. The process of restarting an NDB Cluster node which has stopped on its own or been stopped deliberately. This can be done for several different reasons, listed here:

- Restarting a node which has shut down on its own. (This is known as *forced shutdown* or *node failure*; the other cases discussed here involve manually shutting down the node and restarting it).
- To update the node's configuration.
- As part of a software or hardware upgrade.
- In order to defragment the node's DataMemory.

Initial node restart. The process of starting an NDB Cluster node with its file system having been removed. This is sometimes used in the course of software upgrades and in other special circumstances.

System crash (system failure). This can occur when so many data nodes have failed that the NDB Cluster's state can no longer be guaranteed.

System restart. The process of restarting an NDB Cluster and reinitializing its state from disk logs and checkpoints. This is required after any shutdown of the cluster, planned or unplanned.

Fragment. Contains a portion of a database table. In the NDB storage engine, a table is broken up into and stored as a number of subsets, usually referred to as fragments. A fragment is sometimes also called a *partition*.

Fragment replica. Under the NDB storage engine, each table fragment has number of fragment replicas in order to provide redundancy.

Transporter. A protocol providing data transfer across a network. The NDB API supports three different types of transporter connections: TCP/IP (local), TCP/IP (remote), and SHM. TCP/IP is, of course, the familiar network protocol that underlies HTTP, FTP, and so forth, on the Internet. SHM stands for Unix-style shared memory segments.

NDB. This originally stood for "Network DataBase". It now refers to the MySQL storage engine (named NDB or NDBCLUSTER) used to enable the NDB Cluster distributed database system.

ACC (Access Manager). An NDB kernel block that handles hash indexes of primary keys providing speedy access to the records. For more information, see The DBACC Block.

TUP (Tuple Manager). This NDB kernel block handles storage of tuples (records) and contains the filtering engine used to filter out records and attributes when performing reads or updates. See The DBTUP Block, for more information.

TC (Transaction Coordinator). Handles coordination of transactions and timeouts in the NDB kernel (see The DBTC Block). Provides interfaces to the NDB API for performing indexes and scan operations.

For more information, see NDB Kernel Blocks, elsewhere in this Guide...

See also NDB Cluster Overview, in the MySQL Manual.

1.4 The NDB Transaction and Scanning API

This section discusses the high-level architecture of the NDB API, and introduces the NDB classes which are of greatest use and interest to the developer. It also covers most important NDB API concepts, including a review of NDB Cluster Concepts.

1.4.1 Core NDB API Classes

The NDB API is an NDB Cluster application interface that implements transactions. It consists of the following fundamental classes:

- Ndb_cluster_connection represents a connection to a cluster.
- Ndb is the main class, and represents a connection to a database.
- NdbDictionary provides meta-information about tables and attributes.
- NdbTransaction represents a transaction.
- NdbOperation represents an operation using a primary key.
- NdbScanOperation represents an operation performing a full table scan.
- NdbIndexOperation represents an operation using a unique hash index.
- NdbIndexScanOperation represents an operation performing a scan using an ordered index.
- NdbRecAttr represents an attribute value.

In addition, the NDB API defines an NdbError structure, which contains the specification for an error.

It is also possible to receive events triggered when data in the database is changed. This is accomplished through the NdbEventOperation class.

The NDB event notification API is not supported prior to MySQL 5.1.

For more information about these classes as well as some additional auxiliary classes not listed here, see Section 2.3, "NDB API Classes, Interfaces, and Structures".

1.4.2 Application Program Basics

The main structure of an application program is as follows:

- 1. Connect to a cluster using the Ndb_cluster_connection object.
- 2. Initiate a database connection by constructing and initialising one or more Ndb objects.
- 3. Identify the tables, columns, and indexes on which you wish to operate, using NdbDictionary and one or more of its subclasses.
- 4. Define and execute transactions using the NdbTransaction class.
- 5. Delete Ndb objects.
- 6. Terminate the connection to the cluster (terminate an instance of Ndb_cluster_connection).

1.4.2.1 Using Transactions

The procedure for using transactions is as follows:

- 1. Start a transaction (instantiate an NdbTransaction object).
- 2. Add and define operations associated with the transaction using instances of one or more of the NdbOperation, NdbScanOperation, NdbIndexOperation, and NdbIndexScanOperation classes.

- 3. Execute the transaction (call NdbTransaction::execute()).
- 4. The operation can be of two different types—Commit or NoCommit:
 - If the operation is of type NoCommit, then the application program requests that the operation portion of a transaction be executed, but without actually committing the transaction. Following the execution of a NoCommit operation, the program can continue to define additional transaction operations for later execution.

NoCommit operations can also be rolled back by the application.

• If the operation is of type Commit, then the transaction is immediately committed. The transaction must be closed after it has been committed (even if the commit fails), and no further operations can be added to or defined for this transaction.

See NdbTransaction::ExecType.

1.4.2.2 Synchronous Transactions

Synchronous transactions are defined and executed as follows:

- 1. Begin (create) the transaction, which is referenced by an NdbTransaction object typically created using Ndb::startTransaction(). At this point, the transaction is merely being defined; it is not yet sent to the NDB kernel.
- 2. Define operations and add them to the transaction, using one or more of the following, along with the appropriate methods of the respectiveNdbOperation class (or possibly one or more of its subclasses):
 - NdbTransaction::getNdbOperation()
 - NdbTransaction::getNdbScanOperation()
 - NdbTransaction::getNdbIndexOperation()
 - NdbTransaction::getNdbIndexScanOperation()

At this point, the transaction has still not yet been sent to the NDB kernel.

- 3. Execute the transaction, using the NdbTransaction::execute() method.
- 4. Close the transaction by calling Ndb::closeTransaction().

For an example of this process, see Section 2.5.1, "NDB API Example Using Synchronous Transactions".

To execute several synchronous transactions in parallel, you can either use multiple Ndb objects in several threads, or start multiple application programs.

1.4.2.3 Operations

An NdbTransaction consists of a list of operations, each of which is represented by an instance of NdbOperation, NdbScanOperation, NdbIndexOperation, or NdbIndexScanOperation (that is, of NdbOperation or one of its child classes).

See NDB Access Types, for general information about NDB Cluster access operation types.

NDB Access Types

The data node process has a number of simple constructs which are used to access the data in an NDB Cluster. We have created a very simple benchmark to check the performance of each of these.

There are four access methods:

- **Primary key access.** This is access of a record through its primary key. In the simplest case, only one record is accessed at a time, which means that the full cost of setting up a number of TCP/IP messages and a number of costs for context switching are borne by this single request. In the case where multiple primary key accesses are sent in one batch, those accesses share the cost of setting up the necessary TCP/IP messages and context switches. If the TCP/IP messages are for different destinations, additional TCP/IP messages need to be set up.
- **Unique key access.** Unique key accesses are similar to primary key accesses, except that a unique key access is executed as a read on an index table followed by a primary key access on the table. However, only one request is sent from the MySQL Server, and the read of the index table is handled by the data node. Such requests also benefit from batching.
- Full table scan. When no indexes exist for a lookup on a table, a full table scan is performed. This is sent as a single request to the ndbd process, which then divides the table scan into a set of parallel scans on all NDB data node processes.
- Range scan using ordered index. When an ordered index is used, it performs a scan in the same manner as the full table scan, except that it scans only those records which are in the range used by the query transmitted by the MySQL server (SQL node). All partitions are scanned in parallel when all bound index attributes include all attributes in the partitioning key.

Single-row operations

After the operation is created using NdbTransaction::getNdbOperation() or NdbTransaction::getNdbIndexOperation(), it is defined in the following three steps:

- Specify the standard operation type using NdbOperation::readTuple().
- 2. Specify search conditions using NdbOperation::equal().
- 3. Specify attribute actions using NdbOperation::getValue().

Here are two brief examples illustrating this process. For the sake of brevity, we omit error handling.

This first example uses an NdbOperation:

```
// 1. Retrieve table object
myTable= myDict->getTable("MYTABLENAME");

// 2. Create an NdbOperation on this table
myOperation= myTransaction->getNdbOperation(myTable);

// 3. Define the operation's type and lock mode
myOperation->readTuple(NdbOperation::LM_Read);

// 4. Specify search conditions
myOperation->equal("ATTR1", i);

// 5. Perform attribute retrieval
myRecAttr= myOperation->getValue("ATTR2", NULL);
```

For additional examples of this sort, see Section 2.5.1, "NDB API Example Using Synchronous Transactions".

The second example uses an NdbIndexOperation:

```
// 1. Retrieve index object
myIndex= myDict->getIndex("MYINDEX", "MYTABLENAME");

// 2. Create
myOperation= myTransaction->getNdbIndexOperation(myIndex);

// 3. Define type of operation and lock mode
myOperation->readTuple(NdbOperation::LM_Read);

// 4. Specify Search Conditions
myOperation->equal("ATTR1", i);

// 5. Attribute Actions
myRecAttr = myOperation->getValue("ATTR2", NULL);
```

Another example of this second type can be found in Section 2.5.5, "NDB API Example: Using Secondary Indexes in Scans".

We now discuss in somewhat greater detail each step involved in the creation and use of synchronous transactions.

- 1. **Define single row operation type.** The following operation types are supported:
 - NdbOperation::insertTuple():Inserts a nonexisting tuple.
 - NdbOperation::writeTuple(): Updates a tuple if one exists, otherwise inserts a new tuple.
 - NdbOperation::updateTuple(): Updates an existing tuple.
 - NdbOperation::deleteTuple(): Deletes an existing tuple.
 - NdbOperation::readTuple(): Reads an existing tuple using the specified lock mode.

All of these operations operate on the unique tuple key. When NdbIndexOperation is used, then each of these operations operates on a defined unique hash index.



Note

If you want to define multiple operations within the same transaction, then you need to call NdbTransaction::getNdbOperation() or NdbTransaction::getNdbIndexOperation() for each operation.

- 2. **Specify Search Conditions.** The search condition is used to select tuples. Search conditions are set using NdbOperation::equal().
- 3. **Specify Attribute Actions.** Next, it is necessary to determine which attributes should be read or updated. It is important to remember that:
 - Deletes can neither read nor set values, but only delete them.
 - Reads can only read values.
 - Updates can only set values. Normally the attribute is identified by name, but it is also possible to use the attribute's identity to determine the attribute.

NdbOperation::getValue() returns an NdbRecAttr object containing the value as read. To obtain the actual value, one of two methods can be used; the application can either

- Use its own memory (passed through a pointer aValue) to NdbOperation::getValue(), or
- receive the attribute value in an NdbRecAttr object allocated by the NDB API.

The NdbRecAttr object is released when Ndb::closeTransaction() is called. For this reason, the application cannot reference this object following any subsequent call to Ndb::closeTransaction(). Attempting to read data from an NdbRecAttr object before calling NdbTransaction::execute() yields an undefined result.

Scan Operations

Scans are roughly the equivalent of SQL cursors, providing a means to perform high-speed row processing. A scan can be performed on either a table (using an NdbScanOperation) or an ordered index (by means of an NdbIndexScanOperation).

Scan operations have the following characteristics:

- They can perform read operations which may be shared, exclusive, or dirty.
- They can potentially work with multiple rows.
- They can be used to update or delete multiple rows.
- They can operate on several nodes in parallel.

After the operation is created using NdbTransaction::getNdbScanOperation() or NdbTransaction::getNdbIndexScanOperation(), it is carried out as follows:

Define the standard operation type, using NdbScanOperation::readTuples().



Note

See NdbScanOperation::readTuples(), for additional information about deadlocks which may occur when performing simultaneous, identical scans with exclusive locks

- 2. Specify search conditions, using NdbScanFilter, NdbIndexScanOperation::setBound(), or both.
- 3. Specify attribute actions using NdbOperation::getValue().
- 4. Execute the transaction using NdbTransaction::execute().
- 5. Traverse the result set by means of successive calls to NdbScanOperation::nextResult().

Here are two brief examples illustrating this process. Once again, in order to keep things relatively short and simple, we forego any error handling.

This first example performs a table scan using an NdbScanOperation:

```
// 1. Retrieve a table object
myTable= myDict->getTable("MYTABLENAME");

// 2. Create a scan operation (NdbScanOperation) on this table
myOperation= myTransaction->getNdbScanOperation(myTable);

// 3. Define the operation's type and lock mode
myOperation->readTuples(NdbOperation::LM_Read);
```

```
// 4. Specify search conditions
NdbScanFilter sf(myOperation);
sf.begin(NdbScanFilter::OR);
sf.eq(0, i);  // Return rows with column 0 equal to i or
sf.eq(1, i+1); // column 1 equal to (i+1)
sf.end();
// 5. Retrieve attributes
myRecAttr= myOperation->getValue("ATTR2", NULL);
```

The second example uses an NdbIndexScanOperation to perform an index scan:

```
// 1. Retrieve index object
myIndex= myDict->getIndex("MYORDEREDINDEX", "MYTABLENAME");

// 2. Create an operation (NdbIndexScanOperation object)
myOperation= myTransaction->getNdbIndexScanOperation(myIndex);

// 3. Define type of operation and lock mode
myOperation->readTuples(NdbOperation::LM_Read);

// 4. Specify search conditions
// All rows with ATTR1 between i and (i+1)
myOperation->setBound("ATTR1", NdbIndexScanOperation::BoundGE, i);
myOperation->setBound("ATTR1", NdbIndexScanOperation::BoundLE, i+1);

// 5. Retrieve attributes
myRecAttr = MyOperation->getValue("ATTR2", NULL);
```

Some additional discussion of each step required to perform a scan follows:

Define Scan Operation Type. It is important to remember that only a single operation is supported for each scan operation (NdbScanOperation::readTuples()) or NdbIndexScanOperation::readTuples()).



Note

If you want to define multiple scan operations within the same transaction, then you need to call NdbTransaction::getNdbScanOperation() or NdbTransaction::getNdbIndexScanOperation() separately for each operation.

2. **Specify Search Conditions.** The search condition is used to select tuples. If no search condition is specified, the scan will return all rows in the table. The search condition can be an NdbScanFilter (which can be used on both NdbScanOperation and NdbIndexScanOperation) or bounds (which can be used only on index scans - see NdbIndexScanOperation::setBound()). An index scan can use both NdbScanFilter and bounds.



Note

When NdbScanFilter is used, each row is examined, whether or not it is actually returned. However, when using bounds, only rows within the bounds will be examined.

3. **Specify Attribute Actions.** Next, it is necessary to define which attributes should be read. As with transaction attributes, scan attributes are defined by name, but it is also possible to use the attributes' identities to define attributes as well. As discussed elsewhere in this document (see Section 1.4.2.2, "Synchronous Transactions"), the value read is returned by the NdbOperation: :getValue() method as an NdbRecAttr object.

Using Scans to Update or Delete Rows

Scanning can also be used to update or delete rows. This is performed as follows:

- 1. Scanning with exclusive locks using NdbOperation::LM_Exclusive.
- 2. (When iterating through the result set.) For each row, optionally calling either NdbScanOperation::updateCurrentTuple() or NdbScanOperation::deleteCurrentTuple().
- 3. (If performing NdbScanOperation::updateCurrentTuple():) Setting new values for records simply by using NdbOperation::setValue().NdbOperation::equal() should not be called in such cases, as the primary key is retrieved from the scan.



Important

The update or delete is not actually performed until the next call to NdbTransaction::execute() is made, just as with single row operations. NdbTransaction::execute() also must be called before any locks are released; for more information, see Lock Handling with Scans.

Features Specific to Index Scans. When performing an index scan, it is possible to scan only a subset of a table using NdbIndexScanOperation::setBound(). In addition, result sets can be sorted in either ascending or descending order, using NdbIndexScanOperation::readTuples(). Note that rows are returned unordered by default unless *sorted* is set to true.

It is also important to note that, when using NdbIndexScanOperation::BoundEQ (see NdbIndexScanOperation::BoundType) with a partition key, only fragments containing rows will actually be scanned. Finally, when performing a sorted scan, any value passed as the NdbIndexScanOperation::readTuples() method's parallel argument will be ignored and maximum parallelism will be used instead. In other words, all fragments which it is possible to scan are scanned simultaneously and in parallel in such cases.

Lock Handling with Scans

Performing scans on either a table or an index has the potential to return a great many records; however, Ndb locks only a predetermined number of rows per fragment at a time. The number of rows locked per fragment is controlled by the batch parameter passed to NdbScanOperation::readTuples().

In order to enable the application to handle how locks are released,

NdbScanOperation::nextResult() has a Boolean parameter fetchAllowed. If NdbScanOperation::nextResult() is called with fetchAllowed equal to false, then no locks may be released as result of the function call. Otherwise the locks for the current batch may be released.

This next example shows a scan delete that handles locks in an efficient manner. For the sake of brevity, we omit error-handling.

```
int check;

// Outer loop for each batch of rows
while((check = MyScanOperation->nextResult(true)) == 0)
{
    do
    {
        // Inner loop for each row within the batch
        MyScanOperation->deleteCurrentTuple();
    }
    while((check = MyScanOperation->nextResult(false)) == 0);

    // When there are no more rows in the batch, execute all defined deletes
    MyTransaction->execute(NoCommit);
}
```

For a more complete example of a scan, see Section 2.5.4, "NDB API Basic Scanning Example".

Error Handling

Errors can occur either when operations making up a transaction are being defined, or when the transaction is actually being executed. Catching and handling either sort of error requires testing the value returned by NdbTransaction::execute(), and then, if an error is indicated (that is, if this value is equal to -1), using the following two methods in order to identify the error's type and location:

- NdbTransaction::getNdbErrorOperation() returns a reference to the operation causing the most recent error.
- NdbTransaction::getNdbErrorLine() yields the method number of the erroneous method in the operation, starting with 1.

This short example illustrates how to detect an error and to use these two methods to identify it:

```
theTransaction = theNdb->startTransaction();
theOperation = theTransaction->getNdbOperation("TEST_TABLE");
if(theOperation == NULL)
   goto error;

theOperation->readTuple(NdbOperation::LM_Read);
theOperation->setValue("ATTR_1", at1);
theOperation->setValue("ATTR_2", at1); // Error occurs here
theOperation->setValue("ATTR_3", at1);
theOperation->setValue("ATTR_4", at1);

if(theTransaction->execute(Commit) == -1)
{
   errorLine = theTransaction->getNdbErrorLine();
   errorOperation = theTransaction->getNdbErrorOperation();
}
```

Here, errorLine is 3, as the error occurred in the third method called on the NdbOperation object (in this case, theOperation). If the result of NdbTransaction::getNdbErrorLine() is 0, then the error occurred when the operations were executed. In this example, errorOperation is a pointer to the object theOperation. The NdbTransaction::getNdbError() method returns an NdbError object providing information about the error.



Note

Transactions are *not* automatically closed when an error occurs. You must call Ndb::closeTransaction() or NdbTransaction::close() to close the transaction.

See Ndb::closeTransaction(), and NdbTransaction::close().

One recommended way to handle a transaction failure (that is, when an error is reported) is as shown here:

1. Roll back the transaction by calling NdbTransaction::execute() with a special ExecType value for the type parameter.

See NdbTransaction::execute() and NdbTransaction::ExecType, for more information about how this is done.

- 2. Close the transaction by calling NdbTransaction::close().
- 3. If the error was temporary, attempt to restart the transaction.

Several errors can occur when a transaction contains multiple operations which are simultaneously executed. In this case the application must go through all operations and query each of their NdbError objects to find out what really happened.



Important

Errors can occur even when a commit is reported as successful. In order to handle such situations, the NDB API provides an additional NdbTransaction::commitStatus() method to check the transaction's commit status.

See NdbTransaction::commitStatus().

1.4.3 Review of NDB Cluster Concepts

This section covers the NDB Kernel, and discusses NDB Cluster transaction handling and transaction coordinators. It also describes NDB record structures and concurrency issues.

The *NDB Kernel* is the collection of data nodes belonging to an NDB Cluster. The application programmer can for most purposes view the set of all storage nodes as a single entity. Each data node is made up of three main components:

- TC: The transaction coordinator.
- ACC: The index storage component.
- TUP: The data storage component.

When an application executes a transaction, it connects to one transaction coordinator on one data node. Usually, the programmer does not need to specify which TC should be used, but in some cases where performance is important, the programmer can provide "hints" to use a certain TC. (If the node with the desired transaction coordinator is down, then another TC will automatically take its place.)

Each data node has an ACC and a TUP which store the indexes and data portions of the database table fragment. Even though a single TC is responsible for the transaction, several ACCs and TUPs on other data nodes might be involved in that transaction's execution.

1.4.3.1 Selecting a Transaction Coordinator

The default method is to select the transaction coordinator (TC) determined to be the "nearest" data node, using a heuristic for proximity based on the type of transporter connection. In order of nearest to most distant, these are:

- 1. SHM
- 2. TCP/IP (localhost)
- 3. TCP/IP (remote host)

If there are several connections available with the same proximity, one is selected for each transaction in a round-robin fashion. Optionally, you may set the method for TC selection to round-robin mode, where each new set of transactions is placed on the next data node. The pool of connections from which this selection is made consists of all available connections.

As noted in Section 1.4.3, "Review of NDB Cluster Concepts", the application programmer can provide hints to the NDB API as to which transaction coordinator should be uses. This is done by providing a table and a partition key (usually the primary key). If the primary key is the partition key, then the transaction is

placed on the node where the primary fragment replica of that record resides. Note that this is only a hint; the system can be reconfigured at any time, in which case the NDB API chooses a transaction coordinator without using the hint. For more information, see Column::getPartitionKey(), and Ndb::startTransaction().

The application programmer can specify the partition key from SQL by using the following construct:

```
CREATE TABLE ... ENGINE=NDB PARTITION BY KEY (attribute_list);
```

For additional information, see Partitioning, and in particular KEY Partitioning, in the MySQL Manual.

1.4.3.2 NDB Record Structure

The NDB storage engine used by NDB Cluster is a relational database engine storing records in tables as with other relational database systems. Table rows represent records as tuples of relational data. When a new table is created, its attribute schema is specified for the table as a whole, and thus each table row has the same structure. Again, this is typical of relational databases, and NDB is no different in this regard.

Primary Keys. Each record has from 1 up to 32 attributes which belong to the primary key of the table.

Transactions. Transactions are committed first to main memory, and then to disk, after a global checkpoint (GCP) is issued. Since all data are (in most NDB Cluster configurations) synchronously replicated and stored on multiple data nodes, the system can handle processor failures without loss of data. However, in the case of a system-wide failure, all transactions (committed or not) occurring since the most recent GCP are lost.

Concurrency Control.

NDB uses *pessimistic concurrency control* based on locking. If a requested lock (implicit and depending on database operation) cannot be attained within a specified time, then a timeout error results.

Concurrent transactions as requested by parallel application programs and thread-based applications can sometimes deadlock when they try to access the same information simultaneously. Thus, applications need to be written in a manner such that timeout errors occurring due to such deadlocks are handled gracefully. This generally means that the transaction encountering a timeout should be rolled back and restarted.

Hints and Performance.

Placing the transaction coordinator in close proximity to the actual data used in the transaction can in many cases improve performance significantly. This is particularly true for systems using TCP/IP. For example, a Solaris system using a single 500 MHz processor has a cost model for TCP/IP communication which can be represented by the formula

```
[30 microseconds] + ([100 nanoseconds] * [number of bytes])
```

This means that if we can ensure that we use "popular" links we increase buffering and thus drastically reduce the costs of communication.

A simple example would be an application that uses many simple updates where a transaction needs to update one record. This record has a 32-bit primary key which also serves as the partitioning key. Then the keyData is used as the address of the integer of the primary key and keyLen is 4.

1.4.4 The Adaptive Send Algorithm

Discusses the mechanics of transaction handling and transmission in NDB Cluster and the NDB API, and the objects used to implement these.

When transactions are sent using NdbTransaction::execute(), they are not immediately transferred to the NDB Kernel. Instead, transactions are kept in a special send list (buffer) in the Ndb object to which

they belong. The adaptive send algorithm decides when transactions should actually be transferred to the NDB kernel.

The NDB API is designed as a multithreaded interface, and so it is often desirable to transfer database operations from more than one thread at a time. The NDB API keeps track of which Ndb objects are active in transferring information to the NDB kernel and the expected number of threads to interact with the NDB kernel. Note that a given instance of Ndb should be used in at most one thread; different threads should not share the same Ndb object.

There are four conditions leading to the transfer of database operations from Ndb object buffers to the NDB kernel:

- 1. The NDB Transporter (TCP/IP or shared memory) decides that a buffer is full and sends it off. The buffer size is implementation-dependent and may change between NDB Cluster releases. When TCP/IP is the transporter, the buffer size is usually around 64 KB. Since each Ndb object provides a single buffer per data node, the notion of a "full" buffer is local to each data node.
- 2. The accumulation of statistical data on transferred information may force sending of buffers to all storage nodes (that is, when all the buffers become full).
- 3. Every 10 milliseconds, a special transmission thread checks whether or not any send activity has occurred. If not, then the thread will force transmission to all nodes. This means that 20 ms is the maximum amount of time that database operations are kept waiting before being dispatched. A 10-millisecond limit is likely in future releases of NDB Cluster; checks more frequent than this require additional support from the operating system.
- 4. For methods that are affected by the adaptive send algorithm (such as NdbTransaction::execute()), there is a force parameter that overrides its default behavior in this regard and forces immediate transmission to all nodes. See the individual NDB API class listings for more information.

The conditions listed above are subject to change in future releases of NDB Cluster.

1.5 Application-level partitioning

There is no restriction against instantiating multiple Ndb_cluster_connection objects representing connections to different management servers in a single application, nor against using these for creating multiple instances of the Ndb class. Such Ndb_cluster_connection objects (and the Ndb instances based on them) are not required even to connect to the same cluster.

For example, it is entirely possible to perform application-level partitioning of data in such a manner that data meeting one set of criteria are "handed off" to one cluster using an Ndb object that makes use of an Ndb_cluster_connection object representing a connection to that cluster, while data not meeting those criteria (or perhaps a different set of criteria) can be sent to a different cluster through a different instance of Ndb that makes use of an Ndb_cluster_connection "pointing" to the second cluster.

It is possible to extend this scenario to develop a single application that accesses an arbitrary number of clusters. However, in doing so, the following conditions and requirements must be kept in mind:

- A cluster management server (ndb_mgmd) can connect to one and only one cluster without being restarted and reconfigured, as it must read the data telling it which data nodes make up the cluster from a configuration file (config.ini).
- An Ndb_cluster_connection object "belongs" to a single management server whose host name or IP address is used in instantiating this object (passed as the *connection_string* argument to

its constructor); once the object is created, it cannot be used to initiate a connection to a different management server.

(See Ndb_cluster_connection Class Constructor.)

An Ndb object making use of this connection (Ndb_cluster_connection) cannot be re-used to
connect to a different cluster management server (and thus to a different collection of data nodes making
up a cluster). Any given instance of Ndb is bound to a specific Ndb_cluster_connection when
created, and that Ndb_cluster_connection is in turn bound to a single and unique management
server when it is instantiated.

(See Ndb Class Constructor.)

• The bindings previously described persist for the lifetimes of the Ndb and Ndb_cluster_connection objects in question.

Therefore, it is imperative in designing and implementing any application that accesses multiple clusters in a single session, that a separate set of Ndb_cluster_connection and Ndb objects be instantiated for connecting to each cluster management server, and that no confusion arises as to which of these is used to access which NDB Cluster.

It is also important to keep in mind that no direct "sharing" of data or data nodes between different clusters is possible. A data node can belong to one and only one cluster, and any movement of data between clusters must be accomplished on the application level.

For examples demonstrating how connections to two different clusters can be made and used in a single application, see Section 2.5.2, "NDB API Example Using Synchronous Transactions and Multiple Clusters", and Section 3.6.2, "MGM API Event Handling with Multiple Clusters".

1.6 Using NdbInterpretedCode

The next few sections provide information about performing different types of operations with NdbInterpretedCode methods, including resource usage.

- NdbInterpretedCode Methods for Loading Values into Registers
- NdbInterpretedCode Methods for Copying Values Between Registers and Table Columns
- NdbInterpretedCode Register Arithmetic Methods
- NdbInterpretedCode: Labels and Branching
- Register-Based NdbInterpretedCode Branch Operations
- Column-Based NdbInterpretedCode Branch Operations
- Pattern-Based NdbInterpretedCode Branch Operations
- NdbInterpretedCode Bitwise Comparison Operations
- NdbInterpretedCode Result Handling Methods
- NdbInterpretedCode Convenience Methods
- Using Subroutines with NdbInterpretedCode
- NdbInterpretedCode Utility Methods

NdbInterpretedCode Methods for Loading Values into Registers

The methods described in this section are used to load constant values into NdbInterpretedCode program registers. The space required by each of these methods is shown in the following table:

Table 1.1 NdbInterpretedCode methods used to load constant values into NdbInterpretedCode program registers, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
load_const_null()	1	1
load_const_u16()	1	1
load_const_u32()	2	2
load_const_u64()	3	3

NdbInterpretedCode Methods for Copying Values Between Registers and Table Columns

NdbInterpretedCode provides two methods for copying values between a column in the current table row and a program register. The read_attr() method is used to copy a table column value into a program register; write_attr() is used to copy a value from a program register into a table column. Both of these methods require that the table being operated on was specified when creating the NdbInterpretedCode object for which they are called.

The space required by each of these methods is shown in the following table:

Table 1.2 NdbInterpretedCode methods used to copy values between registers and table columns, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
read_attr()	1	1
write_attr()	1	1

For more information, see NdbInterpretedCode::read_attr(), and NdbInterpretedCode::write_attr().

NdbInterpretedCode Register Arithmetic Methods

NdbInterpretedCode provides two methods for performing arithmetic operations on registers. Using add_reg(), you can load the sum of two registers into another register; sub_reg() lets you load the difference of two registers into another register.

The space required by each of these methods is shown in the following table:

Table 1.3 NdbInterpretedCode methods used to perform arithmetic operations on registers, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
add_reg()	1	1
sub_reg()	1	1

For mroe information, see NdbInterpretedCode::add_reg(), and NdbInterpretedCode::sub_reg().

NdbInterpretedCode: Labels and Branching

The NdbInterpretedCode class lets you define labels within interpreted programs and provides a number of methods for performing jumps to these labels based on any of the following types of conditions:

- · Comparison between two register values
- Comparison between a column value and a given constant
- Whether or not a column value matches a given pattern

To define a label, use the def_label() method.

To perform an unconditional jump to a label, use the branch_label() method.

To perform a jump to a given label based on a comparison of register values, use one of the branch_*() methods (branch_ge(), branch_gt(), branch_le(), branch_lt(), branch_eq(), branch_ne(), branch_ne_null(), or branch_eq_null()). See Register-Based NdbInterpretedCode Branch Operations.

To perform a jump to a given label based on a comparison of table column values, use one of the branch_col_*() methods (branch_col_ge(), branch_col_gt(), branch_col_le(), branch_col_le(), branch_col_ne(), branch_col_ne(), branch_col_ne_null(), or branch_col_eq_null()). See Column-Based NdbInterpretedCode Branch Operations.

To perform a jump based on pattern-matching of a table column value, use one of the methods branch_col_like() or branch_col_notlike(). See Pattern-Based NdbInterpretedCode Branch Operations.

Register-Based NdbInterpretedCode Branch Operations

Most of these are used to branch based on the results of register-to-register comparisons. There are also two methods used to compare a register value with NULL. All of these methods require as a parameter a label defined using the def_label() method.

These methods can be thought of as performing the following logic:

```
if(register_value1 condition register_value2)
  goto Label
```

The space required by each of these methods is shown in the following table:

Table 1.4 Register-based NdbInterpretedCode branch methods, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
branch_ge()	1	1
branch_gt()	1	1
branch_le()	1	1
branch_lt()	1	1
branch_eq()	1	1
branch_ne()	1	1

Method	, ,	Request message (words)
branch_ne_null()	1	1
branch_eq_null()	1	1

Column-Based NdbInterpretedCode Branch Operations

The methods described in this section are used to perform branching based on a comparison between a table column value and a given constant value. Each of these methods expects the attribute ID of the column whose value is to be tested rather than a reference to a Column object.

These methods, with the exception of branch_col_eq_null() and branch_col_ne_null(), can be thought of as performing the following logic:

```
if(constant_value condition column_value)
  goto Label
```

In each case (once again excepting $branch_col_eq_null()$ and $branch_col_ne_null()$), the arbitrary constant is the first parameter passed to the method.

The space requirements for each of these methods is shown in the following table, where L represents the length of the constant value:

Table 1.5 Column-based NdbInterpretedCode branch methods, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
branch_col_eq_null()	2	2
branch_col_ne_null()	2	2
branch_col_eq()	2	2 + CEIL(L / 8)
branch_col_ne()	2	2 + CEIL(L / 8)
branch_col_lt()	2	2 + CEIL(L / 8)
branch_col_le()	2	2 + CEIL(L / 8)
branch_col_gt()	2	2 + CEIL(L / 8)
branch_col_ge()	2	2 + CEIL(L / 8)



Note

The expression $\mathtt{CEIL}(L\ /\ 8)$ is the number of whole 8-byte words required to hold the constant value to be compared.

Pattern-Based NdbInterpretedCode Branch Operations

The NdbInterpretedCode class provides two methods which can be used to branch based on a comparison between a column containing character data (that is, a CHAR, VARCHAR, BINARY, or VARBINARY column) and a regular expression pattern.

The pattern syntax supported by the regular expression is the same as that supported by the MySQL Server's LIKE and NOT LIKE operators, including the _ and % metacharacters. For more information about these, see String Comparison Functions and Operators.



Note

This is the same regular expression pattern syntax that is supported by NdbScanFilter; see NdbScanFilter::cmp(), for more information.

The table being operated upon must be supplied when the NdbInterpretedCode object is instantiated. The regular expression pattern should be in plain CHAR format, even if the column is actually a VARCHAR (in other words, there should be no leading length bytes).

These functions behave as shown here:

```
if (column_value [NOT] LIKE pattern)
goto Label;
```

The space requirements for these methods are shown in the following table, where L represents the length of the constant value:

Table 1.6 Pattern-based NdbInterpretedCode branch methods, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
branch_col_like()	2	2 + CEIL(L / 8)
branch_col_notlike()	2	2 + CEIL(L / 8)



Note

The expression $\mathtt{CEIL}(L\ /\ 8)$ is the number of whole 8-byte words required to hold the constant value to be compared.

NdbInterpretedCode Bitwise Comparison Operations

These instructions are used to branch based on the result of a logical AND comparison between a BIT column value and a bitmask pattern.

Use of these methods requires that the table being operated upon was supplied when the NdbInterpretedCode object was constructed. The mask value should be the same size as the bit column being compared. BIT values are passed into and out of the NDB API as 32-bit words with bits set in order from the least significant bit to the most significant bit. The endianness of the platform on which the instructions are executed controls which byte contains the least significant bits. On x86, this is the first byte (byte 0); on SPARC and PPC, it is the last byte.

The buffer length and the request length for each of the methods listed here each requires an amount of space equal to 2 words plus the column width rounded (up) to the nearest whole word:

- branch col and mask eq mask()
- branch_col_and_mask_ne_mask()
- branch_col_and_mask_eq_zero()
- branch_col_and_mask_ne_zero()

NdbInterpretedCode Result Handling Methods

The methods described in this section are used to tell the interpreter that processing of the current row is complete, and—in the case of scans—whether or not to include this row in the results of the scan.

The space requirements for these methods are shown in the following table, where L represents the length of the constant value:

Table 1.7 NdbInterpretedCode result handling methods, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
<pre>interpret_exit_ok()</pre>	1	1
<pre>interpret_exit_nok()</pre>	1	1
<pre>interpret_exit_last_row()</pre>	1	1

NdbInterpretedCode Convenience Methods

The methods described in this section can be used to insert multiple instructions (using specific registers) into an interpreted program.



Important

In addition to updating the table column, these methods use interpreter registers 6 and 7, replacing any existing contents of register 6 with the original column value and any existing contents of register 7 with the modified column value. The table itself must be previously defined when instantiating the NdbInterpretedCode object for which the method is invoked.

The space requirements for these methods are shown in the following table, where L represents the length of the constant value:

Table 1.8 NdbInterpretedCode convenience methods, with required buffer and request message space.

Method	Buffer (words)	Request message (words)
add_val()	4	1; if the supplied value >= 2^{16} : 2; if >= 2^{32} : 3
sub_val()	4	1; if the supplied value >= 2^{16} : 2; if >= 2^{32} : 3

Using Subroutines with NdbInterpretedCode

NdbInterpretedCode supports subroutines which can be invoked from within interpreted programs, with each subroutine being identified by a unique number. Subroutines can be defined only following all main program instructions.



Important

Numbers used to identify subroutines must be contiguous; however, they do not have to be in any particular order.

- The beginning of a subroutine is indicated by invoking the def_sub() method;
- ret_sub() terminates the subroutine; all instructions following the call to def_sub() belong to the subroutine until it is terminated using this method.

• A subroutine is called using the call_sub() method.

Once the subroutine has completed, the program resumes execution with the instruction immediately following the one which invoked the subroutine. Subroutines can also be invoked from other subroutines; currently, the maximum subroutine stack depth is 32.

NdbInterpretedCode Utility Methods

Some additional utility methods supplied by NdbInterpretedCode are listed here:

- copy(): Copies an existing interpreted program by performing a deep copy on the associated NdbInterpretedCode object.
- finalise(): Prepares an interpreted program by resolving all branching instructions and subroutine calls.
- getTable(): Get a reference to the table for which the NdbInterpretedCode object was defined.
- getNdbError(): Get the most recent error associated with this NdbInterpretedCode object.
- getWordsUsed(): Obtain the number of words used from the buffer.

Chapter 2 The NDB API

Table of Contents

2.1 Getting Started with the NDB API	
2.1.1 Compiling and Linking NDB API Programs	
2.1.2 Connecting to the Cluster	
2.1.3 Mapping MySQL Database Object Names and Types to NDB	
2.2 The NDB API Class Hierarachy	33
2.3 NDB API Classes, Interfaces, and Structures	34
2.3.1 The Column Class	34
2.3.2 The Datafile Class	51
2.3.3 The Dictionary Class	56
2.3.4 The Element Structure	74
2.3.5 The Event Class	75
2.3.6 The ForeignKey Class	
2.3.7 The HashMap Class	
2.3.8 The Index Class	
2.3.9 The LogfileGroup Class	
2.3.10 The List Class	
2.3.11 The Ndb Class	
2.3.12 The Ndb class	
2.3.13 The NdbBlob Class	
2.3.14 The NdbDictionary Class	
2.3.15 The NdbError Structure	
2.3.16 The NdbEventOperation Class	
2.3.17 The NdbIndexOperation Class	
2.3.18 The NdbIndexScanOperation Class	
2.3.19 The NdbInterpretedCode Class	
2.3.20 The NdbOperation Class	
2.3.21 The NdbRecAttr Class	
2.3.22 The NdbRecord Interface	
2.3.23 The NdbScanFilter Class	
2.3.24 The NdbScanOperation Class	
2.3.25 The NdbTransaction Class	
2.3.26 The Object Class	
2.3.27 The Table Class	279
2.3.28 The Tablespace Class	304
2.3.29 The Undofile Class	309
2.4 NDB API Errors and Error Handling	314
2.4.1 Handling NDB API Errors	314
2.4.2 NDB Error Codes: by Type	318
2.4.3 NDB Error Codes: Single Listing	
2.4.4 NDB Error Classifications	
2.5 NDB API Examples	
2.5.1 NDB API Example Using Synchronous Transactions	
2.5.2 NDB API Example Using Synchronous Transactions and Multiple Clusters	
2.5.3 NDB API Example: Handling Errors and Retrying Transactions	
2.5.4 NDB API Basic Scanning Example	
2.5.5 NDB API Example: Using Secondary Indexes in Scans	
2.5.6 NDB API Example: Using NdbRecord with Hash Indexes	
2.5.7 NDB API Example Comparing RecAttr and NdbRecord	
	000

2.5.8 NDB API Event Handling Example	554
2.5.9 NDB API Example: Basic BLOB Handling	
2.5.10 NDB API Example: Handling BLOB Columns and Values Using NdbRecord	566
2.5.11 NDB API Simple Array Example	575
2.5.12 NDB API Simple Array Example Using Adapter	581
2.5.13 Timestamp2 Example	587
2.5.14 Common Files for NDB API Array Examples	591

This chapter contains information about the NDB API, which is used to write applications that access data in the NDB storage engine.

2.1 Getting Started with the NDB API

This section discusses preparations necessary for writing and compiling an NDB API application.

2.1.1 Compiling and Linking NDB API Programs

This section provides information on compiling and linking NDB API applications, including requirements and compiler and linker options.

2.1.1.1 General Requirements

To use the NDB API with MySQL, you must have the libndbclient client library and its associated header files installed alongside the regular MySQL client libraries and headers under <code>install_dir/lib</code>. These are automatically installed when you build MySQL using <code>-DWITH_NDBCLUSTER=ON</code> or use a MySQL binary package that supports the NDB storage engine.

This Guide is targeted for use with MySQL NDB Cluster 7.3 and later.

2.1.1.2 Compiler Options

Header Files. In order to compile source files that use the NDB API, you must ensure that the necessary header files can be found. Header files specific to the NDB and MGM APIs are installed in the following subdirectories of the MySQL include directory, respectively:

- include/mysql/storage/ndb/ndbapi
- include/mysql/storage/ndb/mgmapi

Compiler Flags. The MySQL-specific compiler flags needed can be determined using the mysql_config utility that is part of the MySQL installation:

```
$ mysql_config --cflags
-I/usr/local/mysql/include/mysql -Wreturn-type -Wtrigraphs -W -Wformat
-Wsign-compare -Wunused -mcpu=pentium4 -march=pentium4
```

This sets the include path for the MySQL header files but not for those specific to the NDB API. The --include option to mysql_config returns the generic include path switch:

```
shell> mysql_config --include -- i/usr/local/mysql/include/mysql
```

It is necessary to add the subdirectory paths explicitly, so that adding all the needed compile flags to the CXXFLAGS shell variable should look something like this:

```
CFLAGS="$CFLAGS "`mysql_config --cflags`
CFLAGS="$CFLAGS "`mysql_config --include`/storage/ndb
CFLAGS="$CFLAGS "`mysql_config --include`/storage/ndb/ndbapi
CFLAGS="$CFLAGS "`mysql_config --include`/storage/ndb/mgmapi
```



Tip

If you do not intend to use the NDB Cluster management functions, the last line in the previous example can be omitted. However, if you are interested in the management functions only, and do not want or need to access NDB Cluster data except from MySQL, then you can omit the line referencing the ndbapi directory.

2.1.1.3 Linker Options

NDB API applications must be linked against both the MySQL and NDB client libraries. The NDB client library also requires some functions from the mystrings library, so this must be linked in as well.

The necessary linker flags for the MySQL client library are returned by $mysql_config --libs$. For multithreaded applications you should use the $--libs_r$ instead:

```
$ mysql_config --libs_r
-L/usr/local/mysql-5.1/lib/mysql -lmysqlclient_r -lz -lpthread -lcrypt
-lnsl -lm -lpthread -L/usr/lib -lssl -lcrypto
```

It is now necessary only to add -lndbclient to LD_FLAGS, as shown here:

```
LDFLAGS="$LDFLAGS "`mysql_config --libs_r`
LDFLAGS="$LDFLAGS -lndbclient"
```

2.1.1.4 Using Autotools

It is often faster and simpler to use GNU autotools than to write your own makefiles. In this section, we provide an autoconf macro WITH_MYSQL that can be used to add a --with-mysql option to a configure file, and that automatically sets the correct compiler and linker flags for given MySQL installation.

All of the examples in this chapter include a common <code>mysql.m4</code> file defining <code>WITH_MYSQL</code>. A typical complete example consists of the actual source file and the following helper files:

- acinclude
- configure.in
- Makefile.m4

automake also requires that you provide README, NEWS, AUTHORS, and ChangeLog files; however, these can be left empty.

To create all necessary build files, run the following:

```
aclocal
autoconf
automake -a -c
configure --with-mysql=/mysql/prefix/path
```

Normally, this needs to be done only once, after which make will accommodate any file changes.

Example 1-1: acinclude.m4.

```
m4_include([../mysql.m4])
```

Example 1-2: configure.in.

```
AC_INIT(example, 1.0)
AM_INIT_AUTOMAKE(example, 1.0)
WITH_MYSQL()
AC_OUTPUT(Makefile)
```

Example 1-3: Makefile.am.

```
bin_PROGRAMS = example
example_SOURCES = example.cc
```

Example 1-4: WITH_MYSQL source for inclusion in acinclude.m4.

```
dnl configure.in helper macros
dnl
AC_DEFUN([WITH_MYSQL], [
 AC_MSG_CHECKING(for mysql_config executable)
 AC_ARG_WITH(mysql, [ --with-mysql=PATH path to mysql_config binary or mysql prefix dir], [
 if test -x $withval -a -f $withval
   then
     MYSQL_CONFIG=$withval
   elif test -x $withval/bin/mysql_config -a -f $withval/bin/mysql_config
    MYSQL_CONFIG=$withval/bin/mysql_config
   fi
  ],[
  if test -x /usr/local/mysql/bin/mysql_config -a -f /usr/local/mysql/bin/mysql_config
     MYSQL_CONFIG=/usr/local/mysql/bin/mysql_config
   elif test -x /usr/bin/mysql_config -a -f /usr/bin/mysql_config
     MYSQL_CONFIG=/usr/bin/mysql_config
   fi
  ])
  if test "x$MYSQL_CONFIG" = "x"
   AC_MSG_RESULT(not found)
   exit 3
   AC_PROG_CC
   AC_PROG_CXX
    # add regular MySQL C flags
   ADDFLAGS=`$MYSQL_CONFIG --cflags`
   # add NDB API specific C flags
   IBASE=`$MYSQL_CONFIG --include`
    ADDFLAGS="$ADDFLAGS $IBASE/storage/ndb"
   ADDFLAGS="$ADDFLAGS $IBASE/storage/ndb/ndbapi"
   ADDFLAGS="$ADDFLAGS $IBASE/storage/ndb/mgmapi"
   CFLAGS="$CFLAGS $ADDFLAGS"
    CXXFLAGS="$CXXFLAGS $ADDFLAGS"
   LDFLAGS="$LDFLAGS "`$MYSQL_CONFIG --libs_r`" -lndbclient -lmystrings -lmysys"
   LDFLAGS="$LDFLAGS "`$MYSQL_CONFIG --libs_r`" -lndbclient -lmystrings"
   AC_MSG_RESULT($MYSQL_CONFIG)
  fi
])
```

2.1.2 Connecting to the Cluster

This section covers connecting an NDB API application to an NDB Cluster.

2.1.2.1 Include Files

NDB API applications require one or more of the following include files:

• Applications accessing NDB Cluster data using the NDB API must include the file NdbApi.hpp.

- Applications making use of the regular MySQL client API as well as the NDB API must also include mysql.h (in addition to NdbApi.hpp).
- Applications that use NDB Cluster management functions from the MGM API need the include file mgmapi.h.

2.1.2.2 API Initialization and Cleanup

Before using the NDB API, it must first be initialized by calling the ndb_init() function.

Once an NDB API application is complete, you can call ndb_end(0) to perform any necessary cleanup. Keep in mind that, before you invoke this function, all Ndb_cluster_connection objects created in your NDB API application must be cleaned up or destroyed; otherwise, threads created when an Ndb_cluster_connection object's connect() method is invoked do not exit properly, which causes errors on application termination. When an Ndb_cluster_connection is created statically, you must not call ndb_end() in the same scope as the connection object. When the connection object is created dynamically, you can destroy it using delete() before calling ndb_end().

Each of the functions ndb_init() and ndb_end() is defined in the file storage/ndb/include/ndb_init.h.



Note

It should be possible to use $\mathtt{fork}()$ in NDB API applications, but you must do so prior to calling $\mathtt{ndb_init}()$ or $\mathtt{my_init}()$ to avoid sharing of resources such as files and connections between processes.

2.1.2.3 Establishing the Connection

To establish a connection to the server, you must create an instance of Ndb_cluster_connection, whose constructor takes as its argument a cluster connection string. If no connection string is given, localhost is assumed.

The cluster connection is not actually initiated until the Ndb_cluster_connection::connect() method is called. When invoked without any arguments, the connection attempt is retried indefinitely, once per second, until successful. No reporting is done until the connection has been made.

By default an API node connects to the "nearest" data node. This is usually a data node running on the same machine as the nearest, due to the fact that shared memory transport can be used instead of the slower TCP/IP. This may lead to poor load distribution in some cases, so it is possible to enforce a round-robin node connection scheme by calling the set_optimized_node_selection() method with 0 as its argument prior to calling connect().

connect() initiates a connection to an NDB Cluster management node only. To enable connections with data nodes, use wait_until_ready() after calling connect(); wait_until_ready() waits up to a given number of seconds for a connection to a data node to be established.

In the following example, initialization and connection are handled in the two functions <code>example_init()</code> and <code>example_end()</code>, which are included in subsequent examples by means of including the file <code>example_connection.h.</code>

Example 2-1: Connection example.

```
#include <stdio.h>
#include <stdlib.h>
#include <NdbApi.hpp>
#include <mysql.h>
#include <mgmapi.h>
```

```
Ndb_cluster_connection* connect_to_cluster();
void disconnect_from_cluster(Ndb_cluster_connection *c);
Ndb_cluster_connection* connect_to_cluster()
 Ndb_cluster_connection* c;
  if(ndb init())
   exit(EXIT_FAILURE);
 c= new Ndb_cluster_connection();
  if(c->connect(4, 5, 1))
    fprintf(stderr, "Unable to connect to cluster within 30 seconds.\n\n");
    exit(EXIT_FAILURE);
  if(c->wait_until_ready(30, 0) < 0)</pre>
    fprintf(stderr, "Cluster was not ready within 30 seconds.\n\n");
    exit(EXIT FAILURE);
  return c;
void disconnect_from_cluster(Ndb_cluster_connection *c)
 delete c;
 ndb_end(2);
int main(int argc, char* argv[])
 Ndb_cluster_connection *ndb_connection= connect_to_cluster();
 printf("Connection Established.\n\n");
 disconnect_from_cluster(ndb_connection);
  return EXIT_SUCCESS;
```

2.1.3 Mapping MySQL Database Object Names and Types to NDB

The next two sections discuss naming and other conventions followed by the NDB API with regard to MySQL database objects, as well as handling of MySQL data types in NDB API applications.

2.1.3.1 MySQL Database Object Names in the NDB API

This section discusses mapping of MySQL database objects to the NDB API.

Databases and Schemas. Databases and schemas are not represented by objects as such in the NDB API. Instead, they are modelled as attributes of Table and Index objects. The value of the database attribute of one of these objects is always the same as the name of the MySQL database to which the table or index belongs. The value of the schema attribute of a Table or Index object is always 'def' (for "default").

Tables. MySQL table names are directly mapped to NDB table names without modification. Table names starting with 'NDB\$' are reserved for internal use, as is the SYSTAB_0 table in the sys database.

Indexes. There are two different type of NDB indexes:

- · Hash indexes are unique, but not ordered.
- B-tree indexes are ordered, but permit duplicate values.

Names of unique indexes and primary keys are handled as follows:

- For a MySQL UNIQUE index, both a B-tree and a hash index are created. The B-tree index uses the
 MySQL name for the index; the name for the hash index is generated by appending '\$unique' to the
 index name.
- For a MySQL primary key only a B-tree index is created. This index is given the name PRIMARY. There is no extra hash; however, the uniqueness of the primary key is guaranteed by making the MySQL key the internal primary key of the NDB table.

Column Names and Values. NDB column names are the same as their MySQL names.

2.1.3.2 NDB API Handling of MySQL Data Types

This section provides information about the way in which MySQL data types are represented in NDBCLUSTER table columns and how these values can be accessed in NDB API applications.

Numeric data types. The MySQL TINYINT, SMALLINT, INT, and BIGINT data types map to NDB types having the same names and storage requirements as their MySQL counterparts.

The MySQL FLOAT and DOUBLE data types are mapped to NDB types having the same names and storage requirements.

Data types used for character data. The storage space required for a MySQL CHAR column is determined by the maximum number of characters and the column's character set. For most (but not all) character sets, each character takes one byte of storage. When using utf8, each character requires three bytes; utfmb4 uses up to four bytes per character. You can find the maximum number of bytes needed per character in a given character set by checking the Maxlen column in the output of SHOW CHARACTER SET.

An NDB VARCHAR column value maps to a MySQL VARCHAR, except that the first two bytes of the NDB VARCHAR are reserved for the length of the string. A utility function like that shown here can make a VARCHAR value ready for use in an NDB API application:

```
void make_ndb_varchar(char *buffer, char *str)
{
  int len = strlen(str);
  int hlen = (len > 255) ? 2 : 1;
  buffer[0] = len & 0xff;
  if( len > 255 )
     buffer[1] = (len / 256);
  strcpy(buffer+hlen, str);
}
```

You can use this function as shown here:

```
char myVal[128+1]; // Size of myVal (+1 for length)
...
make_ndb_varchar(myVal, "NDB is way cool!!");
myOperation->setValue("myVal", myVal);
```

See Section 2.5.11, "NDB API Simple Array Example", for a complete example program that writes and reads VARCHAR and VARBINARY values to and from a table using the NDB API.

MySQL storage requirements for a VARCHAR or VARBINARY column depend on whether the column is stored in memory or on disk:

- For in-memory columns, the NDB storage engine supports variable-width columns with 4-byte alignment. This means that (for example) a the string 'abcde' stored in a VARCHAR(50) column using the latin1 character set requires 12 bytes—in this case, 2 bytes times 5 characters is 10, rounded up to the next even multiple of 4 yields 12.
- For Disk Data columns, VARCHAR and VARBINARY are stored as fixed-width columns. This means that each of these types requires the same amount of storage as a CHAR of the same size.

Each row in an NDB Cluster BLOB or TEXT column is made up of two separate parts. One of these is of fixed size (256 bytes), and is actually stored in the original table. The other consists of any data in excess of 256 bytes, which stored in a hidden table. The rows in this second table are always 2000 bytes long. This means that record of size bytes in a TEXT or BLOB column requires

- 256 bytes, if size <= 256
- 256 + 2000 * ((size 256) \ 2000) + 1) bytes otherwise

Temporal data types. Storage of temporal types in the NDB API depends on whether MySQL's "old" types without fractional seconds or "new" types with fractional second support are used. Support for fractional seconds was introduced in MySQL 5.6 as well as the NDB Cluster versions based on it—that is, NDB 7.3 and NDB 7.4. These versions use the new temporal types by default, but can be made to use the old ones by starting mysqld with --create-old-temporals=ON. NDB 7.5 and later—that is, those NDB Cluster versions based on MySQL 5.7 and later—can read and write data using the old temporal types, but cannot create tables that use the old types. See Fractional Seconds in Time Values, for more about these changes in the MySQL server.

Because support for the old temporal types is expected be removed in a future release, you are encouraged to migrate any tables using the old temporal types to the new versions of these types. You can do this by executing a copying ALTER TABLE operation on any table using the old temporals, or by means of backing up and restoring any such tables.

You can see whether a given table uses the old or new temporal types by checking the output of the ndb_desc utility supplied with the NDB Cluster distribution. Consider a table created in a database named test, using the following statement, on a mysqld started without the --create-old-temporals option:

```
CREATE TABLE t1 (
    c1 DATETIME,
    c2 DATE,
    c3 TIME,
    c4 TIMESTAMP,
    c5 YEAR) ENGINE=NDB;
```

The relevant portion (the Attributes block) of the output of ndb_desc looks like this:

```
shell> ndb_desc -dtest t1
...
-- Attributes --
c1 Datetime2(0) NULL AT=FIXED ST=MEMORY
c2 Date NULL AT=FIXED ST=MEMORY
c3 Time2(0) NULL AT=FIXED ST=MEMORY
c4 Timestamp2(0) NOT NULL AT=FIXED ST=MEMORY DEFAULT 0
c5 Year NULL AT=FIXED ST=MEMORY
```

The names of the new MySQL temporal types are are suffixed with 2 (for example, Datetime2) to set them apart from the old versions of these types. Assume that we restart mysqld with --create-old-temporals=ON and then create a table t2, also in the test database, using this statement:

```
CREATE TABLE t2 (
c1 DATETIME,
c2 DATE,
```

```
c3 TIME,
c4 TIMESTAMP,
c5 YEAR) ENGINE=NDB;
```

The output from executing ndb_desc on this table as shown includes the Attributes block shown here:

```
shell> ndb_desc -dtest t2
...
-- Attributes --
c1 Datetime NULL AT=FIXED ST=MEMORY
c2 Date NULL AT=FIXED ST=MEMORY
c3 Time NULL AT=FIXED ST=MEMORY
c4 Timestamp NOT NULL AT=FIXED ST=MEMORY DEFAULT 0
c5 Year NULL AT=FIXED ST=MEMORY
```

The affected MySQL types are TIME, DATETIME, and TIMESTAMP. The "new" versions of these types are reflected in the NDB API as Time2, Datetime2, and Timestamp2, respectively, each supporting fractional seconds with up to 6 digits of precision. The new variants use big-endian encoding of integer values which are then processed to determine the components of each temporal type.

For the fractional second part of each of these types, the precision affects the number of bytes needed, as shown in the following table:

Table 2.1 Precision of NDB API new temporal types

Precision	Bytes required	Range
0	0	_
1	1	0-9
2	1	0-99
3	2	0-999
4	2	0-9999
5	3	0-99999
6	3	0-99999

The fractional part for each of the new temporal types is stored in big-endian format—that is, with the highest order byte at the lowest address—using the necessary number of bytes.

The binary layouts of both the old and new versions of these types are described in the next few paragraphs.

Time: The "old" version of this type is stored as a 24-bit signed int value stored in little-endian format (lowest order byte in lowest order address). Byte 0 (bits 0-7) corresponds to hours, byte 2 (bits 8-15) to minutes, and byte 2 (bits 16-23) to seconds according to this formula:

Bit 23 serves as the sign bit; if this bit is set, the time value is considered negative.

Time 2: This is the "new" TIME type added in NDB 7.3 and 7.4 (MySQL 5.6), and is stored as a 3-byte bigendian encoded value plus 0 to 3 bytes for the fractional part. The integer part is encoded as shown in the following table:

Table 2.2 Time2 encoding

Bits	Meaning	Range
23	Sign bit	0-1

Bits	Meaning	Range
22	Interval	0-1
22-13	Hour	1-1023
12-7	Minute	0-63
6-0	Second	0-63

Any fractional bytes in addition to this are handled as described previously.

Date: The representation for the MySQL DATE type is unchanged across NDB versions, and uses a 3-byte unsigned integer stored in little-endian order. The encoding is as shown here:

Table 2.3 Date encoding

Bits	Meaning	Range
23-9	Year	0-32767
8-5	Month	0-15
4-0	Day	0-31

Datetime: The "old" MySQL DATETIME type is represented by a 64-bit unsigned value stored in host byte order, encoded using the following formula:

```
value = second

+ minute * 10^2

+ hour * 10^4

+ day * 10^6

+ month * 10^8

+ year * 10^{10}
```

DateTime2: The "new" DATETIME is encoded as a 5-byte big-endian with an optional fractional part of 0 to 3 bytes, the fractional portion being handled as described previously. The high 5 bytes are encoded as shown here:

Table 2.4 DateTime2 encoding

Bits	Meaning	Range
23	Sign bit	0-1
22	Interval	0-1
22-13	Hour	1-1023
12-7	Minute	0-63
6-0	Second	0-63

The YearMonth bits are encoded as Year = YearMonth / 13 and Month = YearMonth % 13.

Timestamp: The "old" version of this type uses a 32-bit unsigned value representing seconds elapsed since the Unix epoch, stored in host byte order.

Timestamp 2: This is the version of TIMESTAMP implemented in NDB 7.3 and 7.4 (MySQL 5.6), and uses 4 bytes with big-endian eoncoding for the integer potion (unsigned). The optional 3-byte fractional portion is encoded as exaplined earlier in this section.

Additional information. More information about and examples uding data types as expressed in the NDB API can be found in ndb/src/common/util/NdbSqlUtil.cpp. In addition, see Section 2.5.13, "Timestamp2 Example", which provides an example of a simple NDB API application that makes use of the Timestamp2 data type.

2.2 The NDB API Class Hierarachy

This section provides a hierarchical listing of all classes, interfaces, and structures exposed by the NDB API.

- Ndb
 - Key_part_ptr
 - PartitionSpec
- NdbBlob
- Ndb_cluster_connection
- NdbDictionary
 - AutoGrowSpecification
 - Dictionary
 - List
 - Element
 - Column
 - Object
 - Datafile
 - Event
 - ForeignKey
 - HashMap
 - Index
 - LogfileGroup
 - Table
 - Tablespace
 - Undofile
 - RecordSpecification
- NdbError
- NdbEventOperation
- ullet NdbInterpretedCode
- NdbOperation
 - NdbIndexOperation

- NdbScanOperation
 - NdbIndexScanOperation
 - IndexBound
 - ScanOptions
- GetValueSpec
- SetValueSpec
- OperationOptions
- NdbRecAttr
- NdbRecord
- NdbScanFilter
- NdbTransaction

2.3 NDB API Classes, Interfaces, and Structures

This section provides a detailed listing of all classes, interfaces, and stuctures defined in the NDB API.

Each listing includes the following information:

- Description and purpose of the class, interface, or structure.
- Pointers, where applicable, to parent and child classes.
- Detailed listings of all public members, including descriptions of all method parameters and type values.

Class, interface, and structure descriptions are provided in alphabetical order. For a hierarchical listing, see Section 2.2, "The NDB API Class Hierarachy".

2.3.1 The Column Class

This section provides information about the Column class, which models a column in an NDBCLUSTER table.

- Column Class Overview
- Column::ArrayType
- Column Constructor
- Column::equal()
- Column::getArrayType()
- Column::getCharset()
- Column::getColumnNo()
- Column::getDefaultValue()
- Column::getInlineSize()

- Column::getLength()
- Column::getName()
- Column::getNullable()
- Column::getPartitionKey()
- Column::getPartSize()
- Column::getPrecision()
- Column::getPrimaryKey()
- Column::getScale()
- Column::getSize()
- Column::getSizeInBytesForRecord()
- Column::getStorageType()
- Column::getStripeSize()
- Column::getType()
- Column::setArrayType()
- Column::setCharset()
- Column::setDefaultValue()
- Column::setInlineSize
- Column::setLength()
- Column::setName()
- Column::setNullable()
- Column::setPartitionKey()
- Column::setPartSize()
- Column::setPrecision()
- Column::setPrimaryKey()
- Column::setScale()
- Column::setStripeSize()
- Column::setStorageType()
- Column::setType()
- Column::StorageType
- Column::Type

Column Class Overview

Parent class

NdbDictionary

Child classes

Description

None

Each instance of Column is characterized by its type, which is determined by a number of type specifiers:

- Built-in type
- · Array length or maximum length
- Precision and scale (currently not in use)
- Character set (applicable only to columns using string data types)
- Inline and part sizes (applicable only to BLOB columns)

These types in general correspond to MySQL data types and their variants. The data formats are same as in MySQL. The NDB API provides no support for constructing such formats; however, they are checked by the NDB kernel.

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.5 Column class methods and descriptions

Method	Description
Column()	Class constructor; there is also a copy constructor
~Column()	Class destructor
equal()	Compares Column objects
getArrayType()	Gets the column's array type
getCharset()	Get the character set used by a string (text) column (not applicable to columns not storing character data)
getColumnNo()	Gets the column number
getDefaultValue()	Returns the column's default value
getInlineSize()	Gets the inline size of a BLOB column (not applicable to other column types)
getLength()	Gets the column's length
getName()	Gets the name of the column
getNullable()	Checks whether the column can be set to NULL
getPartitionKey()	Checks whether the column is part of the table's partitioning key
getPartSize()	Gets the part size of a BLOB column (not applicable to other column types)
getPrecision()	Gets the column's precision (used for decimal types only)
getPrimaryKey()	Check whether the column is part of the table's primary key

Methods

Method	Description
getScale()	Gets the column's scale (used for decimal types only)
getSize()	Gets the size of an element
getSizeInBytesForR	Getsothe space required for a column by NdbRecord, according to the column's type (added in NDB 7.3.10 and NDB 7.4.7)
getStripeSize()	Gets a BLOB column's stripe size (not applicable to other column types)
getStorageType()	Gets the storage type used by this column
getType()	Gets the column's type (Type value)
setArrayType()	Sets the column's ArrayType
setCharset()	Sets the character set used by a column containing character data (not applicable to nontextual columns)
setDefaultValue()	Sets the column's default value
setInlineSize()	Sets the inline size for a BLOB column (not applicable to non-BLOB columns)
setLength()	Sets the column's length
setName()	Sets the column's name
setNullable()	Toggles the column's nullability
setPartitionKey()	Determines whether the column is part of the table's partitioning key
setPartSize()	Sets the part size for a BLOB column (not applicable to non-BLOB columns)
setPrecision()	Sets the column's precision (used for decimal types only)
setPrimaryKey()	Determines whether the column is part of the primary key
setScale()	Sets the column's scale (used for decimal types only)
setStorageType()	Sets the storage type to be used by this column
setStripeSize()	Sets the stripe size for a BLOB column (not applicable to non-BLOB columns)
setType()	Sets the column's Type

Types

These are the public types of the Column class:

Table 2.6 Column class types and descriptionse.

Туре	Description
ArrayType	Specifies the column's internal storage format
StorageType	Determines whether the column is stored in memory or on disk

Туре	Description
	The column's data type. NDB columns have the same data types as found in MySQL

The assignment (=) operator is overloaded for this class, so that it always performs a deep copy.



Important

Columns created using this class cannot be seen by the MySQL Server. This means that they cannot be accessed by MySQL clients, and that they cannot be replicated. For these reasons, it is often preferable to avoid working with them.

In the NDB API, column names are handled in case-sensitive fashion. (This differs from the MySQL C API.) To reduce the possibility for error, it is recommended that you name all columns consistently using uppercase or lowercase.

As with other database objects, <code>Column</code> object creation and attribute changes to existing columns done using the NDB API are not visible from MySQL. For example, if you change a column's data type using <code>Column::setType()</code>, MySQL will regard the type of column as being unchanged. The only exception to this rule with regard to columns is that you can change the name of an existing column using <code>Column::setName()</code>.

Column::ArrayType

This section provides information about the ArrayType data type, which represents a column's internal attribute format.

Description The attribute storage format can be either fixed or variable.

Enumeration values Possible values are shown, along with descriptions, in the following table:

Table 2.7 Column object ArrayType data type values and descriptions

Name	Description
ArrayTypeFixed	stored as a fixed number of bytes
ArrayTypeShortVar	stored as a variable number of bytes; uses 1 byte overhead
ArrayTypeMediumVar	stored as a variable number of bytes; uses 2 bytes overhead

The fixed storage format is faster but also generally requires more space than the variable format. The default is ArrayTypeShortVar for Var* types and ArrayTypeFixed for others. The default is usually sufficient.

Column Constructor

Description You can create a new Column or copy an existing one using the class

constructor.

A Column created using the NDB API is *not* visible to a MySQL server.

The NDB API handles column names in case-sensitive fashion. For example, if you create a column named "myColumn", you will not be

able to access it later using "Mycolumn" for the name. You can reduce the possibility for error, by naming all columns consistently using only uppercase or only lowercase.

Signature

You can create either a new instance of the Column class, or by copying an existing Column object. Both of these are shown here:

• Constructor for a new Column:

```
Column
  (
    const char* name = ""
)
```

· Copy constructor:

```
Column (
    const Column& column
)
```

Parameters

When creating a new instance of Column, the constructor takes a single argument, which is the name of the new column to be created. The copy constructor also takes one parameter—in this case, a reference to the Column instance to be copied.

Return value

A Column object.

Destructor

The Column class destructor takes no arguments and returns nothing (void).

Column::equal()

Description

This method is used to compare one Column with another to determine whether the two Column objects are the same.

Signature

```
bool equal
(
    const Column& column
) const
```

Parameters

equal() takes a single parameter, a reference to an instance of Column.

Return value

true if the columns being compared are equal, otherwise false.

Column::getArrayType()

Description

This method gets the column's array type.

Signature

```
ArrayType getArrayType
(
void
) const
```

Parameters

None.

Return value

An ArrayType; see Column::ArrayType for possible values.

Column::getCharset()

Description

This gets the character set used by a text column.

This method is applicable only to columns whose Type value is Char, Varchar, or Text.

The NDB API handles column names in case-sensitive fashion; "myColumn" and "Mycolumn" are not considered to refer to the same column. It is recommended that you minimize the possibility of errors from using the wrong lettercase for column names by naming all columns consistently using only uppercase or only lowercase.

Signature

```
CHARSET_INFO* getCharset
(
    void
) const
```

Parameters

None.

Return value

A pointer to a CHARSET_INFO structure specifying both character set and collation. This is the same as a MySQL MY_CHARSET_INFO data structure; for more information, see mysql_get_character_set_info(),in the MySQL Manual.

Column::getColumnNo()

Description

This method gets the sequence number of a column within its containing table or index. If the column is part of an index (such as when returned by getColumn()), it is mapped to its position within that index, and not within the table containing the index.

Signature

```
int getColumnNo
   (
    void
   ) const
```

Parameters

None.

Return value

The column number as an integer.

Column::getDefaultValue()

Description

Gets a column's default value data.

To determine whether a table has any columns with default values, use Table::hasDefaultValues().

Signature

```
const void* getDefaultValue
   (
    unsigned int* len = 0
   ) const
```

Parameters

len holds either the length of the default value data, or 0 in the event that the column is nullable or has no default value.

Return value

The default value data.

Column::getInlineSize()

Description

This method retrieves the inline size of a BLOB column—that is, the number of initial bytes to store in the table's blob attribute. This part is normally in main memory and can be indexed.

This method is applicable only to BLOB columns.

Signature int getInlineSize

(void) const

Parameters None.

Return value The BLOB column's inline size, as an integer.

Column::getLength()

Description This method gets the length of a column. This is either the array length

for the column or—for a variable length array—the maximum length.

Signature int getLength

(void) const

Parameters None.

Return value The (maximum) array length of the column, as an integer.

Column::getName()

Description This method returns the name of the column for which it is called.

The NDB API handles column names in case-sensitive fashion. For example, if you retrieve the name "myColumn" for a given column, attempting to access this column using "Mycolumn" for the name fails with an error such as Column is NULL or Table definition has undefined column. You can reduce the possibility for error, by naming all columns consistently using only uppercase or only lowercase.

Signature const char* getName

(void) const

Parameters None.

Return value The name of the column.

Column::getNullable()

Description This method is used to determine whether the column can be set to

NULL.

Signature bool getNullable

void
) const

Parameters None.

Return value A Boolean value: true if the column can be set to NULL, otherwise

false.

Column::getPartitionKey()

Description

This method is used to check whether the column is part of the table's partitioning key.

A partitioning key is a set of attributes used to distribute the tuples onto the data nodes. This key a hashing function specific to the ${\tt NDB}$ storage engine.

An example where this would be useful is an inventory tracking application involving multiple warehouses and regions, where it might be good to use the warehouse ID and district id as the partition key. This would place all data for a specific district and warehouse in the same storage node. Locally to each fragment the full primary key will still be used with the hashing algorithm in such a case.

For more information about partitioning, partitioning schemes, and partitioning keys in MySQL, see Partitioning, in the MySQL Manual.

The only type of user-defined partitioning that is supported for use with the \mathtt{NDB} storage engine is key partitioning, including linear key partitioning.

Signature

```
bool getPartitionKey
(
void
) const
```

Parameters

None.

Return value

true if the column is part of the partitioning key for the table, otherwise

Column::getPartSize()

Description

This method is used to get the part size of a BLOB column—that is, the number of bytes that are stored in each tuple of the blob table.

This method is applicable to BLOB columns only.

Signature

```
int getPartSize
   (
    void
   ) const
```

Parameters

None.

Return value

The column's part size, as an integer. In the case of a Tinyblob column, this value is 0 (that is, only inline bytes are stored).

Column::getPrecision()

Description

This method gets the precision of a column.

This method is applicable to decimal columns only.

Signature

```
int getPrecision
  (
    void
    const
```

Parameters None.

Return value The column's precision, as an integer. The precision is defined as the

number of significant digits; for more information, see the discussion of the DECIMAL data type in Numeric Data Types, in the MySQL Manual.

Column::getPrimaryKey()

Description This method is used to determine whether the column is part of the

table's primary key.

Signature bool getPrimaryKey

void
) const

Parameters None.

Return value A Boolean value: true if the column is part of the primary key of the

table to which this column belongs, otherwise false.

Column::getScale()

Description This method gets the scale used for a decimal column value.

This method is applicable to decimal columns only.

Signature int getScale

void
) const

Parameters None.

Return value The decimal column's scale, as an integer. The scale of a decimal

column represents the number of digits that can be stored following the decimal point. It is possible for this value to be 0. For more information, see the discussion of the DECIMAL data type in Numeric Data Types, in

the MySQL Manual.

Column::getSize()

Description This function is used to obtain the size of a column.

Signature int getSize

void
) const

Parameters None.

Return value The column's size in bytes (an integer value).

Column::getSizeInBytesForRecord()

Description Gets the space required for a given column by an NdbRecord,

depending on the column's type, as follows:

 For a BLOB column, this value is the same as sizeof(NdbRecord*), which is 4 or 8 bytes (the size of a pointer; platform-dependent). • For columns of all other types, it is the same as the value returned by getSize().

This method was added in NDB 7.3.10 and NDB 7.4.7.

Signature

int getSizeInBytesForRecord
 (
 void
) const

Parameters

None.

Return value

An integer (see Description).

Column::getStorageType()

Description

This method obtains a column's storage type.

Signature

StorageType getStorageType
 (
 void
) const

Parameters

None.

Return value

A StorageType value; for more information about this type, see Column::StorageType.

Column::getStripeSize()

Description

This method gets the stripe size of a BLOB column—that is, the number of consecutive parts to store in each node group.

Signature

int getStripeSize
 (
 void
) const

Parameters

None.

Return value

The column's stripe size, as an integer.

Column::getType()

Description

This method gets the column's data type.

Signature

Parameters

None.

Return value

The Type (data type) of the column. For a list of possible values, see

Column::Type.

Column::setArrayType()

Description

Sets the array type for the column.

Signature

void setArrayType
 (
 ArrayType type
)

Parameters

A Column::ArrayType value. See Column::ArrayType, for more information.

Return value

None.

Column::setCharset()

Description

This method can be used to set the character set and collation of a Char, Varchar, or Text column.

This method is applicable to Char, Varchar, and Text columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

```
void setCharset
(
CHARSET_INFO* cs
)
```

Parameters

This method takes one parameter. *cs* is a pointer to a CHARSET_INFO structure. For additional information, see Column::getCharset().

Return value

None.

Column::setDefaultValue()

Description

This method sets a column value to its default, if it has one; otherwise it sets the column to NULL.

To determine whether a table has any columns with default values, use Table::hasDefaultValues().

Signature

```
int setDefaultValue
   (
     const void* buf,
     unsigned int len
)
```

Parameters

This method takes 2 arguments: a value pointer <code>buf</code>; and the length <code>len</code> of the data, as the number of significant bytes. For fixed size types, this is the type size. For variable length types, the leading 1 or 2 bytes pointed to by <code>buffer</code> also contain size information as normal for the type.

Return value

0 on success, 1 on failure..

Column::setInlineSize

Description

This method gets the inline size of a BLOB column—that is, the number of initial bytes to store in the table's blob attribute. This part is normally kept in main memory, and can be indexed and interpreted.

This method is applicable to BLOB columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

void setInlineSize
 (
 int size
)

Parameters

The integer size is the new inline size for the BLOB column.

Return value

None.

Column::setLength()

Description

This method sets the length of a column. For a variable-length array, this is the maximum length; otherwise it is the array length.

Changes made to columns using this method are not visible to MySQL.

Signature

void setLength
 (
 int length
)

Parameters

This method takes a single argument—the integer value *length* is the new length for the column.

Return value

None.

Column::setName()

Description

This method is used to set the name of a column.

setName() is the only Column method whose result is visible from a MySQL Server. MySQL cannot see any other changes made to existing columns using the NDB API.

Signature

void setName
 (
 const char* name
)

Parameters

This method takes a single argument—the new name for the column.

Return value

This method None.

Column::setNullable()

Description

This method toggles the nullability of a column.

Changes made to columns using this method are not visible to MySQL.

Signature

void setNullable
 (
 bool nullable

Parameters

A Boolean value. Using true makes it possible to insert NULLs into the column; if nullable is false, then this method performs the equivalent of changing the column to NOT NULL in MySQL.

Return value

None.

Column::setPartitionKey()

Description

This method makes it possible to add a column to the partitioning key of the table to which it belongs, or to remove the column from the table's partitioning key.

Changes made to columns using this method are not visible to MySQL.

For additional information, see Column::getPartitionKey().

Signature

```
void setPartitionKey
    (
       bool enable
    )
```

Parameters

The single parameter *enable* is a Boolean value. Passing true to this method makes the column part of the table's partitioning key; if *enable* is false, then the column is removed from the partitioning key.

Return value

None.

Column::setPartSize()

Description

This method sets the part size of a BLOB column—that is, the number of bytes to store in each tuple of the BLOB table.

This method is applicable to BLOB columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

```
void setPartSize
   (
    int size
)
```

Parameters

The integer *size* is the number of bytes to store in the BLOB table. Using zero for this value means only inline bytes can be stored, in effect making the column's type TINYBLOB.

Return value

None.

Column::setPrecision()

Description

This method can be used to set the precision of a decimal column.

This method is applicable to decimal columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

```
void setPrecision
   (
    int precision
)
```

Parameters

This method takes a single parameter—precision is an integer, the value of the column's new precision. For additional information about decimal precision and scale, see Column::getPrecision(), and Column::getScale().

Return value

None.

Column::setPrimaryKey()

Description

This method is used to make a column part of the table's primary key, or to remove it from the primary key.

Changes made to columns using this method are not visible to MySQL.

Signature

void setPrimaryKey
 (
 bool primary
)

Parameters

This method takes a single Boolean value. If it is true, then the column becomes part of the table's primary key; if false, then the column is removed from the primary key.

Return value

None.

Column::setScale()

Description

This method can be used to set the scale of a decimal column.

This method is applicable to decimal columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

```
void setScale
    (
    int scale
)
```

Parameters

This method takes a single parameter—the integer <code>scale</code> is the new scale for the decimal column. For additional information about decimal precision and scale, see Column::getPrecision(), and Column::getScale().

Return value

None.

Column::setStripeSize()

Description

This method sets the stripe size of a BLOB column—that is, the number of consecutive parts to store in each node group.

This method is applicable to BLOB columns only.

Changes made to columns using this method are not visible to MySQL.

Signature

```
void setStripeSize
    (
    int size
)
```

Parameters

This method takes a single argument. The integer *size* is the new stripe size for the column.

Return value

None.

Column::setStorageType()

Description

Sets the storage type for the column.

Signature

void setStorageType

StorageType type

Parameters A Column::StorageType value. See Column::StorageType, for more

information.

Return value None.

Column::setType()

Description This method sets the Type (data type) of a column.

setType() resets all column attributes to their (type dependent) default values; it should be the first method that you call when changing the attributes of a given column

the attributes of a given column.

Changes made to columns using this method are not visible to MySQL.

Signature void setType

(
Type type

Parameters This method takes a single parameter—the new Column:: Type for the

column. The default is Unsigned. For a listing of all permitted values,

see Column::Type.

Return value None.

Column::StorageType

This section provides information about the StorageType data type, which describes the storage type used by a Column object.

Description The storage type used for a given column can be either in memory or

on disk. Columns stored on disk mean that less RAM is required overall but such columns cannot be indexed, and are potentially much slower to

access. The default is StorageTypeMemory.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.8 Column object StorageType data type values and descriptions

Name	Description
StorageTypeMemory	Store the column in memory
StorageTypeDisk	Store the column on disk

Column::Type

This section provides information about the Type data type, which is used to describe a column's data type.

Description Data types for Column objects are analogous to the data types used

by MySQL. The types Tinyint, Tinyintunsigned, Smallint, Smallunsigned, Mediumint, Mediumunsigned, Int, Unsigned, Bigint, Bigunsigned, Float, and Double (that is, types Tinyint

through <code>Double</code> in the order listed in the Enumeration Values table) can be used in arrays.

Do not confuse Column: Type with Object: Type.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.9 Column object Type data type values and descriptions

Name	Description
Undefined	Undefined
Tinyint	1-byte signed integer
Tinyunsigned	1-byte unsigned integer
Smallint	2-byte signed integer
Smallunsigned	2-byte unsigned integer
Mediumint	3-byte signed integer
Mediumunsigned	3-byte unsigned integer
Int	4-byte signed integer
Unsigned	4-byte unsigned integer
Bigint	8-byte signed integer
Bigunsigned	8-byte signed integer
Float	4-byte float
Double	8-byte float
Olddecimal	Signed decimal as used prior to MySQL 5.0 (OBSOLETE)
Olddecimalunsigned	Unsigned decimal as used prior to MySQL 5.0 (OBSOLETE)
Decimal	Signed decimal as used by MySQL 5.0 and later
Decimalunsigned	Unsigned decimal as used by MySQL 5.0 and later
Char	A fixed-length array of 1-byte characters; maximum length is 255 characters
Varchar	A variable-length array of 1-byte characters; maximum length is 255 characters
Binary	A fixed-length array of 1-byte binary characters; maximum length is 255 characters
Varbinary	A variable-length array of 1-byte binary characters; maximum length is 255 characters
Datetime	An 8-byte date and time value, with a precision of 1 second (DEPRECATED)
Datetime2	An 8-byte date and time value, with fractional seconds. Added in NDB 7.3.1.

Name	Description
Date	A 4-byte date value, with a precision of 1 day
Blob	A binary large object; see Section 2.3.13, "The NdbBlob Class"
Text	A text blob
Bit	A bit value; the length specifies the number of bits
Longvarchar	A 2-byte Varchar
Longvarbinary	A 2-byte Varbinary
Time	Time without date (DEPRECATED)
Time2	Time without date, with fractional seconds. Added in NDB 7.3.1.
Year	1-byte year value in the range 1901-2155 (same as MySQL)
Timestamp	Unix time (DEPRECATED)
Timestamp2	Unix time, with fractional seconds. Added in NDB 7.3.1.

The NDB API provides access to time types with microseconds (TIME, DATETIME, and TIMESTAMP) as Time2, Datetime2, and Timestamp2. (Time, Datetime, and Timestamp are deprecated as of the same version.) Use setPrecision() to set up to 6 fractional digits (default 0). Data formats are as in MySQL and must use the correct byte length.

Since NDB can compare any of these values as binary strings, it does not perform any checks on the actual data.

2.3.2 The Datafile Class

This section provides information about the Datafile class, which models an NDB Cluster data file.

- Datafile Class Overview
- Datafile Class Constructor
- Datafile::getFileNo()
- Datafile::getFree()
- Datafile::getNode()
- Datafile::getObjectId()
- Datafile::getObjectStatus()
- Datafile::getObjectVersion()
- Datafile::getPath()
- Datafile::getSize()
- Datafile::getTablespace()
- Datafile::getTablespaceId()

• Datafile::setNode()

• Datafile::setPath()

• Datafile::setSize()

• Datafile::setTablespace()

Datafile Class Overview

Methods

Parent class Object

Child classes None

Description The Datafile class models an NDB Cluster data file, which is used to

store Disk Data table and column data.

Only unindexed column data can be stored on disk. Indexes and indexed columns are stored in memory.

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.10 Datafile class methods and descriptions

Name	Description
Datafile()	Class constructor
~Datafile()	Destructor
getFileNo()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
getFree()	Gets the amount of free space in the data file
getNode()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
getObjectId()	Gets the data file's object ID
getObjectStatus()	Gets the data file's object status
<pre>getObjectVersion()</pre>	Gets the data file's object version
getPath()	Gets the file system path to the data file
getSize()	Gets the size of the data file
getTablespace()	Gets the name of the tablespace to which the data file belongs
getTablespaceId()	Gets the ID of the tablespace to which the data file belongs
setNode()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
setPath()	Sets the name and location of the data file on the file system
setSize()	Sets the data file's size
setTablespace()	Sets the tablespace to which the data file belongs

Types

The Datafile class defines no public types.

Datafile Class Constructor

Description This method creates a new instance of Datafile, or a copy of an

existing one.

Signature To create a new instance:

Datafile
(
void
)

To create a copy of an existing Datafile instance:

Datafile
(
const Datafile& datafile
)

Parameters New instance: None. Copy constructor: a reference to the Datafile

instance to be copied.

Return value A Datafile object.

Datafile::getFileNo()

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature Uint32 getFileNo

void
) const

Parameters None.

Return value The file number, as an unsigned 32-bit integer.

Datafile::getFree()

Description This method gets the free space available in the data file.

Signature Uint64 getFree

(void) const

Parameters None.

Return value The number of bytes free in the data file, as an unsigned 64-bit integer.

Datafile::getNode()

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature Uint32 getNode

(void) const

Parameters None.

Return value

The node ID as an unsigned 32-bit integer.

Datafile::getObjectId()

Description

This method is used to obtain the object ID of the data file.

Signature

virtual int getObjectId
(
void
) const

Parameters

None.

Return value

The datafile's object ID, as an integer.

Datafile::getObjectStatus()

Description

This method is used to obtain the data file's object status.

Signature

) const

Parameters

None.

Return value

The data file's Status. See Object::Status.

Datafile::getObjectVersion()

Description

This method retrieves the data file's object version (see NDB Schema Object Versions).

Signature

virtual int getObjectVersion
(

void
) const

Parameters

None.

Return value

The data file's object version, as an integer.

Datafile::getPath()

Description

This method returns the file system path to the data file.

Signature

const char* getPath

void
) const

Parameters

None.

Return value

The path to the data file on the data node's file system, a string

(character pointer).

Datafile::getSize()

Description

This method gets the size of the data file in bytes.

Signature

Uint64 getSize (void) const

Parameters None.

Return value The size of the data file, in bytes, as an unsigned 64-bit integer.

Datafile::getTablespace()

Description This method can be used to obtain the name of the tablespace to which

the data file belongs.

You can also access the associated tablespace's ID directly. See

Datafile::getTablespaceId().

Signature const char* getTablespace

void
) const

Parameters None.

Return value The name of the associated tablespace (as a character pointer).

Datafile::getTablespaceId()

Description This method gets the ID of the tablespace to which the data file belongs.

You can also access the name of the associated tablespace directly.

See Datafile::getTablespace().

Signature Uint32 getTablespaceId

void
) const

Parameters None.

Return value This method returns the tablespace ID as an unsigned 32-bit integer.

Datafile::setNode()

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature void setNode

Uint32 nodeId

Parameters The node Id of the node on which the data file is to be located (an

unsigned 32-bit integer value).

Return value None.

Datafile::setPath()

Description This method sets the path to the data file on the data node's file system.

Signature const char* setPath

void

Parameters

The path to the file, a string (as a character pointer).

Return value

None.

Datafile::setSize()

Description

This method sets the size of the data file.

Signature

```
void setSize
   (
    Uint64 size
)
```

Parameters

This method takes a single parameter—the desired *size* in bytes for the data file, as an unsigned 64-bit integer.

Return value

None.

Datafile::setTablespace()

Description

This method is used to associate the data file with a tablespace.

Signatures

 $\mathtt{setTablespace}(\)$ can be invoked in either of the two ways listed here:

1. Using the name of the tablespace, as shown here:

```
void setTablespace
   (
      const char* name
)
```

2. Using a reference to a Tablespace object.

```
void setTablespace
   (
      const class Tablespace& tablespace
   )
```

Parameters

This method takes a single parameter, which can be either one of the following:

- The name of the tablespace (as a character pointer).
- A reference tablespace to the corresponding Tablespace object.

Return value

None.

2.3.3 The Dictionary Class

This section provides information about the Dictionary class.

- Dictionary Class Overview
- Dictionary Class Constructor
- Dictionary::beginSchemaTrans()
- Dictionary::createDatafile()
- Dictionary::createEvent()

- Dictionary::createForeignKey()
- Dictionary::createHashMap()
- Dictionary::createIndex()
- Dictionary::createLogfileGroup()
- Dictionary::createRecord()
- Dictionary::createTable()
- Dictionary::createTablespace()
- Dictionary::createUndofile()
- Dictionary::dropDatafile()
- Dictionary::dropEvent()
- Dictionary::dropForeignKey()
- Dictionary::dropIndex()
- Dictionary::dropLogfileGroup()
- Dictionary::dropTable()
- Dictionary::dropTablespace()
- Dictionary::dropUndofile()
- Dictionary::endSchemaTrans()
- Dictionary::getDatafile()
- Dictionary::getDefaultHashMap()
- Dictionary::getEvent()
- Dictionary::getForeignKey()
- Dictionary::getHashMap()
- Dictionary::getIndex()
- Dictionary::getLogfileGroup()
- Dictionary::getNdbError()
- Dictionary::getTable()
- Dictionary::getTablespace()
- Dictionary::getUndofile()
- Dictionary::hasSchemaTrans()
- Dictionary::initDefaultHashMap()
- Dictionary::invalidateIndex()
- Dlctionary::invalidateTable()

• Dictionary::listEvents()

• Dictionary::listIndexes()

• Dictionary::listObjects()

• Dictionary::prepareHashMap()

• Dictionary::releaseRecord()

Dictionary::removeCachedTable()

• Dictionary::removeCachedIndex()

Dictionary Class Overview

Parent class NdbDictionary

Child classes List

Description This is used for defining and retrieving data object metadata. It also

includes methods for creating and dropping database objects.

Methods The following table lists the public methods of this class and the purpose or use of each method:

Table 2.11 Dictionary class methods and descriptions

Name	Description
Dictionary()	Class constructor method
~Dictionary()	Destructor method
beginSchemaTrans()	Begins a schema transaction
createDatafile()	Creates a data file
createEvent()	Creates an event
<pre>createForeignKey()</pre>	Creates a foreign key
createHashMap()	Creates a hash map
createIndex()	Creates an index
createLogfileGroup	(Creates a log file group
createRecord()	Creates an Ndbrecord object
createTable()	Creates a table
<pre>createTablespace()</pre>	Creates a tablespace
createUndofile()	Creates an undo file
dropDatafile()	Drops a data file
dropEvent()	Drops an event
dropForeignKey()	Drops a foreign key
dropIndex()	Drops an index
dropLogfileGroup()	Drops a log file group
dropTable()	Drops a table
dropTablespace()	Drops a tablespace

Name	Description
dropUndofile()	Drops an undo file
endSchemaTrans()	Ends (commits and closes) a schema transaction
getDatafile()	Gets the data file having the given name
getDefaultHashMap(Gets a table's default hash map
getEvent()	Gets the event having the given name
<pre>getForeignKey()</pre>	Gets the foreign key having the given name or reference
getHashMap()	Gets the hash map given its name or associated table
getIndex()	Gets the index having the given name
getLogfileGroup()	Gets the log file group having the given name
getNdbError()	Retrieves the latest error
getTable()	Gets the table having the given name
getTablespace()	Gets the tablespace having the given name
getUndofile()	Gets the undo file having the given name
hasSchemaTrans()	Tells whether a schema transaction currently exists
initDefaultHashMap	(Initializes a atble' default hash map
invalidateTable()	Invalidates a table object
listObjects()	Fetches a list of the objects in the dictionary
listIndexes()	Fetches a list of the indexes defined on a given table
listEvents()	Fetches a list of the events defined in the dictionary
prepareHashMap()	Creates or retrieves a hash map that can be updated
removeCachedTable(Removes a table from the local cache
removeCachedIndex(Removes an index from the local cache

Database objects such as tables and indexes created using the <code>Dictionary::create*()</code> methods cannot be seen by the MySQL Server. This means that they cannot be accessed by MySQL clients, and that they cannot be replicated. For these reasons, it is often preferable to avoid working with them.

The Dictionary class does not have any methods for working directly with columns. You must use Column class methods for this purpose—see Section 2.3.1, "The Column Class", for details.

See Section 2.3.10, "The List Class", and Section 2.3.4, "The Element Structure".

Types

Dictionary Class Constructor

Description

This method creates a new instance of the Dictionary class.

Both the constructor and destructor for this class are protected methods, rather than public.

Signature

```
protected Dictionary
(
Ndb& ndb
)
```

Parameters

An Ndb object.

Return value

A Dictionary object.

Destructor

The destructor takes no parameters and returns nothing:

```
protected ~Dictionary
(
void
)
```

Dictionary::beginSchemaTrans()

Description

Starts a schema transaction. An error occurs if a transaction is already active, or if the kernel metadata is locked. You can determine whether a schema transaction already exists using the hasSchemaTrans() method.

A *metadata operation* occurs whenever data objects are created, altered, or dropped; such an operation can create additional suboperations in the NDB kernel.

The Ndb object and its associated <code>Dictionary</code> support one schema transaction at a time. By default, each metadata operation is executed separately; that is, for each operation, a schema transaction is started implicitly, the operation (including any suboperations) is executed, and the transaction is closed.

It is also possible to begin and end a schema transaction explicitly, and execute a set of user-defined operations atomically within its boundaries. In this case, all operations within the schema transaction either succeed, or are aborted and rolled back, as a unit. This is done by following the steps listed here:

- 1. To begin the schema transaction, call beginSchemaTrans().
- 2. Execute the desired operations (such as createTable()).
- 3. End the schema transaction by calling endSchemaTrans.

Each operation is sent to the NDB kernel, which parses and saves it. A parse failure results in a rollback to the previous user operation before returning, at which point the user can either continue with or abort the entire transaction.

After all operations have been submitted, endSchemaTrans() processes and commits them. In the event of an error, the transaction is immediately aborted.

If the user exits before calling endSchemaTrans(), the NDB
kernel aborts the transaction. If the user exits before the call to
endSchemaTrans() returns, the kernel continues with the request,
and its completion status is reported in the cluster log.

Signature

```
int beginSchemaTrans
   (
     void
)
```

Parameters

None.

Return value

Returns 0 on success, -1 on error.

Dictionary::createDatafile()

Description

This method creates a new data file, given a Datafile object.

Signature

```
int createDatafile
   (
     const Datafile& dFile
   )
```

Parameters

A single argument—a reference to an instance of <code>Datafile</code>—is required.

Return value

0 on success, -1 on failure.

Dictionary::createEvent()

Description

Creates an event, given a reference to an Event object.

You should keep in mind that the NDB API does not track allocated event objects, which means that the user must delete the Event that was obtained using createEvent(), after this object is no longer required.

Signature

```
int createEvent
    (
        const Event& event
    )
```

Parameters

A reference event to an Event object.

Return value

0 on success, -1 on failure.

Dictionary::createForeignKey()

Description

Creates a ForeignKey object, given a reference to this object and an Object ID.

Signature

```
int createForeignKey
   (
     const ForeignKey&,
     ObjectId* = 0,
     int flags = 0
```

Parameters A reference to the ForeignKey object, and an Object ID. An

optional value flags, if used, allows the creation of the foreign key without performing any foreign key checks. If set, its value must be

CreateFK_NoVerify (1).

Return value 0 on success.

Dictionary::createHashMap()

Description Creates a HashMap.

Signature int createHashMap

(
 const HashMap& hashmap,
 ObjectId* id = 0
)

Parameters A reference to the hash map, and, optionally, an ID to be assigned to it.

Return value Returns 0 on success; on failure, returns -1 and sets an error.

Dictionary::createIndex()

Description This method creates an index given an instance of Index and possibly

an optional instance of Table.

Signature This method can be invoked with or without a reference to a table

object:

```
int createIndex
   (
        const Index& index
)
```

```
int createIndex
   (
        const Index& index,
        const Table& table
   )
```

Parameters Required: A reference to an Index object. Optional: A reference to a

Table object.

Return value 0 on success, -1 on failure.

Dictionary::createLogfileGroup()

Description This method creates a new log file group, given an instance of

LogfileGroup.

Signature int createLogfileGroup

(
const LogfileGroup& *lGroup*)

Parameters A single argument, a reference to a LogfileGroup object, is required.

Return value 0 on success, -1 on failure.

Dictionary::createRecord()

Description

Signature

This method is used to create an NdbRecord object for use in table or index scanning operations.

The signature of this method depends on whether the resulting NdbRecord is to be used in table or index operations:

To create an NdbRecord for use in table operations, use the following:

```
NdbRecord* createRecord

(
    const Table* table,
    const RecordSpecification* recSpec,
    Uint32 length,
    Uint32 elSize
)
```

To create an NdbRecord for use in index operations, you can use either of the following:

```
NdbRecord* createRecord

(
    const Index* index,
    const Table* table,
    const RecordSpecification* recSpec,
    Uint32 length,
    Uint32 elSize
)
```

or

```
NdbRecord* createRecord

(
    const Index* index,
    const RecordSpecification* recSpec,
    Uint32 length,
    Uint32 elSize
)
```

Parameters

Dictionary::createRecord() takes the following parameters:

- If this NdbRecord is to be used with an index, a pointer to the corresponding Index object. If the NdbRecord is to be used with a table, this parameter is omitted. (See Section 2.3.8, "The Index Class".)
- A pointer to a Table object representing the table to be scanned.
 If the Ndbrecord produced is to be used with an index, then this optionally specifies the table containing that index. (See Section 2.3.27, "The Table Class".)
- A RecordSpecification used to describe a column.
- The *length* of the record.
- The size of the elements making up this record.

An NdbRecord for use in operations involving the given table or index.

See Section 2.3.22, "The NdbRecord Interface".

Return value

Example

Dictionary::createTable()

Description Creates a table given an instance of Table.

Tables created using this method cannot be seen by the MySQL Server, cannot be updated by MySQL clients, and cannot be replicated.

Signature int createTable

(
const Table& table

Parameters An instance of Table. See Section 2.3.27, "The Table Class", for more

information.

Return value 0 on success, -1 on failure.

Dictionary::createTablespace()

Description This method creates a new tablespace, given a Tablespace object.

Signature int createTablespace

const Tablespace& tSpace

Parameters This method requires a single argument—a reference to an instance of

Tablespace.

Return value 0 on success, -1 on failure.

Dictionary::createUndofile()

Description This method creates a new undo file, given an Undofile object.

 ${\bf Signature} \qquad \qquad {\tt int\ createUndofile}$

const Undofile& uFile

Parameters This method requires one argument: a reference to an instance of

Undofile.

Return value 0 on success, -1 on failure.

Dictionary::dropDatafile()

Description This method drops a data file, given a Datafile object.

Signature int dropDatafile

(
 const Datafile& dFile
)

Parameters A single argument—a reference to an instance of Datafile—is

required.

Return value 0 on success, -1 on failure.

Dictionary::dropEvent()

Description This method drops an event, given a reference to an Event object.

Signature int dropEvent

(

Parameters

This method takes two parameters:

- The name of the event to be dropped, as a string.
- By default, dropEvent() fails if the event specified does not exist.
 You can override this behavior by passing any nonzero value for
 the (optional) force argument; in this case no check is made as to
 whether there actually is such an event, and an error is returned only
 if the event exists but it was for whatever reason not possible to drop
 it.

Return value

0 on success, -1 on failure.

Dictionary::dropForeignKey()

Description

This method drops a foreign key, given a reference to an ForeignKey object to be dropped.

Signature

```
int dropForeignKey
    (
     const ForeignKey&
    )
```

Parameters

A reference to the ForeignKey to be dropped.

Return value

0 on success.

Dictionary::dropIndex()

Description

This method drops an index given an instance of Index, and possibly an optional instance of Table.

Signature

```
int dropIndex
   (
      const Index& index
)
```

```
int dropIndex
    (
      const Index& index,
      const Table& table
    )
```

Parameters

This method takes two parameters, one of which is optional:

- Required: A reference to an Index object.
- : A reference to a Table object.

Return value

0 on success, -1 on failure.

Dictionary::dropLogfileGroup()

Description

Given an instance of LogfileGroup, this method drops the corresponding log file group.

Signature

int dropLogfileGroup

```
(
    const LogfileGroup& lGroup
)
```

Parameters

A single argument, a reference to a LogfileGroup object, is required.

Return value

0 on success, -1 on failure.

Dictionary::dropTable()

Description

Drops a table given an instance of Table.

In NDB 7.3.5 and later, this method drops all foreign key constraints on the *table* that is being dropped, whether the dropped table acts as a parent table, child table, or both. (Bug #18069680)

Prior to NDB 8.0.17, an NDB table dropped using this method persisted in the MySQL data dictionary but could not be dropped using DROP TABLE in the mysql client. In NDB 8.0.17 and later, such "orphan" tables can be dropped using DROP TABLE. (Bug #29125206, Bug #93672)

Signature

```
int dropTable
   (
     const Table& table
)
```

Parameters

An instance of Table. See Section 2.3.27, "The Table Class", for more information.

Return value

0 on success, -1 on failure.

Dictionary::dropTablespace()

Description

This method drops a tablespace, given a Tablespace object.

Signature

```
int dropTablespace
   (
      const Tablespace& tSpace
   )
```

Parameters

This method requires a single argument—a reference to an instance of Tablespace.

Return value

0 on success, -1 on failure.

Dictionary::dropUndofile()

Description

This method drops an undo file, given an Undofile object.

Signature

```
int dropUndofile
   (
      const Undofile& uFile
   )
```

Parameters

This method requires one argument: a reference to an instance of Undofile.

Return value

0 on success, -1 on failure.

Dictionary::endSchemaTrans()

Description

Ends a schema transaction begun with <code>beginSchemaTrans()</code>; causes operations to be processed and either committed, or aborted and rolled back. This method combines transaction execution and closing; separate methods for these tasks are not required (or implemented). This method may be called successfully even if no schema transaction is currently active.

As with many other NDB API methods, it is entirely possible for endSchemaTrans() to overwrite any current error code. For this reason, you should first check for and save any error code that may have resulted from a previous, failed operation.

Signature

```
int endSchemaTrans
   (
     Uint32 flags = 0
)
```

Parameters

The flags determines how the completed transaction is handled. The default is 0, which causes the transaction to be committed.

Dictionary::SchemaTransFlag. You can also use with endSchemaTrans() either of the SchemaTransFlag values shown here:

- SchemaTransAbort (= 1): Causes the transaction to be aborted
- SchemaTransBackground (= 2): Causes the transaction to execute in the background; the result is written to the cluster log, while the application continues without waiting for a response.

Return value

Returns 0 on success; in the event of an error, returns -1 and sets an NdbError error code.

Dictionary::getDatafile()

Description

This method is used to retrieve a Datafile object, given the node ID of the data node where a data file is located and the path to the data file on that node's file system.

Signature

Parameters

This method must be invoked using two arguments, as shown here:

- The 32-bit unsigned integer nodeId of the data node where the data file is located
- The *path* to the data file on the node's file system (string as character pointer)

Return value

A Datafile object—see Section 2.3.2, "The Datafile Class", for details.

Dictionary::getDefaultHashMap()

Description

Get a table's default hash map.

Signature

```
int getDefaultHashMap
   (
     HashMap& dst,
     Uint32 fragments
)
```

or

```
int getDefaultHashMap
   (
     HashMap& dst,
     Uint32 buckets,
     Uint32 fragments
)
```

Return value

Returns 0 on success; on failure, returns -1 and sets an error.

Dictionary::getEvent()

Description

This method is used to obtain a new Event object representing an event, given the event's name.

getEvent() allocates memory each time it is successfully called. You should keep in mind that successive invocations of this method using the same event name return multiple, distinct objects.

The NDB API does not track allocated event objects, which means that the user must delete each Event created using getEvent(), after the object is no longer required.

Signature

```
const Event* getEvent
   (
      const char* eventName
   )
```

Parameters

The eventName, a string (character pointer).

Return value

A pointer to an Event object. See Section 2.3.5, "The Event Class", for more information.

Dictionary::getForeignKey()

Description

This method is used to obtain a new ForeignKey object representing an event, given a reference to the foreign key and its name.

Signature

```
int getForeignKey
   (
    ForeignKey& dst,
    const char* name
)
```

Parameters

A reference to the foreign key and its *name*, a string (character pointer).

Return value

A pointer to a ForeignKey object.

Dictionary::getHashMap()

Description

Gets a hash map by name or by table.

Signatures

```
int getHashMap
    (
          HashMap& dst,
```

```
const char* name
```

or

```
int getHashMap
  (
    HashMap& dst,
    const Table* table
)
```

Parameters

A reference to the hash map and either a name or a Table.

Return value

Returns 0 on success; on failure, returns -1 and sets an error.

Dictionary::getIndex()

Description

This method retrieves a pointer to an index, given the name of the index and the name of the table to which the table belongs.

Signature

```
const Index* getIndex
  (
    const char* iName,
    const char* tName
) const
```

Parameters

Two parameters are required:

- The name of the index (iName)
- The name of the table to which the index belongs (tName)

Both of these are string values, represented by character pointers.

Return value

A pointer to an Index. See Section 2.3.8, "The Index Class", for information about this object.

Dictionary::getLogfileGroup()

Description

This method gets a LogfileGroup object, given the name of the log file group.

Signature

```
LogfileGroup getLogfileGroup
(
const char* name
)
```

Parameters

The name of the log file group.

Return value

An instance of LogfileGroup; see Section 2.3.9, "The LogfileGroup Class", for more information.

Dictionary::getNdbError()

Description

This method retrieves the most recent NDB API error.

Signature

```
const struct NdbError& getNdbError
   (
     void
     ) const
```

Parameters

None.

Return value

A reference to an NdbError object.

Dictionary::getTable()

Description

This method can be used to access a Table whose name is already known.

Signature

```
const Table* getTable
  (
    const char* name
  ) const
```

Parameters

The name of the table.

Return value

A pointer to the table, or NULL if there is no table with the *name* supplied.

Dictionary::getTablespace()

Description

Given either the name or ID of a tablespace, this method returns the corresponding Tablespace object.

Signatures

This method can be invoked in either of the following two ways:

• Using the tablespace name:

```
Tablespace getTablespace
   (
     const char* name
   )
```

• Using the tablespace ID:

```
Tablespace getTablespace
   (
     Uint32 id
   )
```

Parameters

Either one of the following:

- The *name* of the tablespace, a string (as a character pointer)
- The unsigned 32-bit integer id of the tablespace

Return value

A Tablespace Object, as discussed in Section 2.3.28, "The Tablespace Class".

Dictionary::getUndofile()

Description

This method gets an Undofile object, given the ID of the node where an undo file is located and the file system path to the file.

Signature

```
Undofile getUndofile
   (
    Uint32     nodeId,
    const char* path
)
```

Parameters

This method requires the following two arguments:

• The nodeId of the data node where the undo file is located; this value is passed as a 32-bit unsigned integer

• The path to the undo file on the node's file system (string as character pointer)

Return value

An instance of Undofile. For more information, see Section 2.3.29, "The Undofile Class".

Dictionary::hasSchemaTrans()

Description

Tells whether an NDB API schema transaction is ongoing.

Signature

```
bool hasSchemaTrans
   (
     void
     ) const
```

Parameters

Return value

Returns boolean \mathtt{TRUE} if a schema transaction is in progress, otherwise \mathtt{FALSE} .

Dictionary::initDefaultHashMap()

Description

Initialize a default hash map for a table.

Signature

```
int initDefaultHashMap
    (
        HashMap& dst,
        Uint32 fragments
)
```

or

None.

```
int initDefaultHashMap
   (
    HashMap& dst,
    Uint32 buckets,
    Uint32 fragments
)
```

Parameters

A reference to the hash map and the number of fragments. Optionally the number of buckets.

Return value

Returns 0 on success; on failure, returns -1 and sets an error.

Dictionary::invalidateIndex()

Description

This method is used to invalidate a cached index object.

Signature

The index invalidated by this method can be referenced either as an Index object (using a pointer), or by index name and table name, as shown here:

```
void invalidateIndex
    (
        const char* indexName,
        const char* tableName
)

void invalidateIndex
    (
        const Index* index
)
```

Parameters

The names of the index to be removed from the cache and the table to which it belongs (<code>indexName</code> and <code>tableName</code>, respectively), or a pointer to the corresponding <code>Index</code> object.

Return value

None.

Dictionary::invalidateTable()

Description

This method is used to invalidate a cached table object.

Signature

```
void invalidateTable
  (
    const char* name
)
```

It is also possibloe to use a Table object rather than the name of the table, as shown here:

```
void invalidateTable
   (
    const Table* table
)
```

Parameters

The *name* of the table to be removed from the table cache, or a pointer to the corresponding Table object.

Return value

None.

Dictionary::listEvents()

Description

This method returns a list of all events defined within the dictionary.

Signature

```
int listEvents
   (
    List& list
)
```

Parameters

A reference to a List object. (See Section 2.3.10, "The List Class".)

Return value

0 on success; -1 on failure.

Dictionary::listIndexes()

Description

This method is used to obtain a List of all the indexes on a table, given the table's name. (See Section 2.3.10, "The List Class".)

Signature

```
int listIndexes
    (
    List& list,
    const char* table
) const
```

Parameters

listIndexes() takes two arguments, both of which are required:

- A reference to the List that contains the indexes following the call to the method
- The name of the table whose indexes are to be listed

Return value

0 on success, -1 on failure.

Dictionary::listObjects()

Description

This method is used to obtain a list of objects in the dictionary. It is possible to get all of the objects in the dictionary, or to restrict the list to objects of a single type.

Signature

This method has two signatures:

```
int listObjects
    (
    List& list,
    Object::Type type = Object::TypeUndefined
) const
```

and

```
int listObjects
    (
        List& list,
        Object::Type type,
        bool fullyQualified
    ) const
```

Parameters

A reference to a List object is required—this is the list that contains the dictionary's objects after listObjects() is called. (See Section 2.3.10, "The List Class".) An optional second argument type may be used to restrict the list to only those objects of the given type—that is, of the specified Object::Type. (See Object::Type.) If type is not given, then the list contains all of the dictionary's objects.

You can also specify whether or not the object names in the <code>list</code> are fully qualified (that is, whether the object name includes the database, schema, and possibly the table name). If you specify <code>fullyQualified</code>, then you must also specify the <code>type</code>.



Note

Setting fullyQualified to false causes listObjects() to return objects that use fully qualified names.

Return value

0 on success, -1 on failure.

Dictionary::prepareHashMap()

Description

Creates or retrieves a hash map suitable for alteration. Requires a schema transaction to be in progress; see Dictionary::beginSchemaTrans(), for more information.

Signatures

Either of the following:

```
• int prepareHashMap
    (
        const Table& oldTable,
        Table& newTable
    )
```

```
int prepareHashMap
    (
        const Table& oldTable,
        Table& newTable,
        Uint32 buckets
)
```

Parameters

References to the old and new tables. Optionally, a number of buckets.

Return value

Returns 0 on success; on failure, returns -1 and sets an error.

Dictionary::releaseRecord()

Description

This method is used to free an NdbRecord after it is no longer needed.

Signature

void releaseRecord
 (
 NdbRecord* record
)

Parameters

The NdbRecord to be cleaned up.

Return value

None.

Example

See Section 2.3.22, "The NdbRecord Interface".

Dictionary::removeCachedTable()

Description

This method removes the table, specified by name, from the local cache.

Signature

void removeCachedTable
 (
 const char* table
)

Parameters

The name of the *table* to be removed from the cache.

Return value

None.

Dictionary::removeCachedIndex()

Description

This method removes the specified index from the local cache, given the name of the index and that of the table in which it is contained.

Signature

void removeCachedIndex
 (
 const char* index,
 const char* table
)

Parameters

The removeCachedIndex() method requires two arguments:

- The name of the index to be removed from the cache
- The name of the table in which the index is found

Return value

None.

2.3.4 The Element Structure

This section provides information about the Element structure.

Parent class

List

Description

The Element structure models an element of a list; it is used to store an object in a List populated by the Dictionary methods

 ${\tt listObjects(), listIndexes(), and listEvents().}$

Attributes

An Element has the attributes shown in the following table:

Table 2.12 Name, type, initial value, and description of Element structure attributes

Attribute	Туре	Initial Value	Description
id	unsigned int	0	The object's ID
type	Object::T	Whe ject::TypeUndef	iThelobject's type— see Object::Type for possible values
state	Object::S	t@aktjeect∷StateUnde	fihe object's state— see Object::State for possible values
store	Object::S	Worject::StoreUnde	How the object is stored —see Object::Store for possible values
databas	æhar*	0	The database in which the object is found
schema	char*	0	The schema in which the object is found
name	char*	0	The object's name

2.3.5 The Event Class

This section provides information about the Event class.

- Event Class Overview
- Event::addEventColumn()
- Event::addEventColumns()
- Event::addTableEvent()
- Event Constructor
- Event::EventDurability
- Event::EventReport
- Event::getDurability()
- Event::getEventColumn()
- Event::getName()
- Event::getNoOfEventColumns()
- Event::getObjectStatus()
- Event::getObjectVersion()
- Event::getObjectId()
- Event::getReport()

- Event::getTable()
- Event::getTableEvent()
- Event::getTableName()
- Event::mergeEvents()
- Event::setDurability()
- Event::setReport()
- Event::setName()
- Event::setTable()
- Event::TableEvent

Event Class Overview

Methods

Parent class NdbDictionary

Child classes None

Description This class represents a database event in an NDB Cluster.

The following table lists the public methods of the Event class and the purpose or use of each method:

Table 2.13 Event class methods and descriptions

Name	Description
Event()	Class constructor
~Event()	Destructor
addEventColumn()	Adds a column on which events should be detected
addEventColumns()	Adds multiple columns on which events should be detected
addTableEvent()	Adds the type of event that should be detected
getDurability()	Gets the event's durability
getEventColumn()	Gets a column for which an event is defined
getName()	Gets the event's name
getNoOfEventColumn	Gets the number of columns for which an event is defined
getObjectId()	Gets the event's object ID
getObjectStatus()	Gets the event's object status
<pre>getObjectVersion()</pre>	Gets the event's object version
getReport()	Gets the event's reporting options
getTable()	Gets the Table object on which the event is defined
getTableEvent()	Checks whether an event is to be detected

Name	Description
getTableName()	Gets the name of the table on which the event is defined
mergeEvents()	Sets the event's merge flag
setDurability()	Sets the event's durability
setName()	Sets the event's name
setReport()	The the event's reporting options
setTable()	Sets the Table object on which the event is defined

Improved Event API (NDB 7.4.3 and later). NDB 7.4.3 introduces an epoch-driven Event API that supercedes the earlier GCI-based model. The new version of the API also simplifies error detection and handling. These changes are realized in the NDB API by implementing a number of new methods for Ndb and NdbEventOperation, deprecating several other methods of both classes, and adding new type values to TableEvent.

Some of the new methods directly replace or stand in for deprecated methods, but not all of the deprecated methods map to new ones, some of which are entirely new. Old (deprecated) methods are shown in the first column of the following table, and new methods in the second column; old methods corresponding to new methods are shown in the same row.

Table 2.14 Deprecated and new Event API methods in the NDB API, NDB 7.4.3

Name	Description
NdbEventOperation:	: Ny
NdbEventOperation:	: Nything (t)Operation::getEpoch
NdbEventOperation:	Ny Lagestigle stQueuedEpoch()
NdbEventOperation:	:None;duseun() NdbEventOperation::getEventType2()
NdbEventOperation:	:None;user() NdbEventOperation::getEventType2()
NdbEventOperation:	:None:rError()
None	NdbEventOperation::isEmptyEpoch()
None	NdbEventOperation::isErrorEpoch()
Ndb::pollEvents()	Ndb::pollEvents2()
Ndb::nextEvent()	Ndb::nextEvent2()
Ndb::getLatestGCI(Ndb::getHighestQueuedEpoch()
Ndb::getGCIEventOp	e Windows in the control of the cont
Ndb::isConsistent(None

Name	Description
Ndb::isConsistentG	None

Error handling using the new API is accomplished by checking the value returned from <code>getEventType2()</code>, and is no longer handled using the methods <code>hasError()</code> and <code>clearError()</code>, which are now deprecated and subject to removal in a future release of NDB Cluster. In support of this change, the range of possible <code>TableEvent</code> types has been expanded by those listed here:

- TE_EMPTY: Empty epoch
- TE_INCONSISTENT: Inconsistent epoch; missing data or overflow
- TE_OUT_OF_MEMORY: Inconsistent data; event buffer out of memory or overflow

The result of these changes is that, in NDB 7.4.3 and later, you can check for errors while checking a table event's type, as shown here:

For more information, see the detailed descriptions for the Ndb and NdbEventOperation methods shown in the table previously, as well as Event::TableEvent.

These are the public types of the Event class:

Table 2.15 Event class types and descriptions

Name	Description
TableEvent()	Represents the type of a table event
<pre>EventDurability()</pre>	Specifies an event's scope, accessibility, and lifetime
EventReport()	Specifies the reporting option for a table event

Event::addEventColumn()

Types

Description

This method is used to add a column on which events should be detected. The column may be indicated either by its ID or its name.

You must invoke Dictionary::createEvent() before any errors will be detected. See Dictionary::createEvent().

If you know several columns by name, you can enable event detection on all of them at one time by using addEventColumns(). See Event::addEventColumns().

Signatures

This method can be invoked in either of the following ways:

• Identifying the event using its column ID:

```
void addEventColumn
    (
     unsigned attrId
)
```

• Identifying the column by name:

```
void addEventColumn
    (
      const char* columnName
    )
```

Parameters

This method takes a single argument, which may be either one of the following:

- The column ID (attrId), which should be an integer greater than or equal to 0, and less than the value returned by getNoOfEventColumns().
- The column's *name* (as a constant character pointer).

Return value

None.

Event::addEventColumns()

Description

This method is used to enable event detection on several columns at the same time. You must use the names of the columns.

As with addEventColumn(), you must invoke Dictionary::createEvent() before any errors will be detected. See Dictionary::createEvent().

Signature

```
void addEventColumns
   (
    int         n,
    const char** columnNames
)
```

Parameters

This method requires the two arguments listed here:

- The number of columns *n* (an integer).
- The names of the columns *columnNames*—this must be passed as a pointer to a character pointer.

Return value

None.

Event::addTableEvent()

Description This method is used to add types of events that should be detected.

Signature void addTableEvent

(
const TableEvent te

Parameters This method requires a TableEvent value.

Return value None.

Event Constructor

Description The Event constructor creates a new instance with a given name, and

optionally associated with a table.

You should keep in mind that the NDB API does not track allocated event objects, which means that the user must explicitly delete the

Event thus created after it is no longer in use.

Signatures It is possible to invoke this method in either of two ways, the first of

these being by name only, as shown here:

```
Event
   (
     const char* name
)
```

Alternatively, you can use the event name and an associated table, like this:

Parameters At a minimum, a name (as a constant character pointer) for the event

is required. Optionally, an event may also be associated with a table; this argument, when present, is a reference to a Table object (see

Section 2.3.27, "The Table Class").

Return value A new instance of Event.

Destructor. A destructor for this class is supplied as a virtual method which takes no arguments and whose return type is void.

Event::EventDurability

This section provides information about EventDurability, a type defined by the Event class.

Description The values of this type are used to describe an event's lifetime or

persistence as well as its scope.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.16 Event::EventDurability data type values and descriptions

Name	Description	
ED_UNDEFINED	The event is undefined or of an unsupported type.	
ED_SESSION	This event persists only for the duration of the current session, and is available only to the current application. It is deleted after the application disconnects or following a cluster restart.	
	The value ED_SESSI reserved fruse and is supported Cluster rel	ION is or future not yet in any NDB
ED_TEMPORARY	Any application may use the event, but it is deleted following a cluster restart.	
	The value ED_TEMPO reserved for use and is supported Cluster rel Important	DRARY is or future not yet in any NDB
ED_PERMANENT	Any application may use the event, and it persists until deleted by an application—even following a cluster. restart	
	Important	
	The value ED_PERMA reserved for use and is supported Cluster rel	or future not yet in any NDB

Event::EventReport

This section provides information about EventReport, a type defined by the Event class.

Description The values of this type are used to specify reporting options for table

events.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.17 Event::EventReport type values and descriptions

Name	Description
ER_UPDATED	Reporting of update events
ER_ALL	Reporting of all events, except for those not resulting in any updates to the inline parts of BLOB columns
ER_SUBSCRIBE	Reporting of subscription events
ER_DDL	Reporting of DDL events (see Event::setReport(), for more information)

Event::getDurability()

Description This method gets the event's lifetime and scope (that is, its

EventDurability).

Signature EventDurability getDurability

void
) const

Parameters None.

Return value An EventDurability value.

Event::getEventColumn()

Description This method is used to obtain a specific column from among those on

which an event is defined.

Signature const Column* getEventColumn

unsigned no

Parameters The number (no) of the column, as obtained using

getNoOfColumns() (see Event::getNoOfEventColumns()).

Return value A pointer to the Column corresponding to no.

Event::getName()

Description This method obtains the name of the event.

Signature const char* getName

(void) const

Parameters None.

Return value The name of the event, as a character pointer.

Event::getNoOfEventColumns()

Description This method obtains the number of columns on which an event is

defined.

Signature int getNoOfEventColumns

void
) const

Parameters None.

Return value The number of columns (as an integer), or -1 in the case of an error.

Event::getObjectStatus()

Description This method gets the object status of the event.

Signature virtual Object::Status getObjectStatus

void
) const

Parameters None.

Return value The object status of the event. For possible values, see Object::Status.

Event::getObjectVersion()

Description This method gets the event's object version (see NDB Schema Object

Versions).

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The object version of the event, as an integer.

Event::getObjectId()

Description This method retrieves an event's object ID.

Signature virtual int getObjectId

void
) const

Parameters None.

Return value The object ID of the event, as an integer.

Event::getReport()

Description This method is used to obtain the reporting option in force for this event.

Signature EventReport getReport

(void) const

Parameters None.

Return value One of the reporting options specified in Event::EventReport.

Event::getTable()

Description

This method is used to find the table with which an event is associated. It returns a reference to the corresponding Table object. You may also obtain the name of the table directly using getTableName().

Signature

const NdbDictionary::Table* getTable
 (
 void
) const

Parameters

None.

Return value

The table with which the event is associated—if there is one—as a pointer to a Table object; otherwise, this method returns NULL. (See Section 2.3.27, "The Table Class".)

Event::getTableEvent()

Description

This method is used to check whether a given table event will be detected.

Signature

```
bool getTableEvent
   (
      const TableEvent te
   ) const
```

Parameters

This method takes a single parameter, the table event's type—that is, a TableEvent value.

Return value

This method returns true if events of TableEvent type te will be detected. Otherwise, the return value is false.

Event::getTableName()

Description

This method obtains the name of the table with which an event is associated, and can serve as a convenient alternative to getTable(). (See Event::getTable().)

Signature

```
const char* getTableName
  (
    void
    ) const
```

Parameters

None.

Return value

The name of the table associated with this event, as a character pointer.

Event::mergeEvents()

Description

This method is used to set the *merge events flag*, which is false by default. Setting it to true implies that events are merged as follows:

- For a given NdbEventOperation associated with this event, events on the same primary key within the same global checkpoint index (GCI) are merged into a single event.
- A blob table event is created for each blob attribute, and blob events are handled as part of main table events.
- Blob post/pre data from blob part events can be read via NdbBlob methods as a single value.

This flag is not inherited by NdbEventOperation, and must be set on NdbEventOperation explicitly.

Signature

```
void mergeEvents
   (
     bool flag
)
```

Parameters

A Boolean *flag* value.

Return value

None.

Event::setDurability()

Description

This method sets an event's durability—that is, its lifetime and scope.

Signature

void setDurability(EventDurability ed)

Parameters

This method requires a single EventDurability value as a parameter.

-

Return value

None.

Event::setReport()

Description

This method is used to set a reporting option for an event. Possible option values may be found in Event::EventReport.

Reporting of DDL events

You must call setReport() using the EventReport value ER_DDL

(added in the same NDB Cluster versions).

For example, to enable DDL event reporting on an Event object named myEvent, you must invoke this method as shown here:

myEvent.setReport(NdbDictionary::Event::ER_DDL);

Signature

```
void setReport
    (
        EventReport er
)
```

Parameters

An EventReport option value.

Return value

None.

Event::setName()

Description

This method is used to set the name of an event. The name must be unique among all events visible from the current application (see Event::getDurability()).

You can also set the event's name when first creating it. See Event Constructor.

Signature

```
void setName
  (
    const char* name
)
```

Parameters The name to be given to the event (as a constant character pointer).

Return value None.

Event::setTable()

Description This method defines a table on which events are to be detected.

By default, event detection takes place on all columns in the table. Use addEventColumn() to override this behavior. For details, see Event::addEventColumn().

Signature

```
void setTable
    (
      const NdbDictionary::Table& table
    )
```

NDB 7.3.3 and later NDB Cluster releases support the use of a pointer with this method, as shown here:

```
void setTable
    (
      const NdbDictionary::Table*; table
)
```

When so used, this version of setTable() returns -1 if the table pointer is NULL. (Bug #16329082)

Parameters

This method requires a single parameter, a reference to the table (see Section 2.3.27, "The Table Class") on which events are to be detected. NDB 7.3.3 and later. A reference or a pointer to the table can be used.

Return value

None. NDB 7.3.3 and later. -1, if a null table pointer is used.

Event::TableEvent

This section describes TableEvent, a type defined by the Event class.

Description

TableEvent is used to classify the types of events that may be associated with tables in the NDB API.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.18 Event::TableEvent type values and descriptions

Name	Description
TE_INSERT	Insert event on a table
TE_DELETE	Delete event on a table
TE_UPDATE	Update event on a table
TE_DROP	Occurs when a table is dropped
TE_ALTER	Occurs when a table definition is changed
TE_CREATE	Occurs when a table is created
TE_GCP_COMPLETE	Occurs on the completion of a global checkpoint

Name	Description
TE_CLUSTER_FAILURE	Occurs on Cluster failures
TE_STOP	Occurs when an event operation is stopped
TE_NODE_FAILURE	Occurs when a Cluster node fails
TE_SUBSCRIBE	Occurs when a cluster node subscribes to an event
TE_UNSUBSCRIBE	Occurs when a cluster node unsubscribes from an event
TE_EMPTY	Empty epoch received from data nodes
TE_INCONSISTENT	Missing data or buffer overflow at data node
TE_OUT_OF_MEMORY	Overflow in event buffer
TE_ALL	Occurs when any event occurs on a table (not relevant when a specific event is received)

TE_EMPTY, TE_INCONSISTENT, and TE_OUT_OF_MEMORY were added in NDB 7.4.3.

2.3.6 The ForeignKey Class

This section provides information about the ForeignKey class, which models a foreign key on an NDB table.

- ForeignKey Class Overview
- ForeignKey()
- ForeignKey::FkAction
- ForeignKey::getName()
- ForeignKey::getParentTable()
- ForeignKey::getChildTable()
- ForeignKey::getParentColumnCount()
- ForeignKey::getChildColumnCount()
- ForeignKey::getParentIndex()
- ForeignKey::getChildIndex()
- ForeignKey::getParentColumnNo()
- ForeignKey::getChildColumnNo()
- ForeignKey::getOnUpdateAction()
- ForeignKey::getOnDeleteAction()
- ForeignKey::setName()
- ForeignKey::setParent()
- ForeignKey::setChild()

• ForeignKey::setOnUpdateAction()

• ForeignKey::setOnDeleteAction()

ForeignKey::getObjectStatus()

ForeignKey::getObjectId()

• ForeignKey::getObjectVersion()

ForeignKey Class Overview

Parent class Object

Child classes None.

Methods The following table lists the public methods of the ForeignKey class

and the purpose or use of each method:

Table 2.19 ForeignKey class methods and descriptions

Name	Description
ForeignKey()	Class constructor
~ForeignKey()	Class destructor
getName()	Get the foreign key's name
<pre>getParentTable()</pre>	Get the foreign key's parent table
<pre>getChildTable()</pre>	Get the foreign key's child table
getParentColumnCou	Get) the number of columns in the parent table
getChildColumnCoun	Get the number of columns in the child table
getParentColumnNo(Get the column number in the parent table
<pre>getChildColumnNo()</pre>	Get the column number in the child table
<pre>getParentIndex()</pre>	Returns 0 if key points to parent table's primary key
<pre>getChildIndex()</pre>	Returns 0 if child references resolved using child table's primary key
getOnUpdateAction(Get the foreign's key update action (FkAction)
getOnDeleteAction(Get the foreign key's delete action (FkAction)
setName()	Set the foreign key's name
setParent()	Set the foreign key's parent table
setChild()	Set a foreign key's child table
setOnUpdateAction(Set the foreign's key update action (FkAction)
setOnDeleteAction(Set the foreign key's delete action (FkAction)
getObjectStatus()	Get the object status
getObjectId()	Get the object ID

Name	Description
<pre>getObjectVersion()</pre>	Get the object version

Types

The ForeignKey class has one public type, the FkAction type.

ForeignKey()

Description

Create either an entirely new foreign key reference, or a copy of an

existing one.

Signature

New instance:

ForeignKey

```
void
```

Copy constructor:

```
ForeignKey
          (
          const ForeignKey&
          )
```

Parameters

For a new instance: None.

For the copy constructor: A reference to an existing instance of

ForeignKey.

Return value

A new instance of ForeignKey.

ForeignKey::FkAction

This section provides information about FkAction, which is an enumeration modelling a reference action for a foreign key when an update or delete operation is performed on the parent table.

Enumeration values

Possible values are shown, along with the corresponding reference action, in the following table:

Table 2.20 ForeignKey::FkAction data type values and descriptions

Name	Description
NoAction	NO ACTION: Deferred check.
Restrict	RESTRICT: Reject operation on parent table.
Cascade	CASCADE: Perform operation on row from parent table; perform same operation on matching rows in child table.
SetNull	SET NULL: Perform operation on row from parent table; set any matching foreign key columns in child table to NULL.
SetDefault	SET DEFAULT: Currently not supported in NDB Cluster.

See also FOREIGN KEY Constraints, in the MySQL Manual.

ForeignKey::getName()

Description Retrieve the name of the ForeignKey instance for which the method is

invoked.

Signature const char* getName

(void) const

Parameters None.

Return value The name of the ForeignKey.

ForeignKey::getParentTable()

Description Retrieve the parent table of the ForeignKey instance for which the

method is invoked.

Signature const char* getParentTable

void
) const

Parameters None.

Return value A pointer to the parent table of the ForeignKey.

ForeignKey::getChildTable()

Description Retrieve the child table of the ForeignKey instance for which the

method is invoked.

Signature const char* getChildTable

(void) const

Parameters None.

Return value A pointer to the child table of this ForeignKey.

ForeignKey::getParentColumnCount()

Description Retrieve the number of columns in the parent table of this ForeignKey.

Signature unsigned getParentColumnCount

void
) const

Parameters None.

Return value The number of columns in the parent table.

ForeignKey::getChildColumnCount()

Description Retrieve the number of columns in the child table of this ForeignKey.

Signature unsigned getChildColumnCount

void
) const

Parameters None.

Return value The number of columns in the child table.

ForeignKey::getParentIndex()

Description Returns 0 if the child table refers to the parent table's primary key.

Signature const char* getParentIndex

void
) const

Parameters None.

Return value See description.

ForeignKey::getChildIndex()

Description Return 0 if child references are resolved using the child table's primary

key.

Signature const char* getChildIndex

(void) const

Parameters None.

Return value See description.

ForeignKey::getParentColumnNo()

Description This method gets the sequence number of a foreign key column

in the parent table for a given index. See the documentation for Column::getColumnNo(), for information about handling columns in

the NDB API.

Signature int getParentColumnNo

(unsigned *no*) const

Parameters None.

Return value The sequence number of the column.

ForeignKey::getChildColumnNo()

Description This method gets the sequence number of a foreign key column

in the child table for a given index. See the documentation for

Column::getColumnNo() for information about handling columns in

the NDB API.

Signature int getChildColumnNo

unsigned no

Parameters None.

Return value The sequence number of the column.

ForeignKey::getOnUpdateAction()

Description Get the foreign key's ON UPDATE action. This is a

ForeignKey::FkAction and has one of the values NoAction,

Restrict, Cascade, or SetNull.

Signature FkAction getOnUpdateAction

void
) const

Parameters None.

Return value The sequence number of the column.

ForeignKey::getOnDeleteAction()

Description Get the foreign key's ON DELETE action. This is a

ForeignKey::FkAction and has one of the values NoAction,

Restrict, Cascade, Or SetNull.

Signature FkAction getOnDeleteAction

void
) const

Parameters None.

Return value The sequence number of the column.

ForeignKey::setName()

Description Set the name of the ForeignKey instance for which the method is

invoked.

Signature void setName

(
const char*

Parameters The name of the ForeignKey.

Return value None.

ForeignKey::setParent()

Description Set the parent table of a ForeignKey, given a reference to the table,

and optionally, an index to use as the foreign key.

Signature void setParent

const Table&,
const Index* index = 0,
const Column* cols[] = 0

Parameters A reference to a Table (required). Optionally, an index using the

indicated column or columns.

Return value None.

ForeignKey::setChild()

Description Set the child table of a ForeignKey, given a reference to the table, and

optionally, an index to use as the foreign key.

Signature

```
void setChild
  (
    const Table&,
    const Index* index = 0,
    const Column* cols[] = 0
)
```

Parameters

A reference to a Table (required). Optionally, an index using the

indicated column or columns.

Return value None.

ForeignKey::setOnUpdateAction()

Description Set the foreign key's ON UPDATE action.

Signature void setOnUpdateAction

FkAction

Parameters The ON UPDATE action to be performed. This must be a

ForeignKey::FkAction having one of the values NoAction,

Restrict, Cascade, Or SetNull.

Return value None

ForeignKey::setOnDeleteAction()

Description Set the foreign key's ON DELETE action.

Signature void setOnUpdateAction

(FkAction

Parameters The ON UPDATE action to be performed, of type

ForeignKey::FkAction. Must be one of the values NoAction,

Restrict, Cascade, Or SetNull.

Return value None

ForeignKey::getObjectStatus()

Description Get the object status (see Object::Status) for this ForeignKey object.

Signature virtual Object::Status getObjectStatus

(void) const

Parameters None.

Return value The ForeignKey object's status, as a value of type Object::Status.

See this type's documentation for possible values and their

interpretation.

ForeignKey::getObjectId()

Description Get the object ID (see Object::getObjectId()) for this ForeignKey

object.

Signature virtual int getObjectId

(void) const

Parameters None.

Return value The ForeignKey object's ID, as returned by

Object::getObjectId().

ForeignKey::getObjectVersion()

Description Get the object version (see Object::getObjectVersion()) for this

ForeignKey object.

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The ForeignKey object's version number (an integer), as returned by

Object::getObjectVersion().

2.3.7 The HashMap Class

This section provides information about the HashMap class, which models a hash map in an NDB Cluster.

- HashMap Class Overview
- HashMap Constructor
- HashMap::setName()
- HashMap::getName()
- HashMap::setMap()
- HashMap::getMapLen()
- HashMap::getMapValues()
- HashMap::equal()
- HashMap::getObjectStatus()
- HashMap::getObjectVersion()
- HashMap::getObjectId()

HashMap Class Overview

Parent class Object
Child classes None.

Methods The following table lists the public methods of the HashMap class and

the purpose or use of each method:

Table 2.21 HashMap class methods and descriptions

Name	Description
HashMap()	Class constructor
~HashMap()	Class destructor
setName()	Set a name for the hashmap
getName()	Gets a hashmap's name
setMap()	Sets a hashmap's length and values
getMapLen()	Gets a hashmap's length
getMapValues()	Gets the values contained in the hashmap
equal()	Compares this hashmap's values with those of another hashmap
getObjectStatus()	Gets the hashmap's object status
getObjectVersion()	Gets the hashmap's schema object version
getObjectId()	Gets the hashmap's ID

Types

The HashMap class defines no public types.

HashMap Constructor

Description

The HashMap class constructor normally requires no arguments. A copy constructor is also available.

See also Dictionary::createHashMap(), for more information.

Signature

Base constructor:

```
HashMap HashMap
(
void
)
```

Copy constructor:

```
HashMap HashMap (

const HashMap& hashmap
)
```

Destructor:

```
virtual ~HashMap
(
void
)
```

Parameters

None, or the address of an existing HashMap object to be copied.

Return value

A new instance of HashMap, possibly a copy of an existing one.

HashMap::setName()

Description

Sets the name of the hash map.

Signature

void setName

```
(
const char* name
)
```

Parameters

The name to be assigned to the hashmap.

Return value

None.

HashMap::getName()

Description

Gets the name of the hash map.

Signature

```
const char* getName
  (
    void
    const
```

Parameters

None.

Return value

The name of the hash map.

HashMap::setMap()

Description

Assigns a set of values to a has map.

Signature

```
void setMap
   (
     const Uint32* values,
     Uint32 len
)
```

Parameters

A pointer to a set of values of length len.

Return value

None.

HashMap::getMapLen()

Description

Gets the hash map's length; that is, the number of values which it contains. You can obtain the values using getMapValues().

Signature

```
Uint32 getMapLen
   (
     void
     ) const
```

Parameters

None.

Return value

The length of the hash map.

HashMap::getMapValues()

Description

Gets the values listed in the hash map.

Signature

```
int getMapValues
   (
      Uint32* dst,
      Uint32 len
   ) const
```

Parameters

A pointer to a set of values (dst) and the number of values (len).

Return value

Returns 0 on success; on failure, returns -1 and sets error.

HashMap::equal()

Description Compares (only) the values of this HashMap with those of another one.

Signature bool equal

const HashMap& hashmap
) const

Parameters A reference to the hash map to be compared with this one.

Return value None.

HashMap::getObjectStatus()

Description This method retrieves the status of the HashMap for which it is invoked.

The return value is of type Object::Status.

Signature virtual Status getObjectStatus

(void) const

Parameters None.

Return value Returns the current Status of the HashMap.

HashMap::getObjectVersion()

Description The method gets the hash map's schema object version.

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The object's version number, an integer.

HashMap::getObjectId()

Description This method retrieves the hash map's ID.

Signature virtual int getObjectId

void
) const

Parameters None.

Return value The object ID, an integer.

2.3.8 The Index Class

This section provides information about the Index class.

- Index Class Overview
- Index Class Constructor
- Index::addColumn()
- Index::addColumnName()

- Index::addColumnNames()
- Index::getColumn()
- Index::getLogging()
- Index::getName()
- Index::getNoOfColumns()
- Index::getObjectStatus()
- Index::getObjectVersion()
- Index::getObjectId()
- Index::getTable()
- Index::getType()
- Index::setLogging
- Index::setName()
- Index::setTable()
- Index::setType()
- Index::Type

Index Class Overview

Parent class

NdbDictionary

None

Child classes

Description

This class represents an index on an NDB Cluster table column. It is a descendant of the NdbDictionary class, using the Object class.

If you create or change indexes using the NDB API, these modifications cannot be seen by MySQL. The only exception to this is using Index::setName() to rename the index.

Methods

The following table lists the public methods of Index and the purpose or use of each method:

Table 2.22 Index class methods and descriptions

Name	Description
Index()	Class constructor
~Index()	Destructor
addColumn()	Adds a Column object to the index
addColumnName()	Adds a column by name to the index
addColumnNames()	Adds multiple columns by name to the index
getColumn()	Gets a column making up (part of) the index
getLogging()	Checks whether the index is logged to disk
getName()	Gets the name of the index

Name	Description	
getNoOfColumns()	Gets the number of columns belonging to the index	
getObjectStatus()	Gets the index object status	
<pre>getObjectVersion()</pre>	Gets the index object status	
getObjectId()	Gets the index object ID	
getTable()	Gets the name of the table being indexed	
getType()	Gets the index type	
setLogging()	Enable/disable logging of the index to disk	
setName()	Sets the name of the index	
setTable()	Sets the name of the table to be indexed	
setType()	Set the index type	

Types

Index defines one public type, the Type type.

Index Class Constructor

Description

This is used to create an new instance of Index.

Indexes created using the NDB API cannot be seen by the MySQL Server.

Signature

```
Index
  (
    const char* name = ""
)
```

Parameters

The name of the new index. It is possible to create an index without a name, and then assign a name to it later using setName(). See Index::setName().

Return value

A new instance of Index.

Destructor

The destructor (~Index()) is supplied as a virtual method.

Index::addColumn()

Description

This method may be used to add a column to an index.

The order of the columns matches the order in which they are added to the index. However, this matters only with ordered indexes.

Signature

```
\begin{tabular}{ll} \beg
```

Parameters

A reference c to the column which is to be added to the index.

Return value

None.

Index::addColumnName()

Description

This method works in the same way as addColumn(), except that it takes the name of the column as a parameter. See Index::getColumn().

Signature

```
void addColumnName
    (
      const char* name
    )
```

Parameters

The *name* of the column to be added to the index, as a constant character pointer.

Return value

None.

Index::addColumnNames()

Description

This method is used to add several column names to an index definition at one time.

As with the addColumn() and addColumnName() methods, the indexes are numbered in the order in which they were added. This normally matters only for ordered indexes.

Signature

Parameters

This method takes two parameters, listed here:

- The number of columns and names noOfNames to be added to the index.
- The names to be added (as a pointer to a pointer).

Return value

None.

Index::getColumn()

Description

This method retrieves the column at the specified position within the index.

Signature

```
const Column* getColumn
   (
     unsigned no
   ) const
```

Parameters

The ordinal position number no of the column, as an unsigned integer. Use the getNoOfColumns() method to determine how many columns make up the index—see Index::getNoOfColumns(), for details.

Return value

The column having position *no* in the index, as a pointer to an instance of Column. See Section 2.3.1, "The Column Class".

Index::getLogging()

Description

Use this method to determine whether logging to disk has been enabled for the index.

Indexes which are not logged are rebuilt when the cluster is started or restarted.

Ordered indexes currently do not support logging to disk; they are rebuilt each time the cluster is started. (This includes restarts.)

Signature bool getLogging

void
) const

Parameters None.

Return value A Boolean value:

- true: The index is being logged to disk.
- false: The index is not being logged.

Index::getName()

Description This method is used to obtain the name of an index.

Signature const char* getName

void
) const

Parameters None.

Return value The name of the index, as a constant character pointer.

Index::getNoOfColumns()

Description This method is used to obtain the number of columns making up the

index.

Signature unsigned getNoOfColumns

void
) const

Parameters None.

Return value An unsigned integer representing the number of columns in the index.

Index::getObjectStatus()

Description This method gets the object status of the index.

Signature virtual Object::Status getObjectStatus

(
void
) const

Parameters None.

Return value A Status value; see Object::Status, for more information.

Index::getObjectVersion()

Description This method gets the object version of the index (see NDB Schema

Object Versions).

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The object version for the index, as an integer.

Index::getObjectId()

Description This method is used to obtain the object ID of the index.

Signature virtual int getObjectId

(void) const

Parameters None.

Return value The object ID, as an integer.

Index::getTable()

Description This method can be used to obtain the name of the table to which the

index belongs.

Signature const char* getTable

void
) const

Parameters None.

Return value The name of the table, as a constant character pointer.

Index::getType()

Description This method can be used to find the type of index.

Signature Type getType

void
) const

Parameters None.

Return value An index type. See Index::Type, for possible values.

Index::setLogging

Description This method is used to enable or disable logging of the index to disk.

Signature void setLogging

bool enable

Parameters setLogging() takes a single Boolean parameter enable. If enable

is ${\tt true}$, then logging is enabled for the index; if false, then logging of

this index is disabled.

Return value None.

Index::setName()

Description This method sets the name of the index.

This is the only Index::set*() method whose result is visible to a MySQL Server.

Signature

```
void setName
(
const char* name
)
```

Parameters

The desired *name* for the index, as a constant character pointer.

Return value

None.

Index::setTable()

Description

This method sets the table that is to be indexed. The table is referenced by name.

Signature

```
void setTable
(
const char* name
)
```

Parameters

The name of the table to be indexed, as a constant character pointer.

Return value

None.

Index::setType()

Description

This method is used to set the index type.

Signature

```
void setType
     (
         Type type
     )
```

Parameters

The *type* of index. For possible values, see Index::Type.

Return value

None.

Index::Type

This section provides information about the Index type.

Description

This is an enumerated type which describes the sort of column index represented by a given instance of Index.

represented by a given instance of Index.

Do not confuse this enumerated type with Object::Type, or with Column::Type.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.23 Index::Type data type values and descriptions

Name	Description	
Undefined	Undefined object type (initial/default value)	
UniqueHashIndex	Unique unordered hash index (only index type currently supported)	

Name	Description	
OrderedIndex	Nonunique, ordered index	

2.3.9 The LogfileGroup Class

This section provides information about the LogfileGroup class, which models an NDB Cluster Disk Data log file group.

- LogFileGroup Class Overview
- LogfileGroup Constructor
- LogfileGroup::getAutoGrowSpecification()
- LogfileGroup::getName()
- LogfileGroup::getObjectId()
- LogfileGroup::getObjectStatus()
- LogfileGroup::getObjectVersion()
- LogfileGroup::getUndoBufferSize()
- LogfileGroup::getUndoFreeWords()
- LogfileGroup::setAutoGrowSpecification()
- LogfileGroup::setName()
- LogfileGroup::setUndoBufferSize()

LogFileGroup Class Overview

Parent class NdbDictionary

Child classes None

Description This class represents an NDB Cluster Disk Data log file group, which

is used for storing Disk Data undo files. For general information about log file groups and undo files, see NDB Cluster Disk Data Tables, in the

MySQL Manual.

Only unindexed column data can be stored on disk. Indexes and

indexes columns are always stored in memory.

Methods The following table lists the public methods of this class and the

purpose or use of each method:

Table 2.24 LogfileGroup class methods and descriptions

Name	Description		
LogfileGroup()	Class constructor		
~LogfileGroup()	Virtual destructor		
getAutoGrowSpecifi	1		
	AutoGrowSpecification values		

Name	Description			
getName()	Retrieves the log file group's name			
getObjectId()	Get the object ID of the log file group			
getObjectStatus()	Gets the log file group's object status value			
getObjectVersion()	Retrieves the log file group's object version			
getUndoBufferSize(Gets the size of the log file group's undo buffer			
getUndoFreeWords()	Retrieves the amount of free space in the undo buffer			
setAutoGrowSpecifi	Sets An(t) OGrow Specification values for the log file group			
setName()	Sets the name of the log file group			
setUndoBufferSize(Sets the size of the log file group's undo buffer.			

Types

While the LogfileGroup class does not itself define any public types, two of its methods make use of the AutoGrowSpecification data structure as a parameter or return value.

LogfileGroup Constructor

Description

The LogfileGroup class has two public constructors, one of which takes no arguments and creates a completely new instance. The other is a copy constructor.

The Dictionary class also supplies methods for creating and destroying LogfileGroup objects. See Section 2.3.3, "The Dictionary Class".

Signatures

New instance:

```
LogfileGroup
(
void
)
```

Copy constructor:

```
LogfileGroup
(
const LogfileGroup& logfileGroup
)
```

Parameters

When creating a new instance, the constructor takes no parameters. When copying an existing instance, the constructor is passed a reference to the LogfileGroup instance to be copied.

Return value

A LogfileGroup object.

Destructor

```
virtual ~LogfileGroup
(
void
)
```

LogfileGroup::getAutoGrowSpecification()

 ${\color{blue} \textbf{Description}} \qquad \qquad \textbf{This method retrieves the } \textbf{AutoGrowSpecification associated with}$

the log file group.

Signature const AutoGrowSpecification& getAutoGrowSpecification

(void) const

Parameters None.

Return value An AutoGrowSpecification data structure.

LogfileGroup::getName()

Description This method gets the name of the log file group.

Signature const char* getName

void
) const

Parameters None.

Return value The logfile group's name, a string (as a character pointer).

LogfileGroup::getObjectId()

Description This method is used to retrieve the object ID of the log file group.

Signature virtual int getObjectId

void) const

Parameters None.

Return value The log file group's object ID (an integer value).

LogfileGroup::getObjectStatus()

Description This method is used to obtain the object status of the LogfileGroup.

Signature virtual Object::Status getObjectStatus

(void) const

Parameters None.

Return value The logfile group's Status—see Object::Status for possible values.

LogfileGroup::getObjectVersion()

Description This method gets the log file group's object version (see NDB Schema

Object Versions).

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The object version of the log file group, as an integer.

LogfileGroup::getUndoBufferSize()

Description This method retrieves the size of the log file group's undo buffer.

Signature Uint32 getUndoBufferSize

void
) const

Parameters None.

Return value The size of the undo buffer, in bytes.

LogfileGroup::getUndoFreeWords()

Description This method retrieves the number of bytes unused in the log file group's

undo buffer.

Signature Uint64 getUndoFreeWords

void
) const

Parameters None.

Return value The number of bytes free, as a 64-bit integer.

LogfileGroup::setAutoGrowSpecification()

Description This method sets the AutoGrowSpecification data for the log file

group.

Signature void setAutoGrowSpecification

(
 const AutoGrowSpecification& autoGrowSpec
)

Parameters The data is passed as a single parameter, an

AutoGrowSpecification data structure.

Return value None.

LogfileGroup::setName()

Description This method is used to set a name for the log file group.

Signature void setName

const char* name

Parameters The name to be given to the logfile group (character pointer).

Return value None.

LogfileGroup::setUndoBufferSize()

Description This method can be used to set the size of the log file group's undo

buffer.

Signature void setUndoBufferSize

Uint32 size

Parameters The size in bytes for the undo buffer (using a 32-bit unsigned integer

value)

Return value None.

2.3.10 The List Class

This section provides information about the List class.

Parent class Dictionary

Description The List class is a Dictionary subclass that is

used for representing lists populated by the methods

Dictionary::listObjects(), Dictionary::listIndexes(),

and Dictionary::listEvents().

Methods This class has only two methods, a constructor and a destructor.

Neither method takes any arguments.

Calling the constructor creates a new List whose count and elements

attributes are both set equal to 0.

The destructor (~List()) is simply defined in such a way as to remove all elements and their properties. You can find its definition in the file /

storage/ndb/include/ndbapi/NdbDictionary.hpp.

Attributes A List has the following two attributes:

• count, an unsigned integer, which stores the number of elements in

the list.

• elements, a pointer to an array of Element data structures contained in the list. See Section 2.3.4, "The Element Structure".

Types The List class also defines the Element structure.

2.3.11 The Ndb Class

This section provides information about the Ndb class, which models the NDB kernel; it is the primary class of the NDB API.

- Ndb Class Overview
- Ndb Class Constructor
- Ndb::closeTransaction()
- Ndb::computeHash()
- Ndb::createEventOperation()
- Ndb::dropEventOperation()

- Ndb::EventBufferMemoryUsage
- Ndb::getDictionary()
- Ndb::getDatabaseName()
- Ndb::getDatabaseSchemaName()
- Ndb::getGCIEventOperations() (DEPRECATED)
- Ndb::get_eventbuf_max_alloc()
- Ndb::get_eventbuffer_free_percent()
- Ndb::get_event_buffer_memory_usage()
- Ndb::getHighestQueuedEpoch()
- Ndb::getLatestGCI() (DEPRECATED)
- Ndb::getNdbError()
- Ndb::getNdbErrorDetail()
- Ndb::getNdbObjectName()
- Ndb::getNextEventOpInEpoch2()
- Ndb::getNextEventOpInEpoch3()
- Ndb::getReference()
- Ndb::init()
- Ndb::isConsistent() (DEPRECATED)
- Ndb::isConsistentGCI() (DEPRECATED)
- Ndb::isExpectingHigherQueuedEpochs()
- Ndb::Key_part_ptr
- Ndb::nextEvent() (DEPRECATED)
- Ndb::nextEvent2()
- Ndb::PartitionSpec
- Ndb::pollEvents()
- Ndb::pollEvents2()
- Ndb::setDatabaseName()
- Ndb::setDatabaseSchemaName()
- Ndb::setEventBufferQueueEmptyEpoch()
- Ndb::set_eventbuf_max_alloc()
- Ndb::set_eventbuffer_free_percent()
- Ndb::setNdbObjectName()

Ndb::startTransaction()

Ndb Class Overview

Parent class

None

Child classes

None

Description

Any nontrivial NDB API program makes use of at least one instance of Ndb. By using several Ndb objects, it is possible to implement a multithreaded application. You should remember that one Ndb object cannot be shared between threads; however, it is possible for a single thread to use multiple Ndb objects. A single application process can support a maximum of 4711 Ndb objects.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.25 Ndb class methods and descriptions

Name	Description		
Ndb()	Class constructor; represents a connection to an NDB Cluster.		
~Ndb()	Class destructor; terminates a Cluster connection when it is no longer to be used		
<pre>closeTransaction()</pre>	Closes a transaction.		
computeHash()	Computes a distribution hash value.		
createEventOperati	Greates a subscription to a database event. (See Section 2.3.16, "The NdbEventOperation Class".)		
dropEventOperation	Drops a subscription to a database event.		
getDictionary()	Gets a dictionary, which is used for working with database schema information.		
getDatabaseName()	Gets the name of the current database.		
getDatabaseSchemaN	Gets)the name of the current database schema.		
get_eventbuf_max_a	Gets (the current allocated maximum size of the event buffer. Added in NDB 7.3.3.		
get_eventbuffer_fr	Gets the percentage of event buffer memory that should be available before buffering resumes, once the limit has been reached. Added in NDB 7.4.3.		
get_event_buffer_m	Rrovides event buffer memory usage information. Added in NDB 7.4.3.		
getGCIEventOperation	Gets)the next event operation from a GCI. Deprecated in NDB 7.4.3.		
getHighestQueuedEp	Gets)the latest epoch in the event queue. Added in NDB 7.4.3.		
getLatestGCI()	Gets the most recent GCI. Deprecated in NDB 7.4.3.		

Name	Description			
getNdbError()	Retrieves an error. (See Section 2.3.15, "The NdbError Structure".)			
getNdbErrorDetail(Retrieves extra error details.			
<pre>getNdbObjectName()</pre>	Retrieves the Ndb object name if one was set. Added in NDB 7.3.6.			
getNextEventOpInEp	Gets (the next event operation in this global checkpoint.			
getNextEventOpInEp	Gets (the next event operation in this global checkpoint, showing any received anyvalues. Added in NDB 7.3.20, 7.4.18, 7.5.9, and 7.6.4.			
<pre>getReference()</pre>	Retrieves a reference or identifier for the Ndb object instance.			
<pre>init()</pre>	Initializes an Ndb object and makes it ready for use.			
isConsistent()	Whether all received events are consistent. Deprecated in NDB 7.4.3.			
isConsistentGCI()	Whether all received events for a given global checkpoint are consistent. Deprecated in NDB 7.4.3.			
isExpectingHigherQ	Check whether there are new queued epochs, or there was a cluster failure event. Added in NDB 7.3.10 and 7.4.7.			
nextEvent()	Gets the next event from the queue. Deprecated in NDB 7.4.3.			
nextEvent2()	Gets the next event from the queue. Added i NDB 7.4.3.			
pollEvents()	Waits for an event to occur. Deprecated in NDB 7.4.3.			
pollEvents2()	Waits for an event to occur. Added in NDB 7.4.3.			
setDatabaseName()	Sets the name of the current database.			
setDatabaseSchemaN	Sets the name of the current database schema.			
setEventBufferQueu	Enables queuing of empty events. Added in NDB 7.4.11 and NDB 7.5.2.			
set_eventbuf_max_a	Sets the current allocated maximum size of the event buffer. Added in NDB 7.3.3.			
set_eventbuffer_fr	that should be available before buffering resumes, once the limit has been reached. Added in NDB 7.4.3.			
setNdbObjectName()	For debugging purposes: sets an arbitrary name for this Ndb object. Added in NDB 7.3.6.			

Name	Description	
	Begins a transaction. (See Section 2.3.25,	
	"The NdbTransaction Class".)	

Types

The Ndb class does not define any public typesbut does define three data structures, which are listed here:

- EventBuffermemoryUsage
- Key_part_ptr
- PartitionSpec.

Resource consumption by Ndb objects. An Ndb object consumes memory in proportion to the size of the largest operation performed over the lifetime of the object. This is particularly noticeable in cases of large transactions; use of one or both of BLOB or TEXT columns; or both. This memory is held for the lifetime of the object, and once used in this way by the Ndb object, the only way to free this memory is to destroy the object (and then to create a new instance if desired).



Note

The Ndb object is multithread safe in that each Ndb object can be handled by one thread at a time. If an Ndb object is handed over to another thread, then the application must ensure that a memory barrier is used to ensure that the new thread sees all updates performed by the previous thread.

Semaphores and mutexes are examples of easy ways to provide memory barriers without having to bother about the memory barrier concept.

It is also possible to use multiple ${\tt Ndb}$ objects to perform operations on different clusters in a single application. See Section 1.5, "Application-level partitioning", for conditions and restrictions applying to such usage.

Ndb Class Constructor

Description

This creates an instance of Ndb, which represents a connection to the NDB Cluster. All NDB API applications should begin with the creation of at least one Ndb object. This requires the creation of at least one instance of Ndb_cluster_connection, which serves as a container for a cluster connection string.

Signature

Parameters

The Ndb class constructor can take up to 3 parameters, of which only the first is required:

 ndb_cluster_connection is an instance of Ndb_cluster_connection, which represents a cluster connection string. (See Section 2.3.12, "The Ndb_cluster_connection Class".) Prior to NDB 7.3.8 and NDB 7.4.3, it was possible to delete the Ndb_cluster_connection used to create a given instance of Ndb without first deleting the dependent Ndb object. (Bug #19999242)

• catalogName is an optional parameter providing a namespace for the tables and indexes created in any connection from the Ndb object.

This is equivalent to what mysqld considers "the database".

The default value for this parameter is an empty string.

• The optional *schemaName* provides an additional namespace for the tables and indexes created in a given catalog.

The default value for this parameter is the string "def".

Return value

Destructor

An Ndb object.

The destructor for the Ndb class should be called in order to terminate an instance of Ndb. It requires no arguments, nor any special handling.

Ndb::closeTransaction()

Description

This is one of two NDB API methods provided for closing a transaction (the other being NdbTransaction::close()). You must call one of these two methods to close the transaction once it has been completed, whether or not the transaction succeeded.

If the transaction has not yet been committed, it is aborted when this method is called. See Ndb::startTransaction().

Signature

```
void closeTransaction
     (
         NdbTransaction *transaction
     )
```

Parameters

This method takes a single argument, a pointer to the NdbTransaction to be closed.

Return value

None (void).

Ndb::computeHash()

Description

This method can be used to compute a distribution hash value, given a table and its keys.

 ${\tt computeHash()}$ can be used only for tables that use native ${\tt NDB}$ partitioning.

Signature

Parameters

This method takes the following parameters:

- If the method call is successful, <code>hashvalueptr</code> is set to the computed hash value.
- A pointer to a table (see Section 2.3.27, "The Table Class").
- keyData is a null-terminated array of pointers to the key parts that
 are part of the table's distribution key. The length of each key part
 is read from metadata and checked against the passed value (see
 Ndb::Key_part_ptr).
- xfrmbuf is a pointer to temporary buffer used to calculate the hash value.
- xfrmbuflen is the length of this buffer.



Note

If xfrmbuf is NULL (the default), then a call to malloc() or free() is made automatically, as appropriate. computeHash() fails if xfrmbuf is not NULL and xfrmbuflen is too small.

Previously, it was assumed that the memory returned by the malloc() call would always be suitably aligned, which is not always the case. Beginning with NDB 7.3.2, when malloc() provides a buffer to this method, the buffer is explicitly aligned after it is allocated, and before it is actually used. (Bug #16484617)

Return value

0 on success, an error code on failure. If the method call succeeds, the computed hash value is made available through <code>hashvalueptr</code>.

Ndb::createEventOperation()

Description

This method creates a subscription to a database event.

NDB API event subscriptions do not persist after an NDB Cluster has been restored using ndb_restore; in such cases, all of the subscriptions must be recreated explicitly.

Signature

```
NdbEventOperation* createEventOperation
   (
      const char *eventName
   )
```

Parameters

This method takes a single argument, the unique *eventName* identifying the event to which you wish to subscribe.

Return value

A pointer to an NdbEventOperation object (or NULL, in the event of failure). See Section 2.3.16, "The NdbEventOperation Class".

Ndb::dropEventOperation()

Description

This method drops a subscription to a database event represented by an NdbEventOperation object.

Memory used by an event operation which has been dropped is not freed until the event buffer has been completely read. This means you must continue to call ${\tt pollEvents}()$ and ${\tt nextEvent}()$ in such cases until these methods return 0 and ${\tt NULL}$, respectively in order for this memory to be freed.

Signature

```
int dropEventOperation
    (
        NdbEventOperation *eventOp
    )
```

Parameters

This method requires a single input parameter, a pointer to an instance of NdbEventOperation.

Return value

0 on success; any other result indicates failure.

Ndb::EventBufferMemoryUsage

This section describes the EventBufferMemoryUsage structure.

Parent class Ndb

Description This structure was added in NDB 7.4.3 for working with event buffer memory usage statistics. It is used as an argument to

Ndb::get event buffer memory usage().

Attributes

EventBufferMemoryUsage has the attributes shown in the following table:

Table 2.26 EventBufferMemoryUsage structure attributes, with types, initial values, and descriptions

Name	Туре	Initial Value	Description
allocated_	byntæisgned	none	The total event buffer memory allocated, in bytes
used_bytes	unsigned	none	The total memory used, in bytes
usage_perc	ent signed	none	Event buffer memory usage, as a percent (100 * used_bytes / allocated_bytes)

Ndb::getDictionary()

Description

This method is used to obtain an object for retrieving or manipulating database schema information. This <code>Dictionary</code> object contains meta-information about all tables in the cluster.

The dictionary returned by this method operates independently of any transaction. See Section 2.3.3, "The Dictionary Class", for more information.

Signature

NdbDictionary::Dictionary* getDictionary

void
) const

Parameters None.

Return value An instance of the Dictionary class.

Ndb::getDatabaseName()

Description This method can be used to obtain the name of the current database.

Signature const char* getDatabaseName

void

Parameters None.

Return value The name of the current database.

Ndb::getDatabaseSchemaName()

Description This method can be used to obtain the current database schema name.

Signature const char* getDatabaseSchemaName

void

Parameters None.

Return value The name of the current database schema.

Ndb::getGClEventOperations() (DEPRECATED)

Description Iterates over distinct event operations which are part of the current GCI,

becoming valid after calling nextEvent(). You can use this method to obtain summary information for the epoch (such as a list of all tables)

before processing the event data.

This method is deprecated in NDB 7.4.3, and is subject to removal

in a future release. In NDB 7.4.3 and later, you should use

getNextEventOpInEpoch2() instead.

Signature const NdbEventOperation* getGCIEventOperations

Uint32* iter,
Uint32* event_types

Parameters An iterator and a mask of event types. Set *iter=0 to start.

Return value The next event operation; returns NULL when there are no more event

operations. If $event_types$ is not NULL, then after calling the method it

contains a bitmask of the event types received. .

Ndb::get_eventbuf_max_alloc()

Description Gets the maximum memory, in bytes, that can be used for

the event buffer. This is the same as reading the value of the

 ${\tt ndb_eventbuffer_max_alloc} \ \ {\tt system} \ \ {\tt variable} \ \ {\tt in} \ \ {\tt the} \ \ {\tt MySQL} \\ {\tt Server}.$

This method was added in NDB 7.3.3.

Signature unsigned get_eventbuf_max_alloc

(void)

Parameters None.

Return value The mamximum memory available for the event buffer, in bytes.

Ndb::get_eventbuffer_free_percent()

Description Gets ndb_eventbuffer_free_percent—that is, the percentage of

event buffer memory that should be available before buffering resumes, once ndb_eventbuffer_max_alloc has been reached. This value is calculated as $used * 100 / ndb_eventbuffer_max_alloc$, where used is the amount of event buffer memory actually used, in bytes.

This method was added in NDB 7.4.3.

Signature unsigned get_eventbuffer_free_percent

(void

Parameters The percentage (pct) of event buffer memory that must be present.

Valid range is 1 to 99 inclusive.

Return value None.

Ndb::get_event_buffer_memory_usage()

Description Gets event buffer usage as a percentage of

ndb_eventbuffer_max_alloc. Unlike

 ${\tt get_eventbuffer_free_percent(), this \ method \ makes}$

complete usage information available in the form of an

EventBufferMemoryUsage data structure.

This method was added in NDB 7.4.3.

Signature void get_event_buffer_memory_usage

EventBufferMemoryUsage&

Parameters A reference to an EventBufferMemoryUsage structure, which

receives the usage data.

Return value None.

Ndb::getHighestQueuedEpoch()

Description Added in NDB 7.4.3, this method supersedes getLatestGCI(), which

is now deprecated and subject to removal in a future NDB Cluster

release.

Prior to NDB 7.4.7, this method returned the highest epoch number in the event queue. In NDB 7.4.7 and later, it returns the highest epoch number found after calling pollEvents2() (Bug #20700220).

Signature

```
Uint64 getHighestQueuedEpoch
    (
     void
    )
```

Parameters

None.

Return value

The most recent epoch number, an integer.

Ndb::getLatestGCI() (DEPRECATED)

Description

Gets the index for the most recent global checkpoint.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should use getHighestQueuedEpoch() instead.

Signature

```
Uint64 getLatestGCI
    (
     void
)
```

Parameters

None.

Return value

The most recent GCI, an integer.

Ndb::getNdbError()

Description

This method provides you with two different ways to obtain an NdbError object representing an error condition. For more detailed information about error handling in the NDB API, see NDB Cluster API Errors.

Signature

The getNdbError() method actually has two variants.

The first of these simply gets the most recent error to have occurred:

```
const NdbError& getNdbError
    (
     void
)
```

The second variant returns the error corresponding to a given error code:

```
const NdbError& getNdbError
    (
      int errorCode
    )
```

Regardless of which version of the method is used, the NdbError object returned persists until the next NDB API method is invoked.

Parameters

To obtain the most recent error, simply call <code>getNdbError()</code> without any parameters. To obtain the error matching a specific <code>errorCode</code>,

invoke the method passing the code (an int) to it as a parameter. For a listing of NDB API error codes and corresponding error messages, see Section 2.4, "NDB API Errors and Error Handling".

Return value

An NdbError object containing information about the error, including its type and, where applicable, contextual information as to how the error arose. See Section 2.3.15, "The NdbError Structure", for details.

Ndb::getNdbErrorDetail()

Description

This method provides an easy and safe way to access any extra information about an error. Rather than reading these extra details from the NdbError object's details property (now now deprecated in favor of getNdbErrorDetail()-see Bug #48851). This method enables storage of such details in a user-supplied buffer, returning a pointer to the beginning of this buffer. In the event that the string containing the details exceeds the length of the buffer, it is truncated to fit.

getErrorDetail() provides the source of an error in the form of a string. In the case of a unique constraint violation (error 893), this string supplies the fully qualified name of the index where the problem originated, in the format <code>database-name/schema-name/table-name/index-name</code>, (NdbError.details, on the other hand, supplies only an index ID, and it is often not readily apparent to which table this index belongs.) Regardless of the type of error and details concerning this error, the string retrieved by <code>getErrorDetail()</code> is always null-terminated.

Signature

The getNdbErrorDetail() method has the following signature:

Parameters

To obtain detailed information about an error, call getNdbErrorDetail() with a reference to the corresponding NdbError object, a buffer, and the length of this buffer (expressed as an unsigned 32-bit integer).

Return value

When extra details about the *error* are available, this method returns a pointer to the beginning of the *buffer* supplied. As stated previously, if the string containing the details is longer than *bufferLength*, the string is truncated to fit. In the event that no addition details are available, getNdbErrorDetail() returns NULL.

Ndb::getNdbObjectName()

Description

If a name was set for the Ndb object prior to its initialization, you can retrieve it using this method. Used for debugging.

This method was added in NDB 7.3.6. (Bug #18419907)

Signature

```
const char* getNdbObjectName
  (
```

```
void
) const
```

Parameters

None.

Return value

The Ndb object name, if one has been set using setNdbObjectName(). Otherwise, this method returns 0.

Ndb::getNextEventOpInEpoch2()

Description

Iterates over individual event operations making up the current global checkpoint. Use following nextEvent2() to obtain summary information for the epoch, such as a listing of all tables, before processing event data.

Exceptional epochs do not have any event operations associated with them.

Signature

```
const NdbEventOperation* getNextEventOpInEpoch2
   (
     Uint32* iter,
     Uint32* event_types
)
```

Parameters

Set *iter* to 0 initially; this is *NULL* when there are no more events within this epoch. If *event_types* is not *NULL*, it holds a bitmask of the event types received.

Return value

A pointer to the next NdbEventOperation, if there is one.

Ndb::getNextEventOpInEpoch3()

Description

Iterates over individual event operations making up the current global checkpoint. Use following nextEvent2() to obtain summary information for the epoch, such as a listing of all tables, before processing event data. Is the same as getNextEventOpInEpoch3() but with the addition of a third argument which holds the merger of all AnyValues received, showing which bits are set for all operations on a given table.

Exceptional epochs do not have any event operations associated with them.

This method was added in NDB 7.3.20, 7.4.18, 7.5.9, and 7.6.4. (Bug #26333981)

Signature

```
const NdbEventOperation* getNextEventOpInEpoch2
   (
     Uint32* iter,
     Uint32* event_types
     Uint32* cumulative_any_value
   )
```

Parameters

Set *iter* to 0 initially; this is *NULL* when there are no more events within this epoch. If *event_types* is not *NULL*, it holds a bitmask of the event types received. If *cumulative_any_value* is not *NULL*, it holds the merger of all AnyValues received.

Return value

A pointer to the next NdbEventOperation, if there is one.

Ndb::getReference()

Description This method can be used to obtain a reference to a given Ndb

object. This is the same value that is returned for a given operation

corresponding to this object in the output of DUMP 2350.

Signature Uint32 getReference

void

Parameters None.

Return value A 32-bit unsigned integer.

Ndb::init()

Description This method is used to initialize an Ndb object.

Signature int init

(
int maxNoOfTransactions = 4
)

Parameters The init() method takes a single parameter

maxNoOfTransactions of type integer. This parameter specifies the maximum number of parallel NdbTransaction objects that can be handled by this instance of Ndb. The maximum permitted value for maxNoOfTransactions is 1024; if not specified, it defaults to 4.

Each scan or index operation uses an extra NdbTransaction object.

Return value

This method returns an int, which can be either of the following two values:

• 0: indicates that the Ndb object was initialized successfully.

• -1: indicates failure.

Ndb::isConsistent() (DEPRECATED)

Description

Check if all events are consistent. If a node failure occurs when resources are exhausted, events may be lost and the delivered event data might thus be incomplete. This method makes it possible to determine if this is the case.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should instead use NdbEventOperation::getEventType2() to determine the type of event—in this instance, whether the event is of type TE_INCONSISTENT. See Event::TableEvent.

Signature

```
bool isConsistent
(
Uint64& gci
)
```

Parameters

A reference to a global checkpoint index. This is the first inconsistent GCI found, if any.

Return value

true if all events are consistent.

Ndb::isConsistentGCI() (DEPRECATED)

Description

If a node failure occurs when resources are exhausted, events may be lost and the delivered event data might thus be incomplete. This method makes it possible to determine if this is the case by checking whether all events in a given GCI are consistent.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should instead use NdbEventOperation::getEventType2() to determine the type of event—in this instance, whether the event is of type TE_INCONSISTENT. See Event::TableEvent.

Signature

```
bool isConsistentGCI
    (
      Uint64 gci
)
```

Parameters

A global checkpoint index.

Return value

true if this GCI is consistent; false indicates that the GCI may be possibly inconsistent.

Ndb::isExpectingHigherQueuedEpochs()

Description

Check whether higher queued epochs have been seen by the last invocation of Ndb::pollEvents2(), or whether a **TE_CLUSTER_FAILURE** event was found.

It is possible, after a cluster failure has been detected, for the highest queued epoch returned by pollEvents2() not to be increasing any longer. In this case, rather than poll for more events, you should instead consume events with nextEvent() until it detects a TE_CLUSTER_FAILURE is detected, then reconnect to the cluster when it becomes available again.

This method was added in NDB 7.3.10 and 7.4.7 (Bug #18753887).

Signature

```
bool isExpectingHigherQueuedEpochs
    (
       void
    )
```

Parameters

None.

Return value

True if queued epochs were seen by the last pollEvents2() call or, in the event of cluster failure.

Ndb::Key_part_ptr

This section describes the Key_part_ptr structure.

Parent class

Ndb

Description

Key_part_ptr provides a convenient way to define key-part data when starting transactions and computing hash values, by passing in pointers to distribution key values. When the distribution key has

Attributes

multiple parts, they should be passed as an array, with the last part's pointer set equal to NULL. See Ndb::startTransaction(), and Ndb::computeHash(), for more information about how this structure is used.

A Key_part_ptr has the attributes shown in the following table:

Table 2.27 Key_part_ptr structure attributes, with types, initial values, and descriptions

Attribute	Туре	Initial Value	Description
ptr	const void*	none	Pointer to one or more distribution key values
len	unsigned	none	The length of the pointer

Ndb::nextEvent() (DEPRECATED)

Description

Returns the next event operation having data from a subscription queue.

Beginning with NDB 7.3.6, this method clears inconsistent data events from the event queue when processing them. In order to able to clear all such events in these and later versions, applications must call this method even in cases when pollEvents() has already returned 0. (Bug #18716991)

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should use nextEvent2() instead.

Signature

```
NdbEventOperation* nextEvent
(
void
)
```

Parameters

None.

Return value

This method returns an NdbEventOperation object representing the next event in a subscription queue, if there is such an event. If there is no event in the queue, it returns NULL instead.

Ndb::nextEvent2()

Description

Returns the event operation associated with the data dequeued from the event queue. This should be called repeatedly after pollEvents2() populates the queue, until the event queue is empty.

Added in NDB 7.4.3, this method supersedes nextEvent(), which is now deprecated and subject to removal in a future NDB Cluster release.

After calling this method, use NdbEventOperation::getEpoch() to determine the epoch, then check the type of the returned event data using NdbEventOperation::getEventType2(). Handling must be provided for all exceptional TableEvent types, including TE_EMPTY, TE INCONSISTENT, and TE OUT OF MEMORY (also introduced in

NDB 7.4.3). No other NdbEventOperation methods than the two named here should be called for an exceptional epoch. Returning empty epochs (TE_EMPTY) may flood applications when data nodes are idle. If this is not desirable, applications should filter out any empty epochs.

Signature

```
NdbEventOperation* nextEvent2
(
void
)
```

Parameters

None.

Return value

This method returns an NdbEventOperation object representing the next event in an event queue, if there is such an event. If there is no event in the queue, it returns NULL instead.

Ndb::PartitionSpec

This section provides information about the PartitionSpec structure.

Parent class

Ndb

Description

A PartitionSpec is used for describing a table partition using any one of the following criteria:

- A specific partition ID for a table with user-defined partitioning.
- An array made up of a table's distribution key values for a table with native partitioning.
- A row in NdbRecord format containing a natively partitioned table's distribution key values.

Attributes

A PartitionSpec has two attributes, a SpecType and a Spec which is a data structure corresponding to that SpecType, as shown in the following table:

Table 2.28 PartitionSpec attributes with the SpecType values, data structures, and descriptions for each attribute.

SpecType Enumeration	SpecType Value (Uint32)	Data Structure	Description
PS_NONE	0	none	No partitioning information is provided.
PS_USER_DEFINED	1	Ndb::Partitic	user-defined partitioning, a specific partition is identified by its partition ID.
PS_DISTR_KEY_PAR	2_PTR	Ndb::Partitic	having native partitioning, an array containing the

SpecType Enumeration	SpecType Value (Uint32)	Data Structure	Description
			table's distribution key values is used to identify the partition.
PS_DISTR_KEY_RE	O RD	Ndb::Partitio	risperartition is cord identified using a natively partitioned table's distribution key values, as contained in a row given in NdbRecord format.

UserDefined structure. This structure is used when the SpecType is PS_USER_DEFINED.

Table 2.29 Attribute types of the partitionId attribute of the PS_USER_DEFINED SpecType

Attribute	Туре	Description
partitionId	Uint32	The partition ID for the desired table.

KeyPartPtr structure. This structure is used when the SpecType is PS_DISTR_KEY_PART_PTR.

Table 2.30 Attributes of the PS_DISTR_KEY_PART_PTR SpecType, with attribute types and descriptions

Attribute	Туре	Description
tableKeyParts	Key_part_ptr	Pointer to the distribution key values for a table having native partitioning.
xfrmbuf	void*	Pointer to a temporary buffer used for performing calculations.
xfrmbuflen	Uint32	Length of the temporary buffer.

KeyRecord structure. This structure is used when the SpecType is PS_DISTR_KEY_RECORD.

Table 2.31 PS_DISTR_KEY_RECORD SpecType attributes, with attribute types and descriptions

Attribute	Туре	Description
keyRecord	NdbRecord	A row in NdbRecord format, containing a table's distribution keys.
keyRow	const char*	The distribution key data.
xfrmbuf	void*	Pointer to a temporary buffer used for performing calculations.
xfrmbuflen	Uint32	Length of the temporary buffer.

Definition from Ndb.hpp. Because this is a fairly complex structure, we here provide the original source-code definition of PartitionSpec, as given in storage/ndb/include/ndbapi/Ndb.hpp:

```
struct PartitionSpec
   Size of the PartitionSpec structure.
 static inline Uint32 size()
      return sizeof(PartitionSpec);
  enum SpecType
                          = 0,
   PS_NONE
   PS_USER_DEFINED
                          = 1.
   PS_DISTR_KEY_PART_PTR = 2,
   PS_DISTR_KEY_RECORD
 Uint32 type;
  union
   struct {
     Uint32 partitionId;
    } UserDefined;
   struct {
     const Key_part_ptr* tableKeyParts;
      void* xfrmbuf;
     Uint32 xfrmbuflen;
    } KeyPartPtr;
   struct {
      const NdbRecord* keyRecord;
      const char* keyRow;
      void* xfrmbuf;
      Uint32 xfrmbuflen;
    } KeyRecord;
  };
};
```

Ndb::pollEvents()

Description

This method waits for a GCP to complete. It is used to determine whether any events are available in the subscription queue.

This method waits for the next *epoch*, rather than the next GCP. See Section 2.3.16, "The NdbEventOperation Class", for more information.

In NDB 7.4.3 and later, this method is deprecated and subject to removal in a future NDB Cluster release; use pollEvents2() instead.

Prior to NDB 7.4.7, pollEvents() was not compatible with the exceptional TableEvent types added in NDB 7.4.3 (Bug #20646496); in NDB 7.4.7 and later, pollEvents() is compatible with these event types, as described later in this section.

Signature

```
int pollEvents
   (
    int    maxTimeToWait,
    Uint64* latestGCI = 0
)
```

Parameters

This method takes the two parameters listed here:

• The maximum time to wait, in milliseconds, before "giving up" and reporting that no events were available (that is, before the method automatically returns 0).

A negative value causes the wait to be indefinite and never time out. This is not recommended (and is not supported by the successor method pollEvents2()).

• The index of the most recent global checkpoint. Normally, this may safely be permitted to assume its default value, which is 0.

pollEvents() returns a value of type int, which may be interpreted
as follows:

- > 0: There are events available in the queue.
- 0: There are no events available.
- In NDB 7.4.7 and later, a negative value indicates failure and NDB_FAILURE_GCI (~(Uint64)0) indicates cluster failure (Bug #18753887); 1 is returned when encountering an exceptional event, except when only TE_EMPTY events are found, as described later in this section.

In NDB 7.4.7 and later, when pollEvents() finds an exceptional event at the head of the event queue, the method returns 1 and otherwise behaves as follows:

- Empty events (TE_EMPTY) are removed from the event queue head until an event containing data is found. When this results in the entire queue being processed without encountering any data, the method returns 0 (no events available) rather than 1. This behavior makes this event type transparent to an application using pollEvents().
- After encountering an event containing inconsistent data
 (TE_INCONSISTENT) due to data node buffer overflow, the next
 call to nextEvent() call removes the inconsistent data event data
 from the event queue, and returns NULL. You should check the
 inconsistency by calling isConsistent() immediately thereafter.

Important: Although the inconsistent event data is removed from the event queue by calling nextEvent(), information about the inconsistency is removed only by another nextEvent() call following this, that actually finds an event containing data.

 When pollEvents() finds a data buffer overflow event (TE_OUT_OF_MEMORY), the event data is added to the event queue whenever event buffer usage exceeds ndb_eventbuffer_max_alloc. In this case, the next call to nextEvent() exits the process.

Return value

Ndb::pollEvents2()

Description

Waits for an event to occur. Returns as soon as any event data is available. This method also moves an epoch's complete event data to the event queue.

Added in NDB 7.4.3, this method supersedes pollEvents(), which is now deprecated and subject to removal in a future NDB Cluster release.

Signature

```
int pollEvents2
   (
    int aMillisecondNumber,
    Uint64* highestQueuedEpoch = 0
)
```

Parameters

This method takes the two parameters listed here:

• The maximum time to wait, in milliseconds, before giving up and reporting that no events were available (that is, before the method automatically returns 0).

In NDB 7.4.7 and later, specifying a negative value for this argument causes pollEvents2() to return -1, indicating an error (Bug #20762291).

The index of the highest queued epoch. Normally, this may safely be
permitted to assume its default value, which is 0. If this value is not
NULL and new event data is available in the event queue, it is set to
the highest epoch found in the available event data.

Return value

pollEvents2() returns an integer whose value can be interpreted as follows:

- > 0: There are events available in the queue.
- 0: There are no events available.
- < 0: Indicates failure (possible error).

Ndb::setDatabaseName()

Description

This method is used to set the name of the current database.

Signature

```
void setDatabaseName
   (
     const char *databaseName
   )
```

Parameters

setDatabaseName() takes a single, required parameter, the name of the new database to be set as the current database.

Return value

None.

Ndb::setDatabaseSchemaName()

Description

This method sets the name of the current database schema.

Signature

```
void setDatabaseSchemaName
   (
      const char *databaseSchemaName
   )
```

Parameters The name of the database schema.

Return value None.

Ndb::setEventBufferQueueEmptyEpoch()

Description

Queuing of empty epochs is disabled by default. This method can be used to enable such queuing, in which case any new, empty epochs entering the event buffer following the method call are queued.

When queuing of empty epochs is enabled, nextEvent() associates an empty epoch to one and only one of the subscriptions (event operations) connected to the subscribing Ndb object. This means that there can be no more than one empty epoch per subscription, even though the user may have many subscriptions associated with the same Ndb object.

setEventBufferQueueEmptyEpoch() has no associated getter method. This is intentional, and is due to the fact this setter applies to queuing *new* epochs, whereas the queue itself may still reflect the state of affairs that existed prior to invoking the setter. Thus, during a transition period, an empty epoch might be found in the queue even if queuing is turned off.

setEventBufferQueueEmptyEpoch() was added in NDB 7.4.11 and NDB 7.5.2.

Signature

```
void setEventBufferQueueEmptyEpoch
  (
    bool queue_empty_epoch
  )
```

Parameters

This method takes a single input parameter, a boolean. Invoking the method with true enables queuing of empty events; passing false to the method disables such queuing.

Return value None.

Ndb::set_eventbuf_max_alloc()

Description

Sets the maximum memory, in bytes, that can be used for the event buffer. This has the same effect as setting the value of the ndb_eventbuffer_max_alloc system variable in the MySQL Server.

This method was added in NDB 7.3.3.

Signature

Parameters

The desired maximum size for the event buffer, in bytes.

Return value

None.

Ndb::set_eventbuffer_free_percent()

Description

Sets ndb_eventbuffer_free_percent—that is, the percentage of event buffer memory that should be available before buffering resumes, once ndb_eventbuffer_max_alloc has been reached.

This method was added in NDB 7.4.3.

Signature

```
int set_eventbuffer_free_percent
    (
        unsigned pct
)
```

Parameters

The percentage (pct) of event buffer memory that must be present. Valid range is 1 to 99 inclusive.

Return value

The value that was set.

Ndb::setNdbObjectName()

Description

Starting with NDB 7.3.6, you can set an arbitrary, human-readable name to identify an Ndb object for debugging purposes. This name can then be retrieved using getNdbObjectName(). (Bug #18419907) This must be done prior to calling init() for this object; trying to set a name after initialization fails with an error.

You can set a name only once for a given Ndb object; subsequent attempts after the name has already been set fail with an error.

Signature

```
int setNdbObjectName
   (
      const char* name
   )
```

Parameters

A name that is intended to be human-readable.

Return value

0 on success.

Ndb::startTransaction()

Description

This method is used to begin a new transaction. There are three variants, the simplest of these using a table and a partition key or partition ID to specify the transaction coordinator (TC). The third variant makes it possible for you to specify the TC by means of a pointer to the data of the key.

When the transaction is completed it must be closed using NdbTransaction::close() or Ndb::closeTransaction().

Failure to do so aborts the transaction. This must be done regardless of the transaction's final outcome, even if it fails due to an error.

See Ndb::closeTransaction(), and NdbTransaction::close(), for more information.

Signature

```
NdbTransaction* startTransaction
(
    const NdbDictionary::Table* table = 0,
    const char* keyData = 0,
    Uint32* keyLen = 0
)
```

Parameters

This method takes the following three parameters:

- table: A pointer to a Table object. This is used to determine on which node the transaction coordinator should run.
- keyData: A pointer to a partition key corresponding to table.
- keyLen: The length of the partition key, expressed in bytes.

Distribution-aware forms of startTransaction(). It is also possible to employ *distribution awareness* with this method; that is, to suggest which node should act as the transaction coordinator.

Signature

Parameters

When specifying the transaction coordinator, this method takes the four parameters listed here:

- A pointer to a table (Table object) used for deciding which node should act as the transaction coordinator.
- A null-terminated array of pointers to the values of the distribution key columns. The length of the key part is read from metadata and checked against the passed value.

An Ndb::Key part ptr is defined as shown in Ndb::Key part ptr.

A pointer to a temporary buffer, used to calculate the hash value.

If xfrmbuf is NULL (the default), then a call to malloc() or free() is made automatically, as appropriate. startTransaction() fails if xfrmbuf is not NULL and xfrmbuf len is too small.

• The length of the buffer.

Return value

On success, an $\mathtt{NdbTransaction}$ object. In the event of failure, \mathtt{NULL} is returned.

Example

Suppose that the table's partition key is a single BIGINT column. Then you would declare the distribution key array as shown here:

```
Key_part_ptr distkey[2];
```

The value of the distribution key would be defined as shown here:

```
unsigned long long distkeyValue= 23;
```

The pointer to the distribution key array would be set as follows:

```
distkey[0].ptr= (const void*) &distkeyValue;
```

The length of this pointer would be set accordingly:

```
distkey[0].len= sizeof(distkeyValue);
```

The distribution key array must terminate with a NULL element. This is necessary to avoid to having an additional parameter providing the number of columns in the distribution key:

```
distkey[1].ptr= NULL;
distkey[1].len= NULL;
```

Setting the buffer to NULL permits startTransaction() to allocate and free memory automatically:

```
xfrmbuf= NULL;
xfrmbuflen= 0;
```



Note

You can also specify a buffer to save having to make explicit malloc() and free() calls, but calculating an appropriate size for this buffer is not a simple matter; if the buffer is not NULL but its length is too short, then the startTransaction() call fails. However, if you choose to specify the buffer, 1 MB is usually a sufficient size.

Now, when you start the transaction, you can access the node that contains the desired information directly.

Another distribution-aware version of this method makes it possible for you to specify a table and partition (using the partition ID) as a hint for selecting the transaction coordinator, and is defined as shown here:

```
NdbTransaction* startTransaction
    (
        const NdbDictionary::Table* table,
        Uint32 partitionId
    )
```

In the event that the cluster has the same number of data nodes as it has fragment replicas, specifying the transaction coordinator gains no improvement in performance, since each data node contains the entire database. However, where the number of data nodes is greater than the number of fragment replicas (for example, where NoOfReplicas is set equal to 2 in a cluster with four data nodes), you should see a marked improvement in performance by using the distribution-aware version of this method.

It is still possible to use this method as before, without specifying the transaction coordinator. In either case, you must still explicitly close the transaction, whether or not the call to startTransaction() was successful.

2.3.12 The Ndb_cluster_connection Class

This section provides information about the Ndb_cluster_connection class, which models a connection by a management server (ndb_mgmd) to a set of data nodes.

Ndb_cluster_connection Class Overview

- Ndb_cluster_connection Class Constructor
- Ndb_cluster_connection::connect()
- Ndb_cluster_connection::get_auto_reconnect()
- Ndb_cluster_connection::get_latest_error()
- Ndb_cluster_connection::get_latest_error_msg()
- Ndb cluster connection::get max adaptive send time()
- Ndb_cluster_connection::get_next_ndb_object()
- Ndb_cluster_connection::get_num_recv_threads()
- Ndb_cluster_connection::get_recv_thread_activation_threshold()
- Ndb_cluster_connection::get_system_name()
- ndb_cluster_connection::lock_ndb_objects()
- Ndb_cluster_connection::set_auto_reconnect()
- Ndb_cluster_connection::set_data_node_neighbour()
- Ndb_cluster_connection::set_max_adaptive_send_time()
- Ndb_cluster_connection::set_name()
- Ndb_cluster_connection::set_num_recv_threads()
- Ndb_cluster_connection::set_optimized_node_selection()
- Ndb_cluster_connection::set_recv_thread_activation_threshold()
- Ndb_cluster_connection::set_service_uri()
- Ndb_cluster_connection::set_recv_thread_cpu()
- Ndb cluster connection::set timeout()
- Ndb_cluster_connection::unlock_ndb_objects()
- Ndb_cluster_connection::unset_recv_thread_cpu()
- Ndb_cluster_connection::wait_until_ready()

Ndb_cluster_connection Class Overview

Parent class None
Child classes None

Description An NDB application program should begin with the creation of a single

Ndb_cluster_connection object, and typically makes use of a single Ndb_cluster_connection. The application connects to a cluster management server when this object's connect() method is called. By using the wait_until_ready() method it is possible to

wait for the connection to reach one or more data nodes.

Methods

An instance of Ndb_cluster_connection is used to create an Ndb object. Prior to NDB 7.3.8 and NDB 7.4.3, it was possible to delete the Ndb_cluster_connection used to create a given instance of Ndb without first deleting the dependent Ndb object. (Bug #19999242)

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.32 Ndb_cluster_connection class methods and descriptions

Name	Description
Ndb_cluster_connec	Constructor; creates a connection to a cluster of data nodes.
connect()	Connects to a cluster management server.
get_auto_reconnect	Gets the auto-reconnection setting for API nodes using this Ndb_cluster_connection.
<pre>get_latest_error()</pre>	Whether or not the most recent attempt to connect succeeded.
get_latest_error_m	sighthe most recent attempt to connect failed, provides the reason.
get_max_adaptive_s	Get_timeout) before adaptive send forces the sending of all pending signals.
get_num_recv_thread	Get)number of receive threads.
get_next_ndb_object	Used to iterate through multiple Ndb objects.
get_recv_thread_ac	Getactivation level for bound receive threads.
<pre>get_system_name()</pre>	Get the cluster's system name.
lock_ndb_objects()	Disables the creation of new Ndb objects.
set_auto_reconnect	(Enables or disables auto- reconnection of API nodes using this Ndb_cluster_connection.
set_data_node_neight	Sets:a(neighbor node for for optimal transaction coordinator placement
set_max_adaptive_s	Set_timeout to elapse before adaptive send forces the sending of all pending signals.
set_name()	Provides a name for the connection
set_num_recv_thread	Set)number of receive threads to be bound.
set_recv_thread_cp	Set one or more CPUs to bind receive threads to.
set_optimized_node	Used to control node-selection behavior.
set_service_uri()	Set a URI for publication in the ndbinfo.processes table
set_timeout()	Sets a connection timeout
unlock_ndb_objects	(Enables the creation of new Ndb objects.

Name	Description
unset_recv_thread_	unset the binding of the receive thread to one or more CPUs.
<pre>wait_until_ready()</pre>	Waits until a connection with one or more data nodes is successful.

Ndb_cluster_connection Class Constructor

Description

This method creates a connection to an NDB Cluster, that is, to a cluster of data nodes. The object returned by this method is required in order to instantiate an Ndb object. Thus, every NDB API application requires the use of an Ndb_cluster_connection.

Signatures

Ndb_cluster_connection has two constructors. The first of these is shown here:

```
Ndb_cluster_connection
    (
        const char* connection_string = 0
    )
```

The second constructor takes a node ID in addition to the connection string argument. Its signature and parameters are shown here:

```
Ndb_cluster_connection
   (
      const char* connection_string,
      int force_api_nodeid
   )
```

Parameters

The first version of the constructor requires a single *connection_string* parameter, pointing to the location of the management server.

The second version of the constructor takes two arguments, a <code>connection_string</code> and the node ID (<code>force_api_nodeid</code>) to be used by this API node. This node ID overrides any node ID value set in the <code>connection_string</code> argument.

Return value

An instance of Ndb cluster connection.

Ndb_cluster_connection::connect()

Description

This method connects to a cluster management server.

Signature

```
int connect
   (
    int retries = 30,
    int delay = 1,
    int verbose = 0
)
```

Parameters

This method takes three parameters, all of which are optional:

• retries specifies the number of times to retry the connection in the event of failure. The default value is 30.

0 means that no additional attempts to connect are made in the event of failure; using a negative value for *retries* results in the connection attempt being repeated indefinitely.

- The *delay* represents the number of seconds between reconnect attempts; the default is 1 second.
- verbose indicates whether the method should output a report of its progress, with 1 causing this reporting to be enabled; the default is 0 (reporting disabled).

Return value

This method returns an int, which can have one of the following 3 values:

- 0: The connection attempt was successful.
- 1: Indicates a recoverable error.
- -1: Indicates an unrecoverable error.

Ndb_cluster_connection::get_auto_reconnect()

Description This method retrieves the current AutoReconnect setting for a given

Ndb_cluster_connection. For more detailed information, see

Ndb_cluster_connection::set_auto_reconnect().

Signature int get_auto_reconnect

void

Parameters None.

Return value An integer value 0 or 1, corresponding to the current AutoReconnect

setting in effect for for this connection. 0 forces API nodes to use new connections to the cluster, while 1 enables API nodes to re-use existing

connections.

Ndb_cluster_connection::get_latest_error()

Description This method can be used to determine whether or not the most recent

connect() attempt made by this Ndb_cluster_connection
succeeded. If the connection succeeded, get_latest_error()
returns 0; otherwise, it returns 1. If the connection attempt failed, use
Ndb_cluster_connection::get_latest_error_msg() to obtain

an error message giving the reason for the failure.

Signature int get_latest_error

void
) const

Parameters None.

Return value 1 or 0. A return value of 1 indicates that the latest attempt to connect

failed; if the attempt succeeded, a 0 is returned.

Ndb_cluster_connection::get_latest_error_msg()

Description If the most recent connection attempt by this

 $\begin{tabular}{ll} Ndb_cluster_connection failed (as determined by calling $\tt get_latest_error())$, this method provides an error message $\tt and the connection failed (as determined by calling the connection failed (as$

supplying information about the reason for the failure.

Signature const char* get_latest_error_msg

void
) const

Parameters None.

Return value A string containing an error message describing a failure by

Ndb_cluster_connection::connect(). If the most recent connection attempt succeeded, an empty string is returned.

Ndb_cluster_connection::get_max_adaptive_send_time()

Description Get the minimum time in milliseconds that is permit to lapse before the

adaptive send mechanism forces all pending signals to be sent.

Signature Uint32 get_max_adaptive_send_time

(

Parameters None.

Return value Wait time as a number of milliseconds. This should always be a value

between 0 and 10, inclusive.

Ndb cluster connection::get next ndb object()

Description This method is used to iterate over a set of Ndb objects, retrieving them

one at a time.

Signature const Ndb* get_next_ndb_object

const Ndb* p

Parameters This method takes a single parameter, a pointer to the last Ndb object to

have been retrieved or NULL.

Return value Returns the next Ndb object, or NULL if no more Ndb objects are

available.

Iterating over Ndb objects. To retrieve all existing Ndb objects, perform the following three steps:

- 1. Invoke the <code>lock_ndb_objects()</code> method. This prevents the creation of any new instances of <code>Ndb until</code> the <code>unlock_ndb_objects()</code> method is called.
- 2. Retrieve the first available Ndb object by passing NULL to get_next_ndb_object(). You can retrieve the second Ndb object by passing the pointer retrieved by the first call to the next get_next_ndb_object() call, and so on. When a pointer to the last available Ndb instance is used, the method returns NULL.
- 3. After you have retrieved all desired Ndb objects, you should re-enable Ndb object creation by calling the unlock_ndb_objects() method.

Ndb_cluster_connection::get_num_recv_threads()

Description Get the number of receiver threads.

Signature int get_num_recv_threads

void
) const

Parameters None.

Return value The number of receiver threads.

Ndb_cluster_connection::get_recv_thread_activation_threshold()

Description Get the level set for activating the receiver thread bound by

set_recv_thread_cpu().

Signature int get_recv_thread_activation_threshold

void
) const

Parameters None.

Return value An integer threshold value. See

Ndb_cluster_connection::set_recv_thread_activation_threshold(), for

information about interpreting this value.

Ndb_cluster_connection::get_system_name()

Description Gets the system name from the cluster configuration. This is the

value of the Name system configuration parameter set in the cluster's

config.ini configuration file.

Signature const char* get_system_name

(void) const

Parameters None.

Return value The cluster system name. If not set in the cluster configuration file,

this is a generated value in the form $MC_timestamp$ (for example, $MC_20170426182343$), using the time that the management server

was started.

ndb_cluster_connection::lock_ndb_objects()

Description Calling this method prevents the creation of new instances of the Ndb

class. This method must be called prior to iterating over multiple Ndb

objects using get_next_ndb_object().

Signature void lock_ndb_objects

void
) const

This method was made const in NDB 7.3.15, 7.4.13, and 7.5.4 (Bug #23709232).

For more information, see

Ndb_cluster_connection::get_next_ndb_object().

138

Parameters None.

Return value None.

Ndb_cluster_connection::set_auto_reconnect()

Description

An API node that is disconnected from the cluster is forced to use a new connection object to reconnect, unless this behavior is overridden by setting AutoReconnect = 1 in the config.ini file or calling this method with 1 as the input value. Calling the method with 0 for the value has the same effect as setting the AutoReconnect configuration parameter (also introduced in those NDB Cluster versions) to 0; that is, API nodes are forced to create new connections.



Important

When called, this method overrides any setting for AutoReconnect made in the config.ini file.

For more information, see Defining SQL and Other API Nodes in an NDB Cluster.

Signature

```
void set_auto_reconnect
    (
    int value
)
```

Parameters

A *value* of 0 or 1 which determines API node reconnection behavior. 0 forces API nodes to use new connections (Ndb_cluster_connection objects); 1 permits API nodes to re-use existing connections to the cluster.

Return value None.

Ndb_cluster_connection::set_data_node_neighbour()

Description

Set data node neighbor of the connection, used for optimal placement of the transaction coordinator. This method be used after creating the Ndb_cluster_connection, but prior to starting any query threads. This is due to the fact that this method may change the internal state of the Ndb_cluster_connection shared by the threads using it. This state is not thread-safe; changing it can lead to non-optimal node selection at the time of the change.

You can use the ndb_data_node_neighbour server system variable to set a data node neighbor for an NDB Cluster SQL node.

This method was added in NDB 7.5.2.

Signature

```
void set_data_node_neighbour
    (
      Uint32 neighbour_node
    )
```

Parameters

The ID of the node to be used as the neighbor.

Return value None.

Ndb_cluster_connection::set_max_adaptive_send_time()

Description Set the minimum time in milliseconds that is permit to lapse before the

adaptive send mechanism forces all pending signals to be sent.

Signature void set_max_adaptive_send_time

Uint32 milliseconds

Parameters Wait time in milliseconds. The range is 0-10, with 10 being the default

value.

Return value None.

Ndb_cluster_connection::set_name()

Description Sets a name for the connection. If the name is specified, it is reported in

the cluster log.

Signature void set_name

(const char* name

Parameters The *name* to be used as an identifier for the connection.

Return value None.

Ndb_cluster_connection::set_num_recv_threads()

Description Set the number of receiver threads bound to the CPU (or CPUs)

determined using set_recv_thread_cpu() and with the threshold

set by set_recv_thread_activation_threshold().

This method should be invoked before trying to connect to any other

nodes.

Signature int set_num_recv_threads

(
Uint32 num_recv_threads
)

Parameters The number of receive threads. The only supported value is 1.

Return value —1 indicates an error; any other value indicates success.

Ndb_cluster_connection::set_optimized_node_selection()

Description This method can be used to override the connect() method's default

behavior as regards which node should be connected to first.

Signature void set_optimized_node_selection

(
int value
)

Parameters An integer *value*.

Return value None.

Ndb_cluster_connection::set_recv_thread_activation_threshold()

Description

Set the level for activating the receiver thread bound by set_recv_thread_cpu(). Below this level, normal user threads are used to receive signals.

Signature

```
int set_recv_thread_activation_threshold
   (
      Uint32 threshold
   )
```

Parameters

An integer threshold value. 16 or higher means that receive threads are never used as receivers. 0 means that the receive thread is always active, and that retains poll rights for its own exclusive use, effectively blocking all user threads from becoming receivers. In such cases care should be taken to ensure that the receive thread does not compete with the user thread for CPU resources; it is preferable for it to be locked to a CPU for its own exclusive use. The default is 8.

Return value

-1 indicates an error; any other value indicates success.

Ndb_cluster_connection::set_service_uri()

Description

Beginning with NDB 7.5.7 and NDB 7.6.2, this method can be used to create a URI for publication in service_URI column of the the application's row in the ndbinfo.processes table.

Provided that this method is called prior to invoking <code>connect()</code>, the service URI is published immediately upon connection; otherwise, it is published after a delay of up to <code>HeartbeatIntervalDbApi</code> milliseconds.

Signature

```
int set_service_uri
   (
      const char* scheme,
      const char* host,
      int port,
      const char* path
   )
```

Parameters

This method takes the parameters listed here:

- scheme: The URI scheme. This is resticted to lowercase letters, numbers, and the characters ., +, and - (period, plus sign, and dash). The maximu length is 16 characters; any characters over this limit are truncated.
- host: The URI network address or host name. The maximum length is 48 characters (sufficient for an IPv6 network address); any characters over this limit are truncated. If null, each data node reports the network address from its own connection to this node. An Ndb_cluster_connection that uses multiple transporters or network addresses to connect to different data nodes is reflected in multiple rows in the ndbinfo.processes table.
- port: The URI port. This is not published if it is equal to 0.
- path: The URI path, possibly followed by a query string beginning with?. The maximum combined length of the path and query may not exceed 128 characters; if longer, it is truncated to this length.

The path may not begin with a double slash (//).

Return value

0 on success, 1 in the event of a syntax error.

Ndb cluster connection::set recv thread cpu()

Description

Set the CPU or CPUs to which the receiver thread should be bound. Set the level for activating the receiver thread as a receiver by invoking set recy thread activation threshold(). Unset the binding for this receiver thread by invoking unset_recv_thread_cpu().

Signature

```
int set_recv_thread_cpu
     Uint16* cpuid_array,
     Uint32 array_len,
      Uint32 recv_thread_id = 0
```

Parameters

This method takes three parameters, listed here:

- An array of one or more CPU IDs to which the receive thread should be bound
- · The length of this array
- The thread ID of the receive thread to bind. The default value is 0.

Return value

1 indicates an error; any other value indicates success.

Ndb_cluster_connection::set_timeout()

Description

Used to set a timeout for the connection, to limit the amount of time that we may block when connecting.

This method is actually a wrapper for the MGM API function ndb mgm set timeout().

Signature

```
int set timeout
      int timeout_ms
```

Parameters

The length of the timeout, in milliseconds (timeout_ms). Currently, only multiples of 1000 are accepted.

Return value

0 on success; any other value indicates failure.

Ndb_cluster_connection::unlock_ndb_objects()

Description

This method undoes the effects of the lock_ndb_objects() method, making it possible to create new instances of Ndb. unlock_ndb_objects() should be called after you have finished retrieving Ndb objects using the get_next_ndb_object() method.

Signature

```
void unlock_ndb_objects
    (
      void
    ) const
```

This method was made const in NDB 7.3.15, 7.4.13, and 7.5.4 (Bug #23709232).

For more information, see

Ndb_cluster_connection::get_next_ndb_object().

Parameters None.

Return value None.

Ndb_cluster_connection::unset_recv_thread_cpu()

Description Unset the CPU or CPUs to which the receiver thread was bound using

set_recv_thread_cpu().

Signature int unset_recv_thread_cpu (

Uint32 recv_thread_id
)

Parameters The thread ID of the receiver thread to be unbound.

Return value —1 indicates an error; any other value indicates success.

Ndb_cluster_connection::wait_until_ready()

Description This method is needed to establish connections with the data nodes.

It waits until the requested connection with one or more data nodes is successful, or until a timeout condition is met.

Signature int wait_until_ready

int wait_until_ready
 (
 int timeoutBefore,
 int timeoutAfter
)

Parameters

This method takes two parameters:

- timeoutBefore determines the number of seconds to wait until the first "live" node is detected. If this amount of time is exceeded with no live nodes detected, then the method immediately returns a negative value.
- timeoutAfter determines the number of seconds to wait after the first "live" node is detected for all nodes to become active. If this amount of time is exceeded without all nodes becoming active, then the method immediately returns a value greater than zero.

Return value

wait_until_ready() returns an int, whose value is interpreted as
follows:

- = 0: All nodes are "live".
- > 0: At least one node is "live" (however, it is not known whether all nodes are "live").
- < 0: An error occurred.

2.3.13 The NdbBlob Class

This section provides information about the NdbBlob class, which models a handle to a blob column and provides read and write access to blob column values. This object has a number of different states and provides several modes of access to blob data; these are also described in this section.

- NdbBlob Class Overview
- NdbBlob::ActiveHook
- NdbBlob::blobsFirstBlob()
- NdbBlob::blobsNextBlob()
- NdbBlob::close()
- NdbBlob::getBlobEventName()
- NdbBlob::getBlobTableName()
- NdbBlob::getColumn()
- NdbBlob::getLength()
- NdbBlob::getNull()
- NdbBlob::getNdbError()
- NdbBlob::getNdbOperation()
- NdbBlob::getPos()
- NdbBlob::getState()
- NdbBlob::getValue()
- NdbBlob::getVersion()
- NdbBlob::readData()
- NdbBlob::setActiveHook()
- NdbBlob::setNull()
- NdbBlob::setPos()
- NdbBlob::setValue()
- NdbBlob::State
- NdbBlob::truncate()
- NdbBlob::writeData()

NdbBlob Class Overview

Parent class None
Child classes None

Description This class has no public constructor. An instance of NdbBlob is created

using the NdbOperation::getBlobHandle() method during the operation preparation phase. (See Section 2.3.20, "The NdbOperation

Class".) This object acts as a handle on a BLOB column.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.33 NdbBlob class methods and descrptions

Name	Description	
blobsFirstBlob()	Gets the first blob in a list.	
blobsNextBlob()	Gets the next blob in a list	
close()	Release internal resources prior to commit or abort	
<pre>getBlobEventName()</pre>	Gets a blob event name	
<pre>getBlobTableName()</pre>	Gets a blob data segment's table name.	
getColumn()	Gets a blob column.	
getLength()	Gets the length of a blob, in bytes	
getNdbError()	Gets an error (an NdbError object)	
<pre>getNdbOperation()</pre>	Get a pointer to the operation (NdbOperation object) to which this NdbBlob object belonged when created.	
getNull()	Checks whether a blob value is NULL	
getPos()	Gets the current position for reading/writing	
getState()	Gets the state of an NdbBlob object	
getValue()	Prepares to read a blob value	
getVersion()	Checks whether a blob is statement-based or event-based	
readData()	Reads data from a blob	
setActiveHook()	Defines a callback for blob handle activation	
setNull()	Sets a blob to NULL	
setPos()	Sets the position at which to begin reading/writing	
setValue()	Prepares to insert or update a blob value	
truncate()	Truncates a blob to a given length	
writeData()	Writes blob data	

 ${\tt getBlobTableName()} \ \ {\tt and} \ {\tt getBlobEventName()} \ \ {\tt are} \ \ {\tt static} \\ \ \ {\tt methods}.$

Most NdbBlob methods (nearly all of those whose return type is int) return 0 on success and -1 in the event of failure.

The public types defined by NdbBlob are shown here:

Table 2.34 NdbBlob types and descriptions

Name	Description
ActiveHook()	Callback for NdbBlob::setActiveHook()

Types

Name	Description
State()	Represents the states that may be assumed by the NdbBlob.

BLOB Data Storage. BLOB data is stored in 2 locations:

- The header and inline bytes are stored in the blob attribute.
- The blob's data segments are stored in a separate table named NDB\$BLOB_tid_cid, where tid is the table ID, and cid is the blob column ID.

The inline and data segment sizes can be set using the appropriate Column methods when the table is created. See Section 2.3.1, "The Column Class", for more information about these methods.

Data Access Types. NdbBlob supports 3 types of data access: These data access types can be applied in combination, provided that they are used in the order given above.

- In the preparation phase, the NdbBlob methods getValue() and setValue() are used to prepare a read or write of a BLOB value of known size.
- Also in the preparation phase, setActiveHook() is used to define a routine which is invoked as soon as the handle becomes active.
- In the active phase, readData() and writeData() are used to read and write BLOB values having arbitrary sizes.

BLOB Operations.BLOB operations take effect when the next transaction is executed. In some cases, NdbBlob is forced to perform implicit execution. To avoid this, you should always operate on complete blob data segments.

Use NdbTransaction::executePendingBlobOps() to flush reads and writes, which avoids any execution penalty if no operations are pending. This is not necessary following execution of operations, or after the next scan result.

NdbBlob also supports reading post- or pre-blob data from events. The handle can be read after the next event on the main table has been retrieved. The data becomes available immediately. (See Section 2.3.16, "The NdbEventOperation Class", for more information.)

BLOBs and NdbOperations. NdbOperation methods acting on NdbBlob objects have the following characteristics:.

- NdbOperation::insertTuple() must use NdbBlob::setValue() if the BLOB attribute is nonnullable.
- NdbOperation::readTuple() used with any lock mode can read but not write blob values.

When the $LM_CommittedRead$ lock mode is used with readTuple(), the lock mode is automatically upgraded to LM_Read whenever blob attributes are accessed.

- NdbOperation::updateTuple() can either overwrite an existing value using NdbBlob::setValue(), or update it during the active phase.
- NdbOperation::writeTuple() always overwrites blob values, and must use NdbBlob::setValue() if the BLOB attribute is nonnullable.
- NdbOperation::deleteTuple() creates implicit, nonaccessible BLOB handles.
- A scan with any lock mode can use its blob handles to read blob values but not write them.

A scan using the LM_Exclusive lock mode can update row and blob values using updateCurrentTuple(); the operation returned must explicitly create its own blob handle.

A scan using the LM_Exclusive lock mode can delete row values (and therefore blob values) using deleteCurrentTuple(); this create implicit nonaccessible blob handles.

An operation which is returned by lockCurrentTuple() cannot update blob values.

Known Issues. The following are known issues or limitations encountered when working with NdbBlob objects:

- Too many pending BLOB operations can overflow the I/O buffers.
- The table and its BLOB data segment tables are not created atomically.

NdbBlob::ActiveHook

ActiveHook is a data type defined for use as a callback for the setActiveHook() method. (See NdbBlob::setActiveHook().)

Definition. ActiveHook is a custom data type defined as shown here:

```
typedef int ActiveHook
    (
        NdbBlob* me,
        void* arg
)
```

Description

This is a callback for NdbBlob::setActiveHook(), and is invoked immediately once the prepared operation has been executed (but not committed). Any calls to getValue() or setValue() are performed first. The BLOB handle is active so readData() or writeData() can be used to manipulate the BLOB value. A user-defined argument is passed along with the NdbBlob. setActiveHook() returns a nonzero value in the event of an error.

NdbBlob::blobsFirstBlob()

Description

This method initialises a list of blobs belonging to the current operation and returns the first blob in the list.

Signature

NdbBlob* blobsFirstBlob (void

Parameters

None.

Return value

A pointer to the desired blob.

NdbBlob::blobsNextBlob()

Description

Use the method to obtain the next in a list of blobs that was initialised using blobsFirstBlob(). See NdbBlob::blobsFirstBlob().

Signature

```
NdbBlob* blobsNextBlob
(
void
)
```

Parameters None.

Return value A pointer to the desired blob.

NdbBlob::close()

Description Closes the blob handle, releasing internal resources as it does so, prior

to committing or aborting the transaction. In other words, this signals that an application has finished with reading from a given blob. This method can be called only when the blob's State is Agricus.

method can be called only when the blob's State is Active.

```
Signature

int close
(
bool execPendingBlobOps = true
)
```

Parameters This method has a single boolean parameter <code>execPendingBlobOps</code>.

If the value of this parameter true (the default), any pending blob operations are flushed before the blob handle is closed. If <code>execPendingBlobOps</code> is false, then it is assumed that the blob handle has no pending read or write operations to flush.

Return value 0 on success.

Read operations and locking. When a blob handle is created on a read operation using LM_Read or LM_Exclusive as the LockMode, the read operation can be unlocked only once all Blob handles created on this operation have been closed.

When a row containing blobs has been read with lock mode LM_CommittedRead, the mode is automatically upgraded to LM_Read to ensure consistency. In this case, when all the blob handles for the row have been closed, an unlock operation for the row is automatically performed by the call to the close() method, which adds a pending write operation to the blob. The upgraded lock is released following the call to execute().

NdbBlob::getBlobEventName()

Description This method gets a blob event name. The blob event is created if the

main event monitors the blob column. The name includes the main

event name.

Signature static int getBlobEventName

```
char* name,
Ndb* ndb,
const char* event,
const char* column
)
```

Parameters

This method takes the four parameters listed here:

- name: The name of the blob event.
- ndb: The relevant Ndb object.
- event: The name of the main event.
- column: The blob column.

Return value 0 on success, -1 on failure.

148

NdbBlob::getBlobTableName()

Description

This method gets the blob data segment table name.

This method is generally of use only for testing and debugging purposes.

Signature

Parameters

This method takes the four parameters listed here:

- name: The name of the blob data segment table.
- *ndb*: The relevant Ndb object.
- table: The name of the main table.
- column: The blob column.

Return value

Returns 0 on success, -1 on failure.

NdbBlob::getColumn()

Description

Use this method to get the ${\tt BLOB}$ column to which the ${\tt NdbBlob}$ belongs.

Signature

Parameters

None.

Return value

A Column object.

NdbBlob::getLength()

Description

This method gets the blob's current length in bytes.

Signature

```
int getLength
   (
    Uint64& length
)
```

Parameters

A reference to the length.

Return value

The blob's length in bytes. For a NULL blob, this method returns 0. to distinguish between a blob whose length is 0 blob and one which is NULL, use the getNull() method.

NdbBlob::getNull()

Description

This method checks whether the blob's value is NULL.

Signature

int getNull

```
(
int& isNull
)
```

Parameters

A reference to an integer *isNull*. Following invocation, this parameter has one of the following values, interpreted as shown here:

- -1: The blob is undefined. If this is a nonevent blob, this result causes a state error.
- 0: The blob has a nonnull value.
- 1: The blob's value is NULL.

Return value

None.

NdbBlob::getNdbError()

Description

Use this method to obtain an error object. The error may be blobspecific or may be copied from a failed implicit operation. The error code is copied back to the operation unless the operation already has a nonzero error code.

Signature

```
const NdbError& getNdbError
  (
    void
    const
```

Parameters

None.

Return value

An NdbError object.

NdbBlob::getNdbOperation()

Description

This method can be used to find the operation with which the handle for this NdbBlob is associated.

Signature

```
const NdbOperation* getNdbOperation
  (
    void
    const
```

Parameters

None.

Return value

A pointer to an operation.

The operation referenced by the pointer returned by this method may be represented by either an NdbOperation or NdbScanOperation object.

See Section 2.3.20, "The NdbOperation Class", and Section 2.3.24, "The NdbScanOperation Class", for more information.

NdbBlob::getPos()

Description

This method gets the current read/write position in a blob.

Signature

```
int getPos
   (
     Uint64& pos
)
```

Parameters

One parameter, a reference to the position.

Return value

Returns 0 on success, or -1 on failure. (Following a successful invocation, *pos* will hold the current read/write position within the blob, as a number of bytes from the beginning.)

NdbBlob::getState()

Description

This method gets the current state of the NdbBlob object for which it is invoked. Possible states are described in NdbBlob::State.

Signature

```
State getState
(
void
)
```

Parameters

None.

Return value

A value of type State.

NdbBlob::getValue()

Description

Use this method to prepare to read a blob value; the value is available following invocation. Use $\mathtt{getNull}()$ to check for a \mathtt{NULL} value; use $\mathtt{getLength}()$ to get the actual length of the blob, and to check for truncation. $\mathtt{getValue}()$ sets the current read/write position to the point following the end of the data which was read.

Signature

```
int getValue
   (
     void* data,
     Uint32 bytes
)
```

Parameters

This method takes two parameters. The first of these is a pointer to the data to be read; the second is the number of bytes to be read.

Return value

0 on success, -1 on failure.

NdbBlob::getVersion()

Description

This method is used to distinguish whether a blob operation is statement-based or event-based.

Signature

```
void getVersion
   (
    int& version
)
```

Parameters

This method takes a single parameter, an integer reference to the blob version (operation type).

Return value

One of the following three values:

- -1: This is a "normal" (statement-based) blob.
- 0: This is an event-operation based blob, following a change in its data.
- 1: This is an event-operation based blob, prior to any change in its data.

getVersion() is always successful, assuming that it is invoked as a method of a valid instance of NdbBlob.

NdbBlob::readData()

Description

This method is used to read data from a blob.

Signature

```
int readData
   (
    void*    data,
    Uint32& bytes
)
```

Parameters

readData() accepts a pointer to the *data* to be read, and a reference to the number of *bytes* read.

Return value

Returns 0 on success, -1 on failure. Following a successful invocation, *data* points to the data that was read, and *bytes* holds the number of bytes read.

NdbBlob::setActiveHook()

Description

This method defines a callback for blob handle activation. The queue of prepared operations will be executed in no-commit mode up to this point; then, the callback is invoked. For additional information, see NdbBlob::ActiveHook.

Signature

```
int setActiveHook
   (
        ActiveHook* activeHook,
        void* arg
)
```

Parameters

This method requires the two parameters listed here:

- A pointer to an ActiveHook.
- A pointer to void, for any data to be passed to the callback.

Return value

0 on success, -1 on failure.

NdbBlob::setNull()

Description

This method sets the value of a blob to ${\tt NULL}.$

Signature

```
int setNull
  (
    void
)
```

Parameters

None.

Return value

0 on success; -1 on failure.

NdbBlob::setPos()

Description

This method sets the position within the blob at which to read or write data.

Signature

```
int setPos
```

```
Uint64 pos
```

Parameters

The setPos() method takes a single parameter pos (an unsigned 64-bit integer), which is the position for reading or writing data. The value of pos must be between 0 and the blob's current length.



Important

"Sparse" blobs are not supported in the NDB API; in other words, there can be no unused data positions within a blob.

Return value

0 on success, -1 on failure.

NdbBlob::setValue()

Description

This method is used to prepare for inserting or updating a blob value. Any existing blob data that is longer than the new data is truncated. The data buffer must remain valid until the operation has been executed. setValue() sets the current read/write position to the point following the end of the data. You can set data to a null pointer (0) in order to create a NULL value.

Signature

```
int setValue
    (
      const void* data,
      Uint32 bytes
)
```

Parameters

This method takes the two parameters listed here:

- The data that is to be inserted or used to overwrite the blob value.
- The number of *bytes*—that is, the length—of the *data*.

Return value

0 on success, -1 on failure.

NdbBlob::State

This is an enumerated data type which represents the possible states of an NdbBlob instance.

Description

An NdbBlob may assume any one of these states

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.35 NdbBlob::State type values and descriptions

Name	Description
Idle	The NdbBlob has not yet been prepared for use with any operations.
Prepared	This is the state of the NdbBlob prior to operation execution.
Active	This is the BLOB handle's state following execution or the fetching of the next result, but before the transaction is committed.
Closed	This state occurs after the transaction has been committed.

Name	Description
Invalid	This follows a rollback or the close of a transaction.

NdbBlob::truncate()

Description This method is used to truncate a blob to a given length.

Signature int truncate (

(
Uint64 length = 0
)

Parameters truncate() takes a single parameter which specifies the new length

to which the blob is to be truncated. This method has no effect if <code>length</code> is greater than the blob's current length (which you can check

using getLength()).

Return value 0 on success, -1 on failure.

NdbBlob::writeData()

Description This method is used to write data to an NdbBlob. After a successful

invocation, the read/write position will be at the first byte following the

data that was written to the blob.

A write past the current end of the blob data extends the blob

automatically.

Signature int writeData (const void* data,

Const void* data,
Uint32 bytes

Parameters This method takes two parameters, a pointer to the *data* to be written,

and the number of bytes to write.

Return value 0 on success, -1 on failure.

2.3.14 The NdbDictionary Class

This section provides information about the NdbDictionary class, which stores meta-information about NDB database objects, such as tables, columns, and indexes.

While the preferred method of database object creation and deletion is through the MySQL Server, NdbDictionary also permits the developer to perform these tasks through the NDB API.

- NdbDictionary Class Overview
- NdbDictionary::AutoGrowSpecification
- NdbDictionary::getEmptyBitmask()
- NdbDictionary::getFirstAttrld()
- NdbDictionary::getNextAttrId()
- NdbDictionary::getNullBitOffset()

- NdbDictionary::getOffset()
- NdbDictionary::getRecordIndexName()
- NdbDictionary::getRecordRowLength()
- NdbDictionary::getRecordTableName()
- NdbDictionary::getRecordType()
- NdbDictionary::getValuePtr()
- NdbDictionary::isNull()
- NdbDictionary::RecordSpecification
- NdbDictionary::setNull()

NdbDictionary Class Overview

Parent class None

Child classes Dictionary, Column, Object

For the numeric equivalents to enumerations of NdbDictionary subclasses, see the file /storage/ndb/include/ndbapi/NdbDictionary.hpp in the NDB Cluster source tree.

Description

This is a data dictionary class that supports enquiries about tables, columns, and indexes. It also provides ways to define these database objects and to remove them. Both sorts of functionality are supplied using inner classes that model these objects. These include the following inner classes:

- Table for working with tables
- Column for creating table columns
- Index for working with secondary indexes
- Dictionary for creating database objects and making schema enquiries
- Event for working with events in the cluster.

Additional Object subclasses model the tablespaces, log file groups, data files, and undo files required for working with NDB Cluster Disk Data table, as well as with foreign key constraints.

Tables and indexes created using NdbDictionary cannot be viewed from the MySQL Server.

Dropping indexes through the NDB API that were created originally from an NDB Cluster causes inconsistencies. It is possible that a table from which one or more indexes have been dropped using the NDB API will no longer be usable by MySQL following such operations. In this event, the table must be dropped, and then re-created using MySQL to make it accessible to MySQL once more.

Methods

NdbDictionary itself has no public instance methods, only static methods that are used for working with NdbRecord objects. Operations not using NdbRecord are accomplished by means of NdbDictionary subclass instance methods. The following table lists the public methods of NdbDictionary and the purpose or use of each method:

Table 2.36 NdbDictionary class methods and descriptions

Name	Description
<pre>getEmptyBitmask()</pre>	Returns an empty column presence bitmask which can be used with NdbRecord
<pre>getFirstAttrId()</pre>	Get the first attribute ID specified by a given NdbRecord object
getRecordIndexName	Gets the name of the index object referred to by an NdbRecord
getRecordRowLength	Get the number of bytes needed to store one row of data using a given NdbRecord
getRecordTableName	Gets the name of the table object referred to by an NdbRecord
getRecordType()	Gets the RecordType of an NdbRecord
getValuePtr()	Returns a pointer to the beginning of stored data specified by attribute ID, using NdbRecord
isNull()	Show whether the null bit for a column is true or false
setNull()	Set a column's null bit

Types

NdbDictionary defines two data structures, listed here:

- AutoGrowSpecification
- RecordSpecification

NdbDictionary::AutoGrowSpecification

This section provides information about the AutoGrowSpecification data structure.

Parent class NdbDictionary

Description The AutoGrowSpecification is a data structure defined in the

NdbDictionary class, and is used as a parameter to or return value of some of the methods of the Tablespace and LogfileGroup classes.

Members AutoGrowSpecification has the members shown in the following

table:

Table 2.37 NdbDictionary::AutoGrowSpecification data structure member names and descriptions

Name	Description
min_free	???
max_size	???

Name	Description
file_size	???
filename_pattern	???

NdbDictionary::getEmptyBitmask()

Description Returns an empty column presence bitmask which can be used with

any NdbRecord to specify that no NdbRecord columns are to be

included in the operation.

Signature static const unsigned char* getEmptyBitmask

void

Parameters None.

Return value An empty bitmask.

NdbDictionary::getFirstAttrld()

Description Get the first attribute ID specified by an NdbRecord object. Returns

false if no attribute ID is specified.

Signature static bool getFirstAttrId

(
 const NdbRecord* record,
 Uint32& firstAttrId
)

Parameters A pointer to an NdbRecord and a reference to the attribute

(firstAttrID).

Return value Boolean false, when no attribute ID can be obtained.

NdbDictionary::getNextAttrld()

Description Get the next attribute ID specified by an NdbRecord object following

the attribute ID passed in. Returns false when there are no more

attribute IDs to be returned.

Signature static bool getNextAttrId

(
 const NdbRecord* record,
 Uint32& attrId
)

Parameters A pointer to an NdbRecord and a reference to an attribute ID.

Return value Boolean false, when no attribute ID can be obtained.

NdbDictionary::getNullBitOffset()

Description Get the offset of the given attribute ID's null bit from the start of the

NdbRecord row. Returns false if the attribute ID is not present.

Signature static bool getNullBitOffset

(
 const NdbRecord* record,
 Uint32 attrId,

Uint32& bytes,
Uint32& bit

Parameters An NdbRecord record in which to get the null bit offset of the given

attribute ID (attrId). The offset is expressed as a number of bytes

(bytes) plus a number of bits within the last byte (bit).

Return value Boolean false, if the attribute with the given ID is not present.

NdbDictionary::getOffset()

Description Get the offset of the given attribute ID's storage from the start of the

NdbRecord row. Returns false if the attribute id is not present

Signature static bool getOffset

(
 const NdbRecord* record,
 Uint32 attrId,
 Uint32& offset
)

Parameters The offset of the given attribute ID's storage from the start of the

NdbRecord row.

Return value Boolean false, if no attribute ID can be found.

NdbDictionary::getRecordIndexName()

Description Get the name of the Index object that the NdbRecord refers to.

Signature static const char* getRecordIndexName

(const NdbRecord* record

Parameters A pointer to the NdbRecord for which to get the name.

Return value The name, if any. Otherwise, or if the NdbRecord object is not of the

IndexAccess type, this method returns null.

NdbDictionary::getRecordRowLength()

Description Get the number of bytes needed to store one row of data laid out as

described by the NdbRecord structure passed in to this method.

Signature

static Uint32 getRecordRowLength
 (
 const NdbRecord* record
)

Parameters An NdbRecord object.

Return value The number of bytes needed per row.

NdbDictionary::getRecordTableName()

Description Return the name of the table object that the NdbRecord refers to. This

method returns null if the record is not a TableAccess.

Signature static const char* getRecordTableName

```
(
const NdbRecord* record
)
```

Parameters

The record (NdbRecord object) for which to get the table name.

Return value

The name of the table, or null if the NdbRecord object' type is not TableAccess.

NdbDictionary::getRecordType()

Description

Return the type of the NdbRecord object passed.

Signature

```
static RecordType getRecordType
    (
      const NdbRecord* record
    )
```

Parameters

An NdbRecord object.

Return value

The RecordType of the NdbRecord (IndexAccess or TableAccess).

NdbDictionary::getValuePtr()

Description

Returns a pointer to the beginning of stored data specified by attribute ID, by looking up the offset of the column stored in the NdbRecord object and returning the sum of the row position and the offset.

Signature

This method provides both row-const and non-row-const versions:

```
static const char* getValuePtr
    (
        const NdbRecord* record,
        const char* row,
        Uint32 attrId
)
static char* getValuePtr
    (
        const NdbRecord* record,
        char* row,
        Uint32 attrId
)
```

Parameters

A pointer to an NdbRecord object describing the row format, a pointer to the start of the row data (const in the const version of this method), and the attribute ID of the column.

Return value

A pointer to the start of the attribute in the row. This is null if the attribute is not part of the NdbRecord definition.

NdbDictionary::isNull()

Description

Indicate whether the null bit for the given column is set to true or false. The location of the null bit in relation to the row pointer is obtained from the passed NdbRecord object. If the column is not nullable, or if the column is not part of the NdbRecord definition, the method returns false.

Signature

```
static bool isNull
```

```
const NdbRecord* record,
  const char* row,
  Uint32 attrId
)
```

Parameters A pointer to an NdbRecord object describing the row format, a pointer

to the start of the row data, and the attribute ID of the column to check.

Return value Boolean true if the attribute ID exists in this NdbRecord, is nullable,

and this row's null bit is set; otherwise, Boolean false.

NdbDictionary::RecordSpecification

This section provides information about the RecordSpecification structure.

Parent class NdbDictionary

Description This structure is used to specify columns and range offsets when

creating NdbRecord objects.

Members The elements making up this structure are shown in the following table:

Table 2.38 NdbDictionary::RecordSpecification attributes, with types and descriptions

Name	Туре	Description
column	Column	The column described by this entry (the column's maximum size defines the field size for the row). Even when creating an NdbRecord for an index, this must point to a column obtained from the underlying table, and not from the index itself.
offset	Uint32	The offset of data from the beginning of a row. For reading blobs, the blob handle (NdbBlob), rather than the actual blob data, is written into the row. This means that there must be at least sizeof(NdbBlob*) must be available in the row.
nullbit_byte_offs	etint32	The offset from the beginning of the row of the byte containing the NULL bit.
nullbit_bit_in_by	tÆint32	NULL bit (0-7).

nullbit_byte_offset and nullbit_bit_in_byte are not used for non-nullable columns.

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbDictionary::setNull()

Description

Set the null bit for the given column to the supplied value. The offset for the null bit is obtained from the passed NdbRecord object. If the attribute ID is not part of the NdbRecord, or if it is not nullable, this method returns an error (-1).

Signature

```
static int setNull
    (
        const NdbRecord* record,
        char* row,
        Uint32 attrId,
        bool value
    )
```

Parameters

A pointer to the *record* (NdbRecord object) describing the row format; a pointer to the start of the *row* data; the attribute ID of the column (attrId); and the *value* to set the null bit to (true or false).

Return value

Returns 0 on success; returns -1 if the attrId is not part of the record, or is not nullable.

2.3.15 The NdbError Structure

This section provides information about the NdbError data structure, which contains status and other information about errors, including error codes, classifications, and messages.

- NdbError Overview
- NdbError::Classification
- NdbError::Status

NdbError Overview

Description

An NdbError consists of six parts, listed here, of which one is deprecated:

 Error status: This describes the impact of an error on the application, and reflects what the application should do when the error is encountered.

The error status is described by a value of the Status type. See NdbError::Status, for possible Status values and how they should be interpreted.

2. Error classification: This represents a logical error type or grouping.

The error classification is described by a value of the Classification type. See NdbError::Classification, for possible classifications and their interpretation. Additional information is provided in Section 2.4.4, "NDB Error Classifications".

3. *Error code*: This is an NDB API internal error code which uniquely identifies the error.



Important

It is *not* recommended to write application programs which are dependent on specific error codes. Instead, applications should check error status and classification. More information about errors can also be obtained by checking error messages and (when available) error detail messages. However—like error codes—these error messages and error detail messages are subject to change.

A listing of current error codes, broken down by classification, is provided in Section 2.4.2, "NDB Error Codes: by Type". This listing is updated with new NDB Cluster releases. You can also check the file storage/ndb/src/ndbapi/ndberror.c in the NDB Cluster sources.

- MySQL Error code: This is the corresponding MySQL Server error code. MySQL error codes are not discussed in this document; please see Server Error Message Reference, in the MySQL Manual, for information about these.
- 5. *Error message*: This is a generic, context-independent description of the error.
- Error details: This can often provide additional information (not found in the error message) about an error, specific to the circumstances under which the error is encountered. However, it is not available in all cases.

Where not specified, the error detail message is NULL.



Note

This property is deprecated and scheduled for eventual removal. For obtaining error details, you should use the Ndb::getNdbErrorDetail() method instead.

Specific NDB API error codes, messages, and detail messages are subject to change without notice.

Definition

The NdbError structure contains the following members, whose types are as shown here:

- Status status: The error status.
- Classification classification: The error type (classification).
- int code: The NDB API error code.
- int mysql_code: The MySQL error code.
- const char* message: The error message.
- char* details: The error detail message.

details is deprecated and scheduled for eventual removal. You
should use the Ndb::getNdbErrorDetail() method instead. (Bug
#48851)

Types

NdbError defines the two data types listed here:

- Classification: The type of error or the logical grouping to which the error belongs.
- Status: The error status.

NdbError::Classification

This section provides information about the Classification data type.

Description

This type describes the type of error, or the logical group to which it belongs.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.39 NdbError Classification data type values and descriptions

Name	Description
NoError	Indicates success (no error occurred)
ApplicationError	An error occurred in an application program
NoDataFound	A read operation failed due to one or more missing records.
ConstraintViolatio	A constraint violation occurred, such as attempting to insert a tuple having a primary key value already in use in the target table.
SchemaError	An error took place when trying to create or use a table.
InsufficientSpace	There was insufficient memory for data or indexes.
TemporaryResourceE	This type of error is typically encountered when there are too many active transactions.

Name	Description
NodeRecoveryError	This is a temporary failure which was likely caused by a node recovery in progress, some examples being when information sent between an application and NDB is lost, or when there is a distribution change.
OverloadError	This type of error is often caused when there is insufficient log file space.
TimeoutExpired	A timeout, often caused by a deadlock.
UnknownResultError	It is not known whether a transaction was committed.
InternalError	A serious error has occurred in NDB itself.
FunctionNotImpleme:	The application attempted to use a function which is not yet implemented.
UnknownErrorCode	This is seen where the NDB error handler cannot determine the correct error code to report.
NodeShutdown	This is caused by a node shutdown.
SchemaObjectExists	The application attempted to create a schema object that already exists.
InternalTemporary	A request was sent to a node other than the master.

Related information specific to certain error conditions can be found in Section 2.4.2, "NDB Error Codes: by Type", and in Section 2.4.4, "NDB Error Classifications".

NdbError::Status

This section provides information about the Status data type.

Description This type is used to describe an error's status.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.40 NdbError Status data type values and descriptions

Name	Description
Success	No error has occurred
TemporaryError	A temporary and usually recoverable error; the application should retry the operation giving rise to the error
PermanentError	Permanent error; not recoverable
UnknownResult	The operation's result or status is unknown

Related information specific to certain error conditions can be found in Section 2.4.4, "NDB Error Classifications".

2.3.16 The NdbEventOperation Class

This section provides information about the NdbEventOperation class, which is used to monitor changes (events) in a database. It provides the core functionality used to implement NDB Cluster Replication.

- NdbEventOperation Class Overview
- NdbEventOperation::clearError() (DEPRECATED)
- NdbEventOperation::execute()
- NdbEventOperation::getBlobHandle()
- NdbEventOperation::getEpoch()
- NdbEventOperation::getEventType() (DEPRECATED)
- NdbEventOperation::getEventType2()
- NdbEventOperation::getGCI() (DEPRECATED)
- NdbEventOperation::getLatestGCI() (DEPRECATED)
- NdbEventOperation::getNdbError()
- NdbEventOperation::getPreBlobHandle()
- NdbEventOperation::getPreValue()
- NdbEventOperation::getState()
- NdbEventOperation::getValue()
- NdbEventOperation::hasError() (DEPRECATED)
- NdbEventOperation::isConsistent() (DEPRECATED)
- NdbEventOperation::isEmptyEpoch()
- NdbEventOperation::isErrorEpoch()
- NdbEventOperation::isOverrun()
- NdbEventOperation::mergeEvents()
- NdbEventOperation::State
- NdbEventOperation::tableFragmentationChanged()
- NdbEventOperation::tableFrmChanged()
- NdbEventOperation::tableNameChanged()
- NdbEventOperation::tableRangeListChanged()

NdbEventOperation Class Overview

Parent class None
Child classes None

Description NdbEventOperation represents a database event.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.41 NdbEventOperation class methods and descriptions

Name	Description
clearError()	Clears the most recent error. Deprecated in NDB 7.4.3.
execute()	Activates the NdbEventOperation
getBlobHandle()	Gets a handle for reading blob attributes
getEpoch()	Retrieves the epoch for the event data most recently retrieved. Added in NDB 7.4.3.
<pre>getEventType()</pre>	Gets the event type. Deprecated in NDB 7.4.3.
getEventType2()	Gets the event type. Added in NDB 7.4.3.
getGCI()	Retrieves the GCI of the most recently retrieved event. Deprecated in NDB 7.4.3.
<pre>getLatestGCI()</pre>	Retrieves the most recent GCI (whether or not the corresponding event has been retrieved). Deprecated in NDB 7.4.3.
getNdbError()	Gets the most recent error
<pre>getPreBlobHandle()</pre>	Gets a handle for reading the previous blob attribute
getPreValue()	Retrieves an attribute's previous value
getState()	Gets the current state of the event operation
getValue()	Retrieves an attribute value
hasError()	Whether an error has occurred as part of this operation. Deprecated in NDB 7.4.3.
isConsistent()	Detects event loss caused by node failure. Deprecated in NDB 7.4.3.
isEmptyEpoch()	Detects an empty epoch. Added in NDB 7.4.3.
isErrorEpoch()	Detects an error epoch, and retrieves the error if there is one. Added in NDB 7.4.3.
isOverrun()	Whether event loss has taken place due to a buffer overrun. Deprecated in NDB 7.4.3.
mergeEvents()	Makes it possible for events to be merged
tableFragmentation	Checks to see whether the fragmentation for a table has changed
tableFrmChanged()	Checks to see whether a table . FRM file has changed
tableNameChanged()	Checks to see whether the name of a table has changed
tableRangeListChan	Checks to see whether a table range partition list name has changed

Types

NdbEventOperation defines one enumerated type, the State type.

Creating an Instance of NdbEventOperation. This class has no public constructor or destructor. Instead, instances of NdbEventOperation are created as the result of method calls on Ndb and NdbDictionary objects, subject to the following conditions:

- 1. There must exist an event which was created using Dictionary::createEvent(). This method returns an instance of the Event class.
- 2. An NdbEventOperation object is instantiated using Ndb::createEventOperation(), which acts on an instance of Event.

An instance of this class is removed by invoking Ndb::dropEventOperation.



Tip

A detailed example demonstrating creation and removal of event operations is provided in Section 2.5.8, "NDB API Event Handling Example".

Known Issues. The following issues may be encountered when working with event operations in the NDB API:

- The maximum number of active NdbEventOperation objects is currently fixed at compile time at 2 *
 MaxNoOfTables.
- Currently, all INSERT, DELETE, and UPDATE events—as well as all attribute changes—are sent to the API, even if only some attributes have been specified. However, these are hidden from the user and only relevant data is shown after calling Ndb::nextEvent().

Note that false exits from Ndb::pollEvents() may occur, and thus the following nextEvent() call returns zero, since there was no available data. In such cases, simply call pollEvents() again.

See Ndb::pollEvents(), and Ndb::nextEvent() (DEPRECATED).

- Event code does *not* check the table schema version. When a table is dropped, make sure that you drop any associated events.
- If you have received a complete epoch, events from this epoch are not re-sent, even in the event of a node failure. However, if a node failure has occurred, subsequent epochs may contain duplicate events, which can be identified by duplicated primary keys.

In the NDB Cluster replication code, duplicate primary keys on INSERT operations are normally handled by treating such inserts as REPLACE operations.



Tip

To view the contents of the system table containing created events, you can use the ndb_select_all utility as shown here:

ndb_select_all -d sys 'NDB\$EVENTS_0'

NdbEventOperation::clearError() (DEPRECATED)

Description

Clears the error most recently associated with this event operation.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release.

Signature void clearError

void

Parameters None.

Return value None.

NdbEventOperation::execute()

Description Activates the NdbEventOperation, so that it can begin

> receiving events. Changed attribute values may be retrieved after Ndb::nextEvent() has returned a value other than NULL.

One of getValue(), getPreValue(), getBlobValue(), or getPreBlobValue() must be called before invoking execute().

Before attempting to use this method, you should have read the explanations provided in Ndb::nextEvent() (DEPRECATED), and NdbEventOperation::getValue(). Also see Section 2.3.16, "The

NdbEventOperation Class".

Signature int execute

void

Parameters None.

Return value This method returns 0 on success and -1 on failure.

NdbEventOperation::getBlobHandle()

This method is used in place of getValue() for blob attributes. Description

The blob handle (NdbBlob) returned by this method supports read

operations only.

To obtain the previous value for a blob attribute, use

getPreBlobHandle().

Signature NdbBlob* getBlobHandle

const char* name

Parameters The *name* of the blob attribute.

Return value A pointer to an NdbBlob object.

NdbEventOperation::getEpoch()

Description Gets the epoch for the latest event data retrieved.

> Added in NDB 7.4.3, this method supersedes getGCI(), which is now deprecated and subject to removal in a future NDB Cluster release.

Signature Uint64 getEpoch

void
) const

Parameters None.

Return value An epoch number (an integer).

NdbEventOperation::getEventType() (DEPRECATED)

Description This method is used to obtain the event's type (TableEvent).

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should use

getEventType2() instead.

Signature NdbDictionary::Event::TableEvent getEventType

(void) const

Parameters None.

Return value A TableEvent value.

NdbEventOperation::getEventType2()

Description This method is used to obtain the event's type (TableEvent).

Added in NDB 7.4.3, this method supersedes getEventType(), which is now deprecated and subject to removal in a future NDB Cluster

release.

Signature getEventType2

(void) const

Parameters None.

Return value A TableEvent value.

NdbEventOperation::getGCI() (DEPRECATED)

Description This method retrieves the GCI for the most recently retrieved event.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should use getEpoch()

instead.

Signature Uint64 getGCI

(void) const

Parameters None.

Return value The global checkpoint index of the most recently retrieved event (an

integer).

NdbEventOperation::getLatestGCI() (DEPRECATED)

Description This method retrieves the most recent GCI.

This method returns the latest epoch number.

The GCI obtained using this method is not necessarily associated with

an event.

This method is deprecated in NDB 7.4.3, and is subject to removal

in a future release. In NDB 7.4.3 and later, you should use

Ndb::getHighestQueuedEpoch() instead.

Signature Uint64 getLatestGCI

(void) const

Parameters None.

Return value The index of the latest global checkpoint, an integer.

NdbEventOperation::getNdbError()

Description This method retrieves the most recent error.

Signature const struct NdbError& getNdbError

void
) const

Parameters None.

Return value A reference to an NdbError structure.

NdbEventOperation::getPreBlobHandle()

Description This function is the same as getBlobHandle(), except that it

is used to access the previous value of the blob attribute. See

NdbEventOperation::getBlobHandle().

Signature NdbBlob* getPreBlobHandle

(const char* name

Parameters The *name* of the blob attribute.

Return value A pointer to an NdbBlob.

NdbEventOperation::getPreValue()

Description This method performs identically to getValue(), except that it is used

to define a retrieval operation of an attribute's previous value rather than

the current value.

Signature NdbRecAttr* getPreValue

const char* name,
char* value = 0

Parameters This method takes the two parameters listed here:

- The name of the attribute (as a constant character pointer).
- A pointer to a value, such that:
 - If the attribute value is not NULL, then the attribute value is returned in this parameter.
 - If the attribute value is NULL, then the attribute value is stored only in the NdbRecAttr object returned by this method.

See *value* Buffer Memory Allocation, for more information regarding this parameter.

Return value

An NdbRecAttr object to hold the value of the attribute, or a NULL pointer indicating that an error has occurred.

NdbEventOperation::getState()

Description

This method gets the event operation's current state.

Signature

```
State getState
   (
     void
   )
```

Parameters

None.

Return value

A State value.

NdbEventOperation::getValue()

Description

This method defines the retrieval of an attribute value. The NDB API allocates memory for the NdbRecAttr object that is to hold the returned attribute value.

This method does *not* fetch the attribute value from the database, and the NdbRecAttr object returned by this method is not readable or printable before calling the execute() method and Ndb::nextEvent() has returned a non-NULL value.

If a specific attribute has not changed, the corresponding NdbRecAttr will be in the state UNDEFINED. This can be checked by using NdbRecAttr::isNULL() which in such cases returns -1.

 ${\tt getValue()} \ \ retrieves \ the \ current \ value. \ Use \ {\tt getPreValue()} \ for \ retrieving \ the \ previous \ value.$

Signature

```
NdbRecAttr* getValue
   (
      const char* name,
      char* value = 0
)
```

Parameters

This method takes the two parameters listed here:

- The name of the attribute (as a constant character pointer).
- A pointer to a value, such that:

- If the attribute value is not NULL, then the attribute value is returned in this parameter.
- If the attribute value is NULL, then the attribute value is stored only in the NdbRecAttr object returned by this method.

See *value* Buffer Memory Allocation, for more information regarding this parameter.

Return value

An NdbRecAttr object to hold the value of the attribute, or a NULL pointer indicating that an error has occurred.

value Buffer Memory Allocation. It is the application's responsibility to allocate sufficient memory for the *value* buffer (if not NULL), and this buffer must be aligned appropriately. The buffer is used directly (thus avoiding a copy penalty) only if it is aligned on a 4-byte boundary and the attribute size in bytes (calculated as NdbRecAttr::get size in bytes()) is a multiple of 4.

NdbEventOperation::hasError() (DEPRECATED)

Description This method is used to determine whether there is an error associated

with this event operation.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should instead use getEventType2() to determine the event type. See

Event::TableEvent.

Signature int hasError

(void) const

Parameters None.

Return value If event loss has taken place, then this method returns 0; otherwise, it

returns 1.

NdbEventOperation::isConsistent() (DEPRECATED)

Description This method is used to determine whether event loss has taken place

following the failure of a node.

This method is deprecated in NDB 7.4.3, and is subject to removal in a future release. In NDB 7.4.3 and later, you should instead use getEventType2() to determine whether the event is of type

TE_INCONSISTENT. See Event::TableEvent.

Signature bool isConsistent

(void) const

Parameters None.

Return value If event loss has taken place, then this method returns false;

otherwise, it returns true.

NdbEventOperation::isEmptyEpoch()

Description This method is used to determine whether consumed event data marks

an empty epoch.

This method was added in NDB 7.4.3.

Signature bool isEmptyEpoch

void

Parameters None.

Return value If this epoch is empty, the method returns true; otherwise, it returns

false.

NdbEventOperation::isErrorEpoch()

Description This method is used to determine whether consumed event data marks

an empty epoch.

This method was added in NDB 7.4.3.

Signature bool isErrorEpoch

(
 NdbDictionary::Event::TableEvent* error_type = 0
)

Parameters If this is an error epoch, error_type contains the TableEvent value

corresponding to the error.

Return value If this epoch is in error, the method returns true; otherwise, it returns

false.

NdbEventOperation::isOverrun()

Description This method is used to determine whether event loss has taken place

due to a buffer overrun.

Signature bool isOverrun

(void) const

Parameters None.

Return value If the event buffer has been overrun, then this method returns true,

otherwise, it returns false.

NdbEventOperation::mergeEvents()

Description This method is used to set the merge events flag. For information about

event merging, see Event::mergeEvents().

The merge events flag is false by default.

Signature void mergeEvents

bool flag

Parameters A Boolean *flag*.

Return value None.

NdbEventOperation::State

This section provides information about the State data type.

Description This type describes the event operation's state.

A State value is returned by the ${\tt getState}($) method.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.42 NdbEventOperation data type values and descriptions

Name	Description
EO_CREATED	The event operation has been created, but execute() has not yet been called.
EO_EXECUTING	The execute() method has been invoked for this event operation.
EO_DROPPED	The event operation is waiting to be deleted, and is no longer usable.
EO_ERROR	An error has occurred, and the event operation is unusable.

NdbEventOperation::tableFragmentationChanged()

Description This method is used to test whether a table's fragmentation

has changed in connection with a TE ALTER event. (See

Event::TableEvent.)

Signature bool tableFragmentationChanged

void
) const

Parameters None.

Return value Returns true if the table's fragmentation has changed; otherwise, the

method returns false.

NdbEventOperation::tableFrmChanged()

Description Use this method to determine whether a table . FRM file has changed in

connection with a TE_ALTER event. (See Event::TableEvent.)

Signature bool tableFrmChanged

void
) const

Parameters None.

Return value Returns true if the table .FRM file has changed; otherwise, the method

returns false.

NdbEventOperation::tableNameChanged()

Description This method tests whether a table name has changed as the result of a

TE_ALTER table event. (See Event::TableEvent.)

Signature bool tableNameChanged

void
) const

Parameters None.

Return value Returns true if the name of the table has changed; otherwise, the

method returns false.

NdbEventOperation::tableRangeListChanged()

Description Use this method to check whether a table range partition list name has

changed in connection with a TE_ALTER event.

Signature bool tableRangeListChanged

void
) const

Parameters None.

Return value This method returns true if range or list partition name has changed;

otherwise it returns false.

2.3.17 The NdbIndexOperation Class

This section provides information about the NdbIndexOperation class.

- NdbIndexOperation Class Overview
- NdbIndexOperation::deleteTuple()
- NdbIndexOperation::getIndex()
- NdbIndexOperation::readTuple()
- NdbIndexOperation::updateTuple()

NdbIndexOperation Class Overview

Parent class NdbOperation

Child classes None

Description NdbIndexOperation represents an index operation for use in

transactions. This class inherits from ${\tt NdbOperation}.$

NdbIndexOperation can be used only with unique hash indexes; to

work with ordered indexes, use NdbIndexScanOperation.

This class has no public constructor. To create an instance of NdbIndexOperation, it is necessary to use the NdbTransaction::getNdbIndexOperation() method.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.43 NdbIndexOperation class methods and descriptions

Name	Description
deleteTuple()	Removes a tuple from a table
getIndex()	Gets the index used by the operation
readTuple()	Reads a tuple from a table
updateTuple()	Updates an existing tuple in a table

Index operations are not permitted to insert tuples.

Types

The NdbIndexOperation class defines no public types of its own.

For more information about the use of NdbIndexOperation, see Single-row operations.

NdbIndexOperation::deleteTuple()

Description This method defines the NdbIndexOperation as a DELETE operation.

When the NdbTransaction::execute() method is invoked, the

operation deletes a tuple from the table.

Signature int deleteTuple

(void

Parameters None.

Return value 0 on success, -1 on failure.

NdbIndexOperation::getIndex()

Description Gets the index, given an index operation.

Signature const NdbDictionary::Index* getIndex

void
) const

Parameters None.

Return value A pointer to an Index object.

NdbIndexOperation::readTuple()

 ${\bf Description} \qquad \qquad {\bf This\ method\ defines\ the\ NdbIndexOperation\ as\ a\ READ\ operation.}$

When the NdbTransaction::execute() method is invoked, the

operation reads a tuple.

Signature int readTuple

(LockMode *mode*

.

Parameters mode specifies the locking mode used by the read operation. See

NdbOperation::LockMode, for possible values.

Return value 0 on success, -1 on failure.

NdbIndexOperation::updateTuple()

Description This method defines the NdbIndexOperation as an UPDATE

operation. When the NdbTransaction::execute() method is

invoked, the operation updates a tuple found in the table.

Signature int updateTuple

(void

Parameters None.

Return value 0 on success, -1 on failure.

2.3.18 The NdbIndexScanOperation Class

This section provides information about the NdbIndexScanOperation class.

- NdbIndexScanOperation Class Overview
- NdbIndexScanOperation::BoundType
- NdbIndexScanOperation::end_of_bound()
- NdbIndexScanOperation::getDescending()
- NdbIndexScanOperation::get_range_no()
- NdbIndexScanOperation::getSorted()
- NdbIndexScanOperation::IndexBound
- NdbIndexScanOperation::readTuples()
- NdbIndexScanOperation::reset_bounds()
- NdbIndexScanOperation::setBound()

NdbIndexScanOperation Class Overview

Parent class NdbScanOperation

Child classes None

Description The NdbIndexScanOperation class represents a scan operation

using an ordered index. This class inherits from NdbScanOperation

and NdbOperation.

 ${\tt NdbIndexScanOperation}\ is\ for\ use\ with\ ordered\ indexes\ only;\ to$

work with unique hash indexes, use NdbIndexOperation.

For more information about the use of NdbIndexScanOperation, see

Scan Operations, and Using Scans to Update or Delete Rows.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.44 NdbIndexScanOperation class methods and descriptions

Name	Description
end_of_bound()	Marks the end of a bound
get_range_no()	Gets the range number for the current row
getDescending()	Checks whether the current scan is sorted
getSorted()	Checks whether the current scan is sorted
readTuples()	Reads tuples using an ordered index
reset_bounds()	Resets bounds, puts the operation in the send queue
setBound()	Defines a bound on the index key for a range scan

Types

The NdbIndexScanOperation class defines one public type BoundType.

This class also defines an IndexBound data structure, for use with operations employing NdbRecord.

NdbIndexScanOperation::BoundType

This section provides information abut the BoundType data type.

Description This type is used to describe an ordered key bound.

Enumeration values Possible values are shown, along with descriptions, in the following table:

Table 2.45 NdbIndexScanOperation::BoundType values, numeric equivalents, and descriptions

Value	Numeric Value	Description
BoundLE	0	Lower bound
BoundLT	1	Strict lower bound
BoundGE	2	Upper bound
BoundGT	3	Strict upper bound
BoundEQ	4	Equality

The numeric values just shown are "safe"; that is, they are fixed in the API, and so can be calculated and used explicitly.

NdbIndexScanOperation::end_of_bound()

Description This method is used to mark the end of a bound; it is used when

batching index reads (that is, when employing multiple ranges).

Signature int end_of_bound

```
(
Uint32 range_no
)
```

Parameters The number of the range on which the bound occurs.

Return value 0 indicates success; -1 indicates failure.

NdbIndexScanOperation::getDescending()

Description This method is used to check whether the scan is descending.

Signature bool getDescending

(void) const

Parameters None.

Return value This method returns true if the scan is sorted in descending order;

otherwise, it returns false.

NdbIndexScanOperation::get_range_no()

Description This method returns the range number for the current row.

Signature int get_range_no

void

Parameters None.

Return value The range number (an integer).

NdbIndexScanOperation::getSorted()

Description This method is used to check whether the scan is sorted.

Signature bool getSorted

(void) const

Parameters None.

Return value true if the scan is sorted, otherwise false.

NdbIndexScanOperation::IndexBound

This section provides information about the IndexBound data structure.

Parent class NdbIndexScanOperation

Description IndexBound is a structure used to describe index scan bounds for

NdbRecord scans.

Members Member names, types, and descriptions are shown in the following

table:

Table 2.46 IndexBound structure member names, types, and descriptions

Name	Туре	Description	
low_key	const char*	Row containing lower bound for scan (or NULL for scan from the start).	
low_key_count	Uint32	Number of columns in lower bound (for bounding by partial prefix).	
low_inclusive	bool	True for <= relation, false for <.	
high_key	const char*	Row containing upper bound for scan (or NULL for scan to the end).	
high_key_count	Uint32	Number of columns in upper bound (for bounding by partial prefix).	
high_inclusive	bool	True for >= relation, false for >.	
range_no	Uint32	Value to identify this bound; may be read using the get_range_no() method (see NdbIndexScanOperation::ge This value must be less than 8192 (set to zero if it is not being used). For ordered scans, range_no must be strictly increasing for each range, or else the result set will not be sorted correctly.	t_range_no(

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbIndexScanOperation::readTuples()

Description

This method is used to read tuples, using an ordered index.

Signature

```
virtual int readTuples
   (
    LockMode mode = LM_Read,
    Uint32    flags = 0,
    Uint32    parallel = 0,
    Uint32    batch = 0
)
```

Parameters

The readTuples() method takes the three parameters listed here:

- The lock mode used for the scan. This is a LockMode value; see NdbOperation::LockMode for more information, including permitted values.
- One or more scan flags; multiple <code>flags</code> are <code>OR'ed</code> together as they are when used with <code>NdbScanOperation::readTuples()</code>. See <code>NdbScanOperation::ScanFlag</code> for possible values.
- The number of fragments to scan in *parallel*; use 0 to specify the maximum automatically.
- The batch parameter specifies how many records will be returned to the client from the server by the next NdbScanOperation::nextResult(true) method call. Use 0 to specify the maximum automatically.



Note

This parameter was ignored prior to MySQL 5.1.12, and the maximum was used.(Bug #20252)

Return value

An integer: 0 indicates success; -1 indicates failure.

NdbIndexScanOperation::reset_bounds()

Description Reso

Resets the bounds, and puts the operation into the list sent on the next call to NdbTransaction::execute().

Signature

```
int reset_bounds
   (
     bool forceSend = false
)
```

Parameters

Set *forceSend* to true in order to force the operation to be sent immediately.

Return value

Returns 0 on success, -1 on failure.

NdbIndexScanOperation::setBound()

Description

This method defines a bound on an index key used in a range scan, and sets bounds for index scans defined using NdbRecord.

As used with NdbRecord, this method is called to add a range to an index scan operation which has been defined with a call to NdbTransaction::scanIndex(). To add more than one range, the index scan operation must have been defined with the SF_MultiRange flag set. (See NdbScanOperation::ScanFlag.)

Where multiple numbered ranges are defined with multiple calls to setBound(), and the scan is ordered, the range number for each range must be larger than the range number for the previously defined range.

Signature

```
int setBound (
```

```
const NdbRecord* keyRecord,
const IndexBound& bound
)
```

Parameters

As used with NdbRecord, this method takes 2 parameters, listed here:

- keyRecord: This is an NdbRecord structure corresponding to the key on which the index is defined.
- The bound to add (see NdbIndexScanOperation::IndexBound).

Return value

Returns 0 on success, -1 on failure.

An additional version of this method can be used when the application knows that rows in-range will be found only within a particular partition. This is the same as that shown previously, except for the addition of a PartitionSpec. Doing so limits the scan to a single partition, improving system efficiency.

Signature (when specifying a partition)

```
int setBound
   (
      const NdbRecord* keyRecord,
      const IndexBound& bound,
      const Ndb::PartitionSpec* partInfo,
      Uint32 sizeOfPartInfo = 0
   )
```

Parameters (when specifying a partition)

This method can also be invoked with the following four parameters:

- keyRecord: This is an NdbRecord structure corresponding to the key on which the index is defined.
- The bound to be added to the scan (see NdbIndexScanOperation::IndexBound).
- partInfo: This is a pointer to a PartitionSpec, which provides extra information making it possible to scan a reduced set of partitions.
- sizeOfPartInfo: The length of the partition specification.

keyRecord and bound are defined and used in the same way as with the 2-parameter version of this method.

Return value

Returns 0 on success, -1 on failure.

"Old" API usage (prior to introduction of NdbRecord)

Each index key can have a lower bound, upper bound, or both. Setting the key equal to a value defines both upper and lower bounds. Bounds can be defined in any order. Conflicting definitions gives rise to an error.

Bounds must be set on initial sequences of index keys, and all but possibly the last bound must be nonstrict. This means, for example, that " $a \ge 2$ AND $b \ge 3$ " is permissible, but " $a \ge 2$ AND $b \ge 3$ " is not.

The scan may currently return tuples for which the bounds are not satisfied. For example, a <= 2 && b <= 3 not only scans the index up to (a=2, b=3), but also returns any (a=1, b=4) as well.

When setting bounds based on equality, it is better to use BoundEQ instead of the equivalent pair BoundLE and BoundGE. This is especially true when the table partition key is a prefix of the index key.

NULL is considered less than any non-NULL value and equal to another NULL value. To perform comparisons with NULL, use $\mathtt{setBound}()$ with a null pointer (0).

An index also stores all-NULL keys as well, and performing an index scan with an empty bound set returns all tuples from the table.

Signature ("Old" API)

Using the "old" API, this method could be called in either of two ways. Both of these use the bound type and value; the first also uses the name of the bound, as shown here:

The second way to invoke this method under the "old" API uses the bound's ID rather than the name, as shown here:

```
int setBound
   (
     Uint32     id,
     int         type,
     const void* value
)
```

Parameters ("Old" API)

This method takes 3 parameters:

- Either the name or the id of the attribute on which the bound is to be set.
- The bound type—see NdbIndexScanOperation::BoundType.
- A pointer to the bound value (use 0 for NULL).

Return value

Returns 0 on success, -1 on failure.

2.3.19 The NdbInterpretedCode Class

This section provides information about the NdbInterpretedCode class, which can be used to prepare and execute an NDB API interpreted program.

- NdbInterpretedCode Class Overview
- NdbInterpretedCode Constructor
- NdbInterpretedCode::add_reg()
- NdbInterpretedCode::add_val()
- NdbInterpretedCode::branch_col_and_mask_eq_mask()
- NdbInterpretedCode::branch_col_and_mask_eq_zero()
- NdbInterpretedCode::branch col and mask ne mask()
- NdbInterpretedCode::branch_col_and_mask_ne_zero()
- NdbInterpretedCode::branch_col_eq()

- NdbInterpretedCode::branch_col_eq_null()
- NdbInterpretedCode::branch_col_ge()
- NdbInterpretedCode::branch_col_gt()
- NdbInterpretedCode::branch_col_le()
- NdbInterpretedCode::branch_col_like()
- NdbInterpretedCode::branch_col_lt()
- NdbInterpretedCode::branch_col_ne()
- NdbInterpretedCode::branch_col_ne_null()
- NdbInterpretedCode::branch_col_notlike()
- NdbInterpretedCode::branch_eq()
- NdbInterpretedCode::branch_eq_null()
- NdbInterpretedCode::branch_ge()
- NdbInterpretedCode::branch_gt()
- NdbInterpretedCode::branch_label()
- NdbInterpretedCode::branch_le()
- NdbInterpretedCode::branch_lt()
- NdbInterpretedCode::branch_ne()
- NdbInterpretedCode::branch_ne_null()
- NdbInterpretedCode::call sub()
- NdbInterpretedCode::copy()
- NdbInterpretedCode::def_label()
- NdbInterpretedCode::def sub()
- NdbInterpretedCode::finalise()
- NdbInterpretedCode::getNdbError()
- NdbInterpretedCode::getTable()
- NdbInterpretedCode::getWordsUsed()
- NdbInterpretedCode::interpret_exit_last_row()
- NdbInterpretedCode::interpret_exit_nok()
- NdbInterpretedCode::interpret_exit_ok()
- NdbInterpretedCode::load_const_null()
- NdbInterpretedCode::load_const_u16()
- NdbInterpretedCode::load_const_u32()

NdbInterpretedCode::load_const_u64()

NdbInterpretedCode::read_attr()

NdbInterpretedCode::ret_sub()

NdbInterpretedCode::sub_reg()

• NdbInterpretedCode::sub_val()

NdbInterpretedCode::write_attr()

NdbInterpretedCode Class Overview

Parent class None.

Child classes None.

Description

NdbInterpretedCode represents an interpreted program for use in operations created using NdbRecord, or with scans created using the old API. The NdbScanFilter class can also be used to generate an NDB interpreted program using this class.

To create an NdbInterpretedCode object, invoke the constructor, optionally supplying a table for the program to operate on, and a buffer for program storage and finalization. If no table is supplied, then only instructions which do not access table attributes can be used. Beginning with NDB 8.0.18, an instance of Ndbrecord can be used for this purpose, in place of the Table.

Each NDB API operation applies to one table, and so does any NdbInterpretedCode program attached to that operation.

If no buffer is supplied, then an internal buffer is dynamically allocated and extended as necessary. Once the NdbInterpretedCode object is created, you can add instructions and labels to it by calling the appropriate methods as described later in this section. When the program has completed, finalize it by calling the finalise() method, which resolves any remaining internal branches and calls to label and subroutine offsets.

A single finalized NdbInterpretedCode program can be used by more than one operation. It need not be re-prepared for successive operations.

To use the program with NdbRecord operations and scans, pass it at operation definition time using the OperationOptions or ScanOptions parameter. When the program is no longer required, the NdbInterpretedCode object can be deleted, along with any user-supplied buffer.

For additional information and examples, see Section 1.6, "Using NdbInterpretedCode".

This interface is still under development, and so is subject to change without notice. The NdbScanFilter API is a more stable API for defining scanning and filtering programs.

Methods

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.47 NdbInterpretedCode class methods and descriptions

Name	Description
NdbInterpretedCode	Class constructor
add_reg()	Add two register values and store the result in a third register
add_val()	Add a value to a table column value
branch_col_and_mas	பாறார்கை©ையாள value ANDed with a bitmask is equal to the bitmask
branch_col_and_mas	շխտրը ifeaccolumn value ANDed with a bitmask is equal to 0
branch_col_and_mas	Jump ifækolumn value ANDed with a bitmask is not equal to the bitmask
branch_col_and_mas	Jump ifeacolumn value ANDed with a bitmask is not equal to 0
branch_col_eq()	Jump if a column value is equal to another
branch_col_eq_null	Jump if a column value is NULL
branch_col_ge()	Jump if a column value is greater than or equal to another
branch_col_gt()	Jump if a column value is greater than another
branch_col_le()	Jump if a column value is less than or equal to another
branch_col_like()	Jump if a column value matches a pattern
branch_col_lt()	Jump if a column value is less than another
branch_col_ne()	Jump if a column value is not equal to another
branch_col_ne_null	Jump if a column value is not NULL
branch_col_notlike	Jump if a column value does not match a pattern
branch_eq()	Jump if one register value is equal to another
branch_eq_null()	Jump if a register value is NULL
branch_ge()	Jump if one register value is greater than or equal to another
branch_gt()	Jump if one register value is greater than another
branch_label()	Unconditional jump to a label
branch_le()	Jump if one register value is less than or equal to another
branch_lt()	Jump if one register value is less than another

Name	Description
branch_ne()	Jump if one register value is not equal to another
branch_ne_null()	Jump if a register value is not NULL
call_sub()	Call a subroutine
copy()	Make a deep copy of an NdbInterpretedCode object
<pre>def_label()</pre>	Create a label for use within the interpreted program
def_sub()	Define a subroutine
finalise()	Completes interpreted program and prepares it for use
getNdbError()	Gets the most recent error associated with this NdbInterpretedCode object
getTable()	Gets the table on which the program is defined
getWordsUsed()	Gets the number of words used in the buffer
interpret_exit_las	Return a row as part of the result, and do not check any more rows in this fragment
interpret_exit_nok	Do not return a row as part of the result
<pre>interpret_exit_ok(</pre>	Return a row as part of the result
<pre>load_const_null()</pre>	Load a NULL value into a register
<pre>load_const_u16()</pre>	Load a 16-bit numeric value into a register
load_const_u32()	Load a 32-bit numeric value into a register
load_const_u64()	Load a 64-bit numeric value into a register
read_attr()	Read a table column value into a register
ret_sub()	Return from a subroutine
sub_reg()	Subtract two register values and store the result in a third register
sub_val()	Subtract a value from a table column value
write_attr()	Write a register value into a table column

For reasons of efficiency, methods of this class provide minimal error checking.

See also Section 1.6, "Using NdbInterpretedCode".

Types

This class defines no public types.

NdbInterpretedCode Constructor

Description

This is the ${\tt NdbInterpretedCode}$ class constuctor.

Signature

```
NdbInterpretedCode
    (
        const NdbDictionary::Table* table = 0,
        Uint32* buffer = 0,
```

```
Uint32 buffer_word_size = 0
)
```

Alternative constructor (NDB 8.0.18 and later)

```
NdbInterpretedCode
    (
        const NdbRecord&,
        Uint32* buffer = 0,
        Uint32 buffer_word_size = 0);
```

Parameters

The NdbInterpretedCode constructor takes three parameters, as described here:

- The table against which this program is to be run. Prior to NDB 8.0.18, this parameter must be supplied if the program is tablespecific—that is, if it reads from or writes to columns in a table. In NDB 8.0.18 and later, the constructor accepts an NdbRecord in place of the Table
- A pointer to a *buffer* of 32-bit words used to store the program.
- buffer_word_size is the length of the buffer passed in. If the program exceeds this length then adding new instructions will fail with error 4518 Too many instructions in interpreted program.

Alternatively, if no buffer is passed, a buffer will be dynamically allocated internally and extended to cope as instructions are added.

Return value

An instance of NdbInterpretedCode.

NdbInterpretedCode::add_reg()

Description

This method sums the values stored in any two given registers and stores the result in a third register.

Signature

```
int add_reg
   (
     Uint32 RegDest,
     Uint32 RegSource1,
     Uint32 RegSource2
)
```

Parameters

This method takes three parameters. The first of these is the register in which the result is to be stored (RegDest). The second and third parameters (RegSource1 and RegSource2) are the registers whose values are to be summed.

For storing the result, it is possible to re-use one of the registers whose values are summed; that is, <code>RegDest</code> can be the same as <code>RegSource1</code> or <code>RegSource2</code>.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::add_val()

Description

This method adds a specified value to the value of a given table column, and places the original and modified column values in registers 6 and 7. It is equivalent to the following series of NdbInterpretedCode

method calls, where attrId is the table column' attribute ID and aValue is the value to be added:

```
read_attr(6, attrId);
load_const_u32(7, aValue);
add_reg(7,6,7);
write_attr(attrId, 7);
```

aValue can be a 32-bit or 64-bit integer.

Signature

This method can be invoked in either of two ways, depending on whether aValue is 32-bit or 64-bit.

32-bit aValue:

```
int add_val
    (
      Uint32 attrId,
      Uint32 aValue
)
```

64-bit aValue:

```
int add_val
    (
      Uint32 attrId,
      Uint64 aValue
)
```

Parameters

A table column attribute ID and a 32-bit or 64-bit integer value to be added to this column value.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_and_mask_eq_mask()

Description

This method is used to compare a BIT column value with a bitmask; if the column value ANDed together with the bitmask is equal to the bitmask, then execution jumps to a specified label specified in the method call.

Signature

```
int branch_col_and_mask_eq_mask
   (
      const void* mask,
      Uint32 unused,
      Uint32 attrId,
      Uint32 Label
)
```

Parameters

This method can accept four parameters, of which three are actually used. These are described in the following list:

- A pointer to a constant *mask* to compare the column value to
- A Uint 32 value which is currently unused.
- The attrId of the column to be compared.
- A program *Label* to jump to if the condition is true.

Return value

This method returns 0 on success and -1 on failure.

NdbInterpretedCode::branch_col_and_mask_eq_zero()

Description

This method is used to compare a BIT column value with a bitmask; if the column value $\underline{\mbox{ANDed}}$ together with the bitmask is equal to 0, then execution jumps to a specified label specified in the method call.

Signature

```
int branch_col_and_mask_eq_zero
   (
     const void* mask,
     Uint32 unused,
     Uint32 attrId,
     Uint32 Label
)
```

Parameters

This method can accept the following four parameters, of which three are actually used:

- A pointer to a constant *mask* to compare the column value to.
- A Uint32 value which is currently unused.
- The attrId of the column to be compared.
- A program Labe1 to jump to if the condition is true.

Return value

This method returns 0 on success and -1 on failure.

NdbInterpretedCode::branch_col_and_mask_ne_mask()

Description

This method is used to compare a BIT column value with a bitmask; if the column value ANDed together with the bitmask is not equal to the bitmask, then execution jumps to a specified label specified in the method call.

Signature

```
int branch_col_and_mask_ne_mask
   (
      const void* mask,
      Uint32 unused,
      Uint32 attrId,
      Uint32 Labe1
)
```

Parameters

This method accepts four parameters, of which three are actually used. These described in the following list:

- A pointer to a constant *mask* to compare the column value to.
- A Uint32 value which is currently unused.
- The attrId of the column to be compared.
- A program *Label* to jump to if the condition is true.

Return value

This method returns 0 on success and -1 on failure.

NdbInterpretedCode::branch_col_and_mask_ne_zero()

Description

This method is used to compare a BIT column value with a bitmask; if the column value ANDed together with the bitmask is not equal to 0, then execution jumps to a specified label specified in the method call.

Signature

```
int branch_col_and_mask_ne_zero
   (
      const void* mask,
      Uint32 unused,
      Uint32 attrId,
      Uint32 Label
   )
```

Parameters

This method accepts the following four parameters, of which three are actually used:

- A pointer to a constant *mask* to compare the column value to.
- A Uint32 value which is currently unused.
- The attrId of the column to be compared.
- A program *Labe1* to jump to if the condition is true.

Return value

This method returns 0 on success and -1 on failure.

NdbInterpretedCode::branch_col_eq()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the values are equal. In NDB 8.0.18 and later, it can also be used to compare two columns for equality.

Signature

Compare a column with a value:

```
int branch_col_eq
   (
      const void* val,
      Uint32 len,
      Uint32 attrId,
      Uint32 Label
)
```

Compare two columns:

```
int branch_col_eq
    (
      Uint32 attrId1,
      Uint32 attrId2,
      Uint32 label
)
```

Parameters

When comparing a column and a value, this method takes the following four parameters:

- A constant value (val)
- The length of the value (in bytes)
- The attribute ID of the table column whose value is to be compared with val
- A Label (previously defined using def_label()) to jump to if the compared values are equal

When comparing two table column values, the parameters required are shown here:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- *label*: Location to jump to if the compared columns are the same. Must already have been defined using def_label()

When using this method to compare two columns, the columns must be of exactly the same type.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_eq_null()

Description

This method tests the value of a table column and jumps to the indicated program label if the column value is NULL.

Signature

```
int branch_col_eq_null
   (
     Uint32 attrId,
     Uint32 Labe1
)
```

Parameters

This method requires the following two parameters:

- · The attribute ID of the table column
- The program label to jump to if the column value is ${\tt NULL}$

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_ge()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the constant column value. In NDB 8.0.18 and later, it can also be used to compare two columns and perform the jump if the value of the first column is greater than or equal to that of the second.

Signature

Compare value with column:

```
int branch_col_ge
   (
      const void* val,
      Uint32 len,
      Uint32 attrId,
      Uint32 label
   )
```

Compare values of two columns:

```
int branch_col_ge
   (
    Uint32 attrId1,
   Uint32 attrId2,
   Uint32 label
```

Parameters

When used to compare a value with a column, this method takes the four parameters listed here:

- A constant value (val)
- The length of the value (in bytes)
- The attribute ID of the table column whose value is to be compared with val
- A *label* (previously defined using def_label()) to jump to if the constant value is greater than or equal to the column value

The method takes the parameters listed here when used to compare two columns:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- labe1: Jump to this if the first column value is greater than or equal to the second

When comparing two columns, the types of the columns must be exactly the same in all respects.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_gt()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the constant is greater than the column value. In NDB 8.0.18 and later, this method is overloaded such that it can be used to compare two column values and make the jump if the first is greater than the second.

Signature

Compare value with column:

```
int branch_col_ge
   (
      const void* val,
      Uint32 len,
      Uint32 attrId,
      Uint32 label
   )
```

Compare values of two columns:

```
int branch_col_ge
   (
     Uint32 attrId1,
     Uint32 attrId2,
     Uint32 labe1
)
```

Parameters

When used to compare a value with a table column, this method takes the following four parameters:

- A constant value (val)
- The length of the value (in bytes)
- The attribute ID of the table column whose value is to be compared with val
- A Label (previously defined using def_label()) to jump to if the constant value is greater than the column value

The method takes the three parameters listed here when used to compare two columns:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- label: Jump to this if the first column value is greater than or equal to the second

When comparing two columns, the types of the columns must be exactly the same in all respects.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_le()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the constant is less than or equal to the column value. Beginning with NDB 8.0.18, it can also be used to compare two table column values in this fashion.

Signature

Compare a table column value with a constant:

```
int branch_col_le
   (
     const void* val,
     Uint32 len,
     Uint32 attrId,
     Uint32 Label
)
```

Compare values of two table columns:

```
int branch_col_ge
   (
    Uint32 attrId1,
    Uint32 attrId2,
    Uint32 label
)
```

Parameters

When comparing a table column value with a constant, this method takes the four parameters listed here:

- A constant value (val)
- The length of the value (in bytes)

- The attribute ID of the table column whose value is to be compared with val
- A Label (previously defined using def_label()) to jump to if the constant value is less than or equal to the column value

The method takes the three parameters listed here when used to compare two table column values:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- labe1: Jump to this if the first column value is less than or equal to the second

When comparing two table column values, the types of the column values must be exactly the same in all respects.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_like()

Description

This method tests a table column value against a regular expression pattern and jumps to the indicated program label if they match.

Signature

```
int branch_col_like
   (
     const void* val,
     Uint32 len,
     Uint32 attrId,
     Uint32 Label
)
```

Parameters

This method takes four parameters, which are listed here:

- A regular expression pattern (val); see Pattern-Based
 NdbInterpretedCode Branch Operations, for the syntax supported
- Length of the pattern (in bytes)
- The attribute ID for the table column being tested
- The program label to jump to if the table column value matches the pattern

Return value

0 on success, -1 on failure

NdbInterpretedCode::branch_col_lt()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the constant is less than the column value. In NDB 8.0.18 and later, two table column values can be compared instead.

Signature

Compare a table column value with a constant:

```
int branch_col_lt
```

```
(
  const void* val,
  Uint32 len,
  Uint32 attrId,
  Uint32 Label
)
```

Compare two table column values:

```
int branch_col_lt
    (
      Uint32 attrId1,
      Uint32 attrId2,
      Uint32 label
)
```

Parameters

When comparing a table column value with a constant, this method takes the following four parameters:

- A constant value (val)
- The length of the value (in bytes)
- The attribute ID of the table column whose value is to be compared with val
- A Label (previously defined using def_label()) to jump to if the constant value is less than the column value

When used to compare two table column values, <code>branch_col_lt()</code> takes the following three parameters:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- label: Jump to this if the first column value is less than the second

When comparing two table column values, the types of the table column values must be exactly the same. This means that they must have the same length, precision, and scale.

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_col_ne()

Description

This method compares a table column value with an arbitrary constant and jumps to the specified program label if the two values are not equal. In NDB 8.0.18 and later, it can also be used to compare a table column value with another table column value instead.

Signature

Compare a table column value with a constant:

```
int branch_col_ne
   (
      const void* val,
      Uint32 len,
      Uint32 attrId,
      Uint32 Label
)
```

Compare two table column values:

```
int branch_col_ne
   (
     Uint32 attrId1,
     Uint32 attrId2,
     Uint32 label
)
```

Parameters

When comparing a table column value with a constant, this method takes the four parameters listed here:

- A constant value (val)
- The length of the value (in bytes)
- The attribute ID of the table column whose value is to be compared with val
- A Label (previously defined using def_label()) to jump to if the compared values are unequal

When comparing two table column values, the parameters required are shown here:

- AttrId1: The attribute ID of the first table column whose value is to be compared
- AttrId2: The attribute ID of the second table column
- *label*: Location to jump to if the compared columns are not the same. Must already have been defined using def_label()

When using this method to compare two table column values, the columns must be of exactly the same type.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_ne_null()

Description

This method tests the value of a table column and jumps to the indicated program label if the column value is not NULL.

Signature

```
int branch_col_ne_null
   (
     Uint32 attrId,
     Uint32 Label
)
```

Parameters

This method requires the following two parameters:

- The attribute ID of the table column
- The program label to jump to if the column value is not NULL. The label must have been defined previously using def_label().

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::branch_col_notlike()

Description

This method is similar to branch_col_like() in that it tests a table column value against a regular expression pattern; however it jumps to the indicated program label only if the pattern and the column value do not match.

Signature

```
int branch_col_notlike
   (
     const void* val,
     Uint32 len,
     Uint32 attrId,
     Uint32 Label
)
```

Parameters

This method takes the following four parameters:

- A regular expression pattern (val); see Pattern-Based
 NdbInterpretedCode Branch Operations, for the syntax supported
- Length of the pattern (in bytes)
- The attribute ID for the table column being tested
- The program label to jump to if the table column value does not match the pattern. The Label must have been defined previously using def_label().

Return value

Returns 0 on success, -1 on failure

NdbInterpretedCode::branch_eq()

Description

This method compares two register values; if they are equal, then the interpreted program jumps to the specified label.

Signature

```
int branch_eq
    (
        Uint32 RegLvalue,
        Uint32 RegRvalue,
        Uint32 Label
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared—RegLvalue and RegRvalue—and the program Label to jump to if they are equal. Label must have been defined previously using def_label().

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_eq_null()

Description

This method compares a register value with NULL; if the register value is null, then the interpreted program jumps to the specified label.

Signature

```
int branch_eq_null
   (
     Uint32 RegLvalue,
     Uint32 Labe1
)
```

Parameters

This method takes two parameters, the register whose value is to be compared with NULL (RegLvalue) and the program Label to jump to

if RegLvalue is null. Label must have been defined previously using def label().

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_ge()

Description

This method compares two register values; if the first is greater than or equal to the second, the interpreted program jumps to the specified label.

Signature

```
int branch_ge
   (
     Uint32 RegLvalue,
     Uint32 RegRvalue,
     Uint32 Label
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared—RegLvalue and RegRvalue—and the program Label to jump to if RegLvalue is greater than or equal to RegRvalue. Label must have been defined previously using $def_label()$.

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_gt()

Description

This method compares two register values; if the first is greater than the second, the interpreted program jumps to the specified label.

Signature

```
int branch_gt
    (
      Uint32 RegLvalue,
      Uint32 RegRvalue,
      Uint32 Label
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared—RegLvalue and RegRvalue—and the program Label to jump to if RegLvalue is greater than RegRvalue. Label must have been defined previously using def label().

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_label()

Description

This method performs an unconditional jump to an interpreted program label (see NdbInterpretedCode::def label()).

Signature

```
int branch_label
   (
    Uint32 Label
)
```

Parameters

This method takes a single parameter, an interpreted program *Label* defined using def_label().

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_le()

Description

This method compares two register values; if the first is less than or equal to the second, the interpreted program jumps to the specified label.

Signature

```
int branch_le
    (
      Uint32 RegLvalue,
      Uint32 RegRvalue,
      Uint32 Labe1
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared—RegLvalue and RegRvalue—and the program Label to jump to if RegLvalue is less than or equal to RegRvalue. Label must have been defined previously using $def_label()$.

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_lt()

Description

This method compares two register values; if the first is less than the second, the interpreted program jumps to the specified label.

Signature

```
int branch_lt
   (
     Uint32 RegLvalue,
     Uint32 RegRvalue,
     Uint32 Labe1
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared—RegLvalue and RegRvalue—and the program Label to jump to if RegLvalue is less than RegRvalue. Label must have been defined previously using $def_label()$.

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch ne()

Description

This method compares two register values; if they are not equal, then the interpreted program jumps to the specified label.

Signature

```
int branch_ne
   (
     Uint32 RegLvalue,
     Uint32 RegRvalue,
     Uint32 Labe1
)
```

Parameters

This method takes three parameters, the registers whose values are to be compared (RegLvalue and RegRvalue) and the program label to jump to if they are not equal. Label must have been defined previously using def_label().

Return value

0 on success, -1 on failure.

NdbInterpretedCode::branch_ne_null()

Description

This method compares a register value with NULL; if the value is not null, then the interpreted program jumps to the specified label.

Signature int branch_ne_null

(
Uint32 RegLvalue,
Uint32 Label

Parameters

This method takes two parameters, the register whose value is to be compared with NULL (RegLvalue) and the program Label to jump to if RegLvalue is not null. Label must have been defined previously using def label().

Return value 0 on success, -1 on failure.

NdbInterpretedCode::call_sub()

Description This method is used to call a subroutine.

Signature int call_sub

Uint32 SubroutineNumber

Parameters This method takes a single parameter, the number identifying the

subroutine to be called.

Return value Returns 0 on success, -1 on failure.

NdbInterpretedCode::copy()

Description Makes a deep copy of an NdbInterpretedCode object.

Signature int copy

const NdbInterpretedCode& src

Parameters A reference to the copy.

Return value 0 on success, or an error code.

NdbInterpretedCode::def_label()

Description This method defines a label to be used as the target of one or more

jumps in an interpreted program.

def_label() uses a 2-word buffer and requires no space for request messages.

Signature int def_label

(int LabelNum

Parameters This method takes a single parameter *Labe INum*, an integer whose

value must be unique among all values used for labels within the

interpreted program.

Return value 0 on success; -1 on failure.

NdbInterpretedCode::def_sub()

Description This method is used to mark the start of a subroutine. See Using

Subroutines with NdbInterpretedCode, for more information.

Signature

int def_sub
 (
 Uint32 SubroutineNumber
)

Parameters

A single parameter, a number used to identify the subroutine.

Return value

Returns 0 on success, -1 otherwise.

NdbInterpretedCode::finalise()

Description

This method prepares an interpreted program, including any subroutines it might have, by resolving all branching instructions and calls to subroutines. It must be called before using the program, and can be invoked only once for any given NdbInterpretedCode object.

If no instructions have been defined, this method attempts to insert a single interpret_exit_ok() method call prior to finalization.

Signature

int finalise
 (
 void
)

Parameters

None.

Return value

Returns 0 on success, -1 otherwise.

NdbInterpretedCode::getNdbError()

Description

This method returns the most recent error associated with this NdbInterpretedCode object.

Signature

const class NdbError& getNdbError
 (
 void
) const

Parameters

None.

Return value

A reference to an NdbError object.

NdbInterpretedCode::getTable()

Description

This method can be used to obtain a reference to the table for which the NdbInterpretedCode object was defined.

Signature

void
) const

Parameters

None.

Return value

A pointer to a Table object. Returns NULL if no table object was supplied when the NdbInterpretedCode was instantiated.

NdbInterpretedCode::getWordsUsed()

Description

This method returns the number of words from the buffer that have been used, whether the buffer is one that is user-supplied or the internally-provided buffer.

Signature Uint32 getWordsUsed

void
) const

Parameters None.

Return value The 32-bit number of words used from the buffer.

NdbInterpretedCode::interpret_exit_last_row()

Description For a scanning operation, invoking this method indicates that this row

should be returned as part of the scan, and that no more rows in this fragment should be scanned. For other types of operations, the method

causes the operation to be aborted.

Signature int interpret_exit_last_row

(void

Parameters None.

Return value Returns 0 if successful, -1 otherwise.

NdbInterpretedCode::interpret_exit_nok()

Description For scanning operations, this method is used to indicate that the

current row should not be returned as part of the scan, and to cause the program should move on to the next row. It causes other types of

operations to be aborted.

Signature int interpret_exit_nok

(
Uint32 ErrorCode = 626 // HA_ERR_KEY_NOT_FOUND
)

Parameters This method takes a single (optional) parameter *ErrorCode*.

(For a complete listing of NDB error codes, see Section 2.4.2, "NDB Error Codes: by Type".) If not supplied, this defaults to 626 (HA_ERR_KEY_NOT_FOUND, Tuple did not exist. Applications should use error code 626 or another code in the range 6000 to 6999

inclusive.

For any values other than those mentioned here, the behavior of this method is undefined, and is subject to change at any time without prior

notice.

Return value Returns 0 on success, -1 on failure.

NdbInterpretedCode::interpret_exit_ok()

Description For a scanning operation, this method indicates that the current row

should be returned as part of the results of the scan and that the program should move on to the next row. For other operations, calling

this method causes the interpreted program to exit.

Signature int interpret_exit_ok

void

Parameters None.

Return value Returns 0 on success, -1 on failure.

NdbInterpretedCode::load_const_null()

Description This method is used to load a NULL value into a register.

Signature int load_const_null

Uint32 RegDest

Parameters This method takes a single parameter, the register into which to place

the NULL.

Return value Returns 0 on success, -1 otherwise.

NdbInterpretedCode::load_const_u16()

Description This method loads a 16-bit value into the specified interpreter register.

Signature int load_const_u16

Uint32 RegDest,
Uint32 Constant

Parameters This method takes the following two parameters:

• RegDest: The register into which the value should be loaded.

• A Constant value to be loaded

Return value Returns 0 on success, -1 otherwise.

NdbInterpretedCode::load_const_u32()

Description This method loads a 32-bit value into the specified interpreter register.

Signature int load_const_u32

(
 Uint32 RegDest,
 Uint32 Constant

Parameters This method takes the following two parameters:

• RegDest: The register into which the value should be loaded.

• A Constant value to be loaded

Return value Returns 0 on success, -1 otherwise.

NdbInterpretedCode::load_const_u64()

Description This method loads a 64-bit value into the specified interpreter register.

Signature int load_const_u64 (

Uint32 RegDest,
Uint64 Constant

Parameters

This method takes the following two parameters:

- RegDest: The register into which the value should be loaded.
- A Constant value to be loaded

Return value

Returns 0 on success, -1 otherwise.

NdbInterpretedCode::read_attr()

Description

The read_attr() method is used to read a table column value into a program register. The column may be specified either by using its attribute ID or as a pointer to a Column object.

Signature

This method can be called in either of two ways. The first of these is by referencing the column by its attribute ID, as shown here:

```
int read_attr
    (
      Uint32 RegDest,
      Uint32 attrId
)
```

Alternatively, you can reference the column as a Column object, as shown here:

```
int read_attr
    (
        Uint32 RegDest,
        const NdbDictionary::Column* column
)
```

Parameters

This method takes two parameters, as described here:

- The register to which the column value is to be copied (RegDest).
- Either of the following references to the table column whose value is to be copied:
 - The table column's attribute ID (attrId)
 - A pointer to a *column*—that is, a pointer to an *Column* object referencing the table column

Return value

Returns 0 on success, and -1 on failure.

NdbInterpretedCode::ret_sub()

Description

This method marks the end of the current subroutine.

Signature

```
int ret_sub
   (
     void
)
```

Parameters

None.

Return value

Returns 0 on success, -1 otherwise.

NdbInterpretedCode::sub_reg()

Description

This method gets the difference between the values stored in any two given registers and stores the result in a third register.

Signature

```
int sub_reg
   (
     Uint32 RegDest,
     Uint32 RegSource1,
     Uint32 RegSource2
)
```

Parameters

This method takes three parameters. The first of these is the register in which the result is to be stored (RegDest). The second and third parameters (RegSource1 and RegSource2) are the registers whose values are to be subtracted. In other words, the value of register RegDest is calculated as the value of the expression shown here:

```
(value in register RegSource1) - (value in register RegSource2)
```

It is possible to re-use one of the registers whose values are subtracted for storing the result; that is, <code>RegDest</code> can be the same as <code>RegSource1</code> or <code>RegSource2</code>.

Return value

0 on success; -1 on failure.

NdbInterpretedCode::sub_val()

Description

This method subtracts a specified value from the value of a given table column, and places the original and modified column values in registers 6 and 7. It is equivalent to the following series of NdbInterpretedCode method calls, where attrId is the table column' attribute ID and aValue is the value to be subtracted:

```
read_attr(6, attrId);
load_const_u32(7, aValue);
sub_reg(7,6,7);
write_attr(attrId, 7);
```

aValue can be a 32-bit or 64-bit integer.

Signature

This method can be invoked in either of two ways, depending on whether aValue is 32-bit or 64-bit.

32-bit aValue:

```
int sub_val
    (
      Uint32 attrId,
      Uint32 aValue
)
```

64-bit aValue:

```
int sub_val
   (
     Uint32 attrId,
     Uint64 aValue
)
```

Parameters

A table column attribute ID and a 32-bit or 64-bit integer value to be subtracted from this column value.

Return value

Returns 0 on success, -1 on failure.

NdbInterpretedCode::write_attr()

Description

This method is used to copy a register value to a table column. The column may be specified either by using its attribute ID or as a pointer to a Column object.

Signature

This method can be invoked in either of two ways. The first of these is requires referencing the column by its attribute ID, as shown here:

```
int read_attr
    (
      Uint32 attrId,
      Uint32 RegSource
)
```

You can also reference the column as a Column object instead, like this:

```
int read_attr
    (
        const NdbDictionary::Column* column,
        Uint32 RegSource
)
```

Parameters

This method takes two parameters as follows:

- A reference to the table column to which the register value is to be copied. This can be either of the following:
 - The table column's attribute ID (attrId)
 - A pointer to a *column*—that is, a pointer to an *column* object referencing the table column
- The register whose value is to be copied (RegSource).

Return value

Returns 0 on success; -1 on failure.

2.3.20 The NdbOperation Class

This section provides information about the NdbOperation class.

- NdbOperation Class Overview
- NdbOperation::AbortOption
- NdbOperation::deleteTuple()
- NdbOperation::equal()
- NdbOperation::getBlobHandle()
- NdbOperation::getLockHandle
- NdbOperation::getLockMode()
- NdbOperation::getNdbError()
- NdbOperation::getNdbErrorLine()

NdbOperation::getTable()

NdbOperation::getTableName()

NdbOperation::getNdbTransaction()

NdbOperation::getType()

NdbOperation::getValue()

• NdbOperation::GetValueSpec

NdbOperation::insertTuple()

• NdbOperation::LockMode

• NdbOperation::OperationOptions

NdbOperation::readTuple()

NdbOperation::setValue()

• NdbOperation::SetValueSpec

NdbOperation::Type

NdbOperation::updateTuple()

NdbOperation::writeTuple()

NdbOperation Class Overview

Parent class None

Child classes NdbIndexOperation, NdbScanOperation

Description

NdbOperation represents a "generic" data operation. Its subclasses represent more specific types of operations. See NdbOperation::Type

for a listing of operation types and their corresponding NdbOperation

subclasses.

Methods The following table lists the public methods of this class and the purpose or use of each method:

Table 2.48 NdbOperation class methods and descriptions

Name	Description	
deleteTuple()	Removes a tuple from a table	
equal()	Defines a search condition using equality	
getBlobHandle()	Used to access blob attributes	
getLockHandle()	Gets a lock handle for the operation	
getLockMode()	Gets the operation's lock mode	
getNdbError()	Gets the latest error	
getNdbErrorLine()	Gets the number of the method where the latest error occurred	
getTableName()	Gets the name of the table used for this operation	

Name	Description	
getTable()	Gets the table object used for this operation	
getNdbTransaction(Gets the NdbTransaction object for this operation	
getType()	Gets the type of operation	
getValue()	Allocates an attribute value holder for later	
	access	
<pre>insertTuple()</pre>	Adds a new tuple to a table	
readTuple()	Reads a tuple from a table	
setValue()	Defines an attribute to set or update	
updateTuple()	Updates an existing tuple in a table	
writeTuple()	Inserts or updates a tuple	

This class has no public constructor. To create an instance of NdbOperation, you must use NdbTransaction::getNdbOperation().

Types

The NdbOperation class defines three public types, shown in the following table:

Table 2.49 NdbOperation class types and descriptions

Name	Description
AbortOption	Determines whether a failed operation causes failure of the transaction of which it is part
LockMode	The type of lock used when performing a read operation
Туре	Operation access types

For more information about the use of NdbOperation, see Single-row operations.

NdbOperation::AbortOption

This section provides information about the AbortOption data type.

Description

This type is used to determine whether failed operations should force a transaction to be aborted. It is used as an argument to the <code>execute()</code> method—see NdbTransaction::execute(), for more information.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.50 NdbOperation::AbortOption type values and descriptions

Name	Description	
AbortOnError	A failed operation causes the transaction to abort.	
AO_IgnoreOnError	Failed operations are ignored; the transaction continues to execute.	

Name	Description	
DefaultAbortOption	The AbortOption value is set according to the operation type:	
	Read operations: AO_IgnoreOnError	
	• Scan takeover or DML operations: AbortOnError	

See NdbTransaction::execute(), for more information.

NdbOperation::deleteTuple()

Description

This method defines the NdbOperation as a DELETE operation. When the NdbTransaction::execute() method is invoked, the operation deletes a tuple from the table.

Signature

```
virtual int deleteTuple
(
void
)
```

Parameters

None.

Return value

Returns 0 on success, -1 on failure.

NdbOperation::equal()

Description

This method defines a search condition with an equality. The condition is true if the attribute has the given value. To set search conditions on multiple attributes, use several calls to equal(); in such cases all of them must be satisfied for the tuple to be selected.

If the attribute is of a fixed size, its value must include all bytes. In particular a Char value must be native-space padded. If the attribute is of variable size, its value must start with 1 or 2 little-endian length bytes (2 if its type is Long*).

When using <code>insertTuple()</code>, you may also define the search key with <code>setValue()</code>. See NdbOperation::setValue().

Signature

There are 10 versions of equal(), each having slightly different parameters. All of these are shown here:

```
int equal
    (
        const char* name,
        const char* value
    )

int equal
    (
        const char* name,
        Int32     value
    )

int equal
    (
        const char* name,
        Int32     value
    )
```

```
int equal
     const char* name,
     Int64 value
int equal
    const char* name,
    Uint64 value
int equal
     Uint32
     const char* value
int equal
    Uint32 id,
     Int32 value
int equal
    Uint32 id,
     Uint32 value
int equal
    Uint32 id,
     Int64 value
int equal
     Uint32 id,
     Uint64 value
```

Parameters

This method requires two parameters:

- The first parameter can be either of the following:
 - 1. The *name* of the attribute (a string)
 - 2. The id of the attribute (an unsigned 32-bit integer)
- The second parameter is the attribute *value* to be tested. This value can be any one of the following 5 types:
 - String
 - 32-bit integer
 - Unsigned 32-bit integer
 - 64-bit integer
 - Unsigned 64-bit integer

Return value

Returns -1 in the event of an error.

NdbOperation::getBlobHandle()

Description

This method is used in place of <code>getValue()</code> or <code>setValue()</code> for blob attributes. It creates a blob handle (<code>NdbBlob</code> object). A second call with the same argument returns the previously created handle. The handle is linked to the operation and is maintained automatically.

Signature

This method has two forms, depending on whether it is called with the name or the ID of the blob attribute:

```
virtual NdbBlob* getBlobHandle
     (
        const char* name
)
```

or

```
virtual NdbBlob* getBlobHandle
   (
     Uint32 id
)
```

Parameters

This method takes a single parameter, which can be either one of the following:

- The name of the attribute
- The id of the attribute

Return value

Regardless of parameter type used, this method return a pointer to an instance of NdbBlob.

NdbOperation::getLockHandle

Description

Returns a pointer to the current operation's lock handle. When used with NdbRecord, the lock handle must first be requested with the OO_LOCKHANDLE operation option. For other operations, this method can be used alone. In any case, the NdbLockHandle object returned by this method cannot be used until the operation has been executed.

Signature

```
const NdbLockHandle* getLockHandle
  (
    void
  ) const
```

or

Parameters

None.

Return value

Pointer to an NdbLockHandle that can be used by the NdbTransaction methods unlock() and releaseLockHandle().

Using lock handle methods. Shared or exclusive locks taken by read operations in a transaction are normally held until the transaction commits or aborts. Such locks can be released before a transaction commits or aborts by requesting a lock handle when defining the read operation. Once the read operation has been executed, an NdbLockHandle can be used to create a new unlock operation (with NdbTransaction::unlock()). When the unlock operation is executed, the row lock placed by the read operation is released.

The steps required to release these locks are listed here:

- Define the primary key read operation in the normal way with lock mode LM_Read or LM_Exclusive.
- Call NdbOperation::getLockHandle() during operation definition, or, for Ndbrecord, set the OO_LOCKHANDLE operation option when calling NdbTransaction::readTuple().
- Call NdbTransaction::execute(); the row is now locked from this point on, as normal.
- (Use data, possibly making calls to NdbTransaction::execute().)
- Call NdbTransaction::unlock(), passing in the const NdbLockHandle obtained previously to create an unlock operation.
- Call NdbTransaction::execute(); this unlocks the row.

Notes:

- As with other operation types, unlock operations can be batched.
- Each NdbLockHandle object refers to a lock placed on a row by a single primary key read operation. A single row in the database may have concurrent multiple lock holders (mode LM_Read) and may have multiple lock holders pending (LM_Exclusive), so releasing the claim of one lock holder may not result in a change to the observable lock status of the row.
- Lock handles are supported for scan lock takeover operations; the lock handle must be requested before the lock takeover is executed.
- Lock handles and unlock operations are not supported for unique index read operations.

NdbOperation::getLockMode()

Description This method gets the operation's lock mode.

Signature LockMode getLockMode

void
) const

Parameters None.

Return value A LockMode value. See NdbOperation::LockMode.

NdbOperation::getNdbError()

Description This method gets the most recent error (an NdbError object).

Signature const NdbError& getNdbError

void
) const

Parameters None.

Return value An NdbError object.

NdbOperation::getNdbErrorLine()

Description This method retrieves the method number in which the latest error

occurred.

Signature int getNdbErrorLine

(void) const

Parameters None.

Return value The method number (an integer).

NdbOperation::getTable()

Description This method is used to retrieve the table object associated with the

operation.

Signature const NdbDictionary::Table* getTable

(void) const

Parameters None.

Return value A pointer to an instance of Table.

NdbOperation::getTableName()

Description This method retrieves the name of the table used for the operation.

Signature const char* getTableName

void
) const

Parameters None.

Return value The name of the table.

NdbOperation::getNdbTransaction()

Description Gets the NdbTransaction object for this operation.

Signature virtual NdbTransaction* getNdbTransaction

(void) const

Parameters None.

Return value A pointer to an NdbTransaction object.

NdbOperation::getType()

Description This method is used to retrieve the access type for this operation.

Signature Type getType

void

) const

Parameters

None.

Return value

A Type value.

NdbOperation::getValue()

Description

This method prepares for the retrieval of an attribute value. The NDB API allocates memory for an NdbRecAttr object that is later used to obtain the attribute value. This can be done by using one of the many NdbRecAttr accessor methods, the exact method to be used depending on the attribute's data type. (This includes the generic NdbRecAttr::aRef() method, which retrieves the data as char*, regardless of its actual type. You should be aware that this is not type-safe, and requires an explicit cast from the user.)

This method does *not* fetch the attribute value from the database; the NdbRecAttr object returned by this method is not readable or printable before calling NdbTransaction::execute().

If a specific attribute has not changed, the corresponding NdbRecAttr has the state UNDEFINED. This can be checked by using NdbRecAttr::isNULL(), which in such cases returns -1.

See NdbTransaction::execute(), and NdbRecAttr::isNULL().

Signature

There are three versions of this method, each having different parameters:

```
NdbRecAttr* getValue
   (
      const char* name,
      char* value = 0
)

NdbRecAttr* getValue
   (
      Uint32 id,
      char* value = 0
)

NdbRecAttr* getValue
   (
      const NdbDictionary::Column* col,
      char* value = 0
)
```

Parameters

All three forms of this method have two parameters, the second parameter being optional (defaults to 0). They differ only with regard to the type of the first parameter, which can be any one of the following:

- The attribute name
- The attribute id
- The table column on which the attribute is defined

In all three cases, the second parameter is a character buffer in which a non-NULL attribute value is returned. In the event that the attribute

is \mathtt{NULL} , is it stored only in the $\mathtt{NdbRecAttr}$ object returned by this method.

If no <code>value</code> is specified in the <code>getValue()</code> method call, or if 0 is passed as the value, then the <code>NdbRecAttr</code> object provides memory management for storing the received data. If the maximum size of the received data is above a small fixed size, <code>malloc()</code> is used to store it: For small sizes, a small, fixed internal buffer (32 bytes in extent) is provided. This storage is managed by the <code>NdbRecAttr</code> instance; it is freed when the operation is released, such as at transaction close time; any data written here that you wish to preserve should be copied elsewhere before this freeing of memory takes place.

If you pass a non-zero pointer for *value*, then it is assumed that this points to an portion of memory which is large enough to hold the maximum value of the column; any returned data is written to that location. The pointer should be at least 32-bit aligned.

Index columns cannot be used in place of table columns with this method. In cases where a table column is not available, you can use the attribute name, obtained with getName(), for this purpose instead.

Return value

A pointer to an NdbRecAttr object to hold the value of the attribute, or a NULL pointer, indicating an error.

Retrieving integers. Integer values can be retrieved from both the *value* buffer passed as this method's second parameter, and from the NdbRecAttr object itself. On the other hand, character data is available from NdbRecAttr if no buffer has been passed in to getValue() (see NdbRecAttr::aRef()). However, character data is written to the buffer only if one is provided, in which case it cannot be retrieved from the NdbRecAttr object that was returned. In the latter case, NdbRecAttr::aRef() returns a buffer pointing to an empty string.

Accessing bit values. The following example shows how to check a given bit from the *value* buffer. Here, op is an operation (NdbOperation object), name is the name of the column from which to get the bit value, and trans is an NdbTransaction object:

```
Uint32 buf[];
op->getValue(name, buf); /* bit column */
trans->execute();
if(buf[X/32] & 1 << (X & 31)) /* check bit X */
{
    /* bit X set */
}</pre>
```

NdbOperation::GetValueSpec

This section provides information about the GetValueSpec data structure.

Parent class NdbOperation

Description This structure is used to specify an extra value to obtain as part of an

NdbRecord operation.

Members The elements making up this structure are shown in the following table:

Table 2.51 GetValueSpec structure member names, types, and descriptions

Name	Туре	Description
column	const Column*	To specify an extra value to read, the caller must provide this, as well as (optionally NULL) appStorage pointer.
appStorage	void*	If this pointer is null, then the received value is stored in memory managed by the NdbRecAttr object. Otherwise, the received value is stored at the location pointed to (and is still accessable using the NdbRecAttr object).
		Important
		It is the caller's responsibility to ensure that the following conditions are met: 1. appStorage points to sufficient space to store any returned data.
		2. Memory pointed to by appStorage is not reused or freed until after the execute() call returns.
recAttr	NdbRecAttr*	After the operation is defined, recAttr contains a pointer to the

Name	Туре	Description
		NdbRecAttr object for receiving
		the data.

Blob reads cannot be specified using GetValueSpec.

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbOperation::insertTuple()

Description This method defines the NdbOperation to be an INSERT operation.

When the NdbTransaction::execute() method is called, this

operation adds a new tuple to the table.

Signature virtual int insertTuple

(void

Parameters None.

Return value Returns 0 on success, -1 on failure.

NdbOperation::LockMode

This section provides information about the LockMode data type.

Description This type describes the lock mode used when performing a read

operation.

Enumeration values Possible values for this type are shown, along with descriptions, in the

following table:

Table 2.52 NdbOperation::LockMode type values and descriptions

Name	Description	
LM_Read	Read with shared lock	
LM_Exclusive	Read with exclusive lock	
LM_CommittedRead	Ignore locks; read last committed	
LM_SimpleRead	Read with shared lock, but release lock directly	

There is also support for dirty reads (LM_Dirty), but this is normally for internal purposes only, and should not be used for applications deployed in a production setting.

NdbOperation::OperationOptions

This section provides information about the OperationOptions data structure.

Parent class NdbOperation

Description These options are passed to the NdbRecord-based primary key and

scan takeover operation methods defined in the ${\tt NdbTransaction}$ and

NdbScanOperation classes.

Most NdbTransaction::*Tuple() methods (see Section 2.3.25, "The NdbTransaction Class") take a supplementary <code>sizeOfOptions</code> parameter. This is optional, and is intended to permit the interface implementation to remain backward compatible with older unrecompiled clients that may pass an older (smaller) version of the <code>OperationOptions</code> structure. This effect is achieved by passing <code>sizeof(OperationOptions)</code> into this parameter.

Each option type is marked as present by setting the corresponding bit in <code>optionsPresent</code>. (Only the option types marked in <code>optionsPresent</code> need have sensible data.) All data is copied out of the <code>OperationOptions</code> structure (and any subtended structures) at operation definition time. If no options are required, then <code>NULL</code> may be passed instead.

The elements making up this structure are shown in the following table:

Table 2.53 NdbOperation::OperationOptions structure member names, types, and description

Name	Туре	Description
optionsPresen	₩int64	Which flags are present.
[]	Flags:	Type of flags.
	The accepted names and values are shown in the following list:	
	• 00_ABORTOPT: 0x01	ION:
	• 00_GETVALUE: 0x02	
	• OO_SETVALUE: 0x04	
	• OO_PARTITION 0x08	N_ID:
	• OO_INTERPRE' 0x10	red:
	• OO_ANYVALUE: 0x20	
	• OO_CUSTOMDAT	ra:
	• OO_LOCKHANDI 0x80	LE:
	• OO_QUEUABLE	

Members

Name	Туре	Description
	0x100	
	• OO_NOT_QUEU.	ABLE
	0x200	
	• OO_DEFERRED	CONSTAINTS
	0x400	
	• 00_DISABLE_	FK
	0x800	
	• OO_NOWAIT	
	0x1000	
abortOption	AbortOption	An operation-specific abort option; necessary only if the default abortoption behavior is not satisfactory.
extraGetValue	⊈ etValueSpec	Extra column values to be read.
numExtraGetVa	Diest 32	Number of extra column values to be read.
extraSetValue	s etValueSpec	Extra column values to be set.
numExtraSetVa	Liest 32	Number of extra column values to be set.
partitionId	Uint32	Limit the scan to the partition having this ID; alternatively, you can supply an PartitionSpec here. For index scans, partitioning information can be supplied for each range.
interpretedCo	dæ lbInterprete	dinterpeted code to execute as part of the scan.
anyValue	Uint32	An anyValue to be used with this operation. This is used by NDB Cluster Replication to store the SQL node's server ID. By starting the SQL node with the
		server-id-bits option (which causes only some of the server_id's bits to be used for uniquely identifying it) set to less than 32, the remaining bits can be used to store user data.

Name	Туре	Description
partitionInfo		Partition information for bounding this scan.
sizeOfPartInf		Size of the bounding partition information.

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbOperation::readTuple()

 $\label{thm:local_peration} \textbf{Description} \qquad \qquad \textbf{This method defines the $\tt NdbOperation} \ \ \textbf{as a READ operation}. \ \ \textbf{When}$

the NdbTransaction::execute() method is invoked, the operation

reads a tuple.

Signature

virtual int readTuple
 (
 LockMode mode
)

Parameters

mode specifies the locking mode used by the read operation. See NdbOperation::LockMode, for possible values.

Return value

Returns 0 on success, -1 on failure.

NdbOperation::setValue()

Description

This method defines an attribute to be set or updated.

There are a number of NdbOperation::setValue() methods that take a certain type as input (pass by value rather than passing a pointer). It is the responsibility of the application programmer to use the correct types.

The NDB API does check that the application sends a correct length to the interface as given in the length parameter. A char* value can contain any data type or any type of array. If the length is not provided, or if it is set to zero, then the API assumes that the pointer is correct, and does not check it.

To set a NULL value, use the following construct:

```
setValue("ATTR_NAME", (char*)NULL);
```

When you use insertTuple(), the NDB API automatically detects that it is supposed to use equal() instead.

In addition, it is not necessary when using insertTuple() to use setValue() on key attributes before other attributes.

Signature

There are 14 versions of NdbOperation::setValue(), each with slightly different parameters, as listed here:

```
int setValue
    (
        const char* name,
        const char* value
)
```

```
int setValue
  (
   const char* name,
Int32 value
int setValue
  (
   const char* name,
Uint32 value
int setValue
  (
   const char* name,
Int64 value
int setValue
 (
   const char* name,
Uint64 value
int setValue
   const char* name, float value
int setValue
  (
    const char* name,
    double value
int setValue
  (
   Uint32 id,
const char* value
int setValue
  (
   Uint32 id,
    Int32 value
int setValue
 (
   Uint32 id,
Uint32 value
int setValue
  (
   Uint32 id,
Int64 value
int setValue
 (
   Uint32 id,
Uint64 value
int setValue
```

```
(
    Uint32 id,
    float value
)
int setValue
    (
    Uint32 id,
    double value
)
```

Parameters

This method requires the following two parameters:

- The first parameter identifies the attribute to be set, and may be either one of the following:
 - 1. The attribute name (a string)
 - 2. The attribute id (an unsigned 32-bit integer)
- The second parameter is the *value* to which the attribute is to be set; its type may be any one of the following 7 types:
 - String (const char*)
 - 2. 32-bit integer
 - 3. Unsigned 32-bit integer
 - 4. 64-bit integer
 - 5. Unsigned 64-bit integer
 - 6. Double
 - 7. Float

See NdbOperation::equal(), for important information regarding the value's format and length.

Return value

Returns -1 in the event of failure.

NdbOperation::SetValueSpec

This section provides information about the SetValueSpec data structure.

Parent class NdbOperation

Description This structure is used to specify an extra value to set as part of an

NdbRecord operation.

Members The elements making up this structure are shown in the following table:

Table 2.54 NdbOperation::SetValueSpec attributes, with types and descriptions

Name	Туре	Description
column	Column	To specify an extra
		value to read, the

Name	Туре	Description
		caller must provide this, as well as (optionally NULL) appStorage pointer.
value	void*	This must point to the value to be set, or to NULL if the attribute is to be set to NULL. The value pointed to is copied when the operation is defined, and need not remain in place until execution time.

Blob values cannot be set using SetValueSpec.

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbOperation::Type

This section provides information about the Type data type.

Description Type is used to describe the operation access type. Each access type

is supported by ${\tt NdbOperation}$ or one of its subclasses, as shown in

the following table:

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.55 NdbOperation::Type data type values and descriptions

Name	Description
PrimaryKeyAccess	A read, insert, update, or delete operation using the primary key
UniqueIndexAccess	A read, update, or delete operation using a unique
TableScan	A full table scan
OrderedIndexScan	An ordered index scan

NdbOperation::updateTuple()

Description This method defines the NdbOperation as an UPDATE operation.

When the NdbTransaction::execute() method is invoked, the

operation updates a tuple found in the table.

Signature virtual int updateTuple

(void

Parameters None.

Return value Returns 0 on success, -1 on failure.

NdbOperation::writeTuple()

Description This method defines the NdbOperation as a WRITE operation. When

the NdbTransaction::execute() method is invoked, the operation writes a tuple to the table. If the tuple already exists, it is updated;

otherwise an insert takes place.

Signature virtual int writeTuple

(void

Parameters None.

Return value Returns 0 on success, -1 on failure.

2.3.21 The NdbRecAttr Class

This section provides information about the NdbRecAttr class.

- NdbRecAttr Class Overview
- ~NdbRecAttr()
- NdbRecAttr::aRef()
- NdbRecAttr::char_value()
- NdbRecAttr::clone()
- NdbRecAttr::double_value()
- NdbRecAttr::float_value()
- NdbRecAttr::get_size_in_bytes()
- NdbRecAttr::getColumn()
- NdbRecAttr::getType()
- NdbRecAttr::int8_value()
- NdbRecAttr::int32_value()
- NdbRecAttr::int64_value()
- NdbRecAttr::isNULL()
- NdbRecAttr::medium_value()
- NdbRecAttr::short_value()
- NdbRecAttr::u_8_value()
- NdbRecAttr::u_32_value()
- NdbRecAttr::u_64_value()
- NdbRecAttr::u_char_value()
- NdbRecAttr::u_medium_value()

NdbRecAttr::u_short_value()

NdbRecAttr Class Overview

Parent class None

Child classes None

Description

NdbRecAttr contains the value of an attribute. An NdbRecAttr object is used to store an attribute value after it has been retrieved using the NdbOperation::getValue() method. This object is allocated by the NDB API. A brief example is shown here:

```
MyRecAttr = MyOperation->getValue("ATTR2", NULL);

if(MyRecAttr == NULL)
   goto error;

if(MyTransaction->execute(Commit) == -1)
   goto error;

ndbout << MyRecAttr->u_32_value();
```

For additional examples, see Section 2.5.1, "NDB API Example Using Synchronous Transactions".

An NdbRecAttr object is instantiated with its value only when NdbTransaction::execute() is invoked. Prior to this, the value is undefined. (Use NdbRecAttr::isNULL() to check whether the value is defined.) This means that an NdbRecAttr object has valid information only between the times that NdbTransaction::execute() and Ndb::closeTransaction() are called. The value of the NULL indicator is -1 until the NdbTransaction::execute() method is invoked.

NdbRecAttr has a number of methods for retrieving values of various simple types directly from an instance of this class.

It is also possible to obtain a reference to the value regardless of its actual type, by using NdbRecAttr: aRef(); however, you should be aware that this is not type-safe, and requires a cast from the user.

The following table lists all of the public methods of this class and the purpose or use of each method:

Table 2.56 NdbRecAttr class methods and descriptions

Name	Description	
~NdbRecAttr()	Destructor method	
aRef()	Gets a pointer to the attribute value	
char_value()	Retrieves a Char attribute value	
clone()	Makes a deep copy of the RecAttr object	
double_value()	Retrieves a Double attribute value, as a double (8 bytes)	
float_value()	Retrieves a Float attribute value, as a float (4 bytes)	

Methods

Name	Description
get_size_in_bytes(Gets the size of the attribute, in bytes
getColumn()	Gets the column to which the attribute belongs
getType()	Gets the attribute's type (Column:: Type)
isNULL()	Tests whether the attribute is NULL
<pre>int8_value()</pre>	Retrieves a Tinyint attribute value, as an 8-bit integer
int32_value()	Retrieves an Int attribute value, as a 32-bit integer
int64_value()	Retrieves a Bigint attribute value, as a 64-bit integer
medium_value()	Retrieves a Mediumint attribute value, as a 32-bit integer
short_value()	Retrieves a Smallint attribute value, as a 16-bit integer
u_8_value()	Retrieves a Tinyunsigned attribute value, as an unsigned 8-bit integer
u_32_value()	Retrieves an Unsigned attribute value, as an unsigned 32-bit integer
u_64_value()	Retrieves a Bigunsigned attribute value, as an unsigned 64-bit integer
u_char_value()	Retrieves a Char attribute value, as an unsigned char
u_medium_value()	Retrieves a Mediumunsigned attribute value, as an unsigned 32-bit integer
u_short_value()	Retrieves a Smallunsigned attribute value, as an unsigned 16-bit integer

The NdbRecAttr class has no public constructor; an instance of this object is created using NdbTransaction::execute(). For information about the destructor, which is public, see ~NdbRecAttr().

The NdbRecAttr class defines no public types.

Types

~NdbRecAttr()

Description

The NdbRecAttr class destructor method.

You should delete only copies of NdbRecAttr objects that were created in your application using the clone() method.

Signature

```
~NdbRecAttr
(
void
)
```

Parameters

None.

Return value

None.

NdbRecAttr::aRef()

Description This method is used to obtain a reference to an attribute value,

as a char pointer. This pointer is aligned appropriately for the data type. The memory is released by the NDB API when

 ${\tt NdbTransaction::close()} \ \ \textbf{is executed on the transaction which}$

read the value.

Signature char* aRef

(void) const

Parameters A pointer to the attribute value. Because this pointer is constant, this

method can be called anytime after NdbOperation::getValue()

has been called.

Return value None.

NdbRecAttr::char_value()

Description This method gets a Char value stored in an NdbRecAttr object, and

returns it as a char.

Signature char_value

(void) const

Parameters None.

Return value A char value.

NdbRecAttr::clone()

Description This method creates a deep copy of an NdbRecAttr object.

The copy created by this method should be deleted by the application

when no longer needed.

Signature NdbRecAttr* clone

void
) const

Parameters None.

Return value An NdbRecAttr object. This is a complete copy of the original,

including all data.

NdbRecAttr::double_value()

Description This method gets a Double value stored in an NdbRecAttr object,

and returns it as a double.

Signature double_value

void
) const

Parameters None.

Return value A double (8 bytes).

NdbRecAttr::float_value()

Description This method gets a Float value stored in an NdbRecAttr object, and

returns it as a float.

Signature float_value

(void) const

Parameters None.

Return value A float (4 bytes).

NdbRecAttr::get_size_in_bytes()

Description You can use this method to obtain the size of an attribute (element).

Signature Uint32 get_size_in_bytes

void
) const

Parameters None.

Return value The attribute size in bytes, as an unsigned 32-bit integer.

NdbRecAttr::getColumn()

Description This method is used to obtain the column to which the attribute belongs.

Signature const NdbDictionary::Column* getColumn

void
) const

Parameters None.

Return value A pointer to a Column object.

NdbRecAttr::getType()

Description This method is used to obtain the column's data type.

Signature NdbDictionary::Column::Type getType

void
) const

Parameters None.

Return value A Column:: Type value.

NdbRecAttr::int8_value()

Description This method gets a Small value stored in an NdbRecAttr object, and

returns it as an 8-bit signed integer.

Signature Int8 int8_value

(void) const

Parameters None.

Return value An 8-bit signed integer.

NdbRecAttr::int32_value()

Description This method gets an Int value stored in an NdbRecAttr object, and

returns it as a 32-bit signed integer.

Signature Int32 int32_value

void
) const

Parameters None.

Return value A 32-bit signed integer.

NdbRecAttr::int64_value()

Description This method gets a Bigint value stored in an NdbRecAttr object,

and returns it as a 64-bit signed integer.

Signature Int64 int64_value

(void) const

Parameters None.

Return value A 64-bit signed integer.

NdbRecAttr::isNULL()

Description This method checks whether a given attribute value is NULL.

Signature int isNULL

(void) const

Parameters None.

Return value One of the following three values:

- -1: The attribute value is not defined due to an error.
- 0: The attribute value is defined, but is not NULL.
- 1: The attribute value is defined and is NULL.

In the event that NdbTransaction: execute() has not yet been called, the value returned by isNULL() is not determined.

NdbRecAttr::medium_value()

Description Gets the value of a Mediumint value stored in an NdbRecAttr object,

and returns it as a 32-bit signed integer.

Signature Int32 medium_value

(void) const

Parameters None.

Return value A 32-bit signed integer.

NdbRecAttr::short_value()

Description This method gets a Smallint value stored in an NdbRecAttr object,

and returns it as a 16-bit signed integer (short).

Signature short_value

void
) const

Parameters None.

Return value A 16-bit signed integer.

NdbRecAttr::u_8_value()

Description This method gets a Smallunsigned value stored in an NdbRecAttr

object, and returns it as an 8-bit unsigned integer.

Signature Uint8 u_8_value

(void) const

Parameters None.

Return value An 8-bit unsigned integer.

NdbRecAttr::u_32_value()

Description This method gets an Unsigned value stored in an NdbRecAttr object,

and returns it as a 32-bit unsigned integer.

Signature Uint32 u_32_value

(void) const

Parameters None.

Return value A 32-bit unsigned integer.

NdbRecAttr::u_64_value()

Description This method gets a Bigunsigned value stored in an NdbRecAttr

object, and returns it as a 64-bit unsigned integer.

Signature Uint64 u_64_value

(

void
) const

Parameters None.

Return value A 64-bit unsigned integer.

NdbRecAttr::u_char_value()

Description This method gets a Char value stored in an NdbRecAttr object, and

returns it as an unsigned char.

Signature Uint8 u_char_value

void
) const

Parameters None.

Return value An 8-bit unsigned char value.

NdbRecAttr::u_medium_value()

Description This method gets an Mediumunsigned value stored in an

NdbRecAttr object, and returns it as a 32-bit unsigned integer.

Signature Uint32 u_medium_value

void
) const

Parameters None.

Return value A 32-bit unsigned integer.

NdbRecAttr::u_short_value()

Description This method gets a Smallunsigned value stored in an NdbRecAttr

object, and returns it as a 16-bit (short) unsigned integer.

Signature Uint16 u_short_value

(void) const

Parameters None.

Return value A short (16-bit) unsigned integer.

2.3.22 The NdbRecord Interface

This section provides information about the NdbRecord interface.

Decription NdbRecord is an interface which provides a mapping to a full or

a partial record stored in NDB. In the latter case, it can be used in

conjunction with a bitmap to assist in access.

Parent None.

Methods None.

Types None.

NdbRecord has no API methods of its own; rather, it acts as a handle that can be passed between various method calls for use in many different sorts of operations, including the following:

- · Unique key reads and primary key reads
- · Table scans and index scans
- DML operations involving unique keys or primary keys
- · Operations involving index bounds

The same NdbRecord can be used simultaneously in multiple operations, transactions, and threads.

An NdbRecord can be created in NDB API programs by calling Dictionary::createRecord(). In addition, a number of NDB API methods have additional declarations that enable the programmer to leverage NdbRecord:

- NdbScanOperation::nextResult()
 NdbScanOperation::lockCurrentTuple()
 NdbScanOperation::updateCurrentTuple()
 NdbScanOperation::deleteCurrentTuple()
- Dictionary::createRecord()
- Dictionary::releaseRecord()
- NdbTransaction::readTuple()
- NdbTransaction::insertTuple()
- NdbTransaction::updateTuple()
- NdbTransaction::writeTuple()
- NdbTransaction::deleteTuple()
- NdbTransaction::scanTable()
- NdbTransaction::scanIndex()

The following members of NdbIndexScanOperation and NdbDictionary can also be used with NdbRecord scans:

- IndexBound is a structure used to describe index scan bounds.
- RecordSpecification is a structure used to specify columns and range offsets.

You can also use NdbRecord in conjunction with the PartitionSpec structure to perform scans that take advantage of partition pruning, using NdbIndexScanOperation::setBound().

2.3.23 The NdbScanFilter Class

This section provides information about the NdbScanFilter class.

NdbScanFilter Class Overview

- NdbScanFilter::begin()
- NdbScanFilter::BinaryCondition
- NdbScanFilter::cmp()
- NdbScanFilter Constructor
- NdbScanFilter::end()
- NdbScanFilter::eq()
- NdbScanFilter::isfalse()
- NdbScanFilter::isnotnull()
- NdbScanFilter::isnull()
- NdbScanFilter::istrue()
- NdbScanFilter::ge()
- NdbScanFilter::getNdbError()
- NdbScanFilter::getNdbOperation()
- NdbScanFilter::Group
- NdbScanFilter::gt()
- NdbScanFilter::le()
- NdbScanFilter::lt()
- NdbScanFilter::ne()

NdbScanFilter Class Overview

Parent class None

Child classes None

Description NdbScanFilter provides an alternative means of specifying filters for

scan operations.

Because development of this interface is ongoing, the characteristics of the NdbScanFilter class are subject to change in future releases.

Methods The following table lists the public methods of this class and the

purpose or use of each method:

Table 2.57 NdbScanFilter class methods and descriptions

Name	Description
NdbScanFilter()	Constructor method
~NdbScanFilter()	Destructor method
begin()	Begins a compound (set of conditions)

Name	Description	
cmp()	Compares a column value with an arbitrary value	
end()	Ends a compound	
eq()	Tests for equality	
ge()	Tests for a greater-than-or-equal condition	
getNdbError()	Provides access to error information	
getNdbOperation()	Gets the associated NdbOperation	
gt()	Tests for a greater-than condition	
isfalse()	Defines a term in a compound as FALSE	
isnotnull()	Tests whether a column value is not NULL	
isnull()	Tests whether a column value is NULL	
istrue()	Defines a term in a compound as TRUE	
le()	Tests for a less-than-or-equal condition	
lt()	Tests for a less-than condition	
ne()	Tests for inequality	

Types

The NdbScanFilter class defines two public types:

- BinaryCondition: The type of condition, such as lower bound or upper bound.
- Group: A logical grouping operator, such as AND or OR.

NdbScanFilter Integer Comparison Methods. NdbScanFilter provides several convenience methods which can be used in lieu of the cmp() method when the arbitrary value to be compared is an integer: eq(), ge(), gt(), le(), lt(), and ne().

Each of these methods is essentially a wrapper for <code>cmp()</code> that includes an appropriate value of <code>BinaryCondition</code> for that method's <code>condition</code> parameter; for example, <code>NdbScanFilter::eq()</code> is defined like this:

```
int eq(int columnId, Uint32 value)
{
  return cmp(BinaryCondition::COND_EQ, columnId, &value, 4);
}
```

NdbScanFilter::begin()

Description

This method is used to start a compound, and specifies the logical operator used to group the conditions making up the compound. The default is AND.

Signature

```
int begin
   (
     Group group = AND
)
```

Parameters

A Group value: one of AND, OR, NAND, or NOR. See NdbScanFilter::Group, for additional information.

Return value

0 on success, -1 on failure.

NdbScanFilter::BinaryCondition

This section provides information about the BinaryCondition data type.

Description

This type represents a condition based on the comparison of a column value with some arbitrary value—that is, a bound condition. A value of this type is used as the first argument to the cmp() method.

When used in comparisons with <code>COND_EQ</code>, <code>COND_NE</code>, <code>COND_LT</code>, <code>COND_LE</code>, <code>COND_GT</code>, or <code>COND_GE</code>, fixed-length character and binary column values must be prefixed with the column size, and must be padded to length. This is not necessary for such values when used in <code>COND_LIKE</code>, <code>COND_NOTLIKE</code>, <code>COL_AND_MASK_EQ_MASK</code>, <code>COL_AND_MASK_NE_MASK</code>, <code>COL_AND_MASK_EQ_ZERO</code>, or <code>COL_AND_MASK_NE_ZERO</code> comparisons.

Strings compared using COND_LIKE and COND_NOTLIKE can use the pattern metacharacters % and _. See NdbScanFilter::cmp(), for more information.

The BIT comparison operators are COL_AND_MASK_EQ_MASK, COL_AND_MASK_NE_MASK, COL_AND_MASK_EQ_ZERO, and COL_AND_MASK_NE_ZERO. Corresponding methods are available for NdbInterpretedCode and NdbOperation; for more information about these methods, see NdbInterpretedCode Bitwise Comparison Operations.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.58 NdbScanFilter data type values and descriptions

Name	Description	Column type compared
COND_EQ	Equality (=)	any
COND_NE	Inequality (<> or !=)	any
COND_LE	Lower bound (<=)	any
COND_LT	Strict lower bound (<)	any
COND_GE	Upper bound (>=)	any
COND_GT	Strict upper bound (>)	any
COND_LIKE	LIKE condition	string or binary
COND_NOTLIKE	NOT LIKE condition	string or binary
COL_AND_MASK_EQ_MA	©olumn value ANDed with bitmask is equal to bitmask	BIT
COL_AND_MASK_NE_MA	©olumn value ANDed with bitmask is not equal to bitmask	BIT
COL_AND_MASK_EQ_ZE	Column value ANDed with bitmask is equal to zero	BIT

Name	Description	Column type compared
COL_AND_MASK_NE_ZE	Column value ANDed with bitmask is not equal to zero	BIT

NdbScanFilter::cmp()

Description

Signature

Parameters

This method is used to define a comparison between a given value and the value of a column. Beginning with NDB 8.0.18, it can also be used to compare two columns. (This method does not actually execute the comparison, which is done later when performing the scan for which this NdbScanFilter is defined.)

In many cases, where the value to be compared is an integer, you can instead use one of several convenience methods provided by NdbScanFilter for this purpose. See NdbScanFilter Integer Comparison Methods.

```
int cmp
(
    BinaryCondition condition,
    int columnId,
    const void* value,
    Uint32 length = 0
)
```

Addtionally, in NDB 8.0.18 and later:

```
int cmp
  (
    BinaryCondition condition,
    int ColumnId1,
    int ColumnId2
)
```

When used to compare a value with a column, this method takes the following parameters:

condition: This represents the condition to be tested which
compares the value of the column having the column ID columnID
with some arbitrary value. The condition is a BinaryCondition
value; for permitted values and the relations that they represent, see
NdbScanFilter::BinaryCondition.

The *condition* values COND_LIKE or COND_NOTLIKE are used to compare a column value with a string pattern.

- columnId: This is the column's identifier, which can be obtained using the Column::getColumnNo() method.
- *value*: The value to be compared, repesented as a pointer to void.

When using a COND_LIKE or COND_NOTLIKE comparison condition, the *value* is treated as a string pattern. This string must not be padded or use a prefix. The string *value* can include the pattern metacharacters or "wildcard" characters % and _, which have the meanings shown here:

Table 2.59 Pattern metacharacters used with COND_LIKE and COND_NOTLIKE comparisons

Metacharacter	Description
8	Matches zero or more characters
_	Matches exactly one character

To match against a literal "%" or "_" character, use the backslash (\) as an escape character. To match a literal "\" character, use \\.

These are the same wildcard characters that are supported by the SQL LIKE and NOT LIKE operators, and are interpreted in the same way. See String Comparison Functions and Operators, for more information.

• *length*: The length of the value to be compared. The default value is 0. Using 0 for the *length* has the same effect as comparing to NULL, that is using the <code>isnull()</code> method.

When used to compare two columns, \mbox{cmp} () takes the following parameters:

- condition: The condition to be tested when comparing the columns. The condition may be any one of the BinaryCondition values EQ, NE, LT, LE, GT, or GE. Other values are not accepted.
- columnID1: ID of the first of the two columns to be compared.
- columnID1: ID of the second column.

Columns being compared using this method must be of exactly the same type. This includes length, precision, scale, and all other particulars.

This method returns an integer: 0 on success, and −1 on failure.

Return value

NdbScanFilter Constructor

Description

This is the constructor method for NdbScanFilter, and creates a new instance of the class.

Signature

NdbScanFilter
(
 class NdbOperation* op
)

Parameters

This method takes a single parameter, a pointer to the NdbOperation to which the filter applies.

Return value

A new instance of NdbScanFilter.

Destructor

The destructor takes no arguments and does not return a value. It should be called to remove the NdbScanFilter object when it is no longer needed.

NdbScanFilter::end()

Description

This method completes a compound, signalling that there are no more conditions to be added to it.

Signature

```
int end
  (
    void
)
```

Parameters

None.

Return value

Returns 0 on success, or -1 on failure.

NdbScanFilter::eq()

Description

This method is used to perform an equality test on a column value and an integer.

Signature

```
int eq
    (
    int ColId,
    Uint32 value
)
```

or

```
int eq
    (
    int ColId,
    Uint64 value
)
```

Parameters

This method takes two parameters, listed here:

- The ID (ColId) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

Returns 0 on success, or -1 on failure.

NdbScanFilter::isfalse()

Description

Defines a term of the current group as FALSE.

Signature

```
int isfalse
  (
    void
  )
```

Parameters

None.

Return value

0 on success, or -1 on failure.

NdbScanFilter::isnotnull()

Description

This method is used to check whether a column value is not NULL.

Signature

```
int isnotnull
    (
      int ColId
)
```

Parameters

The ID of the column whose value is to be tested.

Return value

Returns 0, if the column value is not NULL.

NdbScanFilter::isnull()

Description

This method is used to check whether a column value is NULL.

Signature

```
int isnull
   (
    int ColId
)
```

Parameters

The ID of the column whose value is to be tested.

Return value

Returns 0, if the column value is NULL.

NdbScanFilter::istrue()

Description

Defines a term of the current group as TRUE.

Signature

```
int istrue
(
void
```

Parameters

None.

Return value

Returns 0 on success, -1 on failure.

NdbScanFilter::ge()

Description

This method is used to perform a greater-than-or-equal test on a column value and an integer.

Signature

This method accepts both 32-bit and 64-bit values, as shown here:

```
int ge
    (
        int ColId,
        Uint32 value
    )

int ge
    (
        int ColId,
        Uint64 value
```

Parameters

Like eq(), lt(), le(), and the other NdbScanFilter methods of this type, this method takes two parameters:

- The ID (ColId) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

0 on success; -1 on failure.

NdbScanFilter::getNdbError()

Description

Because errors encountered when building an NdbScanFilter do not propagate to any involved NdbOperation object, it is necessary to use this method to access error information.

Signature const NdbError& getNdbError

void

Parameters None.

Return value A reference to an NdbError.

NdbScanFilter::getNdbOperation()

Description If the NdbScanFilter was constructed with an NdbOperation, this

method can be used to obtain a pointer to that NdbOperation object.

Signature NdbOperation* getNdbOperation

void

Parameters None.

Return value A pointer to the NdbOperation associated with this NdbScanFilter,

if there is one. Otherwise, NULL.

NdbScanFilter::Group

This section provides information about the Group data type.

Description This type is used to describe logical (grouping) operators, and is used

with the begin() method. (See NdbScanFilter::begin().)

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.60 NdbScanFilter::Group data type values and descriptions

Value	Description
AND	Logical and: A and B and C
OR	Logical OR: A OR B OR C
NAND	Logical NOT AND: NOT (A AND B AND C)
NOR	Logical NOT OR: NOT (A OR B OR C)

NdbScanFilter::gt()

Description This method is used to perform a greater-than (strict upper bound) test

on a column value and an integer.

Signature This method accommodates both 32-bit and 64-bit values:

```
int gt
    (
    int ColId,
    Uint32 value
)
int gt
    (
    int ColId,
```

```
Uint64 value
```

Parameters

Like the other $\mbox{NdbScanFilter}$ methods of this type, this method takes two parameters:

- The ID (ColId) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

0 on success; -1 on failure.

NdbScanFilter::le()

Description

This method is used to perform a less-than-or-equal test on a column value and an integer.

Signature

This method has two variants, to accommodate 32-bit and 64-bit values:

```
int le
    (
    int ColId,
    Uint32 value
)

int le
    (
    int ColId,
    Uint64 value
)
```

Parameters

Like the other ${\tt NdbScanFilter}$ methods of this type, this method takes two parameters:

- The ID (Colid) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

Returns 0 on success, or -1 on failure.

NdbScanFilter::lt()

Description

This method is used to perform a less-than (strict lower bound) test on a column value and an integer.

Signature

This method has 32-bit and 64-bit variants, as shown here:

```
int lt
    (
        int ColId,
        Uint32 value
    )
int lt
    (
        int ColId,
        Uint64 value
    )
```

Parameters

Like eq(), ne(), and the other NdbScanFilter methods of this type, this method takes two parameters, listed here:

- The ID (ColId) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

Retrturns 0 on success, or -1 on failure.

NdbScanFilter::ne()

Description

This method is used to perform an inequality test on a column value and an integer.

Signature

This method has 32-bit and 64-bit variants, as shown here:

```
int ne
    (
        int ColId,
        Uint32 value
    )
int ne
    (
        int ColId,
        Uint64 value
    )
```

Parameters

Like eq() and the other NdbScanFilter methods of this type, this method takes two parameters:

- The ID (ColId) of the column whose value is to be tested
- An integer with which to compare the column value; this integer may be either 32-bit or 64-bit, and is unsigned in either case.

Return value

Returns 0 on success, or -1 on failure.

2.3.24 The NdbScanOperation Class

This section provides information about the NdbScanOperation class.

- NdbScanOperation Class Overview
- NdbScanOperation::close()
- NdbScanOperation::deleteCurrentTuple()
- NdbScanOperation::getNdbTransaction()
- NdbScanOperation::getPruned()
- NdbScanOperation::lockCurrentTuple()
- NdbScanOperation::nextResult()
- NdbScanOperation::readTuples()
- NdbScanOperation::restart()

NdbScanOperation::ScanFlag

• NdbScanOperation::ScanOptions

NdbScanOperation::updateCurrentTuple()

NdbScanOperation Class Overview

Parent class NdbOperation

Child classes NdbIndexScanOperation

Description The NdbScanOperation class represents a scanning operation used

in a transaction. This class inherits from ${\tt NdbOperation}.$

Methods The following table lists the public methods of this class and the

purpose or use of each method:

Table 2.61 NdbScanOperation class methods and descriptions

Name	Description
close()	Closes the scan
deleteCurrentTuple	Deletes the current tuple
<pre>lockCurrentTuple()</pre>	Locks the current tuple
nextResult()	Gets the next tuple
getNdbTransaction(Gets the NdbTransaction object for this
	scan
getPruned()	Used to find out whether this scan is pruned to a single partition
readTuples()	Reads tuples
restart()	Restarts the scan
updateCurrentTuple	Updates the current tuple

This class has no public constructor. To create an instance of NdbScanOperation, it is necessary to use the NdbTransaction::getNdbScanOperation() method.

Types This class defines two public types, which are listed here:

• ScanFlag

• ScanOptions.

For more information about the use of NdbScanOperation, see Scan Operations, and Using Scans to Update or Delete Rows.

NdbScanOperation::close()

Description

Calling this method closes a scan. Rows returned by this scan are no longer available after the scan has been closed using this method.

See Scans with exclusive locks, for information about multiple threads attempting to perform the same scan with an exclusive lock and how this can affect closing the scans.

Signature

```
void close
   (
     bool forceSend = false,
     bool releaseOp = false
)
```

Parameters

This method takes the two parameters listed here:

- forceSend defaults to false; call close() with this parameter set to true in order to force transactions to be sent.
- releaseOp also defaults to false; set this to true in order to release the operation.

Prior to NDB 7.3.8, the buffer allocated by an NdbScanOperation for receiving the scanned rows was not released until the NdbTransaction owning the scan operation was closed (Bug #75128, Bug #20166585). In these and subsequent versions of NDB Cluster, the buffer is released whenever the cursor navigating the result set is closed using the close() method, regardless of the value of the releaseOp argument.

Return value

None.

NdbScanOperation::deleteCurrentTuple()

Description

This method is used to delete the current tuple.

Signature

```
const NdbOperation* deleteCurrentTuple
   (
     NdbTransaction* takeOverTrans,
     const NdbRecord* record,
     char* row = 0,
     const unsigned char* mask = 0,
     const NdbOperation::OperationOptions* opts = 0,
     Uint32 sizeOfOpts = 0
   )
```

For more information, see Section 2.3.22, "The NdbRecord Interface".

Parameters

When used with the NdbRecord interface, this method takes the parameters listed here:

- The transaction (*takeOverTrans*) that should perform the lock; when using NdbRecord with scans, this parameter is not optional.
- The NdbRecord referenced by the scan. This *record* value is required, even if no records are being read.
- The row from which to read. Set this to NULL if no read is to occur.
- The mask pointer is optional. If it is present, then only columns for which the corresponding bit in the mask is set are retrieved by the scan.
- OperationOptions (opts) can be used to provide more finelygrained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation

options; the options supported for each type of operation are shown in the following table:

Table 2.62 Operation types for the NdbRecord OperationOptions

Operation type (Method)	OperationOptions Flags Supported
readTuple()	OO_ABORTOPTION, OO_GETVALUE, OO_PARTITION_ID, OO_INTERPRETED
<pre>insertTuple()</pre>	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_ANYVALUE
updateTuple()	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_INTERPRETED, OO_ANYVALUE
writeTuple()	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_ANYVALUE
<pre>deleteTuple()</pre>	OO_ABORTOPTION, OO_GETVALUE, OO_PARTITION_ID, OO_INTERPRETED, OO_ANYVALUE

- The optional sizeOfOptions parameter is used to preserve backward compatibility of this interface with previous definitions of the OperationOptions structure. If an unusual size is detected by the interface implementation, it can use this to determine how to interpret the passed OperationOptions structure. To enable this functionality, the caller should pass sizeof(NdbOperation::OperationOptions) for the value of this argument.
- If options are specified, their length (sizeOfOpts) must be specified as well.

Return value

Returns 0 on success, or -1 on failure.

NdbScanOperation::getNdbTransaction()

Description Gets the NdbTransaction object for this scan.

Signature NdbTransaction* getNdbTransaction

> biov) const

Parameters None.

Return value A pointer to an NdbTransaction object.

NdbScanOperation::getPruned()

Description

This method is used to determine whether or not a given scan operation has been pruned to a single partition. For scans defined using NdbRecord, this method can be called before or after the scan is executed. For scans not defined using NdbRecord, getPruned() is valid only after the scan has been executed.

Signature bool getPruned

void
) const

Parameters

None.

Return value

Returns true, if the scan is pruned to a single table partition.

NdbScanOperation::lockCurrentTuple()

Description

This method locks the current tuple.

Signature

This method can be called with an optional single parameter, in either of the two ways shown here:

The following signature is also supported for this method, when using NdbRecord:

```
NdbOperation *lockCurrentTuple
    (
        NdbTransaction* takeOverTrans,
        const NdbRecord* record,
        char* row = 0,
        const unsigned char* mask = 0
)
```

This method also supports specifying one or more OperationOptions (also when using NdbRecord):

```
NdbOperation *lockCurrentTuple
   (
     NdbTransaction* takeOverTrans,
     const NdbRecord* record,
     char* row = 0,
     const unsigned char* mask = 0,
     const NdbOperation::OperationOptions* opts = 0,
     Uint32 sizeOfOptions = 0
)
```

Parameters (without NdbRecord)

This method takes a single, optional parameter—the transaction that should perform the lock. If this is omitted, the transaction is the current one.

Parameters (using NdbRecord)

When using the NdbRecord interface, this method takes these parameters, as described in the following list:

- The transaction (takeOverTrans) that should perform the lock; when using NdbRecord with scans, this parameter is not optional.
- The NdbRecord referenced by the scan. This is required, even if no records are being read.
- The row from which to read. Set this to NULL if no read is to occur.

- The mask pointer is optional. If it is present, then only columns for which the corresponding bit in the mask is set are retrieved by the scan.
- The opts argument can take on any of the following OperationOptions values: OO_ABORTOPTION, OO_GETVALUE, and OO_ANYVALUE.
- If options are specified, their length (sizeOfOptions) must be specified as well.

Calling an NdbRecord scan lock takeover on an NdbRecAttr-style scan is not valid, nor is calling an NdbRecAttr-style scan lock takeover on an NdbRecord-style scan.

Return value

This method returns a pointer to an NdbOperation object, or NULL.

NdbScanOperation::nextResult()

Description

This method is used to fetch the next tuple in a scan transaction. Following each call to <code>nextResult()</code>, the buffers and <code>NdbRecAttr</code> objects defined in <code>NdbOperation::getValue()</code> are updated with values from the scanned tuple.

When nextResult() is executed following end-of-file, NDB returns error code 4210 (Ndb sent more info than length specified) and the extra transaction object is freed by returning it to the idle list for the right TC node.

Signatures

This method can be invoked in one of two ways. The first of these is shown here:

```
int nextResult
   (
    bool fetchAllowed = true,
    bool forceSend = false
)
```

It is also possible to use this method as shown here:

```
int nextResult
   (
     const char*& outRow,
     bool fetchAllowed = true,
     bool forceSend = false
)
```

Parameters (2-parameter version)

This method takes the following two parameters:

 Normally, the NDB API contacts the NDB kernel for more tuples whenever it is necessary; setting fetchAllowed to false keeps this from happening.

Disabling fetchAllowed by setting it to false forces NDB to process any records it already has in its caches. When there are no more cached records it returns 2. You must then call nextResult() with fetchAllowed equal to true in order to contact NDB for more records.

While nextResult(false) returns 0, you should transfer the record to another transaction using execute(NdbTransaction::NoCommit). When nextResult(false) returns 2, you should normally execute and commit the other transaction. This causes any locks to be transferred to the other transaction, updates or deletes to be made, and then, the locks to be released. Following this, you can call nextResult(true) to have more records fetched and cached in the NDB API.



Note

If you do not transfer the records to another transaction, the locks on those records will be released the next time that the \mathtt{NDB} Kernel is contacted for more records.

Disabling fetchAllowed can be useful when you want to update or delete all of the records obtained in a given transaction, as doing so saves time and speeds up updates or deletes of scanned records.

forceSend defaults to false, and can normally be omitted.
 However, setting this parameter to true means that transactions are sent immediately. See Section 1.4.4, "The Adaptive Send Algorithm", for more information.

Parameters (3-parameter version)

This method can also be called with the following three parameters:

- Calling nextResult() sets a pointer to the next row in outRow (if returning 0). This pointer is valid (only) until the next call to nextResult() when fetchAllowed is true. The NdbRecord object defining the row format must be specified beforehand using NdbTransaction::scanTable() (or NdbTransaction::scanIndex().
- When false, fetchAllowed forces NDB to process any records it
 already has in its caches. See the description for this parameter in the
 previous Parameters subsection for more details.
- Setting forceSend to true means that transactions are sent immediately, as described in the previous Parameters subsection, as well as in Section 1.4.4, "The Adaptive Send Algorithm".

This method returns one of the following 4 integer values, interpreted as shown in the following list:

- -1: Indicates that an error has occurred.
- 0: Another tuple has been received.
- 1: There are no more tuples to scan.
- 2: There are no more cached records (invoke nextResult(true) to fetch more records).

Example

Return value

See Section 2.5.4, "NDB API Basic Scanning Example".

249

NdbScanOperation::readTuples()

Description

This method is used to perform a scan.

Signature

```
virtual int readTuples
   (
    LockMode mode = LM_Read,
    Uint32   flags = 0,
    Uint32   parallel = 0,
    Uint32   batch = 0
)
```

Parameters

This method takes the four parameters listed here:

• The lock *mode*; this is a LockMode value.

Scans with exclusive locks. When scanning with an exclusive lock, extra care must be taken due to the fact that, if two threads perform this scan simultaneously over the same range, then there is a significant probability of causing a deadlock. The likelihood of a deadlock is increased if the scan is also ordered (that is, using SF_OrderBy or SF_Descending).

The NdbScanOperation::close() method is also affected by this deadlock, since all outstanding requests are serviced before the scan is actually closed.

- One or more ScanFlag values. Multiple values are OR'ed together
- The number of fragments to scan in *parallel*; use 0 to require that the maximum possible number be used.
- The batch parameter specifies how many records will be returned to the client from the server by the next NdbScanOperation::nextResult(true) method call. Use 0 to specify the maximum automatically.

Return value

Returns 0 on success, -1 on failure.

NdbScanOperation::restart()

Description

Use this method to restart a scan without changing any of its getValue() calls or search conditions.

Signature

```
int restart
   (
     bool forceSend = false
   )
```

Parameters

Call this method with *forceSend* set to true in order to force the transaction to be sent.

Return value

0 on success; -1 on failure.

NdbScanOperation::ScanFlag

This section provides information about the ScanFlag data type.

Description

Values of this type are the scan flags used with the readTuples() method. More than one may be used, in which case, they are

Enumeration values

OR'ed together as the second argument to that method. See NdbScanOperation::readTuples(), for more information.

Possible values are shown, along with descriptions, in the following table:

Table 2.63 NdbScanOperation::ScanFlag values and descriptions

Value	Description
SF_TupScan	Scan in TUP order (that is, in the order of the rows in memory). Applies to table scans only.
SF_DiskScan	Scan in disk order (order of rows on disk). Applies to table scans only.
SF_OrderBy	Ordered index scan (ascending); rows returned from an index scan are sorted, and ordered on the index key. Scans in either ascending or descending order are affected by this flag, which causes the API to perform a merge-sort among the ordered scans of each fragment to obtain a single sorted result set.
	Notes:
	 Ordered indexes are distributed, with one ordered index for each fragment of a table.
	 Range scans are often parallel across all index fragments. Occasionally, they can be pruned to one index fragment.
	 Each index fragment range scan can return results in either ascending or descending order. Ascending is the default; to choose descending order, set the SF_Descending flag.
	 When multiple index fragments are scanned in parallel, the results are sent back to NDB where they can optionally be merge-sorted before being returned to the user. This merge sorting is controlled using the SF_OrderBy and SF_OrderByFull flags.
	 If SF_OrderBy or SF_OrderByFull is not used, the results from each index fragment are in order (either ascending or descending), but results from different fragments may be interleaved.
	When using SF_OrderBy or SF_OrderByFull, some extra constraints

Value	Description
	are imposed internally; these are listed here:
	If the range scan is not pruned to one index fragment then all index fragments must be scanned in parallel. (Unordered scans can be executed with less than full parallelism.)
	Results from every index fragment must be available before returning any rows, to ensure a correct merge sort. This serialises the "scrolling" of the scan, potentially resulting in lower row throughput.
	 Unordered scans can return rows to the API client before all index fragments have returned any batches, and can overlap next-batch requests with row processing.
SF_OrderByFull	This is the same as SF_OrderBy, except that all key columns are added automatically to the read bitmask.
SF_Descending	Causes an ordered index scan to be performed in descending order.
SF_ReadRangeNo	For index scans, when this flag is set, NdbIndexScanOperation::get_range_no can be called to read back the range_no defined in NdbIndexScanOperation::setBound(). In addition, when this flag is set, and SF_OrderBy or SF_OrderByFull is also set, results from ranges are returned in their entirety before any results are returned from subsequent ranges.
SF_MultiRange	Indicates that this scan is part of a multirange scan; each range is scanned separately.
SF_KeyInfo	Requests KeyInfo to be sent back to the caller. This enables the option to take over the row lock taken by the scan, using lockCurrentTuple(), by making sure that the kernel sends back the information needed to identify the row and the lock. This flag is enabled by default for scans using LM_Exclusive, but must be explicitly specified to enable the taking over of LM_Read locks. (See the LockMode documentation for more information.)

NdbScanOperation::ScanOptions

This section provides information about the ScanOptions data structure.

Parent class

NdbScanOperation

Description

This data structure is used to pass options to the NdbRecord-based scanTable() and scanIndex() methods of the NdbTransaction class. Each option type is marked as present by setting the corresponding bit in the optionsPresent field. Only the option types marked in the optionsPresent field need have sensible data.

All data is copied out of the ScanOptions structure (and any subtended structures) at operation definition time. If no options are required, then NULL may be passed as the ScanOptions pointer.

The elements making up this structure are shown in the following table:

Table 2.64 NdbScanOperation::ScanOptions attributes, with types and descriptions

Name	Туре	Description
optionsPresent	Uint64	Which options are present.
[]	Type: SO_SCANFLAGS: 0x01 SO_PARALLEL: 0x02 SO_BATCH: 0x04 SO_GETVALUE: 0x08 SO_PARTITION_ID: 0x10 SO_INTERPRETED: 0x20 SO_CUSTOMDATA: 0x40 SO_PARTINFO: 0x80	Type of options.
scan_flags	Uint32	Flags controlling scan behavior; see NdbScanOperation::ScanFlagfor more information.
parallel	Uint32	Scan parallelism; 0 (the default) sets maximum parallelism.
batch	Uint32	Batch size for transfers from data

Members

Name	Туре	Description
		nodes to API nodes; 0 (the default) enables this to be selected automatically.
extraGetValues	GetValueSpec	Extra values to be read for each row matching the sdcan criteria.
numExtraGetValues	Uint32	Number of extra values to be read.
partitionId	Uint32	Limit the scan to the partition having this ID; alternatively, you can supply an PartitionSpec here. For index scans, partitioning information can be supplied for each range.
interpretedCode	NdbInterpretedCode	Interpeted code to execute as part of the scan.
customData	void*	Data pointer to associate with this scan operation.
partitionInfo	PartitionSpec	Partition information for bounding this scan.
sizeOfPartInfo	Uint32	Size of the bounding partition information.

For more information, see Section 2.3.22, "The NdbRecord Interface".

NdbScanOperation::updateCurrentTuple()

Description

This method is used to update the current tuple.

Signature

Originally, this method could be called with a single. optional parameter, in either of the ways shown here:

```
NdbOperation* updateCurrentTuple

( void
)

NdbOperation* updateCurrentTuple

( NdbTransaction* updateTrans
)
```

It is also possible to employ this method, when using ${\tt NdbRecord}$ with scans, as shown here:

See Section 2.3.22, "The NdbRecord Interface", for more information.

Parameters (original)

This method takes a single, optional parameter—the transaction that should perform the lock. If this is omitted, the transaction is the current one.

Parameters (using NdbRecord)

When using the NdbRecord interface, this method takes the following parameters, as described in the following list:

- The takeover transaction (takeOverTrans).
- The record (NdbRecord object) referencing the column used for the scan.
- The row to read from. If no attributes are to be read, set this equal to NULL.
- The mask pointer is optional. If it is present, then only columns for which the corresponding bit in the mask is set are retrieved by the scan.

Return value

This method returns an NdbOperation object or NULL.

2.3.25 The NdbTransaction Class

This section provides information about the NdbTransaction class.

- NdbTransaction Class Overview
- NdbTransaction::close()
- NdbTransaction::commitStatus()
- NdbTransaction::CommitStatusType
- NdbTransaction::deleteTuple()
- NdbTransaction::ExecType
- NdbTransaction::execute()
- NdbTransaction::executePendingBlobOps()
- NdbTransaction::getGCI()
- NdbTransaction::getMaxPendingBlobReadBytes()
- NdbTransaction::getMaxPendingBlobWriteBytes()
- NdbTransaction::getNdbError()
- NdbTransaction::getNdbErrorLine()

- NdbTransaction::getNdbErrorOperation()
- NdbTransaction::getNdbIndexOperation()
- NdbTransaction::getNdbIndexScanOperation()
- NdbTransaction::getNdbOperation()
- NdbTransaction::getNdbScanOperation()
- NdbTransaction::getNextCompletedOperation()
- NdbTransaction::getTransactionId()
- NdbTransaction::insertTuple()
- NdbTransaction::readTuple()
- NdbTransaction::refresh()
- NdbTransaction::releaseLockHandle()
- NdbTransaction::scanIndex()
- NdbTransaction::scanTable()
- NdbTransaction::setMaxPendingBlobReadBytes()
- NdbTransaction::setMaxPendingBlobWriteBytes()
- NdbTransaction::setSchemaObjectOwnerChecks()
- NdbTransaction::unlock()
- NdbTransaction::updateTuple()
- NdbTransaction::writeTuple()

NdbTransaction Class Overview

Parent class None Child classes None

Description A transaction is represented in the NDB API by an NdbTransaction

> object, which belongs to an Ndb object and is created using Ndb::startTransaction(). A transaction consists of a list of operations represented by the NdbOperation class, or by one of its subclasses—NdbScanOperation, NdbIndexOperation, or NdbIndexScanOperation. Each operation access exactly one table.

The following table lists the public methods of this class and the

purpose or use of each method:

Table 2.65 NdbTransaction class methods and descriptions

Name	Description
close()	Closes a transaction
commitStatus()	Gets the transaction's commit status

Name	Description
deleteTuple()	Delete a tuple using NdbRecord
execute()	Executes a transaction
executePendingBlob	Texecutes a transaction in NoCommit mode if it includes any blob part operations of the specified types that are not yet executed.
getGCI()	Gets a transaction's global checkpoint ID (GCI)
getMaxPendingBlobR	Get⊵the-current blob read batch size
getMaxPendingBlobW	Getethetourrent blob write batch size
getNdbError()	Gets the most recent error
<pre>getNdbErrorLine()</pre>	Gets the line number where the most recent error occurred
getNdbErrorOperati	Gets the most recent operation which caused an error
getNextCompletedOp	Getsioperations that have been executed; used for finding errors
getNdbOperation()	Gets an NdbOperation
getNdbScanOperation	Gets an NdbScanOperation
getNdbIndexOperati	Gets an NdbIndexOperation
getNdbIndexScanOpe	Getsan MdbIndexScanOperation
<pre>getTransactionId()</pre>	Gets the transaction ID
insertTuple()	Insert a tuple using NdbRecord
readTuple()	Read a tuple using NdbRecord
refresh()	Keeps a transaction from timing out
releaseLockHandle(Release an NdbLockHandle object once it is no longer needed
scanIndex()	Perform an index scan using NdbRecord
scanTable()	Perform a table scan using NdbRecord
setMaxPendingBlobR	Setthe blob read batch size
setMaxPendingBlobW	Setethe blob write batch size
setSchemaObjectOwn	Enable or disable schema object ownership checks
unlock()	Create an unlock operation on the current transaction
updateTuple()	Update a tuple using NdbRecord
writeTuple()	Write a tuple using NdbRecord

The methods readTuple(), insertTuple(), updateTuple(), writeTuple(), deleteTuple(), scanTable(), and scanIndex() require the use of NdbRecord.

NdbTransaction defines 2 public types as shown in the following table:

Types

Table 2.66 NdbTransaction class types and descriptions

Name	Description
CommitStatusType()	Describes the transaction's commit status
ExecType()	Determines whether the transaction should be committed or rolled back

Using Transactions. After obtaining an NdbTransaction object, it is employed as follows:

- 1. An operation is allocated to the transaction using any one of the following methods:
 - getNdbOperation()
 - getNdbScanOperation()
 - getNdbIndexOperation()
 - getNdbIndexScanOperation()

Calling one of these methods defines the operation. Several operations can be defined on the same NdbTransaction object, in which case they are executed in parallel. When all operations are defined, the execute() method sends them to the NDB kernel for execution.

2. The <code>execute()</code> method returns when the NDB kernel has completed execution of all operations previously defined.

All allocated operations should be properly defined before calling the execute() method.

- 3. execute() operates in one of the three modes listed here:
 - NdbTransaction::NoCommit: Executes operations without committing them.
 - NdbTransaction::Commit: Executes any remaining operation and then commits the complete transaction.
 - NdbTransaction::Rollback: Rolls back the entire transaction.

execute() is also equipped with an extra error handling parameter, which provides the two
alternatives listed here:

- NdbOperation::AbortOnError: Any error causes the transaction to be aborted. This is the default behavior.
- NdbOperation:: AO_IgnoreError: The transaction continues to be executed even if one or more of the operations defined for that transaction fails.

NdbTransaction::close()

Description This method closes a transaction. It is equivalent to calling Ndb::closeTransaction().

If the transaction has not yet been committed, it is aborted when this

method is called. See Ndb::startTransaction().

void close

Signature

void

Parameters None.

Return value None.

NdbTransaction::commitStatus()

Description This method gets the transaction's commit status.

Signature CommitStatusType commitStatus

(void

Parameters None.

Return value The commit status of the transaction, a value of type

CommitStatusType.

NdbTransaction::CommitStatusType

This section provides information about the CommitStatusType data type.

Description This type is used to describe a transaction's commit status.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 2.67 NdbTransaction::CommitStatusType values and descriptions

Name	Description
NotStarted	The transaction has not yet been started.
Started	The transaction has started, but is not yet committed.
Committed	The transaction has completed, and has been committed.
Aborted	The transaction was aborted.
NeedAbort	The transaction has encountered an error, but has not yet been aborted.

A transaction's commit status ca be read using commitStatus().

NdbTransaction::deleteTuple()

Description Deletes a tuple using NdbRecord.

Signature const NdbOperation* deleteTuple

```
(
  const NdbRecord* key_rec,
  const char* key_row,
  const NdbRecord* result_rec,
  char* result_row,
  const unsigned char* result_mask = 0,
  const NdbOperation::OperationOptions* opts = 0,
  Uint32 sizeOfOptions = 0
```

Parameters

This method takes the following parameters:

- key_rec is a pointer to an NdbRecord for either a table or an index.
 If on a table, then the delete operation uses a primary key; if on
 an index, then the operation uses a unique key. In either case, the
 key_rec must include all columns of the key.
- The key_row passed to this method defines the primary or unique key of the tuple to be deleted, and must remain valid until execute() is called.
- The result rec is the NdbRecord to be used.
- The result row can be NULL if no attributes are to be returned.
- The result_mask, if not NULL, defines a subset of attributes to be read and returned to the client. The mask is copied, and so does not need to remain valid after the call to this method returns.
- OperationOptions (opts) can be used to provide more finely-grained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation options; for the options supported by each type of operation, see NdbTransaction::readTuple().
- The optional <code>sizeOfOptions</code> parameter provides backward compatibility of this interface with previous definitions of the <code>OperationOptions</code> structure. If an unusual size is detected by the interface implementation, it can use this to determine how to interpret the passed <code>OperationOptions</code> structure. To enable this functionality, the caller should pass <code>sizeof(NdbOperation::OperationOptions)</code> for the value of this argument.

Return value

A const pointer to the NdbOperation representing this write operation. The operation can be checked for errors if necessary.

NdbTransaction::ExecType

This section provides information about the ExecType data type.

Description

This type sets the transaction's execution type; that is, whether it should execute, execute and commit, or abort. It is used as a parameter to the execute() method. (See NdbTransaction::execute().)

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 2.68 NdbTransaction::ExecType values and descriptions

Name	Description
NoCommit	The transaction should execute, but not commit.

Name	Description
Commit	The transaction should execute and be committed.
Rollback	The transaction should be rolled back.

NdbTransaction::execute()

Description

This method is used to execute a transaction.

Signature

```
int execute
   (
        ExecType execType,
        NdbOperation::AbortOption abortOption = NdbOperation::DefaultAbortOp
   int force = 0
   )
```

Parameters

The execute() method takes the three parameters listed here:

- The execution type (ExecType value); see
 NdbTransaction::ExecType, for more information and possible values.
- An abort option (NdbOperation::AbortOption value).

Errors arising from this method are found with NdbOperation::getNdbError() rather than NdbTransaction::getNdbError().information.

- A *force* parameter, which determines when operations should be sent to the NDB Kernel. It takes ones of the values listed here:
 - 0: Nonforced; detected by the adaptive send algorithm.
 - 1: Forced; detected by the adaptive send algorithm.
 - 2: Nonforced; not detected by the adaptive send algorithm.

See Section 1.4.4, "The Adaptive Send Algorithm", for more information.

Return value

Returns 0 on success, or -1 on failure. The fact that the transaction did not abort does not necessarily mean that each operation was successful; you must check each operation individually for errors.

This method reports a failure *if and only if* the transaction was aborted. The transaction's error information is set in such cases to reflect the actual error code and category.

In the case where a **NoDataFound** error is a possibility, you must check for it explicitly, as shown in this example:

```
Ndb_cluster_connection myConnection;

if( myConnection.connect(4, 5, 1) )
{
    cout << "Unable to connect to cluster within 30 secs." << endl;
    exit(-1);
}

Ndb myNdb(&myConnection, "test");</pre>
```

```
// define operations...

myTransaction = myNdb->startTransaction();

if(myTransaction->getNdbError().classification == NdbError:NoDataFound)
{
    cout << "No records found." << endl;
    // ...
}

myNdb->closeTransaction(myTransaction);
```

NdbTransaction::executePendingBlobOps()

Description This method executes the transaction with ExecType equal to

 ${\tt NoCommit} \ \ \text{if there remain any blob part operations of the given types}$

which have not yet been executed.

Signature int executePendingBlobOps

Uint8 flags = 0xFF

Parameters The flags argument is the result of a bitwise OR, equal to 1 <<

optype, where optype is an NdbOperation::Type. The default corresponds to NdbOperation::Type::PrimaryKeyAccess.

concepting to Napoperation. Type. Frimary Reyaccess.

Returns 0 on success, or -1 on failure. The fact that the transaction did not abort does not necessarily mean that each operation was successful; you must check each operation individually for errors.

NdbTransaction::getGCI()

Signature

Return value

Description This method retrieves the transaction's global checkpoint ID (GCI).

Each committed transaction belongs to a GCI. The log for the committed transaction is saved on disk when a global checkpoint occurs.

By comparing the GCI of a transaction with the value of the latest GCI restored in a restarted NDB Cluster, you can determine whether or not the transaction was restored.

Whether or not the global checkpoint with this GCI has been saved on disk cannot be determined by this method.

The GCI for a scan transaction is undefined, since no updates are performed in scan transactions.

No GCI is available until execute() has been called with

ExecType::Commit.

int getGCI
 (
 void
)

Parameters None.

Return value The transaction's GCI, or -1 if none is available.

NdbTransaction::getMaxPendingBlobReadBytes()

Description Gets the current batch size in bytes for blob read operations. When

the volume of blob data to be read within a given transaction exceeds this amount, all of the transaction's pending blob read operations are

executed.

Signature Uint32 getMaxPendingBlobReadBytes

(void) const

Parameters None.

Return value The current blob read batch size, in bytes. See

NdbTransaction::setMaxPendingBlobReadBytes(), for more information.

NdbTransaction::getMaxPendingBlobWriteBytes()

Description Gets the current batch size in bytes for blob write operations. When the

volume of blob data to be written within a given transaction exceeds this amount, all of the transaction's pending blob write operations are

executed.

Signature Uint32 getMaxPendingBlobWriteBytes

void
) const

Parameters None.

Return value The current blob write batch size, in bytes. See

NdbTransaction::setMaxPendingBlobWriteBytes(), for more information.

NdbTransaction::getNdbError()

Description This method is used to obtain the most recent error (NdbError).

Signature const NdbError& getNdbError

void
) const

Parameters None.

Return value A reference to an NdbError object.

For additional information about handling errors in transactions, see Error Handling.

NdbTransaction::getNdbErrorLine()

Description This method return the line number where the most recent error

occurred.

Signature int getNdbErrorLine

void

Parameters None.

Return value The line number of the most recent error.

For additional information about handling errors in transactions, see Error Handling.

NdbTransaction::getNdbErrorOperation()

Description This method retrieves the operation that caused an error.

To obtain more information about the actual error, use the

NdbOperation::getNdbError() method of the NdbOperation

object returned by getNdbErrorOperation().

Signature NdbOperation* getNdbErrorOperation

void

Parameters None.

Return value A pointer to an NdbOperation.

For additional information about handling errors in transactions, see Error Handling.

NdbTransaction::getNdbIndexOperation()

Description This method is used to create an NdbIndexOperation associated

with a given table.

All index operations within the same transaction must be initialised with this method. Operations must be defined before they are executed.

Signature NdbIndexOperation* getNdbIndexOperation

(
 const NdbDictionary::Index* index
)

Parameters The Index object on which the operation is to be performed.

Return value A pointer to the new NdbIndexOperation.

NdbTransaction::getNdbIndexScanOperation()

Description This method is used to create an NdbIndexScanOperation

associated with a given table.

All index scan operations within the same transaction must be initialised with this method. Operations must be defined before they are executed.

Signature NdbIndexScanOperation* getNdbIndexScanOperation

const NdbDictionary::Index* index

Parameters The Index object on which the operation is to be performed.

Return value A pointer to the new NdbIndexScanOperation.

NdbTransaction::getNdbOperation()

Description This method is used to create an NdbOperation associated with a

given table.

All operations within the same transaction must be initialized with this method. Operations must be defined before they are executed.

Signature NdbOperation* getNdbOperation

(
 const NdbDictionary::Table* table
)

Parameters The Table object on which the operation is to be performed.

Return value A pointer to the new NdbOperation.

NdbTransaction::getNdbScanOperation()

Description This method is used to create an NdbScanOperation associated with

a given table.

All scan operations within the same transaction must be initialized with this method. Operations must be defined before they are executed.

Signature NdbScanOperation* getNdbScanOperation

(
 const NdbDictionary::Table* table
)

Parameters The Table object on which the operation is to be performed.

Return value A pointer to the new NdbScanOperation.

NdbTransaction::getNextCompletedOperation()

Description This method is used to retrieve a transaction's completed operations. It

is typically used to fetch all operations belonging to a given transaction

to check for errors.

NdbTransaction::getNextCompletedOperation(NULL)

returns the transaction's first NdbOperation object;

 $\label{local_norm} \mbox{NdbTransaction::getNextCompletedOperation(\it{myOp}) } \mbox{\bf returns}$

the NdbOperation object defined after NdbOperation myOp.

This method should only be used after the transaction has been

executed, but before the transaction has been closed.

Signature const NdbOperation* getNextCompletedOperation

const NdbOperation* op

Parameters This method requires a single parameter op, which is an operation

(NdbOperation object), or NULL.

Return value The operation following op, or the first operation defined for the

transaction if getNextCompletedOperation() was called using

NULL.

NdbTransaction::getTransactionId()

Description This method is used to obtain the transaction ID.

Signature Uint64 getTransactionId

```
(
void
)
```

Parameters

None.

Return value

The transaction ID, as an unsigned 64-bit integer.

NdbTransaction::insertTuple()

Description

Inserts a tuple using NdbRecord.

Signatures

```
const NdbOperation* insertTuple
  (
    const NdbRecord* key_rec,
    const char* key_row,
    const NdbRecord* attr_rec,
    const char* attr_row,
    const unsigned char* mask = 0,
    const NdbOperation::OperationOptions* opts = 0,
    Uint32 sizeOfOptions = 0
  )
```

```
const NdbOperation* insertTuple
   (
      const NdbRecord* combined_rec,
      const char* combined_row,
      const unsigned char* mask = 0,
      const NdbOperation::OperationOptions* opts = 0,
      Uint32 sizeOfOptions = 0
   )
```

Parameters

insertTuple() takes the following parameters:

 A pointer to an NdbRecord indicating the record (key_rec) to be inserted.

This method can also be called using a single NdbRecord pointer and single char pointer (combined_rec, combined_row) where the single NdbRecord represents record and attribute and data.

- A row (key_row) of data to be inserted.
- A pointer to an NdbRecord indicating an attribute (attr_rec) to be inserted.
- A row (attr_row) of data to be inserted as the attribute.
- A mask which can be used to filter the columns to be inserted.
- OperationOptions (opts) can be used to provide more finely-grained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation options; for the options supported by each type of operation, see NdbTransaction::readTuple().
- The optional sizeOfOptions parameter is used to preserve backward compatibility of this interface with previous definitions of the OperationOptions structure. If an unusual size is detected by the interface implementation, it can use this to

determine how to interpret the passed <code>OperationOptions</code> structure. To enable this functionality, the caller should pass <code>sizeof(NdbOperation::OperationOptions)</code> for the value of this argument.

Return value

A const pointer to the NdbOperation representing this insert operation.

NdbTransaction::readTuple()

Description

Signature

This method reads a tuple using NdbRecord objects.

```
const NdbOperation* readTuple
  (
    const NdbRecord* key_rec,
    const char* key_row,
    const NdbRecord* result_rec,
    char* result_row,
    NdbOperation::LockMode lock_mode = NdbOperation::LM_Read,
    const unsigned char* result_mask = 0,
    const NdbOperation::OperationOptions* opts = 0,
    Uint32 sizeOfOptions = 0
)
```

Parameters

This method takes the following parameters:

- key_rec is a pointer to an NdbRecord for either a table or an index.
 If on a table, then the operation uses a primary key; if on an index,
 then the operation uses a unique key. In either case, the key_rec
 must include all columns of the key.
- The key_row passed to this method defines the primary or unique key of the affected tuple, and must remain valid until execute() is called.

The mask, if not NULL, defines a subset of attributes to read, update, or insert. Only if $(\max[attrId >> 3] \& (1 << (attrId \& 7)))$ is set is the column affected. The mask is copied by the methods, so need not remain valid after the call returns.

- result rec is a pointer to an NdbRecord used to hold the result
- result_row defines a buffer for the result data.
- *lock_mode* specifies the lock mode in effect for the operation. See NdbOperation::LockMode, for permitted values and other information.
- result_mask defines a subset of attributes to read. Only if
 mask[attrId >> 3] & (1<<(attrId & 7)) is set is the column
 affected. The mask is copied, and so need not remain valid after the
 method call returns.
- OperationOptions (opts) can be used to provide more finelygrained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation options; the options supported for each type of operation are shown in the following table:

Table 2.69 Operation types for NdbTransaction::readTuple() OperationOptions (opts) parameter, with operation options supported by each type

Operation type (Method)	OperationOptions Flags Supported
readTuple()	OO_ABORTOPTION, OO_GETVALUE, OO_PARTITION_ID, OO_INTERPRETED
<pre>insertTuple()</pre>	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_ANYVALUE
updateTuple()	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_INTERPRETED, OO_ANYVALUE
writeTuple()	OO_ABORTOPTION, OO_SETVALUE, OO_PARTITION_ID, OO_ANYVALUE
deleteTuple()	OO_ABORTOPTION, OO_GETVALUE, OO_PARTITION_ID, OO_INTERPRETED, OO_ANYVALUE

• The optional <code>sizeOfOptions</code> parameter is used to preserve backward compatibility of this interface with previous definitions of the <code>OperationOptions</code> structure. If an unusual size is detected by the interface implementation, it can use this to determine how to interpret the passed <code>OperationOptions</code> structure. To enable this functionality, the caller should pass <code>sizeof(NdbOperation::OperationOptions)</code> for the value of this argument.

Return value

A pointer to the NdbOperation representing this read operation (this can be used to check for errors).

NdbTransaction::refresh()

Description

This method updates the transaction's timeout counter, and thus avoids aborting due to transaction timeout.

It is not advisable to take a lock on a record and maintain it for a extended time since this can impact other transactions.

Signature

```
int refresh
  (
    void
  )
```

Parameters

None.

Return value

Returns 0 on success, -1 on failure.

NdbTransaction::releaseLockHandle()

Description

This method is used to release a lock handle (see NdbOperation::getLockHandle) when it is no longer required. For NdbRecord primary key read operations, this cannot be called until the associated read operation has been executed.

All lock handles associated with a given transaction are released when that transaction is closed.

Signature

```
int releaseLockHandle
   (
     const NdbLockHandle* lockHandle
)
```

Parameters

The NdbLockHandle object to be released.

Return value

0 on success.

NdbTransaction::scanIndex()

Description

Perform an index range scan of a table, with optional ordering.

Signature

```
NdbIndexScanOperation* scanIndex
(
    const NdbRecord* key_record,
    const NdbRecord* result_record,
    NdbOperation::LockMode lock_mode = NdbOperation::LM_Read,
    const unsigned char* result_mask = 0,
    const NdbIndexScanOperation::IndexBound* bound = 0,
    const NdbScanOperation::ScanOptions* options = 0,
    Uint32 sizeOfOptions = 0
)
```

Parameters

- The key_record describes the index to be scanned. It must be a
 key record for the index; that is, it must specify, at a minimum, all of
 the key columns of the index. The key_record must be created from
 the index to be scanned (and not from the underlying table).
- The result_record describes the rows to be returned from the scan. For an ordered index scan, result_record must be a key record for the index to be scanned; that is, it must include (at a minimum) all of the columns in the index (the full index key is needed by the NDB API for merge-sorting the ordered rows returned from each fragment).

Like the <code>key_record</code>, the <code>result_record</code> must be created from the underlying table, and not from the index to be scanned. Both the <code>key_record</code> and <code>result_record</code> NdbRecord structures must stay in place until the scan operation is closed.

- The <code>result_mask</code> pointer is optional. If it is present, only those columns for which the corresponding bits (by attribute ID order) in <code>result_mask</code> are set are actually retrieved in the scan. The <code>result_mask</code> is copied internally, so in contrast to <code>result_record</code> it need not be valid when <code>execute()</code> is invoked.
- A single IndexBound can be specified either in this call or in a separate call to NdbIndexScanOperation::setBound().
 To perform a multi-range read, the scan_flags in the ScanOptions structure must include SF_MULTIRANGE.
 Additional bounds can be added using successive calls to NdbIndexScanOperation::setBound().

To specify an equals bound, use the same row pointer for the low key and high key with the low and high inclusive bits set.

For multi-range scans, the <code>low_key</code> and <code>high_key</code> pointers must be unique. In other words, it is not permissible to reuse the same row buffer for several different range bounds within a single scan. However, it is permissible to use the same row pointer as <code>low_key</code> and <code>high_key</code> in order to specify an equals bound; it is also permissible to reuse the rows after the <code>scanIndex()</code> method returns—that is, they need not remain valid until <code>execute()</code> time (unlike the <code>NdbRecord</code> pointers).

- To specify additional options, pass a ScanOptions structure.
- The <code>sizeOfOptions</code> exists to enable backward compatability for this interface. This parameter indicates the size of the <code>ScanOptions</code> structure at the time the client was compiled, and enables detection of the use of an old-style <code>ScanOptions</code> structure. If this functionality is not required, this argument can be left set to 0.

The current NdbIndexScanOperation, which can be used for error checking.

Return value

NdbTransaction::scanTable()

Description

Signature

Parameters

This method performs a table scan, using an NdbRecord object to read out column data.

```
NdbScanOperation* scanTable
   (
      const NdbRecord* result_record,
      NdbOperation::LockMode lock_mode = NdbOperation::LM_Read,
      const unsigned char* result_mask = 0,
      Uint32 scan_flags = 0,
      Uint32 parallel = 0,
      Uint32 batch = 0
   )
```

The scanTable() method takes the following parameters:

- A pointer to an NdbRecord for storing the result. This
 result_record must remain valid until after the execute() call
 has been made.
- The lock_mode in effect for the operation. See
 NdbOperation::LockMode, for permitted values and other information.
- The result_mask pointer is optional. If it is present, only those columns for which the corresponding bits (by attribute ID order) in result_mask are set are actually retrieved in the scan. The result_mask is copied internally, so in contrast to result_record it need not be valid when execute() is invoked.
- scan_flags can be used to impose ordering and sorting conditions for scans. See NdbScanOperation::ScanFlag, for a list of permitted values.

- The *parallel* argument is the desired parallelism, or 0 for maximum parallelism (receiving rows from all fragments in parallel), which is the default.
- batch determines whether batching is employed. The default is 0 (off).

Return value

A pointer to the NdbScanOperation representing this scan. The operation can be checked for errors if necessary.

NdbTransaction::setMaxPendingBlobReadBytes()

Description Sets the batch size in bytes for blob read operations. When the volume

of blob data to be read within a given transaction exceeds this amount, all of the transaction's pending blob read operations are executed.

Signature void setMaxPendingBlobReadBytes

Uint32 bytes

Parameters The batch size, as the number of bytes. Using 0 causes blob read

batching to be disabled, which is the default behavior (for backward

compatibility).

Return value None.



Note

blob read batching can also be controlled in the <code>mysql</code> client and other MySQL client application using the MySQL Server's <code>--ndb-blob-read-batch-bytes</code> option and its associated MySQL Server system variables.

NdbTransaction::setMaxPendingBlobWriteBytes()

Description Sets the batch size in bytes for blob write operations. When the volume

of blob data to be written within a given transaction exceeds this amount, all of the transaction's pending blob write operations are

executed.

Signature void setMaxPendingBlobWriteBytes

Uint32 bytes

Parameters The batch size, as the number of bytes. Using 0 causes blob write

batching to be disabled, which is the default behavior (for backward

compatibility).

Return value None.



Note

blob write batching can also be controlled in the <code>mysql</code> client and other MySQL client application using the MySQL Server's <code>--ndb-blob-write-batch-bytes</code> option and its associated MySQL Server system variables.

NdbTransaction::setSchemaObjectOwnerChecks()

Description

Enables or disables a schema object ownership check when multiple Ndb_cluster_connection objects are in use. When this check is enabled, objects used by this transaction are checked to make sure that they belong to the NdbDictionary owned by this connection. This is done by acquiring the schema objects of the same names from the connection and comparing these with the schema objects passed to the transaction. If they do not match, an error is returned.

This method is available for debugging purposes beginning with NDB 7.3.9 and NDB 7.4.4. (Bug #19875977) You should be aware that enabling this check carries a performance penalty and for this reason you should avoid doing so in a production setting.

Signature

```
void setSchemaObjOwnerChecks
   (
    bool runChecks
)
```

Parameters

A single parameter *runChecks*. Use true to enable ownership checks, false to disable them.

Return value

None.

NdbTransaction::unlock()

Description

This method creates an unlock operation on the current transaction; when executed, the unlock operation removes the lock referenced by the NdbLockHandle (see NdbOperation::getLockHandle) passed to the method.

Signature

```
const NdbOperation* unlock
   (
      const NdbLockHandle* lockHandle,
      NdbOperation::AbortOption ao = NdbOperation::DefaultAbortOption
   )
```

Parameters

A pointer to a lock handle; in addition, optionally, an AbortOption value *ao*.

In the event that the unlock operation fails—for example, due to the row already being unlocked—the AbortOption specifies how this is handled, the default being that errors cause transactions to abort.

Return value

A pointer to an NdbOperation (the unlock operation created).

NdbTransaction::updateTuple()

Description

Updates a tuple using an NdbRecord object.

Signature

```
const NdbOperation* updateTuple
   (
      const NdbRecord* key_rec,
      const char* key_row,
      const NdbRecord* attr_rec,
      const char* attr_row,
      const unsigned char* mask = 0,
      const NdbOperation::OperationOptions* opts = 0,
      Uint32 sizeOfOptions = 0
   )
```

Parameters

updateTuple() takes the following parameters:

- key_rec is a pointer to an NdbRecord for either a table or an index.
 If on a table, then the operation uses a primary key; if on an index,
 then the operation uses a unique key. In either case, the key_rec
 must include all columns of the key.
- The key_row passed to this method defines the primary or unique key of the affected tuple, and must remain valid until execute() is called.
- attr rec is an NdbRecord referencing the attribute to be updated.



Note

For unique index operations, the attr_rec must refer to the underlying table of the index, not to the index itself.

- attr_row is a buffer containing the new data for the update.
- The mask, if not NULL, defines a subset of attributes to be updated.
 The mask is copied, and so does not need to remain valid after the call to this method returns.
- OperationOptions (opts) can be used to provide more finely-grained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation options; for the options supported by each type of operation, see NdbTransaction::readTuple().
- The optional <code>sizeOfOptions</code> parameter is used to preserve backward compatibility of this interface with previous definitions of the <code>OperationOptions</code> structure. If an unusual size is detected by the interface implementation, it can use this to determine how to interpret the passed <code>OperationOptions</code> structure. To enable this functionality, the caller should pass <code>sizeof(NdbOperation::OperationOptions)</code> for the value of this argument.

The NdbOperation representing this operation (can be used to check for errors).

Return value

NdbTransaction::writeTuple()

Description

Signature

This method is used with NdbRecord to write a tuple of data.

```
const NdbOperation* writeTuple
   (
      const NdbRecord* key_rec,
      const char* key_row,
      const NdbRecord* attr_rec,
      const char* attr_row,
      const unsigned char* mask = 0,
      const NdbOperation::OperationOptions* opts = 0,
      Uint32 sizeOfOptions = 0
   )
```

Parameters

This method takes the following parameters:

- key_rec is a pointer to an NdbRecord for either a table or an index.
 If on a table, then the operation uses a primary key; if on an index, then the operation uses a unique key. In either case, the key_rec must include all columns of the key.
- The key_row passed to this method defines the primary or unique key of the tuple to be written, and must remain valid until execute() is called.
- attr_rec is an NdbRecord referencing the attribute to be written.

For unique index operations, the attr_rec must refer to the underlying table of the index, not to the index itself.

- attr row is a buffer containing the new data.
- The mask, if not NULL, defines a subset of attributes to be written.
 The mask is copied, and so does not need to remain valid after the call to this method returns.
- OperationOptions (opts) can be used to provide more finely-grained control of operation definitions. An OperationOptions structure is passed with flags indicating which operation definition options are present. Not all operation types support all operation options; for the options supported by each type of operation, see NdbTransaction::readTuple().
- The optional <code>sizeOfOptions</code> parameter is used to provide backward compatibility of this interface with previous definitions of the <code>OperationOptions</code> structure. If an unusual size is detected by the interface implementation, it can use this to determine how to interpret the passed <code>OperationOptions</code> structure. To enable this functionality, the caller should pass <code>sizeof(NdbOperation::OperationOptions)</code> for the value of this argument.

Return value

A const pointer to the NdbOperation representing this write operation. The operation can be checked for errors if and as necessary.

2.3.26 The Object Class

This section provides information about the <code>Object</code> class, which contains meta-information about database objects such as tables and indexes. <code>Object</code> subclasses model these and other database objects.

- Object Class Overview
- Object::FragmentType
- Object::getObjectStatus()
- Object::getObjectId()
- Object::getObjectVersion()

NdbDictionary

• Object::PartitionBalance

• Object::State

· Object::Status

• Object::Store

• Object::Type

Object Class Overview

Parent class

Child classes

Datafile, Event, Index, LogfileGroup, Table, Tablespace, Undofile, HashMap, ForeignKey

Methods

The following table lists the public methods of the Object class and the purpose or use of each method:

Table 2.70 Object class methods and descriptions

Name	Description
getObjectId()	Gets an object's ID
getObjectStatus()	Gets an object's status
<pre>getObjectVersion()</pre>	Gets the version of an object

All 3 of these methods are pure virtual methods, and are reimplemented in the Table, Index, and Event subclasses where needed.

Types

These are the public types of the Object class:

Table 2.71 Object class types and descriptions

Name	Description
FragmentType	Fragmentation type used by the object (a table or index)
State	The object's state (whether it is usable)
Status	The object's state (whether it is available)
Store	Whether the object has been temporarily or permanently stored
Type	The object's type (what sort of table, index, or other database object the Object represents)

Object::FragmentType

This section provides information about the FragmentType type, which describes the fragmentation type of an instance of Object.

Description

This parameter specifies how data in the table or index is distributed among the cluster's data nodes, that is, the number of fragments per node. The larger the table, the larger the number of fragments that should be used. Note that all fragment replicas count as a single

fragment. For a table, the default is FragAllMedium. For a unique hash index, the default is taken from the underlying table and cannot currently be changed.

Enumeration values

Possible values for FragmentType are shown, along with descriptions, in the following table:

Table 2.72 FragmentType values and descriptions

Name	Description
FragUndefined	The fragmentation type is undefined or the default
FragAllMedium	Two fragments per node
FragAllLarge	Four fragments per node
DistrKeyHash	Distributed hash key
DistrKeyLin	Distributed linear hash key
UserDefined	User defined
HashMapPartition	Hash map partition

Object::getObjectStatus()

Description

This method retrieves the status of the object for which it is invoked.

Signature

```
virtual Status getObjectStatus
(
void
) const
```

Parameters

None.

Return value

Returns the current Status of the Object.

Object::getObjectId()

Description

This method retrieves the object's ID.

Signature

```
virtual int getObjectId
(
void
) const
```

Parameters

None.

Return value

The object ID, an integer.

Object::getObjectVersion()

Description

The method gets the current version of the object.

Signature

```
virtual int getObjectVersion
    (
     void
    ) const
```

Parameters

None.

Return value

The object's version number, an integer.

Object::PartitionBalance

This section provides information about the PartitionBalance data type.

Description This type enumerates partition balance settings (fragment count types)

from which to choose when using $\mathtt{setPartitionBalance}()$. This is

also the type returned by getPartitionBalance()

Enumeration values Possible values for PartitionBalance are shown, along with

descriptions, in the following table:

Table 2.73 Object::PartitionBalance data type values and descriptions

Name	Description
PartitionBalance_F	ய்se ene ifragment per LDM per node
PartitionBalance_F	ป se ene ifragment per LDM per node group
PartitionBalance_F	ப் se நாக் fragment per node
PartitionBalance_F	ப் se pre frægment per node group
PartitionBalance_S	dese setting determined by setPartitionBalance()

Prior to NDB 7.5.4, this was known as FragmentCountType, and could take one of the values FragmentCount_OnePerLDMPerNode, FragmentCount_OnePerLDMPerNodeGroup, FragmentCount_OnePerNode, FragmentCount_OnePerNodeGroup, or FragmentCount_Specific. These values correspond to those shown in the previous table, in the order shown.

Object::State

This section provides information about the State type, which models the state of the Object.

Description This parameter provides us with the object's state. By *state*, we mean

whether or not the object is defined and is in a usable condition.

Enumeration values Possible values for State are shown, along with descriptions, in the

following table:

Table 2.74 Object State type values and descriptions

Name	Description
StateUndefined	Undefined
StateOffline	Offline, not useable
StateBuilding	Building (e.g. restore?), not useable(?)
StateDropping	Going offline or being dropped; not usable
StateOnline	Online, usable
StateBackup	Online, being backed up, usable
StateBroken	Broken; should be dropped and re-created

Object::Status

This section provides information about the Status type, which models the status of an Object.

Description Reading an object's Status tells whether or not it is available in the

NDB kernel.

Enumeration values Possible values for Status are shown, along with descriptions, in the

following table:

Table 2.75 Object Status data type values and descriptions

Name	Description
New	The object exists only in memory, and has not yet been created in the NDB kernel
Changed	The object has been modified in memory, and must be committed in the NDB Kernel for changes to take effect
Retrieved	The object exists, and has been read into main memory from the NDB Kernel
Invalid	The object has been invalidated, and should no longer be used
Altered	The table has been altered in the NDB kernel, but is still available for use

Object::Store

This section provides information about the Store type, which describes the persistence of an Object.

Description Reading this value tells us is the object is temporary or permanent.

Enumeration values Possible values for Store are shown, along with descriptions, in the

following table:

Table 2.76 Object Store data type values and descriptions

Name	Description
StoreUndefined	The object is undefined
StoreTemporary	Temporary storage; the object or data will be deleted on system restart
StorePermanent	The object or data is permanent; it has been logged to disk

Object::Type

This section provides information about the Type type.

Description The Type of the object can be one of several different sorts of index,

trigger, tablespace, and so on.

Enumeration values Possible values for Type are shown, along with descriptions, in the

following table:

Table 2.77 Object Type data type values and descriptions

Name	Description
TypeUndefined	Undefined

Name	Description
SystemTable	System table
UserTable	User table (may be temporary)
UniqueHashIndex	Unique (but unordered) hash index
OrderedIndex	Ordered (but not unique) index
HashIndexTrigger	Index maintenance (internal)
IndexTrigger	Index maintenance (internal)
SubscriptionTrigge	Backup or replication (<i>internal</i>)
ReadOnlyConstraint	Trigger (internal)
Tablespace	Tablespace
LogfileGroup	Log file group
Datafile	Data file
Undofile	Undo file
ReorgTrigger	Trigger
HashMap	Hash map
ForeignKey	Foreign key
FKParentTrigger	Trigger on a foreign key's parent table
FKChildTrigger	Trigger on a foreign key's child table

For more information about ForeignKey, FKParentTrigger, and FKChildTrigger, see Section 2.3.6, "The ForeignKey Class".

2.3.27 The Table Class

This section provides information about the Table class, which models a database table in the NDB API.

- Table Class Overview
- Table::addColumn()
- Table::aggregate()
- Table Constructor
- Table::equal()
- Table::getColumn()
- Table::getDefaultNoPartitionsFlag()
- Table::getExtraMetadata()
- Table::getFragmentCount()
- Table::getFragmentData()
- Table::getFragmentDataLen()
- Table::getFragmentNodes()
- Table::getFragmentType()

- Table::getFrmData()
- Table::getFrmLength()
- Table::getHashMap()
- Table::getKValue()
- Table::getLinearFlag()
- Table::getLogging()
- Table::getMaxLoadFactor()
- Table::getMaxRows()
- Table::getMinLoadFactor()
- Table:getName()
- Table::getNoOfColumns()
- Table::getNoOfPrimaryKeys()
- Table::getObjectId()
- Table::getObjectStatus()
- Table::getObjectType() (OBSOLETE)
- Table::getObjectVersion()
- Table::getPartitionBalance()
- Table::getPartitionBalanceString()
- Table::getPartitionId()
- Table::getPrimaryKey()
- Table::getRangeListData()
- Table::getRangeListDataLen()
- Table::getRowChecksumIndicator()
- Table::getRowGCIIndicator()
- Table::getSingleUserMode()
- Table::getTableId()
- Table::getTablespace()
- Table::getTablespaceData()
- Table::getTablespaceDataLen()
- Table::getTablespaceNames()
- Table::getTablespaceNamesLen()
- Table::hasDefaultValues()

- Table::setDefaultNoPartitionsFlag()
- Table::setExtraMetadata()
- Table::setFragmentCount()
- Table::setFragmentData()
- Table::setFragmentType()
- Table::setFrm()
- Table::setHashMap()
- Table::setKValue()
- Table::setLinearFlag()
- Table::setLogging()
- Table::setMaxLoadFactor()
- Table::setMaxRows()
- Table::setMinLoadFactor()
- Table::setName()
- Table::setObjectType() (OBSOLETE)
- Table::setPartitionBalance()
- Table::setRangeListData()
- Table::setRowChecksumIndicator()
- Table::setRowGCIIndicator()
- Table::setSingleUserMode()
- Table::setStatusInvalid()
- Table::setTablespace()
- Table::setTablespaceData()
- Table::setTablespaceNames()
- Table::SingleUserMode
- Table::validate()

Table Class Overview

Parent class NdbDictionary

Child classes None

Description The Table class represents a table in an NDB Cluster database. This

class extends the Object class, which in turn is an inner class of the

NdbDictionary class.

It is possible using the NDB API to create tables independently of the MySQL server. However, it is usually not advisable to do so, since tables created in this fashion cannot be seen by the MySQL server. Similarly, it is possible using Table methods to modify existing tables, but these changes (except for renaming tables) are not visible to MySQL.

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.78 Table class methods and descriptions

Table() Class constructor addColumn() Adds a column to the table aggregate() Computes aggregate data for the table equal() Gets a column (by name) from the table getDefaultNoPartitionsF	Name	Description
addColumn() Adds a column to the table aggregate() Computes aggregate data for the table equal() Gets a column (by name) from the table getDefaultNoPartitionsFl Checks whether the default number of partitions is being used getFragmentCount() Gets the number of fragments for this table getExtraMetadata() gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the table's hash map. getKValue() getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	Table()	Class constructor
aggregate() computes aggregate data for the table equal() Gets a column (by name) from the table getDefaultNoPartitionsFl Decks whether the default number of partitions is being used getFragmentCount() Gets the number of fragments for this table getExtraMetadata() Gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	~Table()	Destructor
compares the table with another table getColumn() Gets a column (by name) from the table getDefaultNoPartitionsFl	addColumn()	Adds a column to the table
getColumn() Gets a column (by name) from the table getDefaultNoPartitionsFl Specks whether the default number of partitions is being used getFragmentCount() Gets the number of fragments for this table getExtraMetadata() Gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKvalue() Gets the table's Kvalue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	aggregate()	Computes aggregate data for the table
table getDefaultNoPartitionsFl Checks whether the default number of partitions is being used getFragmentCount() Gets the number of fragments for this table getExtraMetadata() Gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	equal()	Compares the table with another table
partitions is being used getFragmentCount() Gets the number of fragments for this table getExtraMetadata() Gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getColumn()	
table getExtraMetadata() Gets extra metadata for this table getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getDefaultNoPartitionsF	
getFragmentData() Gets table fragment data (ID, state, and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFragmentCount()	_
and node group) getFragmentDataLen() Gets the length of the table fragment data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getExtraMetadata()	Gets extra metadata for this table
data getFragmentNodes() Gets IDs of data nodes on which fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getHashMap() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFragmentData()	
fragments are located getFragmentType() Gets the table's FragmentType getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFragmentDataLen()	
getFrmData() Gets the data from the table .FRM file getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	<pre>getFragmentNodes()</pre>	
getFrmLength() Gets the length of the table's .FRM file getHashMap() Gets the table's hash map. getKValue() Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFragmentType()	Gets the table's FragmentType
getHashMap() Gets the table's hash map. Gets the table's KValue getLinearFlag() Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFrmData()	Gets the data from the table . FRM file
getKValue() Gets the table's KValue Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getFrmLength()	Gets the length of the table's . FRM file
Gets the current setting for the table's linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getHashMap()	Gets the table's hash map.
linear hashing flag getLogging() Checks whether logging to disk is enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getKValue()	Gets the table's KValue
enabled for this table getMaxLoadFactor() Gets the table's maximum load factor getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getLinearFlag()	
getMaxRows() Gets the maximum number of rows that this table may contain getMinLoadFactor() Gets the table's minimum load factor	<pre>getLogging()</pre>	00 0
that this table may contain getMinLoadFactor() Gets the table's minimum load factor	getMaxLoadFactor()	Gets the table's maximum load factor
	getMaxRows()	
getName() Gets the table's name	getMinLoadFactor()	Gets the table's minimum load factor
	getName()	Gets the table's name

Methods

Name	Description
getNoOfColumns()	Gets the number of columns in the table
getNoOfPrimaryKeys()	Gets the number of columns in the table's primary key.
getObjectId()	Gets the table's object ID
getObjectStatus()	Gets the table's object status
getObjectType()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
<pre>getObjectVersion()</pre>	Gets the table's object version
<pre>getPartitionBalance()</pre>	Gets partition balance (fragment count type) used for this table (NDB 7.5.4 and later)
getPartitionBalanceStrir	Gets partition balance used for this table, as a string (NDB 7.5.4 and later)
getPartitionId()	Gets a partition ID from a hash value
getPrimaryKey()	Gets the name of the table's primary key
getRangeListData()	Gets a RANGE or LIST array
getRangeListDataLen()	Gets the length of the table RANGE or LIST array
getRowChecksumIndicator(Checks whether the row checksum indicator has been set
getRowGCIIndicator()	Checks whether the row GCI indicator has been set
getSingleUserMode()	Gets the SingleUserMode for this table
getTableId()	Gets the table's ID
getTablespace()	Gets the tablespace containing this table
getTablespaceData()	Gets the ID and version of the tablespace containing the table
getTablespaceDataLen()	Gets the length of the table's tablespace data
getTablespaceNames()	Gets the names of the tablespaces used in the table fragments
hasDefaultValues()	Determine whether table has any columns using default values
setDefaultNoPartitionsFl	Toggles whether the default number of partitions should be used for the table
setExtraMetadata()	Sets extra metadata for this table
getFragmentCount()	Gets the number of fragments for this table

Name	Description
setFragmentData()	Sets the fragment ID, node group ID, and fragment state
setFragmentType()	Sets the table's FragmentType
setFrm()	Sets the .FRM file to be used for this table
setHashMap()	Sets the table's hash map.
setKValue()	Set the KValue
setLinearFlag()	Sets the table's linear hashing flag
setLogging()	Toggle logging of the table to disk
setMaxLoadFactor()	Set the table's maximum load factor (MaxLoadFactor)
setMaxRows()	Sets the maximum number of rows in the table
setMinLoadFactor()	Set the table's minimum load factor (MinLoadFactor)
setPartitionBalance()	Sets the partition balance (fragment count type) for this table (NDB 7.5.4 and later)
setName()	Sets the table's name
setObjectType()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
setRangeListData()	Sets LIST and RANGE partition data
setRowChecksumIndicator	\$ets the row checksum indicator
setRowGCIIndicator()	Sets the row GCI indicator
setSingleUserMode()	Sets the SingleUserMode value for this table
setStatusInvalid()	
setTablespace()	Set the tablespace to use for this table
setTablespaceData()	Sets the tablespace ID and version
setTablespaceNames()	Sets the tablespace names for fragments
validate()	Validates the definition for a new table prior to creating it

Types

The Table class defines a single public type SingleUserMode.

The assignment (=) operator is overloaded for this class, so that it always performs a deep copy.

As with other database objects, Table object creation and attribute changes to existing tables done using the NDB API are not visible from MySQL. For example, if you add a new column to a table using Table::addColumn(), MySQL cannot see the new column. The only exception to this rule with regard to tables is that a change of name of an existing NDB table using Table::setName() is visible to MySQL.

Calculating Table Sizes. When calculating the data storage one should add the size of all attributes (each attribute consuming a minimum of 4 bytes) and well as 12 bytes overhead. Variable size attributes

have a size of 12 bytes plus the actual data storage parts, with an additional overhead based on the size of the variable part. For example, consider a table with 5 attributes: one 64-bit attribute, one 32-bit attribute, two 16-bit attributes, and one array of 64 8-bit attributes. The amount of memory consumed per record by this table is the sum of the following:

- · 8 bytes for the 64-bit attribute
- · 4 bytes for the 32-bit attribute
- 8 bytes for the two 16-bit attributes, each of these taking up 4 bytes due to right-alignment
- 64 bytes for the array (64 * 1 byte per array element)
- · 12 bytes overhead

This totals 96 bytes per record. In addition, you should assume an overhead of about 2% for the allocation of page headers and wasted space. Thus, 1 million records should consume 96 MB, and the additional page header and other overhead comes to approximately 2 MB. Rounding up yields 100 MB.

Table::addColumn()

Description Adds a column to a table.

Signature void addColumn

(const Column& column

Parameters A reference to the column which is to be added to the table.

Return value This method's return type is void, but it does create a copy of the

original Column object.

Table::aggregate()

Description This method computes aggregate data for the table. It is required in

order for aggregate methods such as getNoOfPrimaryKeys() to work properly before the table has been created and retrieved via

getTableId().

Signature int aggregate

struct NdbError& error

Parameters A reference to an NdbError object.

Return value An integer, whose value is 0 on success, and -1 if the table is in an

inconsistent state. In the latter case, the *error* is also set.

Table Constructor

Description Creates a Table instance. There are two versions of the Table

constructor, one for creating a new instance, and a copy constructor.

Tables created in the NDB API using this method are not accessible

from MySQL.

Signature New instance:

```
Table
   (
     const char* name = ""
)
```

Copy constructor:

```
Table
(
const Table& table
)
```

Parameters

For a new instance, the name of the table to be created. For a copy, a reference to the table to be copied.

Return value

A Table object.

Destructor

virtual ~Table()

Table::equal()

Description

This method is used to compare one instance of Table with another.

Signature

```
bool equal
(
    const Table& table
) const
```

Parameters

A reference to the Table object with which the current instance is to be compared.

Return value

true if the two tables are the same, otherwise false.

Table::getColumn()

Description

This method is used to obtain a column definition, given either the index or the name of the column.

Signature

This method can be invoked using either the column ID or column name, as shown here:

Parameters

Either of: the column's index in the table (as it would be returned by the column's getColumnNo() method), or the name of the column.

Return value

A pointer to the column with the specified index or name. If there is no such column, then this method returns NULL.

Table::getDefaultNoPartitionsFlag()

Description

This method is used to find out whether the default number of partitions is used for the table.

Signature

Uint32 getDefaultNoPartitionsFlag (void) const

Parameters

None.

Return value

A 32-bit unsigned integer.

Table::getExtraMetadata()

Description

Get and unpack extra metadata for this table.

This method was added in NDB 8.0.13.

Signature

int getExtraMetadata
 (
 Uint32& version,
 void** data,
 Uint32* length
) const

Parameters

This method takes the following three parameters:

- version: By convention, as used in NDB Cluster code, 1 means that the extra metadata contains a .frm file (BLOB) as in NDB 7.6 and earlier; 2 indicates that it is serialized dictionary information as in NDB 8.0. The values are actually arbritrary, and application-specific.
- data: The stored data retrieved as metadata.
- *length*: The length of the stored data (metadata).

Return value

Returns 0 on success, any other value on failure. A nonzer4o value should be interpreted as an error code for the type of error.

Table::getFragmentCount()

Description

This method gets the number of fragments in the table.

Signature

Uint32 getFragmentCount
 (
 void
) const

Parameters

None.

Return value

The number of table fragments, as a 32-bit unsigned integer.

Table::getFragmentData()

Description

This method gets the table's fragment data (ID, state, and node group).

Signature

const void* getFragmentData
 (
 void
) const

Parameters

None.

Return value

A pointer to the data to be read.

Table::getFragmentDataLen()

Description

Gets the length of the table fragment data to be read, in bytes.

Signature

```
Uint32 getFragmentDataLen
(
void
) const
```

Parameters

None.

Return value

The number of bytes to be read, as an unsigned 32-bit integer.

Table::getFragmentNodes()

Description

This method retrieves a list of nodes storing a given fragment.

Signature

```
Uint32 getFragmentNodes
   (
      Uint32 fragmentId,
      Uint32* nodeIdArrayPtr,
      Uint32 arraySize
   ) const
```

Parameters

This method takes the following three parameters:

- fragmentId: The ID of the desired fragment.
- nodeIdArrayPtr: Pointer to an array of node IDs of the nodes containing this fragment.



Note

Normally, the primary fragment is entry 0 in this array.

 arraySize: The size of the array containing the node IDs. If this is less than the number of fragments, then only the first arraySize entries are written to this array.

Return value

A return value of 0 indicates an error; otherwise, this is the number of table fragments, as a 32-bit unsigned integer.

Table::getFragmentType()

Description

This method gets the table's fragmentation type.

Signature

```
FragmentType getFragmentType
(
   void
) const
```

Parameters

None.

Return value

An Object::FragmentType value.

Table::getFrmData()

Description

The the data from the .FRM file associated with the table.

Signature

const void* getFrmData

```
(
void
) const
```

Parameters None.

Return value A pointer to the .FRM data.

Table::getFrmLength()

Description Gets the length of the table's . FRM file data, in bytes.

Signature Uint32 getFrmLength

void
) const

Parameters None.

Return value The length of the .FRM file data (an unsigned 32-bit integer).

Table::getHashMap()

Description Get the hash map used for this table.

Signature bool getHashMap

(
 Uint32* id = 0,
 Uint32* version = 0
) const

Parameters The table ID and version.

Return value True if the table has a hash map, otherwise false.

Table::getKValue()

Description This method gets the KValue, a hashing parameter which is currently

restricted to the value 6. In a future release, it may become feasible to

set this parameter to other values.

Signature int getKValue (

void
) const

Parameters None.

Return value An integer (currently always 6).

Table::getLinearFlag()

Description This method retrieves the value of the table's linear hashing flag.

Signature bool getLinearFlag

void
) const

Parameters None.

Return value true if the flag is set, and false if it is not.

Table::getLogging()

Description This class is used to check whether a table is logged to disk—that is,

whether it is permanent or temporary.

Signature bool getLogging

(void) const

Parameters None.

Return value Returns a Boolean value. If this method returns true, then full

checkpointing and logging are done on the table. If false, then the table is a temporary table and is not logged to disk; in the event of a system restart the table still exists and retains its definition, but it will be

empty. The default logging value is true.

Table::getMaxLoadFactor()

Description This method returns the load factor (a hashing parameter) when splitting

of the containers in the local hash tables begins.

Signature int getMaxLoadFactor

(void) const

Parameters None.

Return value An integer whose maximum value is 100. When the maximum value is

returned, this means that memory usage is optimised. Smaller values indicate that less data is stored in each container, which means that

keys are found more quickly but more memory is consumed.

Table::getMaxRows()

Description This method gets the maximum number of rows that the table can hold.

This is used for calculating the number of partitions.

Signature Uint64 getMaxRows

void
) const

Parameters None.

Return value The maximum number of table rows, as a 64-bit unsigned integer.

Table::getMinLoadFactor()

Description This method gets the value of the load factor when reduction of the

hash table begins. This should always be less than the value returned

by getMaxLoadFactor().

Signature int getMinLoadFactor

void
) const

Parameters None.

Return value A percentage expressed as an integer; see Table::getMaxLoadFactor().

Table:getName()

Description Gets the name of a table.

Signature const char* getName

(void) const

Parameters None.

Return value The name of the table (a string).

Table::getNoOfColumns()

Description This method is used to obtain the number of columns in a table.

Signature int getNoOfColumns

void
) const

Parameters None.

Return value An integer representing the number of columns in the table.

Table::getNoOfPrimaryKeys()

Description This method finds the number of primary key columns in the table.

Signature int getNoOfPrimaryKeys

void
) const

Parameters None.

Return value An integer representing the number of primary key columns in the table.

Table::getObjectId()

Description This method gets the table's object ID.

Signature virtual int get0bjectId

(void) const

Parameters None.

Return value The object ID is returned as an integer.

Table::getObjectStatus()

Description This method gets the table's status...

Signature virtual Object::Status getObjectStatus

(

void) const

Parameters None.

Return value An Object::Status value.

Table::getObjectType() (OBSOLETE)

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature Object::Type getObjectType

void
) const

Parameters None.

Return value Returns an Object::Type value.

Table::getObjectVersion()

Description This method gets the table's object version (see NDB Schema Object

Versions).

Signature virtual int getObjectVersion

void
) const

Parameters None.

Return value The table's object version, as an integer.

Table::getPartitionBalance()

Description This method gets the table' partition balance scheme (fragment count

type).

Prior to NDB 7.5.4, this method was known as

getFragmentCountType().

Signature Object::PartitionBalance getPartitionBalance

(void) const

Parameters None.

Return value The partition balancing scheme, as a value of type

Object::PartitionBalance.

Table::getPartitionBalanceString()

Description This method gets the table' partition balance scheme (fragment count

type), and returns it as a string.

Prior to NDB 7.5.4, this method was known as

getFragmentCountTypeString().

Signature const char* getPartitionBalanceString

void
) const

Parameters None.

Return value The partition balancing scheme, as a string value.

Table::getPartitionId()

Description Gets a table partition ID, given its hash value.

Signature Uint32 getPartitionId

Uint32 *hashvalue*

) const

Parameters A hashvalue. Note that if the table has not actually been retrieved

(using, for example, getTableId()), then the result is likely not to be

accurate or useful.

Return value The identifier of the partition corresponding to the *hashvalue*.

Table::getPrimaryKey()

Description This method is used to obtain the name of the table's primary key.

Signature const char* getPrimaryKey

int *no*) const

Parameters None.

Return value The name of the primary key, a string (character pointer).

Table::getRangeListData()

Description This method gets the range or list data associated with the table.

Signature const void* getRangeListData

void
) const

Parameters None.

Return value A pointer to the data.

Table::getRangeListDataLen()

Description This method gets the size of the table's range or list array.

Signature Uint32 getRangeListDataLen

void
) const

Parameters None.

Return value

The length of the list or range array, as an integer.

Table::getRowChecksumIndicator()

Description Check whether the row checksum indicator has been set.

Signature bool getRowChecksumIndicator

void
) const

Parameters None.

Return value A true or false value.

Table::getRowGCIIndicator()

Description Checks whether the row GCI indicator has been set.

Signature bool getRowGCIIndicator

void
) const

Parameters None.

Return value A true or false value.

Table::getSingleUserMode()

Description Gets the single user mode of the table.

Signature enum SingleUserMode getSingleUserMode

void
) const

Parameters None.

Return value A SingleUserMode value.

Table::getTableId()

Description This method gets a table's ID.

Signature int getTableId

(void) const

Parameters None.

Return value The table ID, as an integer.

Table::getTablespace()

Description This method is used in two ways: to obtain the name of the tablespace

to which this table is assigned; to verify that a given tablespace is the

one being used by this table.

Signatures To obtain the name of the tablespace, invoke without any arguments:

```
const char* getTablespace
   (
    void
   ) const
```

To determine whether the tablespace is the one indicated by the given ID and version, supply these as arguments, as shown here:

```
bool getTablespace
   (
     Uint32* id = 0,
     Uint32* version = 0
   ) const
```

Parameters

The number and types of parameters depend on how this method is being used:

- A. When used to obtain the name of the tablespace in use by the table, it is called without any arguments.
- B. When used to determine whether the given tablespace is the one being used by this table, then getTablespace() takes two parameters:
 - The tablespace id, given as a pointer to a 32-bit unsigned integer
 - The tablespace version, also given as a pointer to a 32-bit unsigned integer

The default value for both id and version is 0.

Return value

The return type depends on how the method is called:

- A. When getTablespace() is called without any arguments, it returns a Tablespace object instance.
- B. When called with two arguments, it returns true if the tablespace is the same as the one having the ID and version indicated; otherwise, it returns false.

Table::getTablespaceData()

Description

This method gets the table's tablespace data (ID and version).

Signature

const void* getTablespaceData
 (
 void
 const

Parameters

None.

Return value

A pointer to the data.

Table::getTablespaceDataLen()

Description

This method is used to get the length of the table's tablespace data.

Signature

Uint32 getTablespaceDataLen

(
void
) const

Parameters None.

Return value The length of the data, as a 32-bit unsigned integer.

Table::getTablespaceNames()

Description This method gets a pointer to the names of the tablespaces used in the

table fragments.

Signature const void* getTablespaceNames

void

Parameters None.

Return value Returns a pointer to the tablespace name data.

Table::getTablespaceNamesLen()

Description This method gets the length of the tablespace name data returned by

getTablespaceNames(). (See Table::getTablespaceNames().)

Signature Uint32 getTablespaceNamesLen

void
) const

Parameters None.

Return value Returns the length of the name data, in bytes, as a 32-but unsigned

integer.

Table::hasDefaultValues()

Description Used to determine whether the table has any columns that are defined

with default values other than NULL.

To read and write default column values, use Column::getDefaultValue() and

Column::setDefaultValue().

Signature bool hasDefaultValues

(void) const

Parameters None.

Return value Returns true if the table has any non-NULL columns with default

values, otherwise false.

Table::setDefaultNoPartitionsFlag()

Description This method sets an indicator that determines whether the default

number of partitions is used for the table.

Signature

```
void setDefaultNoPartitionsFlag
   (
    Uint32 indicator
   ) const
```

Parameters

This method takes a single argument *indicator*, a 32-bit unsigned integer.

Return value

None.

Table::setExtraMetadata()

Description

Store packed extra metadata for this table. The data is packed without any modification into the buffer of the given Table object.

Added in NDB 8.0.13.

Signature

```
int setExtraMetadata
   (
    Uint32 version,
    const void* data,
    Uint32 length
)
```

Parameters

The three parameters used by this method are listed here:

- version: As used in NDB Cluster code, 1 means that the extra
 metadata contains a .frm file (BLOB) as in NDB 7.6 and earlier; 2
 indicates that it is serialized dictionary information as in NDB 8.0. You
 should be aware that this is merely a convention, and the values can
 be application-specific, as desired.
- data: The actual data to be stored as metadata.
- length: The length of the data to be stored.

Return value

0 on success. Any other value indicates failure; in this case, the value is an error code indicating indicating the type of error.

Table::setFragmentCount()

Description

Sets the number of table fragments.

Signature

```
void setFragmentCount
   (
     Uint32 count
)
```

Parameters

count is the number of fragments to be used for the table.

Return value

None.

Table::setFragmentData()

Description

This method writes an array containing the following fragment information:

- Fragment ID
- Node group ID

· Fragment State

Signature

```
void setFragmentData
   (
    const void* data,
    Uint32 len
)
```

Parameters

This method takes the following two parameters:

- A pointer to the fragment data to be written
- The length (len) of this data, in bytes, as a 32-bit unsigned integer

Return value

None.

Table::setFragmentType()

Description

This method sets the table's fragmentation type.

Signature

```
void setFragmentType
   (
    FragmentType fragmentType
)
```

Parameters

This method takes one argument, an Object::FragmentType value.

Return value

None.

Table::setFrm()

Description

This method is used to write data to this table's .FRM file.

Signature

```
void setFrm
    (
      const void* data,
      Uint32 len
)
```

Parameters

This method takes the following two arguments:

- A pointer to the data to be written.
- The length (len) of the data.

Return value

None.

Table::setHashMap()

Description

Set a hash map for the table.

Signature

```
int setHashMap
  (
    const class HashMap &
  )
```

Parameters

A reference to the hash map.

Return value

Returns 0 on success; on failure, returns -1 and sets error.

Table::setKValue()

Description This sets the KValue, a hashing parameter.

Signature void setKValue

int kValue

Parameters kValue is an integer. Currently the only permitted value is 6. In a future

version this may become a variable parameter.

Return value None.

Table::setLinearFlag()

Description Set the table's linear hash flag. See Table::getLinearFlag().

Signature void setLinearFlag

(
Uint32 flag

)

Parameters The *flag* is a 32-bit unsigned integer.

Return value None.

Table::setLogging()

Description Toggles the table's logging state. See Table::getLogging().

Signature void setLogging

(bool *enable*

Parameters If enable is true, then logging for this table is enabled; if it is false,

then logging is disabled.

Return value None.

Table::setMaxLoadFactor()

Description This method sets the maximum load factor when splitting the containers

in the local hash tables.

Signature void setMaxLoadFactor

int max

Parameters This method takes a single parameter max, an integer representation

of a percentage (for example, 45 represents 45 percent). For more

information, see Table::getMaxLoadFactor().

This should never be greater than the minimum load factor.

Return value None.

Table::setMaxRows()

Description This method sets the maximum number of rows that can be held by the

table.

Signature void setMaxRows

(
Uint64 maxRows

Parameters maxRows is a 64-bit unsigned integer that represents the maximum

number of rows to be held in the table.

Return value None.

Table::setMinLoadFactor()

Description This method sets the minimum load factor when reduction of the hash

table begins.

Signature void setMinLoadFactor

int min

Parameters This method takes a single parameter min, an integer representation

of a percentage (for example, 45 represents 45 percent). For more

information, see Table::getMinLoadFactor().

Return value None.

Table::setName()

Description This method sets the name of the table.

This is the only set*() method of Table whose effects are visible to

MySQL.

Signature void setName

const char* name

Parameters name is the (new) name of the table.

Return value None.

Table::setObjectType() (OBSOLETE)

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature void setObjectType

Object::Type type

Parameters The desired object type. This must be one of the Type values listed in

Object::Type.

Return value None.

Table::setPartitionBalance()

Description Sets the table's partition balancing scheme.

Prior to NDB 7.5.4, this method was known as

setFragmentCountType().

Signature void setPartitionBalance

(
Object::PartitionBalance scheme

Parameters scheme is the partition balancing scheme to be used for the table. This

is a value of type PartitionBalance.

Return value None.

Table::setRangeListData()

Description This method sets an array containing information that maps range

values and list values to fragments. This is essentially a sorted map consisting of fragment-ID/value pairs. For range partitions there is one pair per fragment. For list partitions it could be any number of pairs, but

at least as many pairs as there are fragments.

Signature void setRangeListData

(const void* data, Uint32 len

Parameters

This method requires the following two parameters:

- A pointer to the range or list data containing the ID/value pairs
- The length (len) of this data, as a 32-bit unsigned integer.

Return value None.

Table::setRowChecksumIndicator()

Description Set the row checksum indicator.

Signature void setRowChecksumIndicator

bool value
) const

Parameters A true or false *value*.

Return value None.

Table::setRowGCIIndicator()

Description Sets the row GCI indicator.

Signature void setRowGCIIndicator

bool value

) const

Parameters A true or false *value*.

Return value None.

Table::setSingleUserMode()

Description Sets a SingleUserMode for the table.

Signature void setSingleUserMode

enum SingleUserMode

Parameters A SingleUserMode value.

Return value None.

Table::setStatusInvalid()

Description Forces the table's status to be invalidated.

Signature void setStatusInvalid

void
) const

Parameters None.

Return value None.

Table::setTablespace()

Description This method sets the tablespace for the table.

See Section 2.3.28, "The Tablespace Class".

Signatures Using the name of the tablespace:

```
void setTablespace
    (
      const char* name
)
```

Using a Tablespace object:

```
void setTablespace
    (
        const class Tablespace& tablespace
    )
```

Parameters This method can be called with a single argument, which can be of

either one of these two types:

- The name of the tablespace (a string).
- A reference to an existing Tablespace instance.

Return value None.

Table::setTablespaceData()

Description This method sets the ta

This method sets the tablespace information for each fragment, and includes a tablespace ID and a tablespace version.

Signature

```
void setTablespaceData
   (
     const void* data,
     Uint32 len
)
```

Parameters

This method requires the following two parameters:

- A pointer to the data containing the tablespace ID and version
- The length (len) of this data, as a 32-bit unsigned integer.

Return value None.

Table::setTablespaceNames()

Description

Sets the names of the tablespaces used by the table fragments.

Signature

```
void setTablespaceNames
   (
      const void* data
      Uint32 len
)
```

Parameters

This method takes the following two parameters:

- A pointer to the tablespace names data
- The length (len) of the names data, as a 32-bit unsigned integer.

Return value

None.

Table::SingleUserMode

This section provides information about the SingleUserMode data type.

Description

Single user mode specifies access rights to the table when single user mode is in effect.

Enumeration values

Possible values for SingleUserMode are shown, along with descriptions, in the following table:

Table 2.79 Table::SingleUserMode values and descriptions

Name	Description
SingleUserModeLock	eThe table is locked (unavailable).
SingleUserModeRead	⊽Fhe∕table is available in read-only mode.
SingleUserModeRead	withe table is available in read-write mode.

Table::validate()

Description

This method validates the definition for a new table prior to creating it, executes the Table::aggregate() method, and performs

additional checks. validate() is called automatically when a table is created or retrieved. For this reason, it is usually not necessary to call aggregate() or validate() directly.

You should be aware that, even after the validate() method is called, there may still exist errors which can be detected only by the NDB kernel when the table is actually created.

Signature

```
int validate
   (
     struct NdbError& error
)
```

Parameters

A reference to an NdbError object.

Return value

An integer, whose value is 0 on success, and -1 if the table is in an inconsistent state. In the latter case, the error is also set.

2.3.28 The Tablespace Class

This section provides information about the Tablespace class.

- Tablespace Class Overview
- Tablespace Constructor
- Tablespace::getAutoGrowSpecification()
- Tablespace::getDefaultLogfileGroup()
- Tablespace::getDefaultLogfileGroupId()
- Tablespace::getExtentSize()
- Tablespace::getObjectId()
- Tablespace::getName()
- Tablespace::getObjectStatus()
- Tablespace::getObjectVersion()
- Tablespace::setAutoGrowSpecification()
- Tablespace::setDefaultLogfileGroup()
- Tablespace::setExtentSize()
- Tablespace::setName()

Tablespace Class Overview

Parent class NdbDictionary

Child classes None

Description The Tablespace class models an NDB Cluster Disk Data tablespace,

which contains the data files used to store Cluster Disk Data. For

an overview of Cluster Disk Data and data file characteristics, see CREATE TABLESPACE Statement, in the MySQL Manual.

Only unindexed column data can be stored on disk. Indexes and indexes columns are always stored in memory.

The following table lists the public methods of this class and the purpose or use of each method:

Table 2.80 Tablespace class methods and descriptions

Name	Description
Tablespace()	Class constructor
~Tablespace()	Virtual destructor method
getAutoGrowSpecifi	AutoGrowSpecification structure associated with the tablespace
getDefaultLogfileG	Gets (the name of the tablespace's default log file group
getDefaultLogfileG	Getsithe ID of the tablespace's default log file group
<pre>getExtentSize()</pre>	Gets the extent size used by the tablespace
getName()	Gets the name of the tablespace
getObjectId()	Gets the object ID of a Tablespace instance
getObjectStatus()	Used to obtain the Object::Status of the Tablespace instance for which it is called
<pre>getObjectVersion()</pre>	Gets the object version of the Tablespace object for which it is invoked
setAutoGrowSpecifi	dsed to set the auto-grow characteristics of the tablespace
setDefaultLogfileG	Sets the tablespace's default log file group
<pre>setExtentSize()</pre>	Sets the size of the extents used by the tablespace
setName()	Sets the name for the tablespace

Types

Methods

The Tablespace class defines no public types of its own; however, two of its methods make use of the AutoGrowSpecification data structure.

Tablespace Constructor

Description

These methods are used to create a new instance of Tablespace, or to copy an existing one.



Note

The Dictionary class also supplies methods for creating and dropping tablespaces.

Signatures.

New instance:

```
Tablespace
(
void
)
```

Copy constructor:

```
Tablespace
(
    const Tablespace& tablespace
)
```

Parameters New instance: None. Copy constructor: a reference to an existing

Tablespace instance.

Return value A Tablespace object.

Destructor. The class defines a virtual destructor ~Tablespace() which takes no arguments and returns no value.

Tablespace::getAutoGrowSpecification()

Description.

Signature const AutoGrowSpecification& getAutoGrowSpecification

void
) const

Parameters None.

Return value A reference to the structure which describes the tablespace auto-grow

characteristics; for details, see NdbDictionary::AutoGrowSpecification.

Tablespace::getDefaultLogfileGroup()

Description This method retrieves the name of the tablespace's default log file

group.

Alternatively, you may wish to obtain the ID of the default log file group;

see Tablespace::getDefaultLogfileGroupId().

Signature const char* getDefaultLogfileGroup

void
) const

Parameters None.

Return value The name of the log file group (string value as character pointer).

Tablespace::getDefaultLogfileGroupId()

Description This method retrieves the ID of the tablespace's default log file group.

You can also obtain directly the name of the default log file group rather

than its ID; see Tablespace::getDefaultLogfileGroup().

Signature Uint32 getDefaultLogfileGroupId

(

void
) const

Parameters None.

Return value The ID of the log file group, as an unsigned 32-bit integer.

Tablespace::getExtentSize()

Description This method is used to retrieve the extent size—that is the size of the

memory allocation units—used by the tablespace.



Note

The same extent size is used for all data files contained in a given tablespace.

Signature Uint32 getExtentSize

(void) const

Parameters None.

Return value The tablespace's extent size in bytes, as an unsigned 32-bit integer.

Tablespace::getObjectId()

Description This method retrieves the tablespace's object ID.

Signature virtual int getObjectId

void
) const

Parameters None.

Return value The object ID, as an integer.

Tablespace::getName()

Description This method retrieves the name of the tablespace.

Signature const char* getName

(void) const

Parameters None.

Return value The name of the tablespace, a string value (as a character pointer).

Tablespace::getObjectStatus()

Description This method is used to retrieve the object status of a tablespace.

Signature virtual Object::Status getObjectStatus

virtual object..Status getobjectstatus
(
 void
) const

Parameters None.

Return value An Object::Status value.

Tablespace::getObjectVersion()

Description This method gets the tablespace object version (see NDB Schema

Object Versions).

Signature virtual int getObjectVersion

(void) const

Parameters None.

Return value The object version, as an integer.

Tablespace::setAutoGrowSpecification()

Description This method is used to set the auto-grow characteristics of the

tablespace.

Signature void setAutoGrowSpecification

(
const AutoGrowSpecification& autoGrowSpec

Parameters This method takes a single parameter, an AutoGrowSpecification

data structure.

Return value None.

Tablespace::setDefaultLogfileGroup()

Description This method is used to set a tablespace's default log file group.

Signature This method can be called in two different ways. The first of these uses

the name of the log file group, as shown here:

```
void setDefaultLogfileGroup
    (
      const char* name
    )
```

This method can also be called by passing it a reference to a LogfileGroup object:

```
void setDefaultLogfileGroup
   (
      const class LogfileGroup& 1Group
   )
```

The NDB API provides no method for setting a log file group as the default for a tablespace by referencing the log file group's ID.

Parameters Either the *name* of the log file group to be assigned to the tablespace, or

a reference *1Group* to this log file group.

Return value None.

Tablespace::setExtentSize()

Description This method sets the tablespace's extent size.

Signature void setExtentSize

Uint32 size

Parameters The size to be used for this tablespace's extents, in bytes.

Return value None.

Tablespace::setName()

Description This method sets the name of the tablespace.

Signature void setName

(const char* name

Parameters The name of the tablespace, a string (character pointer).

Return value None.

2.3.29 The Undofile Class

This section provides information about the Undofile class.

- Undofile Class Overview
- Undofile Constructor
- Undofile::getFileNo() (OBSOLETE)
- Undofile::getLogfileGroup()
- Undofile::getLogfileGroupId()
- Undofile::getNode() (OBSOLETE)
- Undofile::getObjectId()
- Undofile::getObjectStatus()
- Undofile::getObjectVersion()
- Undofile::getPath()
- Undofile::getSize()
- Undofile::setLogfileGroup()
- Undofile::setNode() (OBSOLETE)
- Undofile::setPath()
- Undofile::setSize()

Undofile Class Overview

Parent class NdbDictionary

Child classes None

Description The Undofile class models an NDB Cluster Disk Data undo file, which

stores data used for rolling back transactions.

Only unindexed column data can be stored on disk. Indexes and

indexes columns are always stored in memory.

Methods The following table lists the public methods of this class and the purpose or use of each method:

Table 2.81 Undofile class methods and descriptions

Name	Description
Undofile()	Class constructor
~Undofile()	Virtual destructor
getFileNo()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
getLogfileGroup()	Gets the name of the log file group to which the undo file belongs
getLogfileGroupId(Gets the ID of the log file group to which the undo file belongs
getNode()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
getObjectId()	Gets the undo file's object ID
getObjectStatus()	Gets the undo file's Status
<pre>getObjectVersion()</pre>	Gets the undo file's object version
getPath()	Gets the undo file's file system path
getSize()	Gets the size of the undo file
setLogfileGroup()	Sets the undo file's log file group using the name of the log file group or a reference to the corresponding LogfileGroup object
setNode()	Removed in NDB 7.5.0 (Bug #47960, Bug #11756088)
setPath()	Sets the file system path for the undo file
setSize()	Sets the undo file's size

Types

The Undofile class defines no public types.

Undofile Constructor

Description The class constructor can be used to create a new Undofile instance,

or to copy an existing one.

Signatures Create a new instance:

Undofile

```
(
void
)
```

Copy constructor:

```
Undofile
   (
     const Undofile& undoFile
   )
```

Parameters New instance: None. The copy constructor takes a single argument—a

reference to the Undofile object to be copied.

Return value An Undofile object.

Destructor. The class defines a virtual destructor which takes no arguments and has the return type void.

Undofile::getFileNo() (OBSOLETE)

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature Uint32 getFileNo

(void) const

Parameters None.

Return value The number of the undo file, as an unsigned 32-bit integer.

Undofile::getLogfileGroup()

Description This method retrieves the name of the log file group to which the undo

file belongs.

Signature const char* getLogfileGroup

void
) const

Parameters None.

Return value The name of the log file group, a string value (as a character pointer).

Undofile::getLogfileGroupId()

Description This method retrieves the ID of the log file group to which the undo file

belongs.

It is also possible to obtain the name of the log file group directly. See

Undofile::getLogfileGroup()

Signature Uint32 getLogfileGroupId

void
) const

Parameters None.

Return value

The ID of the log file group, as an unsigned 32-bit integer.

Undofile::getNode() (OBSOLETE)

Description

This method did not work as intended, and was removed in NDB 7.5.0 (Bug #47960, Bug #11756088).

Signature

Uint32 getNode (void) const

Parameters

None.

Return value

The node ID, as an unsigned 32-bit integer.

Undofile::getObjectId()

Description

This method retrieves the undo file's object ID.

Signature

virtual int getObjectId
 (
 void
) const

Parameters

None.

Return value

The object ID, as an integer.

Undofile::getObjectStatus()

Description

This method is used to retrieve the object status of an undo file.

Signature

virtual Object::Status getObjectStatus
 (
 void
) const

Parameters

None.

Return value

An Object::Status value.

Undofile::getObjectVersion()

Description

This method gets the undo file's object version (see NDB Schema Object Versions).

Signature

virtual int getObjectVersion
 (

void
) const

Parameters

None.

Return value

The object version, as an integer.

Undofile::getPath()

Description

This method retrieves the path matching the location of the undo file on

the data node's file system.

Signature const char* getPath

void
) const

Parameters None.

Return value The file system path, a string (as a character pointer).

Undofile::getSize()

Description This method gets the size of the undo file in bytes.

Signature Uint64 getSize

void
) const

Parameters None.

Return value The size in bytes of the undo file, as an unsigned 64-bit integer.

Undofile::setLogfileGroup()

Description Given either a name or an object reference to a log file group, the

setLogfileGroup() method assigns the undo file to that log file

group.

Signature Using a log file group name:

void setLogfileGroup
 (
 const char* name
)

Using a reference to an instance of LogfileGroup:

void setLogfileGroup
 (
 const class LogfileGroup & logfileGroup
)

Parameters The name of the log file group (a character pointer), or a reference to a

LogfileGroup instance.

Return value None.

Undofile::setNode() (OBSOLETE)

Description This method did not work as intended, and was removed in NDB 7.5.0

(Bug #47960, Bug #11756088).

Signature void setNode

(
Uint32 nodeId

Parameters The node Id of the data node where the undo file is to be placed; this is

an unsigned 32-bit integer.

Return value None.

Undofile::setPath()

Description This method is used to set the file system path of the undo file on the

data node where it resides.

Signature void setPath

const char* path

Parameters The desired *path* to the undo file.

Return value None.

Undofile::setSize()

Description Sets the size of the undo file in bytes.

Signature void setSize

(
Uint64 size

Parameters The intended size of the undo file in bytes, as an unsigned 64-bit

integer.

Return value None.

2.4 NDB API Errors and Error Handling

This section contains a discussion of error handling in NDB API applications as well as listing listings of the most common NDB error codes and messages, along with their classifications and likely causes for which they might be raised.

For information about the NdbError structure, which is used to convey error information to NDB API applications, see Section 2.3.15, "The NdbError Structure".



Important

It is strongly recommended that you *not* depend on specific error codes in your NDB API applications, as they are subject to change over time. Instead, you should use the NdbError::Status and error classification in your source code, or consult the output of perror --ndb *error_code* to obtain information about a specific error code.

If you find a situation in which you need to use a specific error code in your application, please file a bug report at http://bugs.mysql.com/ so that we can update the corresponding status and classification.

2.4.1 Handling NDB API Errors

This section describes how NDB API errors can be detected and mapped onto particular operations.

NDB API errors can be generated in either of two ways:

- · When an operation is defined
- When an operation is executed

Errors raised during operation definition. Errors generated during operation definition result in a failure return code from the method called. The actual error can be determined by examining the relevant NdbOperation object, or the operation's NdbTransaction object.

Errors raised during operation execution. Errors occurring during operation execution cause the transaction of which they are a part to be aborted unless the AO_IgnoreError abort option is set for the operation.

By default, read operations are run with AO_IgnoreError, and write operations are run with AbortOnError, but this can be overridden by the user. When an error during execution causes a transaction to be aborted, the execute() method returns a failure return code. If an error is ignored due to AO_IgnoreError being set on the operation, the execute() method returns a success code, and the user must examine all operations for failure using NdbOperation::getNdbError(). For this reason, the return value of getNdbError() should usually be checked, even if execute() returns success. If the client application does not keep track of NdbOperation objects during execution, then NdbTransaction::getNextCompletedOperation() can be used to iterate over them.

You should also be aware that use of NdbBlob can result in extra operations being added to the batches executed. This means that, when iterating over completed operations using getNextCompletedOperation(), you may encounter operations related to NdbBlob objects which were not defined by your application.



Note

A read whose LockMode is CommittedRead cannot be AbortOnError. In this case, it is always be IgnoreError.

In all cases where operation-specific errors arise, an execution error with an operation is marked against both the operation and the associated transaction object. Where there are multiple operation errors in a single NdbTransaction::execute() call, due to operation batching and the use of AO_IgnoreError, only the first is marked against the NdbTransaction object. The remaining errors are recorded against the corresponding NdbOperation objects only.

It is also possible for errors to occur during execution—such as a data node failure—which are marked against the transaction object, but *not* against the underlying operation objects. This is because these errors apply to the transaction as a whole, and not to individual operations within the transaction.

For this reason, applications should use NdbTransaction::getNdbError() as the first way to determine whether an NdbTransaction::execute() call failed. If the batch of operations being executed included operations with the AO_IgnoreError abort option set, then it is possible that there were multiple failures, and the completed operations should be checked individually for errors using NdbOperation::getNdbError().

Implicit NdbTransaction::execute() calls in scan and BLOB methods. Scan operations are executed in the same way as other operations, and also have implicit execute() calls within the NdbScanOperation::nextResult() method. When NdbScanOperation::nextResult() indicates failure (that is, if the method returns -1), the transaction object should be checked for an error. The NdbScanOperation may also contain the error, but only if the error is not operation-specific.

Some BLOB manipulation methods also have implicit internal execute() calls, and so can experience operation execution failures at these points. The following NdbBlob methods can generate implicit execute() calls; this means that they also require checks of the NdbTransaction object for errors via NdbTransaction::getNdbError() if they return an error code:

• setNull()

- truncate()
- readData()
- writeData()

Summary. In general, it is possible for an error to occur during execution (resulting in a failure return code) when calling any of the following methods:

```
• NdbTransaction::execute()
```

```
• NdbBlob::setNull()
```

- NdbBlob::truncate()
- NdbBlob::readData()
- NdbBlob::writeData()
- NdbScanOperation::nextResult()



Note

This method does *not* perform an implicit <code>execute()</code> call. The <code>NdbBlob</code> methods can cause other defined operations to be executed when these methods are called; however, <code>nextResult()</code> calls do not do so.

If this happens, the NdbTransaction::getNdbError() method should be called to identify the first error that occurred. When operations are batched, and there are IgnoreError operations in the batch, there may be multiple operations with errors in the transaction. These can be found by using NdbTransaction::getNextCompletedOperation() to iterate over the set of completed operations, calling NdbOperation::getNdbError() for each operation.

When IgnoreError has been set on any operations in a batch of operations to be executed, the NdbTransaction::execute() method indicates success even where errors have actually occurred, as long as none of these errors caused a transaction to be aborted. To determine whether there were any ignored errors, the transaction error status should be checked using NdbTransaction::getNdbError(). Only if this indicates success can you be certain that no errors occurred. If an error code is returned by this method, and operations were batched, then you should iterate over all completed operations to find all the operations with ignored errors.

Example (pseudocode). We begin by executing a transaction which may have batched operations and a mix of AO IgnoreError and AbortOnError abort options:

int execResult= NdbTransaction.execute(args);



Note

For the number and permitted values of args, see NdbTransaction::execute().

Next, because errors on AO_IgnoreError operations do not affect execResult—that is, the value returned by execute()—we check for errors on the transaction:

```
NdbError err= NdbTransaction.getNdbError();
if (err.code != 0)
{
```

An nonzero value for the error code means that an error was raised on the transaction. This could be due to any of the following conditions:

- A transaction-wide error, such as a data node failure, that caused the transaction to be aborted
- A single operation-specific error, such as a constraint violation, that caused the transaction to be aborted
- A single operation-specific ignored error, such as no data found, that did not cause the transaction to be aborted
- The first of many operation-specific ignored errors, such as no data found when batching, that did not cause the transaction to be aborted
- First of a number of operation-specific ignored errors such as no data found (when batching) before an aborting operation error (transaction aborted)

```
if (execResult != 0)
{
```

The transaction has been aborted. The recommended strategy for handling the error in this case is to test the transaction error status and take appropriate action based on its value:

```
switch (err.status)
{
   case value1:
     // statement block handling value1 ...
   case value2:
     // statement block handling value2 ...
     // (etc. ...)
   case valueN:
     // statement block handling valueN ...
}
```

Since the transaction was aborted, it is generally necessary to iterate over the completed operations (if any) and find the errors raised by each only if you wish to do so for reporting purposes.

```
}
else
{
```

The transaction itself was not aborted, but there must be one or more ignored errors. In this case, you should iterate over the operations to determine what happened and handle the cause accordingly.

```
}
}
```

To handle a NdbScanOperation::nextResult() which returns -1, indicating that the operation failed (omitting cases where the operation was successful):

```
int nextrc= NdbScanOperation.nextResult(args);
```



Note

For the number and permitted values of *args*, see NdbScanOperation::nextResult().

```
if (nextrc == -1) {
```

First, you should check the NdbScanOperation object for any errors:

```
NdbError err= NdbScanOperation.getNdbError();
if (err.code == 0)
{
```

No error was found in the scan operation; the error must belong to the transaction as whole.

```
}
err= NdbTransaction.getNdbError();
```

Now you can handle the error based on the error status:

```
switch (err.status)
{
    case valuel:
        // statement block handling value1 ...
    case value2:
        // statement block handling value2 ...
        // (etc. ...)
    case valueN:
        // statement block handling valueN ...
}
```

For information about NDB API error classification and status codes, see Section 2.4.4, "NDB Error Classifications". While you should not rely on a specific error code or message text in your NDB API applications—since error codes and messages are both subject to change over time—it can be useful to check error codes and messages to help determine why a particular failure occurred. For more information about these, see Section 2.4.2, "NDB Error Codes: by Type". For more about NdbError and the types of information which can be obtained from NdbError objects, see Section 2.3.15, "The NdbError Structure".

2.4.2 NDB Error Codes: by Type

This section contains a number of error code lists, one for each type of NDB API error. The error types include the following:

- · No error
- · Application error
- Scan application error
- Configuration or application error (currently unused)
- · No data found
- · Constraint violation
- Schema error
- · User defined error
- · Insufficient space
- Temporary Resource error
- Node Recovery error

- Overload error
- · Timeout expired
- · Node shutdown
- Internal temporary
- Unknown result error
- Unknown error code (currently unused)
- Internal error
- · Function not implemented

The information in each list includes, for each error:

- The NDB error code
- The corresponding MySQL error code
- · The NDB classification code

See Section 2.4.4, "NDB Error Classifications", for the meanings of these classification codes.

• The text of the error message

Similar errors have been grouped together in each list. Each list is ordered alphabetically.

You can always obtain the latest error codes and information from the file storage/ndb/src/ndbapi/ndberror.cpp. (In previous releases of NDB Cluster, this file was named ndberror.c.)

These types are also shown in the error_status column of the ndbinfo.error_messages table.

2.4.2.1 No error

The following list enumerates all NDB errors of type NE (No error).

Error code 0

MySQL error 0

Error message No error

2.4.2.2 Application error

The following list enumerates all NDB errors of type AE (Application error).

Error code 1233

MySQL error DMEC

Error message Table read-only

Error code 1302

MySQL error DMEC

Error message A backup is already running

MySQL error DMEC

Error message Backup not supported in diskless mode (change Diskless)

Error code 1329

MySQL error DMEC

Error message Backup during software upgrade not supported

Error code 1342

MySQL error DMEC

Error message Backup failed to allocate buffers (check configuration)

Error code 1343

MySQL error DMEC

Error message Backup failed to setup fs buffers (check configuration)

Error code 1344

MySQL error DMEC

Error message Backup failed to allocate tables (check configuration)

Error code 1345

MySQL error DMEC

Error message Backup failed to insert file header (check configuration)

Error code 1346

MySQL error DMEC

Error message Backup failed to insert table list (check configuration)

Error code 1347

MySQL error DMEC

Error message Backup failed to allocate table memory (check configuration)

Error code 1348

MySQL error DMEC

Error message Backup failed to allocate file record (check configuration)

Error code 1349

MySQL error DMEC

Error message Backup failed to allocate attribute record (check configuration)

Error message Node already reserved

Error code 1702

MySQL error DMEC

Error message Node already connected

Error code 1704

MySQL error DMEC

Error message Node type mismatch

Error code 21000

MySQL error HA_ERR_CANNOT_ADD_FOREIGN

Error message Create foreign key failed - parent key is primary key and on-update-

cascade is not allowed

Error code 21026

MySQL error HA_ERR_CANNOT_ADD_FOREIGN

Error message Create foreign key failed in NDB - parent index is not unique index

Error code 21033

MySQL error HA_ERR_CANNOT_ADD_FOREIGN

Error message Create foreign key failed in NDB - No parent row found

Error code 21034

MySQL error HA_ERR_CANNOT_ADD_FOREIGN

Error message Create foreign key failed - child table has Blob or Text column and on-

delete-cascade is not allowed

Error code 21040

MySQL error DMEC

Error message Drop foreign key failed in NDB - foreign key not found

Error code 21060

MySQL error DMEC

Error message Build foreign key failed in NDB - foreign key not found

Error code 21080

MySQL error HA_ERR_ROW_IS_REFERENCED

Error message Drop table not allowed in NDB - referenced by foreign key on another

table

MySQL error HA_ERR_DROP_INDEX_FK

Error message Drop index not allowed in NDB - used as parent index of a foreign key

Error code 21082

MySQL error HA_ERR_DROP_INDEX_FK

Error message Drop index not allowed in NDB - used as child index of a foreign key

Error code 21090

MySQL error HA_ERR_CANNOT_ADD_FOREIGN

Error message Create foreign key failed in NDB - name contains invalid character (/)

Error code 242

MySQL error DMEC

Error message Zero concurrency in scan

Error code 244

MySQL error DMEC

Error message Too high concurrency in scan

Error code 261

MySQL error DMEC

Error message DML count in transaction exceeds config parameter

MaxDMLOperationsPerTransaction/MaxNoOfConcurrentOperations

Error code 269

MySQL error DMEC

Error message No condition and attributes to read in scan

Error code 281

MySQL error HA_ERR_NO_CONNECTION

Error message Operation not allowed due to cluster shutdown in progress

Error code 299

MySQL error DMEC

Error message Operation not allowed or aborted due to single user mode

Error code 311

MySQL error DMEC

Error message Undefined partition used in setPartitionId

MySQL error DMEC

Error message Invalid no of nodes specified for new nodegroup

Error code 321

MySQL error DMEC

Error message Invalid nodegroup id

Error code 322

MySQL error DMEC

Error message Invalid node(s) specified for new nodegroup, node already in nodegroup

Error code 323

MySQL error DMEC

Error message Invalid nodegroup id, nodegroup already existing

Error code 324

MySQL error DMEC

Error message Invalid node(s) specified for new nodegroup, no node in nodegroup is

started

Error code 325

MySQL error DMEC

Error message Invalid node(s) specified for new nodegroup, node ID invalid or

undefined

Error code 4004

MySQL error DMEC

Error message Attribute name or id not found in the table

Error code 4100

MySQL error DMEC

Error message Status Error in NDB

Error code 4101

MySQL error DMEC

Error message No connections to NDB available and connect failed

Error code 4102

Error message Type in NdbTamper not correct

Error code 4103

MySQL error DMEC

Error message No schema connections to NDB available and connect failed

Error code 4104

MySQL error DMEC

Error message Ndb Init in wrong state, destroy Ndb object and create a new

Error code 4105

MySQL error DMEC

Error message Too many Ndb objects

Error code 4106

MySQL error DMEC

Error message All Not NULL attribute have not been defined

Error code 4114

MySQL error DMEC

Error message Transaction is already completed

Error code 4116

MySQL error DMEC

Error message Operation was not defined correctly, probably missing a key

Error code 4117

MySQL error DMEC

Error message Could not start transporter, configuration error

Error code 4118

MySQL error DMEC

Error message Parameter error in API call

Error code 4120

MySQL error DMEC

Error message Scan already complete

Error code 4121

Error message Cannot set name twice for an Ndb object

Error code 4122

MySQL error DMEC

Error message Cannot set name after Ndb object is initialised

Error code 4123

MySQL error DMEC

Error message Free percent out of range. Allowed range is 1-99

Error code 417

MySQL error DMEC

Error message Bad operation reference - double unlock

Error code 4200

MySQL error DMEC

Error message Status Error when defining an operation

Error code 4201

MySQL error DMEC

Error message Variable Arrays not yet supported

Error code 4202

MySQL error DMEC

Error message Set value on tuple key attribute is not allowed

Error code 4203

MySQL error DMEC

Error message Trying to set a NOT NULL attribute to NULL

Error code 4204

MySQL error DMEC

Error message Set value and Read/Delete Tuple is incompatible

Error code 4205

MySQL error DMEC

Error message No Key attribute used to define tuple

Error code 4206

Error message Not allowed to equal key attribute twice

Error code 4207

MySQL error DMEC

Error message Key size is limited to 4092 bytes

Error code 4208

MySQL error DMEC

Error message Trying to read a non-stored attribute

Error code 4209

MySQL error DMEC

Error message Length parameter in equal/setValue is incorrect

Error code 4210

MySQL error DMEC

Error message Ndb sent more info than the length he specified

Error code 4211

MySQL error DMEC

Error message Inconsistency in list of NdbRecAttr-objects

Error code 4212

MySQL error DMEC

Error message Ndb reports NULL value on Not NULL attribute

Error code 4213

MySQL error DMEC

Error message Not all data of an attribute has been received

Error code 4214

MySQL error DMEC

Error message Not all attributes have been received

Error code 4215

MySQL error DMEC

Error message More data received than reported in TCKEYCONF message

Error code 4216

Error message More than 8052 bytes in setValue cannot be handled

Error code 4217

MySQL error DMEC

Error message It is not allowed to increment any other than unsigned ints

Error code 4218

MySQL error DMEC

Error message Currently not allowed to increment NULL-able attributes

Error code 4219

MySQL error DMEC

Error message Maximum size of interpretative attributes are 64 bits

Error code 4220

MySQL error DMEC

Error message Maximum size of interpretative attributes are 64 bits

Error code 4221

MySQL error DMEC

Error message Trying to jump to a non-defined label

Error code 4222

MySQL error DMEC

Error message Label was not found, internal error

Error code 4223

MySQL error DMEC

Error message Not allowed to create jumps to yourself

Error code 4224

MySQL error DMEC

Error message Not allowed to jump to a label in a different subroutine

Error code 4225

MySQL error DMEC

Error message All primary keys defined, call setValue/getValue

Error code 4226

Error message Bad number when defining a label

Error code 4227

MySQL error DMEC

Error message Bad number when defining a subroutine

Error code 4228

MySQL error DMEC

Error message Illegal interpreter function in scan definition

Error code 4229

MySQL error DMEC

Error message Illegal register in interpreter function definition

Error code 4230

MySQL error DMEC

Error message Illegal state when calling getValue, probably not a read

Error code 4231

MySQL error DMEC

Error message Illegal state when calling interpreter routine

Error code 4232

MySQL error DMEC

Error message Parallelism can only be between 1 and 240

Error code 4233

MySQL error DMEC

Error message Calling execute (synchronous) when already prepared asynchronous

transaction exists

Error code 4234

MySQL error DMEC

Error message Illegal to call setValue in this state

Error code 4235

MySQL error DMEC

Error message No callback from execute

Error code 4236

Error message Trigger name too long

Error code 4237

MySQL error DMEC

Error message Too many triggers

Error code 4238

MySQL error DMEC

Error message Trigger not found

Error code 4239

MySQL error DMEC

Error message Trigger with given name already exists

Error code 4240

MySQL error DMEC

Error message Unsupported trigger type

Error code 4241

MySQL error DMEC

Error message Index name too long

Error code 4242

MySQL error DMEC

Error message Too many indexes

Error code 4243

MySQL error DMEC

Error message Index not found

Error code 4247

MySQL error DMEC

Error message Illegal index/trigger create/drop/alter request

Error code 4248

MySQL error DMEC

Error message Trigger/index name invalid

Error code 4249

Error message Invalid table

Error code 4250

MySQL error DMEC

Error message Invalid index type or index logging option

Error code 4251

MySQL error HA_ERR_FOUND_DUPP_UNIQUE

Error message Cannot create unique index, duplicate keys found

Error code 4252

MySQL error DMEC

Error message Failed to allocate space for index

Error code 4253

MySQL error DMEC

Error message Failed to create index table

Error code 4254

MySQL error DMEC

Error message Table not an index table

Error code 4255

MySQL error DMEC

Error message Hash index attributes must be specified in same order as table

attributes

Error code 4256

MySQL error DMEC

Error message Must call Ndb::init() before this function

Error code 4257

MySQL error DMEC

Error message Tried to read too much - too many getValue calls

Error code 4258

MySQL error DMEC

Error message Cannot create unique index, duplicate attributes found in definition

Error code 4259

Error message Invalid set of range scan bounds

Error code 4264

MySQL error DMEC

Error message Invalid usage of blob attribute

Error code 4265

MySQL error DMEC

Error message The method is not valid in current blob state

Error code 4266

MySQL error DMEC

Error message Invalid blob seek position

Error code 4271

MySQL error DMEC

Error message Invalid index object, not retrieved via getIndex()

Error code 4272

MySQL error DMEC

Error message Table definition has undefined column

Error code 4275

MySQL error DMEC

Error message The blob method is incompatible with operation type or lock mode

Error code 4276

MySQL error DMEC

Error message Missing NULL ptr in end of keyData list

Error code 4277

MySQL error DMEC

Error message Key part len is to small for column

Error code 4278

MySQL error DMEC

Error message Supplied buffer to small

Error code 4279

Error message Malformed string

Error code 4280

MySQL error DMEC

Error message Inconsistent key part length

Error code 4281

MySQL error DMEC

Error message Too many keys specified for key bound in scanIndex

Error code 4282

MySQL error DMEC

Error message range_no not strictly increasing in ordered multi-range index scan

Error code 4283

MySQL error DMEC

Error message key_record in index scan is not an index ndbrecord

Error code 4284

MySQL error DMEC

Error message Cannot mix NdbRecAttr and NdbRecord methods in one operation

Error code 4285

MySQL error DMEC

Error message NULL NdbRecord pointer

Error code 4286

MySQL error DMEC

Error message Invalid range_no (must be < 4096)

Error code 4287

MySQL error DMEC

Error message The key_record and attribute_record in primary key operation do not

belong to the same table

Error code 4288

MySQL error DMEC

Error message Blob handle for column not available

Error code 4289

Error message API version mismatch or wrong

sizeof(NdbDictionary::RecordSpecification)

Error code 4290

MySQL error DMEC

Error message Missing column specification in NdbDictionary::RecordSpecification

Error code 4291

MySQL error DMEC

Error message Duplicate column specification in NdbDictionary::RecordSpecification

Error code 4292

MySQL error DMEC

Error message NdbRecord for tuple access is not an index key NdbRecord

Error code 4293

MySQL error DMEC

Error message Error returned from application scanIndex() callback

Error code 4294

MySQL error DMEC

Error message Scan filter is too large, discarded

Error code 4295

MySQL error DMEC

Error message Column is NULL in Get/SetValueSpec structure

Error code 4296

MySQL error DMEC

Error message Invalid AbortOption

Error code 4297

MySQL error DMEC

Error message Invalid or unsupported OperationOptions structure

Error code 4298

MySQL error DMEC

Error message Invalid or unsupported ScanOptions structure

Error code 4299

Error message Incorrect combination of ScanOption flags, extraGetValues ptr and

numExtraGetValues

Error code 4300

MySQL error DMEC

Error message Tuple Key Type not correct

Error code 4301

MySQL error DMEC

Error message Fragment Type not correct

Error code 4302

MySQL error DMEC

Error message Minimum Load Factor not correct

Error code 4303

MySQL error DMEC

Error message Maximum Load Factor not correct

Error code 4304

MySQL error DMEC

Error message Maximum Load Factor smaller than Minimum

Error code 4305

MySQL error DMEC

Error message K value must currently be set to 6

Error code 4306

MySQL error DMEC

Error message Memory Type not correct

Error code 4307

MySQL error DMEC

Error message Invalid table name

Error code 4308

MySQL error DMEC

Error message Attribute Size not correct

Error code 4309

Error message Fixed array too large, maximum 64000 bytes

Error code 4310

MySQL error DMEC

Error message Attribute Type not correct

Error code 4311

MySQL error DMEC

Error message Storage Mode not correct

Error code 4312

MySQL error DMEC

Error message Null Attribute Type not correct

Error code 4313

MySQL error DMEC

Error message Index only storage for non-key attribute

Error code 4314

MySQL error DMEC

Error message Storage Type of attribute not correct

Error code 4315

MySQL error DMEC

Error message No more key attributes allowed after defining variable length key

attribute

Error code 4316

MySQL error DMEC

Error message Key attributes are not allowed to be NULL attributes

Error code 4317

MySQL error DMEC

Error message Too many primary keys defined in table

Error code 4318

MySQL error DMEC

Error message Invalid attribute name or number

Error code 4319

Error message createAttribute called at erroneus place

Error code 4322

MySQL error DMEC

Error message Attempt to define distribution key when not prepared to

Error code 4323

MySQL error DMEC

Error message Distribution Key set on table but not defined on first attribute

Error code 4324

MySQL error DMEC

Error message Attempt to define distribution group when not prepared to

Error code 4325

MySQL error DMEC

Error message Distribution Group set on table but not defined on first attribute

Error code 4326

MySQL error DMEC

Error message Distribution Group with erroneus number of bits

Error code 4327

MySQL error DMEC

Error message Distribution key is only supported on part of primary key

Error code 4328

MySQL error DMEC

Error message Disk memory attributes not yet supported

Error code 4329

MySQL error DMEC

Error message Variable stored attributes not yet supported

Error code 4335

MySQL error DMEC

Error message Only one autoincrement column allowed per table. Having a table

without primary key uses an autoincremented hidden key, i.e. a table

without a primary key can not have an autoincremented column

Error message Result or attribute record must be a base table ndbrecord, not an index

ndbrecord

Error code 4341

MySQL error DMEC

Error message Not all keys read when using option SF_OrderBy

Error code 4342

MySQL error DMEC

Error message Scan defined but not prepared

Error code 4343

MySQL error DMEC

Error message Table with blobs does not support refresh

Error code 4377

MySQL error DMEC

Error message Database and schema name must be set on Ndb object

Error code 4400

MySQL error DMEC

Error message Status Error in NdbSchemaCon

Error code 4401

MySQL error DMEC

Error message Only one schema operation per schema transaction

Error code 4402

MySQL error DMEC

Error message No schema operation defined before calling execute

Error code 4410

MySQL error DMEC

Error message Schema transaction is already started

Error code 4411

MySQL error DMEC

Error message Schema transaction not possible until upgrade complete

Error message Schema transaction is not started

Error code 4501

MySQL error DMEC

Error message Insert in hash table failed when getting table information from Ndb

Error code 4502

MySQL error DMEC

Error message GetValue not allowed in Update operation

Error code 4503

MySQL error DMEC

Error message GetValue not allowed in Insert operation

Error code 4504

MySQL error DMEC

Error message SetValue not allowed in Read operation

Error code 4505

MySQL error DMEC

Error message NULL value not allowed in primary key search

Error code 4506

MySQL error DMEC

Error message Missing getValue/setValue when calling execute

Error code 4507

MySQL error DMEC

Error message Missing operation request when calling execute

Error code 4508

MySQL error DMEC

Error message GetValue not allowed for NdbRecord defined operation

Error code 4509

MySQL error DMEC

Error message Non SF_MultiRange scan cannot have more than one bound

Error message User specified partition id not allowed for scan takeover operation

Error code 4511

MySQL error DMEC

Error message Blobs not allowed in NdbRecord delete result record

Error code 4512

MySQL error DMEC

Error message Incorrect combination of OperationOptions optionsPresent, extraGet/

SetValues ptr and numExtraGet/SetValues

Error code 4513

MySQL error DMEC

Error message Only one scan bound allowed for non-NdbRecord setBound() API

Error code 4514

MySQL error DMEC

Error message Can only call setBound/equal() for an NdbIndexScanOperation

Error code 4515

MySQL error DMEC

Error message Method not allowed for NdbRecord, use OperationOptions or

ScanOptions structure instead

Error code 4516

MySQL error DMEC

Error message Illegal instruction in interpreted program

Error code 4517

MySQL error DMEC

Error message Bad label in branch instruction

Error code 4518

MySQL error DMEC

Error message Too many instructions in interpreted program

Error code 4519

MySQL error DMEC

Error message NdbInterpretedCode::finalise() not called

MySQL error DMEC

Error message Call to undefined subroutine

Error code 4521

MySQL error DMEC

Error message Call to undefined subroutine, internal error

Error code 4522

MySQL error DMEC

Error message setBound() called twice for same key

Error code 4523

MySQL error DMEC

Error message Pseudo columns not supported by NdbRecord

Error code 4524

MySQL error DMEC

Error message NdbInterpretedCode is for different table

Error code 4535

MySQL error DMEC

Error message Attempt to set bound on non key column

Error code 4536

MySQL error DMEC

Error message NdbScanFilter constructor taking NdbOperation is not supported for

NdbRecord

Error code 4537

MySQL error DMEC

Error message Wrong API. Use NdbInterpretedCode for NdbRecord operations

Error code 4538

MySQL error DMEC

Error message NdbInterpretedCode instruction requires that table is set

Error code 4539

MySQL error DMEC

Error message NdbInterpretedCode not supported for operation type

MySQL error DMEC

Error message Attempt to pass an Index column to createRecord. Use base table

columns only

Error code 4542

MySQL error DMEC

Error message Unknown partition information type

Error code 4543

MySQL error DMEC

Error message Duplicate partitioning information supplied

Error code 4544

MySQL error DMEC

Error message Wrong partitionInfo type for table

Error code 4545

MySQL error DMEC

Error message Invalid or Unsupported PartitionInfo structure

Error code 4546

MySQL error DMEC

Error message Explicit partitioning info not allowed for table and operation

Error code 4547

MySQL error DMEC

Error message RecordSpecification has overlapping offsets

Error code 4548

MySQL error DMEC

Error message RecordSpecification has too many elements

Error code 4549

MySQL error DMEC

Error message getLockHandle only supported for primary key read with a lock

Error code 4550

MySQL error DMEC

Error message Cannot releaseLockHandle until operation executed

MySQL error DMEC

Error message NdbLockHandle already released

Error code 4552

MySQL error DMEC

Error message NdbLockHandle does not belong to transaction

Error code 4553

MySQL error DMEC

Error message NdbLockHandle original operation not executed successfully

Error code 4554

MySQL error DMEC

Error message NdbBlob can only be closed from Active state

Error code 4555

MySQL error DMEC

Error message NdbBlob cannot be closed with pending operations

Error code 4556

MySQL error DMEC

Error message RecordSpecification has illegal value in column_flags

Error code 4557

MySQL error DMEC

Error message Column types must be identical when comparing two columns

Error code 4558

MySQL error DMEC

Error message Pending Blob operations must be executed before this call

Error code 4600

MySQL error DMEC

Error message Transaction is already started

Error code 4601

MySQL error DMEC

Error message Transaction is not started

MySQL error DMEC

Error message You must call getNdbOperation before executeScan

Error code 4603

MySQL error DMEC

Error message There can only be ONE operation in a scan transaction

Error code 4604

MySQL error DMEC

Error message takeOverScanOp, to take over a scanned row one must explicitly

request keyinfo on readTuples call

Error code 4605

MySQL error DMEC

Error message You may only call readTuples() once for each operation

Error code 4607

MySQL error DMEC

Error message There may only be one operation in a scan transaction

Error code 4608

MySQL error DMEC

Error message You can not takeOverScan unless you have used openScanExclusive

Error code 4609

MySQL error DMEC

Error message You must call nextScanResult before trying to takeOverScan

Error code 4707

MySQL error DMEC

Error message Too many event have been defined

Error code 4708

MySQL error DMEC

Error message Event name is too long

Error code 4709

MySQL error DMEC

Error message Can't accept more subscribers

MySQL error DMEC

Error message Event not found

Error code 4711

MySQL error DMEC

Error message Creation of event failed

Error code 4712

MySQL error DMEC

Error message Stopped event operation does not exist. Already stopped?

Error code 4714

MySQL error DMEC

Error message Index stats sys tables NDB_INDEX_STAT_PREFIX do not exist

Error code 4715

MySQL error DMEC

Error message Index stats for specified index do not exist

Error code 4716

MySQL error DMEC

Error message Index stats methods usage error

Error code 4717

MySQL error DMEC

Error message Index stats cannot allocate memory

Error code 4720

MySQL error DMEC

Error message Index stats sys tables NDB_INDEX_STAT_PREFIX partly missing or

invalid

Error code 4723

MySQL error DMEC

Error message Mysqld: index stats request ignored due to recent error

Error code 4724

MySQL error DMEC

Error message Mysqld: index stats request aborted by stats thread

MySQL error DMEC

Error message Index stats were deleted by another process

Error code 720

MySQL error DMEC

Error message Attribute name reused in table definition

Error code 763

MySQL error DMEC

Error message DDL is not supported with mixed data-node versions

Error code 771

MySQL error HA_WRONG_CREATE_OPTION

Error message Given NODEGROUP doesn't exist in this cluster

Error code 776

MySQL error DMEC

Error message Index created on temporary table must itself be temporary

Error code 777

MySQL error DMEC

Error message Cannot create a temporary index on a non-temporary table

Error code 778

MySQL error DMEC

Error message A temporary table or index must be specified as not logging

Error code 789

MySQL error HA_WRONG_CREATE_OPTION

Error message Logfile group not found

Error code 793

MySQL error DMEC

Error message Object definition too big

Error code 794

MySQL error DMEC

Error message Schema feature requires data node upgrade

MySQL error DMEC

Error message A disk table must not be specified as no logging

Error code 823

MySQL error DMEC

Error message Too much attrinfo from application in tuple manager

Error code 829

MySQL error DMEC

Error message Corrupt data received for insert/update

Error code 831

MySQL error DMEC

Error message Too many nullable/bitfields in table definition

Error code 850

MySQL error DMEC

Error message Too long or too short default value

Error code 851

MySQL error DMEC

Error message Fixed-size column offset exceeded max.Use VARCHAR or

COLUMN_FORMAT DYNAMIC for memory-stored columns

Error code 874

MySQL error DMEC

Error message Too much attrinfo (e.g. scan filter) for scan in tuple manager

Error code 876

MySQL error DMEC

Error message 876

Error code 877

MySQL error DMEC

Error message 877

Error code 878

MySQL error DMEC

Error message 878

MySQL error DMEC

Error message 879

Error code 880

MySQL error DMEC

Error message Tried to read too much - too many getValue calls

Error code 884

MySQL error DMEC

Error message Stack overflow in interpreter

Error code 885

MySQL error DMEC

Error message Stack underflow in interpreter

Error code 886

MySQL error DMEC

Error message More than 65535 instructions executed in interpreter

Error code 892

MySQL error DMEC

Error message Unsupported type in scan filter

Error code 897

MySQL error DMEC

Error message Update attempt of primary key via ndbcluster internal api (if this occurs

via the MySQL server it is a bug, please report)

Error code 912

MySQL error DMEC

Error message Index stat scan requested with wrong lock mode

Error code 913

MySQL error DMEC

Error message Invalid index for index stats update

Error code 920

MySQL error DMEC

Error message Row operation defined after refreshTuple()

Error code INVALID_BLOCK_NAME

MySQL error DMEC

Error message Invalid block name

Error code INVALID_ERROR_NUMBER

MySQL error DMEC

Error message Invalid error number. Should be >= 0.

Error code INVALID_TRACE_NUMBER

MySQL error DMEC

Error message Invalid trace number.

Error code NODE_NOT_API_NODE

MySQL error DMEC

Error message The specified node is not an API node.

Error code NODE_SHUTDOWN_IN_PROGESS

MySQL error DMEC

Error message Node shutdown in progress

Error code NODE_SHUTDOWN_WOULD_CAUSE_SYSTEM_CRASH

MySQL error DMEC

Error message Node shutdown would cause system crash

Error code NO_CONTACT_WITH_DB_NODES

MySQL error DMEC

Error message No contact with database nodes }

Error code NO_CONTACT_WITH_PROCESS

MySQL error DMEC

Error message No contact with the process (dead ?).

Error code OPERATION_NOT_ALLOWED_START_STOP

MySQL error DMEC

Error message Operation not allowed while nodes are starting or stopping.

Error code QRY_BATCH_SIZE_TOO_SMALL

MySQL error DMEC

Error message Batch size for sub scan cannot be smaller than number of fragments.

Error code QRY_CHAR_OPERAND_TRUNCATED

MySQL error DMEC

Error message Character operand was right truncated

Error code QRY_CHAR_PARAMETER_TRUNCATED

MySQL error DMEC

Error message Character Parameter was right truncated

Error code QRY_DEFINITION_TOO_LARGE

MySQL error DMEC

Error message Query definition too large.

Error code QRY_EMPTY_PROJECTION

MySQL error DMEC

Error message Query has operation with empty projection.

Error code QRY_HAS_ZERO_OPERATIONS

MySQL error DMEC

Error message Query defintion should have at least one operation.

Error code QRY_ILLEGAL_STATE

MySQL error DMEC

Error message Query is in illegal state for this operation.

Error code QRY_IN_ERROR_STATE

MySQL error DMEC

Error message A previous query operation failed, which you missed to catch.

Error code QRY_MULTIPLE_PARENTS

MySQL error DMEC

Error message Multiple 'parents' specified in linkedValues for this operation

Error code QRY_MULTIPLE_SCAN_SORTED

MySQL error DMEC

Error message Query with multiple scans may not be sorted.

Error code QRY_NEST_NOT_SUPPORTED

MySQL error DMEC

Error message FirstInner/Upper has to be an ancestor or a sibling

Error code QRY_NUM_OPERAND_RANGE

MySQL error DMEC

Error message Numeric operand out of range

Error code QRY_OJ_NOT_SUPPORTED

MySQL error DMEC

Error message Outer joined scans not supported by data nodes.

Error code QRY_OPERAND_ALREADY_BOUND

MySQL error DMEC

Error message Can't use same operand value to specify different column values

Error code QRY_OPERAND_HAS_WRONG_TYPE

MySQL error DMEC

Error message Incompatible datatype specified in operand argument

Error code QRY_PARAMETER_HAS_WRONG_TYPE

MySQL error DMEC

Error message Parameter value has an incompatible datatype

Error code QRY_REQ_ARG_IS_NULL

MySQL error DMEC

Error message Required argument is NULL

Error code QRY_RESULT_ROW_ALREADY_DEFINED

MySQL error DMEC

Error message Result row already defined for NdbQueryOperation.

Error code QRY_SCAN_ORDER_ALREADY_SET

MySQL error DMEC

Error message Index scan order was already set in query definition.

Error code QRY_SEQUENTIAL_SCAN_SORTED

MySQL error DMEC

Error message Parallelism cannot be restricted for sorted scans.

Error code QRY_TOO_FEW_KEY_VALUES

MySQL error DMEC

Error message All required 'key' values was not specified

Error code QRY_TOO_MANY_KEY_VALUES

MySQL error DMEC

Error message Too many 'key' or 'bound' values was specified

Error code QRY_UNKNOWN_PARENT

MySQL error DMEC

Error message Unknown 'parent' specified in linkedValue

Error code QRY_UNRELATED_INDEX

MySQL error DMEC

Error message Specified 'index' does not belong to specified 'table'

Error code QRY_WRONG_INDEX_TYPE

MySQL error DMEC

Error message Wrong type of index specified for this operation

Error code QRY_WRONG_OPERATION_TYPE

MySQL error DMEC

Error message This method cannot be invoked on this type of operation (lookup/scan/

index scan).

Error code SEND_OR_RECEIVE_FAILED

MySQL error DMEC

Error message Send to process or receive failed.

Error code SYSTEM_SHUTDOWN_IN_PROGRESS

MySQL error DMEC

Error message System shutdown in progress

Error code UNSUPPORTED_NODE_SHUTDOWN

MySQL error DMEC

Error message Unsupported multi node shutdown. Abort option required.

Error code WRONG_PROCESS_TYPE

MySQL error DMEC

Error message The process has wrong type. Expected a DB process.

2.4.2.3 Configuration or application error

The following list enumerates all NDB errors of type CE (Configuration or application error).

Error message Data node/s configured to have encryption but password not provided

Error code 1309

MySQL error DMEC

Error message Encryption password has bad character/s (see 'HELP START

BACKUP')

Error code 1310

MySQL error DMEC

Error message Encryption password is too long (see 'HELP START BACKUP')

Error code 1311

MySQL error DMEC

Error message Encryption password is of zero length

2.4.2.4 No data found

The following list enumerates all NDB errors of type ND (No data found).

Error code 626

MySQL error HA_ERR_KEY_NOT_FOUND

Error message Tuple did not exist

2.4.2.5 Constraint violation

The following list enumerates all NDB errors of type CV (Constraint violation).

Error code 255

MySQL error HA_ERR_NO_REFERENCED_ROW

Error message Foreign key constraint violated: No parent row found

Error code 256

MySQL error HA_ERR_ROW_IS_REFERENCED

Error message Foreign key constraint violated: Referenced row exists

Error code 630

MySQL error HA_ERR_FOUND_DUPP_KEY

Error message Tuple already existed when attempting to insert

Error code 839

MySQL error DMEC

Error message Illegal null attribute

MySQL error DMEC

Error message Trying to set a NOT NULL attribute to NULL

Error code 893

MySQL error HA_ERR_FOUND_DUPP_KEY

Error message Constraint violation e.g. duplicate value in unique index

2.4.2.6 Schema error

The following list enumerates all NDB errors of type SE (Schema error).

Error code 1224

MySQL error HA_WRONG_CREATE_OPTION

Error message Too many fragments

Error code 1225

MySQL error DMEC

Error message Table not defined in local query handler

Error code 1226

MySQL error HA_ERR_NO_SUCH_TABLE

Error message Table is being dropped

Error code 1227

MySQL error HA_WRONG_CREATE_OPTION

Error message Invalid schema version

Error code 1228

MySQL error DMEC

Error message Cannot use drop table for drop index

Error code 1229

MySQL error DMEC

Error message Too long frm data supplied

Error code 1231

MySQL error DMEC

Error message Invalid table or index to scan

Error message Invalid table or index to scan

Error code 1407

MySQL error DMEC

Error message Subscription not found in subscriber manager

Error code 1415

MySQL error DMEC

Error message Subscription not unique in subscriber manager

Error code 1417

MySQL error DMEC

Error message Table in suscription not defined, probably dropped

Error code 1418

MySQL error DMEC

Error message Subscription dropped, no new subscribers allowed

Error code 1419

MySQL error DMEC

Error message Subscription already dropped

Error code 1421

MySQL error DMEC

Error message Partially connected API in NdbOperation::execute()

Error code 1422

MySQL error DMEC

Error message Out of subscription records

Error code 1423

MySQL error DMEC

Error message Out of table records in SUMA

Error code 1424

MySQL error DMEC

Error message Out of MaxNoOfConcurrentSubOperations

Error code 1425

Error message Subscription being defined...while trying to stop subscriber

Error code 1426

MySQL error DMEC

Error message No such subscriber

Error code 1503

MySQL error DMEC

Error message Out of filegroup records

Error code 1504

MySQL error DMEC

Error message Out of logbuffer memory(specify smaller undo_buffer_size or increase

SharedGlobalMemory)

Error code 1508

MySQL error DMEC

Error message Out of file records

Error code 1509

MySQL error DMEC

Error message File system error, check if path,permissions etc

Error code 1512

MySQL error DMEC

Error message File read error

Error code 1514

MySQL error DMEC

Error message Currently there is a limit of one logfile group

Error code 1515

MySQL error DMEC

Error message Currently there is a 4G limit of one undo/data-file in 32-bit host

Error code 1516

MySQL error DMEC

Error message File too small

Error code 1517

Error message Insufficient disk page buffer memory. Increase DiskPageBufferMemory

or reduce data file size.

Error code 20019

MySQL error HA_ERR_NO_SUCH_TABLE

Error message Query table not defined

Error code 20020

MySQL error HA_ERR_NO_SUCH_TABLE

Error message Query table is being dropped

Error code 20021

MySQL error HA_ERR_TABLE_DEF_CHANGED

Error message Query table definition has changed

Error code 21022

MySQL error DMEC

Error message Create foreign key failed in NDB - parent table is not table

Error code 21023

MySQL error DMEC

Error message Create foreign key failed in NDB - invalid parent table version

Error code 21024

MySQL error DMEC

Error message Create foreign key failed in NDB - child table is not table

Error code 21025

MySQL error DMEC

Error message Create foreign key failed in NDB - invalid child table version

Error code 21027

MySQL error DMEC

Error message Create foreign key failed in NDB - invalid parent index version

Error code 21028

MySQL error DMEC

Error message Create foreign key failed in NDB - child index is not index

Error code 21029

Error message Create foreign key failed in NDB - invalid child index version

Error code 21041

MySQL error DMEC

Error message Drop foreign key failed in NDB - invalid foreign key version

Error code 21042

MySQL error DMEC

Error message Drop foreign key failed in NDB - foreign key not found in TC

Error code 21061

MySQL error DMEC

Error message Build foreign key failed in NDB - invalid foreign key version

Error code 241

MySQL error HA_ERR_TABLE_DEF_CHANGED

Error message Invalid schema object version

Error code 283

MySQL error HA_ERR_NO_SUCH_TABLE

Error message Table is being dropped

Error code 284

MySQL error HA_ERR_TABLE_DEF_CHANGED

Error message Table not defined in transaction coordinator

Error code 285

MySQL error DMEC

Error message Unknown table error in transaction coordinator

Error code 4713

MySQL error DMEC

Error message Column defined in event does not exist in table

Error code 703

MySQL error DMEC

Error message Invalid table format

Error code 704

MySQL error DMEC

Error message Attribute name too long

MySQL error DMEC

Error message Table name too long

Error code 707

MySQL error DMEC

Error message No more table metadata records (increase MaxNoOfTables)

Error code 708

MySQL error DMEC

Error message No more attribute metadata records (increase MaxNoOfAttributes)

Error code 709

MySQL error HA_ERR_NO_SUCH_TABLE

Error message No such table existed

Error code 710

MySQL error DMEC

Error message Internal: Get by table name not supported, use table id.

Error code 712

MySQL error DMEC

Error message No more hashmap metadata records

Error code 723

MySQL error HA_ERR_NO_SUCH_TABLE

Error message No such table existed

Error code 736

MySQL error DMEC

Error message Unsupported array size

Error code 737

MySQL error HA_WRONG_CREATE_OPTION

Error message Attribute array size too big

Error code 738

MySQL error HA_WRONG_CREATE_OPTION

Error message Record too big

MySQL error HA_WRONG_CREATE_OPTION

Error message Unsupported primary key length

Error code 740

MySQL error HA_WRONG_CREATE_OPTION

Error message Nullable primary key not supported

Error code 741

MySQL error DMEC

Error message Unsupported alter table

Error code 743

MySQL error HA_WRONG_CREATE_OPTION

Error message Unsupported character set in table or index

Error code 744

MySQL error DMEC

Error message Character string is invalid for given character set

Error code 745

MySQL error HA_WRONG_CREATE_OPTION

Error message Distribution key not supported for char attribute (use binary attribute)

Error code 750

MySQL error IE

Error message Invalid file type

Error code 751

MySQL error DMEC

Error message Out of file records

Error code 752

MySQL error DMEC

Error message Invalid file format

Error code 753

MySQL error IE

Error message Invalid filegroup for file

Error code 754

MySQL error IE

Error message Invalid filegroup version when creating file

Error code 755

MySQL error HA_MISSING_CREATE_OPTION

Error message Invalid tablespace

Error code 756

MySQL error DMEC

Error message Index on disk column is not supported

Error code 757

MySQL error DMEC

Error message Varsize bitfield not supported

Error code 758

MySQL error DMEC

Error message Tablespace has changed

Error code 759

MySQL error DMEC

Error message Invalid tablespace version

Error code 760

MySQL error DMEC

Error message File already exists,

Error code 761

MySQL error DMEC

Error message Unable to drop table as backup is in progress

Error code 762

MySQL error DMEC

Error message Unable to alter table as backup is in progress

Error code 764

MySQL error HA_WRONG_CREATE_OPTION

Error message Invalid extent size

Error code 765

MySQL error DMEC

Error message Out of filegroup records

MySQL error DMEC

Error message Cant drop file, no such file

Error code 767

MySQL error DMEC

Error message Cant drop filegroup, no such filegroup

Error code 768

MySQL error DMEC

Error message Cant drop filegroup, filegroup is used

Error code 769

MySQL error DMEC

Error message Drop undofile not supported, drop logfile group instead

Error code 770

MySQL error DMEC

Error message Cant drop file, file is used

Error code 773

MySQL error DMEC

Error message Out of string memory, please modify StringMemory config parameter

Error code 774

MySQL error DMEC

Error message Invalid schema object for drop

Error code 775

MySQL error DMEC

Error message Create file is not supported when Diskless=1

Error code 779

MySQL error HA_WRONG_CREATE_OPTION

Error message Invalid undo buffer size

Error code 790

MySQL error HA_WRONG_CREATE_OPTION

Error message Invalid hashmap

MySQL error HA_WRONG_CREATE_OPTION

Error message Too many total bits in bitfields

Error code 792

MySQL error DMEC

Error message Default value for primary key column not supported

Error code 796

MySQL error DMEC

Error message Out of schema transaction memory

Error code 799

MySQL error HA_WRONG_CREATE_OPTION

Error message Non default partitioning without partitions

Error code 881

MySQL error DMEC

Error message Unable to create table, out of data pages (increase DataMemory)

Error code 906

MySQL error DMEC

Error message Unsupported attribute type in index

Error code 907

MySQL error DMEC

Error message Unsupported character set in table or index

Error code 910

MySQL error HA_ERR_NO_SUCH_TABLE

Error message Index is being dropped

Error code 911

MySQL error DMEC

Error message Index stat scan requested on index with unsupported key size

2.4.2.7 Schema object already exists

The following list enumerates all NDB errors of type OE (Schema object already exists).

Error code 4244

MySQL error HA_ERR_TABLE_EXIST

Error message Index or table with given name already exists

Error code 721

MySQL error HA_ERR_TABLE_EXIST

Error message Schema object with given name already exists

Error code 746

MySQL error DMEC

Error message Event name already exists

2.4.2.8 User defined error

The following list enumerates all NDB errors of type UD (User defined error).

Error code 1321

MySQL error DMEC

Error message Backup aborted by user request

Error code 4260

MySQL error DMEC

Error message NdbScanFilter: Operator is not defined in NdbScanFilter::Group

Error code 4261

MySQL error DMEC

Error message NdbScanFilter: Column is NULL

Error code 4262

MySQL error DMEC

Error message NdbScanFilter: Condition is out of bounds

2.4.2.9 Insufficient space

The following list enumerates all NDB errors of type IS (Insufficient space).

Error code 1303

MySQL error DMEC

Error message Out of resources

Error code 1412

MySQL error DMEC

Error message Can't accept more subscribers, out of space in pool

Error message Can't accept more subscriptions, out of space in pool

Error code 1601

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Out of extents, tablespace full

Error code 1602

MySQL error DMEC

Error message No datafile in tablespace

Error code 1603

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Table fragment fixed data reference has reached maximum possible

value (specify MAXROWS or increase no of partitions)

Error code 1604

MySQL error DMEC

Error message Error -1 from get_page

Error code 1605

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Out of page request records when allocating disk record

Error code 1606

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Out of extent records when allocating disk record

Error code 623

MySQL error HA_ERR_RECORD_FILE_FULL

Error message 623

Error code 624

MySQL error HA_ERR_RECORD_FILE_FULL

Error message 624

Error code 625

MySQL error HA_ERR_INDEX_FILE_FULL

Error message Out of memory in Ndb Kernel, hash index part (increase DataMemory)

MySQL error HA_ERR_INDEX_FILE_FULL

Error message Table fragment hash index has reached maximum possible size

Error code 640

MySQL error DMEC

Error message Too many hash indexes (should not happen)

Error code 747

MySQL error DMEC

Error message Out of event records

Error code 826

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Too many tables and attributes (increase MaxNoOfAttributes or

MaxNoOfTables)

Error code 827

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Out of memory in Ndb Kernel, table data (increase DataMemory)

Error code 889

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Table fragment fixed data reference has reached maximum possible

value (specify MAXROWS or increase no of partitions)

Error code 902

MySQL error HA_ERR_RECORD_FILE_FULL

Error message Out of memory in Ndb Kernel, ordered index data (increase

DataMemory)

Error code 903

MySQL error HA_ERR_INDEX_FILE_FULL

Error message Too many ordered indexes (increase MaxNoOfOrderedIndexes)

Error code 904

MySQL error HA_ERR_INDEX_FILE_FULL

Error message Out of fragment records (increase MaxNoOfOrderedIndexes)

Error code 905

MySQL error DMEC

Error message Out of attribute records (increase MaxNoOfAttributes)

MySQL error DMEC

Error message Invalid ordered index tree node size

2.4.2.10 Temporary Resource error

The following list enumerates all NDB errors of type TR (Temporary Resource error).

Error code 1217

MySQL error DMEC

Error message Out of operation records in local data manager (increase

SharedGlobalMemory)

Error code 1218

MySQL error DMEC

Error message Send Buffers overloaded in NDB kernel

Error code 1220

MySQL error DMEC

Error message REDO log files overloaded (increase FragmentLogFileSize)

Error code 1222

MySQL error DMEC

Error message Out of transaction markers in LQH, increase SharedGlobalMemory

Error code 1234

MySQL error DMEC

Error message REDO log files overloaded (increase disk hardware)

Error code 1350

MySQL error DMEC

Error message Backup failed: file already exists (use 'START BACKUP <backup id>')

Error code 1411

MySQL error DMEC

Error message Subscriber manager busy with adding/removing a subscriber

Error code 1413

MySQL error DMEC

Error message Subscriber manager busy with adding the subscription

Error message Subscriber manager has subscribers on this subscription

Error code 1420

MySQL error DMEC

Error message Subscriber manager busy with adding/removing a table

Error code 1501

MySQL error DMEC

Error message Out of undo space

Error code 20000

MySQL error DMEC

Error message Query aborted due out of operation records

Error code 20006

MySQL error DMEC

Error message Query aborted due to out of LongMessageBuffer

Error code 20008

MySQL error DMEC

Error message Query aborted due to out of query memory

Error code 20015

MySQL error DMEC

Error message Query aborted due to out of row memory

Error code 21020

MySQL error DMEC

Error message Create foreign key failed in NDB - no more object records

Error code 217

MySQL error DMEC

Error message 217

Error code 218

MySQL error DMEC

Error message Out of LongMessageBuffer

Error code 219

Error message 219

Error code 221

MySQL error DMEC

Error message Too many concurrently fired triggers, increase SharedGlobalMemory

Error code 233

MySQL error DMEC

Error message Out of operation records in transaction coordinator (increase

SharedGlobalMemory)

Error code 245

MySQL error DMEC

Error message Too many active scans, increase MaxNoOfConcurrentScans

Error code 251

MySQL error DMEC

Error message Out of frag location records in TC (increase SharedGlobalMemory)

Error code 273

MySQL error DMEC

Error message Out of transaction markers databuffer in TC, increase

SharedGlobalMemory

Error code 275

MySQL error DMEC

Error message Out of transaction records for complete phase (increase

SharedGlobalMemory)

Error code 279

MySQL error DMEC

Error message Out of transaction markers in TC, increase SharedGlobalMemory

Error code 2810

MySQL error DMEC

Error message No space left on the device

Error code 2811

MySQL error DMEC

Error message Error with file permissions, please check file system

Error message Error in reading files, please check file system

Error code 288

MySQL error DMEC

Error message Out of index operations in transaction coordinator (increase

SharedGlobalMemory)

Error code 289

MySQL error DMEC

Error message Out of transaction buffer memory in TC (increase

SharedGlobalMemory)

Error code 291

MySQL error DMEC

Error message Out of scanfrag records in TC (increase SharedGlobalMemory)

Error code 293

MySQL error DMEC

Error message Out of attribute buffers in TC block, increase SharedGlobalMemory

Error code 312

MySQL error DMEC

Error message Out of LongMessageBuffer

Error code 4021

MySQL error DMEC

Error message Out of Send Buffer space in NDB API

Error code 4022

MySQL error DMEC

Error message Out of Send Buffer space in NDB API

Error code 4032

MySQL error DMEC

Error message Out of Send Buffer space in NDB API

Error code 414

MySQL error DMEC

Error message 414

MySQL error DMEC

Error message Out of transaction buffers in LQH, increase LongSignalMemory

Error code 419

MySQL error DMEC

Error message Out of signal memory, increase LongSignalMemory

Error code 488

MySQL error DMEC

Error message Too many active scans

Error code 489

MySQL error DMEC

Error message Out of scan records in LQH, increase SharedGlobalMemory

Error code 490

MySQL error DMEC

Error message Too many active scans

Error code 748

MySQL error DMEC

Error message Busy during read of event table

Error code 780

MySQL error DMEC

Error message Too many schema transactions

Error code 783

MySQL error DMEC

Error message Too many schema operations

Error code 784

MySQL error DMEC

Error message Invalid schema transaction state

Error code 785

MySQL error DMEC

Error message Schema object is busy with another schema transaction

Error message Missing schema operation at takeover of schema transaction

Error code 805

MySQL error DMEC

Error message Out of attrinfo records in tuple manager, increase LongSignalMemory

Error code 830

MySQL error DMEC

Error message Out of add fragment operation records

Error code 873

MySQL error DMEC

Error message Out of transaction memory in local data manager, ordered index data

(increase SharedGlobalMemory)

Error code 899

MySQL error DMEC

Error message Rowid already allocated

Error code 909

MySQL error DMEC

Error message Out of transaction memory in local data manager, ordered scan

operation (increase SharedGlobalMemory)

Error code 915

MySQL error DMEC

Error message No free index stats op

Error code 918

MySQL error DMEC

Error message Cannot prepare index stats update

Error code 919

MySQL error DMEC

Error message Cannot execute index stats update

Error code 921

MySQL error DMEC

Error message Out of transaction memory in local data manager, copy tuples (increase

SharedGlobalMemory)

MySQL error DMEC

Error message Out of UNDO buffer memory (increase UNDO_BUFFER_SIZE)

Error code 924

MySQL error DMEC

Error message Out of transaction memory in local data manager, stored procedure

record (increase SharedGlobalMemory)

Error code 925

MySQL error DMEC

Error message Out of transaction memory in local data manager, tup scan operation

(increase SharedGlobalMemory)

Error code 926

MySQL error DMEC

Error message Out of transaction memory in local data manager, acc scan operation

(increase SharedGlobalMemory)

2.4.2.11 Node Recovery error

The following list enumerates all NDB errors of type NR (Node Recovery error).

Error code 1204

MySQL error DMEC

Error message Temporary failure, distribution changed

Error code 1405

MySQL error DMEC

Error message Subscriber manager busy with node recovery

Error code 1427

MySQL error DMEC

Error message Api node died, when SUB_START_REQ reached node

Error code 20016

MySQL error DMEC

Error message Query aborted due to node failure

Error code 250

MySQL error DMEC

Error message Node where lock was held crashed, restart scan transaction

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4002

MySQL error DMEC

Error message Send to NDB failed

Error code 4007

MySQL error DMEC

Error message Send to ndbd node failed

Error code 4010

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4013

MySQL error DMEC

Error message Request timed out in waiting for node failure

Error code 4025

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4027

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4028

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4029

MySQL error DMEC

Error message Node failure caused abort of transaction

Error code 4031

MySQL error DMEC

Error message Node failure caused abort of transaction

MySQL error DMEC

Error message Send to NDB failed

Error code 4035

MySQL error DMEC

Error message Cluster temporary unavailable

Error code 4115

MySQL error DMEC

Error message Transaction was committed but all read information was not received

due to node crash

Error code 4119

MySQL error DMEC

Error message Simple/dirty read failed due to node failure

Error code 499

MySQL error DMEC

Error message Scan take over error, restart scan transaction

Error code 631

MySQL error DMEC

Error message Scan take over error, restart scan transaction

Error code 786

MySQL error DMEC

Error message Schema transaction aborted due to node-failure

2.4.2.12 Overload error

The following list enumerates all NDB errors of type OL (Overload error).

Error code 1221

MySQL error DMEC

Error message REDO buffers overloaded (increase RedoBuffer)

Error code 1518

MySQL error DMEC

Error message IO overload error

Error message Connect failure - out of connection objects (increase

MaxNoOfConcurrentTransactions)

Error code 410

MySQL error DMEC

Error message REDO log files overloaded (decrease TimeBetweenLocalCheckpoints or

increase NoOfFragmentLogFiles)

Error code 677

MySQL error DMEC

Error message Index UNDO buffers overloaded (increase UndoIndexBuffer)

Error code 701

MySQL error DMEC

Error message System busy with other schema operation

Error code 711

MySQL error DMEC

Error message System busy with node restart, schema operations not allowed

Error code 891

MySQL error DMEC

Error message Data UNDO buffers overloaded (increase UndoDataBuffer)

2.4.2.13 Timeout expired

The following list enumerates all NDB errors of type TO (Timeout expired).

Error code 237

MySQL error HA_ERR_LOCK_WAIT_TIMEOUT

Error message Transaction had timed out when trying to commit it

Error code 266

MySQL error HA_ERR_LOCK_WAIT_TIMEOUT

Error message Time-out in NDB, probably caused by deadlock

Error code 4351

MySQL error DMEC

Error message Timeout/deadlock during index build

Error message Time-out due to node shutdown not starting in time

Error code 5025

MySQL error DMEC

Error message Time-out due to node shutdown not completing in time

2.4.2.14 Node shutdown

The following list enumerates all NDB errors of type NS (Node shutdown).

Error code 1223

MySQL error DMEC

Error message Read operation aborted due to node shutdown

Error code 270

MySQL error DMEC

Error message Transaction aborted due to node shutdown

Error code 280

MySQL error DMEC

Error message Transaction aborted due to node shutdown

Error code 4023

MySQL error DMEC

Error message Transaction aborted due to node shutdown

Error code 4030

MySQL error DMEC

Error message Transaction aborted due to node shutdown

Error code 4034

MySQL error DMEC

Error message Transaction aborted due to node shutdown

2.4.2.15 Internal temporary

The following list enumerates all NDB errors of type IT (Internal temporary).

Error code 1703

MySQL error DMEC

Error message Node failure handling not completed

MySQL error DMEC

Error message Not ready for connection allocation yet

Error code 702

MySQL error DMEC

Error message Request to non-master

Error code 787

MySQL error DMEC

Error message Schema transaction aborted

2.4.2.16 Unknown result error

The following list enumerates all NDB errors of type UR (Unknown result error).

Error code 4008

MySQL error DMEC

Error message Receive from NDB failed

Error code 4009

MySQL error HA_ERR_NO_CONNECTION

Error message Cluster Failure

Error code 4012

MySQL error DMEC

Error message Request ndbd time-out, maybe due to high load or communication

problems

2.4.2.17 Internal error

The following list enumerates all NDB errors of type IE (Internal error).

Error code 1237

MySQL error DMEC

Error message LQHKEYREQ Protocol error

Error code 1300

MySQL error DMEC

Error message Undefined error

Error code 1301

Error message Backup issued to not master (reissue command to master)

Error code 1304

MySQL error DMEC

Error message Sequence failure

Error code 1305

MySQL error DMEC

Error message Backup definition not implemented

Error code 1307

MySQL error DMEC

Error message Encrypted backup is not supported by the data node/s

Error code 1322

MySQL error DMEC

Error message Backup already completed

Error code 1323

MySQL error DMEC

Error message 1323

Error code 1324

MySQL error DMEC

Error message Backup log buffer full

Error code 1325

MySQL error DMEC

Error message File or scan error

Error code 1326

MySQL error DMEC

Error message Backup aborted due to node failure

Error code 1327

MySQL error DMEC

Error message 1327

Error code 1340

MySQL error DMEC

Error message Backup undefined error

MySQL error DMEC

Error message No replica to scan on this node (internal index stats error)

Error code 1429

MySQL error DMEC

Error message Subscriber node undefined in SubStartReq (config change?)

Error code 1502

MySQL error DMEC

Error message Filegroup already exists

Error code 1505

MySQL error DMEC

Error message Invalid filegroup

Error code 1506

MySQL error DMEC

Error message Invalid filegroup version

Error code 1507

MySQL error DMEC

Error message File no already inuse

Error code 1510

MySQL error DMEC

Error message File meta data error

Error code 1511

MySQL error DMEC

Error message Out of memory

Error code 1513

MySQL error DMEC

Error message Filegroup not online

Error code 1700

MySQL error DMEC

Error message Undefined error

Error message Query aborted due to empty query tree

Error code 20002

MySQL error DMEC

Error message Query aborted due to invalid request

Error code 20003

MySQL error DMEC

Error message Query aborted due to unknown query operation

Error code 20004

MySQL error DMEC

Error message Query aborted due to invalid tree node specification

Error code 20005

MySQL error DMEC

Error message Query aborted due to invalid tree parameter specification

Error code 20007

MySQL error DMEC

Error message Query aborted due to invalid pattern

Error code 20009

MySQL error DMEC

Error message Query aborted due to query node too big

Error code 20010

MySQL error DMEC

Error message Query aborted due to query node parameters too big

Error code 20011

MySQL error DMEC

Error message Query aborted due to both tree and parameters contain interpreted

program

Error code 20012

MySQL error DMEC

Error message Query aborted due to invalid tree parameter specification: Key

parameter bits mismatch

MySQL error DMEC

Error message Query aborted due to invalid tree parameter specification: Incorrect key

parameter count

Error code 20014

MySQL error DMEC

Error message Query aborted due to internal error

Error code 20017

MySQL error DMEC

Error message Query aborted due to invalid node count

Error code 20018

MySQL error DMEC

Error message Query aborted due to index fragment not found

Error code 202

MySQL error DMEC

Error message 202

Error code 203

MySQL error DMEC

Error message 203

Error code 207

MySQL error DMEC

Error message 207

Error code 208

MySQL error DMEC

Error message 208

Error code 209

MySQL error DMEC

Error message Communication problem, signal error

Error code 21021

MySQL error DMEC

Error message Create foreign key failed in NDB - invalid request

MySQL error DMEC

Error message Create foreign key failed in NDB - object already exists in TC

Error code 21031

MySQL error DMEC

Error message Create foreign key failed in NDB - no more object records in TC

Error code 21032

MySQL error DMEC

Error message Create foreign key failed in NDB - invalid request to TC

Error code 220

MySQL error DMEC

Error message 220

Error code 230

MySQL error DMEC

Error message 230

Error code 232

MySQL error DMEC

Error message 232

Error code 238

MySQL error DMEC

Error message 238

Error code 240

MySQL error DMEC

Error message Invalid data encountered during foreign key trigger execution

Error code 271

MySQL error DMEC

Error message Simple Read transaction without any attributes to read

Error code 272

MySQL error DMEC

Error message Update operation without any attributes to update

MySQL error DMEC

Error message 276

Error code 277

MySQL error DMEC

Error message 277

Error code 278

MySQL error DMEC

Error message 278

Error code 287

MySQL error DMEC

Error message Index corrupted

Error code 290

MySQL error DMEC

Error message Corrupt key in TC, unable to xfrm

Error code 292

MySQL error DMEC

Error message Inconsistent index state in TC block

Error code 294

MySQL error DMEC

Error message Unlocked operation has out of range index

Error code 295

MySQL error DMEC

Error message Unlocked operation has invalid state

Error code 298

MySQL error DMEC

Error message Invalid distribution key

Error code 306

MySQL error DMEC

Error message Out of fragment records in DIH

Error message MEMORY ALLOCATION ERROR

Error code 4001

MySQL error DMEC

Error message Signal Definition Error

Error code 4005

MySQL error DMEC

Error message Internal Error in NdbApi

Error code 4011

MySQL error DMEC

Error message Internal Error in NdbApi

Error code 4107

MySQL error DMEC

Error message Simple Transaction and Not Start

Error code 4108

MySQL error DMEC

Error message Faulty operation type

Error code 4109

MySQL error DMEC

Error message Faulty primary key attribute length

Error code 4110

MySQL error DMEC

Error message Faulty length in ATTRINFO signal

Error code 4111

MySQL error DMEC

Error message Status Error in NdbConnection

Error code 4113

MySQL error DMEC

Error message Too many operations received

Error code 416

Error message Bad state handling unlock request

Error code 4263

MySQL error DMEC

Error message Invalid blob attributes or invalid blob parts table

Error code 4267

MySQL error DMEC

Error message Corrupted blob value

Error code 4268

MySQL error DMEC

Error message Error in blob head update forced rollback of transaction

Error code 4269

MySQL error DMEC

Error message No connection to ndb management server

Error code 4270

MySQL error DMEC

Error message Unknown blob error

Error code 4273

MySQL error DMEC

Error message No blob table in dict cache

Error code 4274

MySQL error DMEC

Error message Corrupted main table PK in blob operation

Error code 4320

MySQL error DMEC

Error message Cannot use the same object twice to create table

Error code 4321

MySQL error DMEC

Error message Trying to start two schema transactions

Error code 4344

MySQL error DMEC

Error message Only DBDICT and TRIX can send requests to TRIX

MySQL error DMEC

Error message TRIX block is not available yet, probably due to node failure

Error code 4346

MySQL error DMEC

Error message Internal error at index create/build

Error code 4347

MySQL error DMEC

Error message Bad state at alter index

Error code 4348

MySQL error DMEC

Error message Inconsistency detected at alter index

Error code 4349

MySQL error DMEC

Error message Inconsistency detected at index usage

Error code 4350

MySQL error DMEC

Error message Transaction already aborted

Error code 4718

MySQL error DMEC

Error message Index stats samples data or memory cache is invalid

Error code 4719

MySQL error DMEC

Error message Index stats internal error

Error code 4721

MySQL error DMEC

Error message Mysqld: index stats thread not open for requests

Error code 4722

MySQL error DMEC

Error message Mysqld: index stats entry unexpectedly not found

MySQL error DMEC

Error message Event not found

Error code 632

MySQL error DMEC

Error message 632

Error code 706

MySQL error DMEC

Error message Inconsistency during table creation

Error code 749

MySQL error HA_WRONG_CREATE_OPTION

Error message Primary Table in wrong state

Error code 772

MySQL error HA_WRONG_CREATE_OPTION

Error message Given fragmentType doesn't exist

Error code 781

MySQL error DMEC

Error message Invalid schema transaction key from NDB API

Error code 782

MySQL error DMEC

Error message Invalid schema transaction id from NDB API

Error code 795

MySQL error DMEC

Error message Out of LongMessageBuffer in DICT

Error code 809

MySQL error DMEC

Error message 809

Error code 812

MySQL error DMEC

Error message 812

Error code 833

MySQL error DMEC

Error message 833

Error code 871

MySQL error DMEC

Error message 871

Error code 882

MySQL error DMEC

Error message 882

Error code 883

MySQL error DMEC

Error message 883

Error code 887

MySQL error DMEC

Error message 887

Error code 888

MySQL error DMEC

Error message 888

Error code 890

MySQL error DMEC

Error message 890

Error code 896

MySQL error DMEC

Error message Tuple corrupted - wrong checksum or column data in invalid format

Error code 901

MySQL error DMEC

Error message Inconsistent ordered index. The index needs to be dropped and

recreated

Error code 914

MySQL error DMEC

Error message Invalid index stats request

Error code 916

MySQL error DMEC

Error message Invalid index stats sys tables

Error code 917

DMEC MySQL error

Error message Invalid index stats sys tables data

2.4.2.18 Function not implemented

The following list enumerates all NDB errors of type NI (Function not implemented).

Error code 4003

MySQL error **DMEC**

Error message Function not implemented yet

Error code 797

MySQL error **DMEC**

Wrong fragment count for fully replicated table Error message

2.4.3 NDB Error Codes: Single Listing

This section lists all NDB errors, ordered by NDB error code. Each listing also includes the error's NDB error type, the corresponding MySQL Server error, and the text of the error message.

// "Outer joined scans need FirstInner/Upper to

MySQL error.

NDB error type. Error type not found be specified"

Error message.

MySQL error. 0

> NDB error type. No error

Error message. No error

MySQL error. 1204 **DMEC**

> Node Recovery error NDB error type.

Error message. Temporary failure, distribution

changed

1217 MySQL error.

> NDB error type. Temporary Resource error

Error message. Out of operation records in local data

manager (increase SharedGlobalMemory)

1218 MySQL error. **DMEC**

> NDB error type. Temporary Resource error

	Error message.	Send Buffers overloaded in NDB kernel
1220	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. FragmentLogFi	REDO log files overloaded (increase leSize)
1221	MySQL error.	DMEC
	NDB error type.	Overload error
	Error message. RedoBuffer)	REDO buffers overloaded (increase
1222	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. increase Shar	Out of transaction markers in LQH, edGlobalMemory
1223	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Read operation aborted due to node
1224	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Too many fragments
1225	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. handler	Table not defined in local query
1226	MySQL error.	HA_ERR_NO_SUCH_TABLE
	NDB error type.	Schema error
	Error message.	Table is being dropped
1227	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Invalid schema version
1228	MySQL error.	DMEC
	NDB error type.	Schema error

	Error message.	Cannot use drop table for drop index
1229	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Too long frm data supplied
1231	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid table or index to scan
1232	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid table or index to scan
1233	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Table read-only
1234	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. disk hardware	
1237	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	LQHKEYREQ Protocol error
1300	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Undefined error
1301	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	
1302	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	A backup is already running
1303	MySQL error.	DMEC

	NDB error type.	Insufficient space
	Error message.	Out of resources
1304	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Sequence failure
1305	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Backup definition not implemented
1306	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (change Diskle	
1307	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. the data node,	
1308	MySQL error.	DMEC
	NDB error type.	Configuration or application error
	Error message. encryption but	Data node/s configured to have t password not provided
1309	MySQL error.	DMEC
	NDB error type.	Configuration or application error
	_	Encryption password has bad character/START BACKUP')
1310	MySQL error.	DMEC
	NDB error type.	Configuration or application error
	Error message. 'HELP START BA	Encryption password is too long (see ACKUP')
1311	MySQL error.	DMEC
	NDB error type.	Configuration or application error
	Error message.	Encryption password is of zero length
1321	MySQL error.	DMEC

	NDB error type.	User defined error
	Error message.	Backup aborted by user request
1322	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Backup already completed
1323	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	1323
1324	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Backup log buffer full
1325	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	File or scan error
1326	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Backup aborted due to node failure
1327	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	1327
1329	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. supported	Backup during software upgrade not
1340	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Backup undefined error
1342	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check config	

1343	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to setup fs buffers aration)
1344	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to allocate tables aration)
1345	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to insert file header aration)
1346	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to insert table list
1347	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to allocate table memory aration)
1348	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. (check configu	Backup failed to allocate file record aration)
1349	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. record (check	Backup failed to allocate attribute configuration)
1350	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. (use 'START BA	Backup failed: file already exists ACKUP <backup id="">')</backup>
1405	MySQL error.	DMEC
	NDB error type.	Node Recovery error

	Error message. recovery	Subscriber manager busy with node
1407	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Subscription not found in subscriber
1411	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. removing a sub	Subscriber manager busy with adding/
1412	MySQL error.	DMEC
	NDB error type.	Insufficient space
	Error message. space in pool	Can't accept more subscribers, out of
1413	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. the subscripti	Subscriber manager busy with adding on
1414	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. this subscript	Subscriber manager has subscribers on ion
1415	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Subscription not unique in subscriber
1416	MySQL error.	DMEC
	NDB error type.	Insufficient space
	Error message. of space in po	Can't accept more subscriptions, out ol
1417	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. probably dropp	Table in suscription not defined, ed

1418	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. subscribers a	
1419	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Subscription already dropped
1420	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. removing a ta	
1421	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. NdbOperation:	
1422	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of subscription records
1423	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of table records in SUMA
1424	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of MaxNoOfConcurrentSubOperations
1425	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. trying to sto	Subscription being definedwhile op subscriber
1426	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	No such subscriber
1427	MySQL error.	DMEC

	NDB error type.	Node Recovery error
	Error message. reached node	Api node died, when SUB_START_REQ
1428	MySQL error.	DMEC
	NDB error type.	Internal error
	_	No replica to scan on this node x stats error)
1429	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. SubStartReq (c	
1501	MySQL error. D	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of undo space
1502	MySQL error. D	DMEC
	NDB error type.	Internal error
	Error message.	Filegroup already exists
1503	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of filegroup records
1504	MySQL error.	DMEC
	NDB error type.	Schema error
	•	Out of logbuffer memory(specify ouffer_size or increase emory)
1505	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Invalid filegroup
1506	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Invalid filegroup version
1507	MySQL error.	DMEC

	NDB error type.	Internal error
	Error message.	File no already inuse
1508	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of file records
1509	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. path,permission	File system error, check if ons etc
1510	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	File meta data error
1511	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Out of memory
1512	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	File read error
1513	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Filegroup not online
1514	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. logfile group	Currently there is a limit of one
1515	MySQL error.	DMEC
	NDB error type.	Schema error
		Currently there is a 4G limit of one e in 32-bit host
1516	MySQL error.	DMEC
	NDB error type.	Schema error

	Error message.	File too small
1517	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. Increase DiskP	Insufficient disk page buffer memory. PageBufferMemory or reduce data file
1518	MySQL error.	DMEC
	NDB error type.	Overload error
	Error message.	IO overload error
1601	MySQL error.	IA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message.	Out of extents, tablespace full
1602	MySQL error.	DMEC
	NDB error type.	Insufficient space
	Error message.	No datafile in tablespace
1603	MySQL error.	IA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
		Table fragment fixed data reference ximum possible value (specify MAXROWS of partitions)
1604	MySQL error.	DMEC
	NDB error type.	Insufficient space
	Error message.	Error -1 from get_page
1605	MySQL error.	IA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message. allocating dis	
1606	MySQL error.	IA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message. disk record	Out of extent records when allocating
1700	MySQL error.	DMEC
	NDB error type.	Internal error

	Error message.	Undefined error
1701	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Node already reserved
1702	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Node already connected
1703	MySQL error.	DMEC
	NDB error type.	Internal temporary
	Error message.	Node failure handling not completed
1704	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Node type mismatch
1705	MySQL error.	DMEC
	NDB error type.	Internal temporary
	Error message. yet	Not ready for connection allocation
20000	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. records	Query aborted due out of operation
20001	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to empty query tree
20002	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to invalid request
20003	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. operation	Query aborted due to unknown query

20004	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. specification	Query aborted due to invalid tree node
20005	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. parameter spec	Query aborted due to invalid tree
20006	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. LongMessageBuf	Query aborted due to out of fer
20007	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to invalid pattern
20008	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Query aborted due to out of query
20009	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to query node too
20010	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. parameters too	Query aborted due to query node big
20011	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. parameters con	Query aborted due to both tree and atain interpreted program

20012	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. parameter spe	Query aborted due to invalid tree cification: Key parameter bits mismatch
20013	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. parameter specount	Query aborted due to invalid tree cification: Incorrect key parameter
20014	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to internal error
20015	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Query aborted due to out of row memory
20016	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message.	Query aborted due to node failure
20017	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Query aborted due to invalid node
20018	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. not found	Query aborted due to index fragment
20019	MySQL error.	HA_ERR_NO_SUCH_TABLE
	NDB error type.	Schema error
	Error message.	Query table not defined
20020	MySQL error.	HA_ERR_NO_SUCH_TABLE
	NDB error type.	Schema error
	Error message.	Query table is being dropped
20021	MySQL error.	HA_ERR_TABLE_DEF_CHANGED

	NDB error type.	Schema error
	Error message.	Query table definition has changed
202	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	202
203	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	203
207	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	207
208	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	208
209	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	Communication problem, signal error
21000	MySQL error.	A_ERR_CANNOT_ADD_FOREIGN
	NDB error type.	Application error
	Error message. is primary key	Create foreign key failed - parent key and on-update-cascade is not allowed
21020	MySQL error.	MEC
	NDB error type.	Temporary Resource error
	Error message. more object re	
21021	MySQL error.	MEC
	NDB error type.	Internal error
	Error message. invalid reques	
21022	MySQL error.	MEC
	NDB error type.	Schema error

	Error message. Create foreign key failed in NDB - parent table is not table
21023	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - invalid parent table version
21024	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - child table is not table
21025	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - invalid child table version
21026	MySQL error. HA_ERR_CANNOT_ADD_FOREIGN
	NDB error type. Application error
	Error message. Create foreign key failed in NDB - parent index is not unique index
21027	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - invalid parent index version
21028	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - child index is not index
21029	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Create foreign key failed in NDB - invalid child index version
21030	MySQL error. DMEC
	NDB error type. Internal error
	Error message. Create foreign key failed in NDB - object already exists in TC

21031	MySQL error. DMEC
	NDB error type. Internal error
	Error message. Create foreign key failed in NDB - no more object records in TC
21032	MySQL error. DMEC
	NDB error type. Internal error
	Error message. Create foreign key failed in NDB - invalid request to TC
21033	MySQL error. HA_ERR_CANNOT_ADD_FOREIGN
	NDB error type. Application error
	Error message. Create foreign key failed in NDB - No parent row found
21034	MySQL error. HA_ERR_CANNOT_ADD_FOREIGN
	NDB error type. Application error
	Error message. Create foreign key failed - child table has Blob or Text column and on-delete-cascade is not allowed
21040	MySQL error. DMEC
	NDB error type. Application error
	Error message. Drop foreign key failed in NDB - foreign key not found
21041	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Drop foreign key failed in NDB - invalid foreign key version
21042	MySQL error. DMEC
	NDB error type. Schema error
	Error message. Drop foreign key failed in NDB - foreign key not found in TC
	MySQL error. DMEC
21060	11,042 011011 21120
21060	NDB error type. Application error
21060	

	NDB error type. Schema error
	Error message. Build foreign key failed in NDB - invalid foreign key version
21080	MySQL error. HA_ERR_ROW_IS_REFERENCED
	NDB error type. Application error
	Error message. Drop table not allowed in NDB - referenced by foreign key on another table
21081	MySQL error. HA_ERR_DROP_INDEX_FK
	NDB error type. Application error
	Error message. Drop index not allowed in NDB - used as parent index of a foreign key
21082	MySQL error. HA_ERR_DROP_INDEX_FK
	NDB error type. Application error
	Error message. Drop index not allowed in NDB - used as child index of a foreign key
21090	MySQL error. HA_ERR_CANNOT_ADD_FOREIGN
	NDB error type. Application error
	<pre>Error message. Create foreign key failed in NDB - name contains invalid character (/)</pre>
217	MySQL error. DMEC
	NDB error type. Temporary Resource error
	Error message. 217
218	MySQL error. DMEC
	NDB error type. Temporary Resource error
	Error message. Out of LongMessageBuffer
219	MySQL error. DMEC
	NDB error type. Temporary Resource error
	Error message. 219
220	MySQL error. DMEC
	NDB error type. Internal error
	Error message. 220
221	MySQL error. DMEC

	NDB error type.	Temporary Resource error
	Error message. increase Share	Too many concurrently fired triggers, dGlobalMemory
230	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	230
232	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	232
233	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. transaction co	Out of operation records in ordinator (increase SharedGlobalMemory)
237	MySQL error.	IA_ERR_LOCK_WAIT_TIMEOUT
	NDB error type.	Timeout expired
	Error message. to commit it	Transaction had timed out when trying
238	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	238
240	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. foreign key tr	Invalid data encountered during igger execution
241	MySQL error.	IA_ERR_TABLE_DEF_CHANGED
	NDB error type.	Schema error
	Error message.	Invalid schema object version
242	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Zero concurrency in scan
244	MySQL error.	DMEC
	NDB error type.	Application error

Error me	ssage. Too high concurrency in scan
245 MySQL e	rror. DMEC
NDB erro	r type. Temporary Resource error
Error me MaxNoOf	ssage. Too many active scans, increase ConcurrentScans
250 MySQL e	rror. DMEC
NDB erro	r type. Node Recovery error
	ssage. Node where lock was held crashed, scan transaction
251 MySQL e	rror. DMEC
NDB erro	r type. Temporary Resource error
Error me	ssage. Out of frag location records in TC se SharedGlobalMemory)
255 MySQL e	rror. HA_ERR_NO_REFERENCED_ROW
NDB erro	r type. Constraint violation
	ssage. Foreign key constraint violated: No row found
256 MySQL e	rror. HA_ERR_ROW_IS_REFERENCED
NDB erro	r type. Constraint violation
	ssage. Foreign key constraint violated: ced row exists
261 MySQL e	rror. DMEC
NDB erro	r type. Application error
config	ssage. DML count in transaction exceeds parameter MaxDMLOperationsPerTransaction/ConcurrentOperations
266 MySQL e	rror. HA_ERR_LOCK_WAIT_TIMEOUT
NDB erro	r type. Timeout expired
Error medeadloc	
269 MySQL e	rror. DMEC
NDB erro	r type. Application error
Error me	ssage. No condition and attributes to read in

270	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Transaction aborted due to node
271	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. attributes to	
272	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. attributes to	
273	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. in TC, increas	Out of transaction markers databuffer se SharedGlobalMemory
275	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of transaction records for (increase SharedGlobalMemory)
276	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	276
277	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	277
278	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	278
279	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. increase Share	

280	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Transaction aborted due to node
281	MySQL error.	HA_ERR_NO_CONNECTION
	NDB error type.	Application error
	Error message. shutdown in pr	
2810	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	No space left on the device
2811	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. check file sys	
2815	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
		•
	Error message. file system	• •
283	file system	• •
283	file system	Error in reading files, please check
283	file system MySQL error.	Error in reading files, please check HA_ERR_NO_SUCH_TABLE
283	MySQL error. NDB error type. Error message.	Error in reading files, please check HA_ERR_NO_SUCH_TABLE Schema error
	MySQL error. NDB error type. Error message.	Error in reading files, please check HA_ERR_NO_SUCH_TABLE Schema error Table is being dropped
	MySQL error. NDB error type. Error message. MySQL error.	Error in reading files, please check HA_ERR_NO_SUCH_TABLE Schema error Table is being dropped HA_ERR_TABLE_DEF_CHANGED
	MySQL error. NDB error type. Error message. MySQL error. NDB error type. Error message. coordinator	Error in reading files, please check HA_ERR_NO_SUCH_TABLE Schema error Table is being dropped HA_ERR_TABLE_DEF_CHANGED Schema error
284	MySQL error. NDB error type. Error message. MySQL error. NDB error type. Error message. coordinator	Error in reading files, please check HA_ERR_NO_SUCH_TABLE Schema error Table is being dropped HA_ERR_TABLE_DEF_CHANGED Schema error Table not defined in transaction

286	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
287	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Index corrupted
288	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of index operations in transaction increase SharedGlobalMemory)
289	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. (increase Shar	Out of transaction buffer memory in TC redGlobalMemory)
290	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Corrupt key in TC, unable to xfrm
291	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. (increase Shar	Out of scanfrag records in TC redGlobalMemory)
292	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Inconsistent index state in TC block
293	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. increase Share	Out of attribute buffers in TC block, edGlobalMemory
294	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. index	Unlocked operation has out of range

295	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Unlocked operation has invalid state
298	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Invalid distribution key
299	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. to single use	Operation not allowed or aborted due r mode
306	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Out of fragment records in DIH
311	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. setPartitionI	Undefined partition used in d
312	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of LongMessageBuffer
320	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. nodegroup	Invalid no of nodes specified for new
321	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid nodegroup id
322	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. nodegroup, no	Invalid node(s) specified for new de already in nodegroup
323	MySQL error.	DMEC

	NDB error type.	Application error
	Error message. already existi	Invalid nodegroup id, nodegroup ng
324	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. nodegroup, no	Invalid node(s) specified for new node in nodegroup is started
325	MySQL error.	OMEC
	NDB error type.	Application error
	Error message. nodegroup, nod	Invalid node(s) specified for new e ID invalid or undefined
4000	MySQL error.	OMEC
	NDB error type.	Internal error
	Error message.	MEMORY ALLOCATION ERROR
4001	MySQL error.	OMEC
	NDB error type.	Internal error
	Error message.	Signal Definition Error
4002	MySQL error.	OMEC
	NDB error type.	Node Recovery error
	Error message.	Send to NDB failed
4003	MySQL error.	OMEC
	NDB error type.	Function not implemented
	Error message.	Function not implemented yet
4004	MySQL error.	OMEC
	NDB error type.	Application error
	Error message. table	Attribute name or id not found in the
4005	MySQL error.	OMEC
	NDB error type.	Internal error
	Error message.	Internal Error in NdbApi
4006	MySQL error.	DMEC
	NDB error type.	Overload error

	Error message.	Connect failure - out of connection rease MaxNoOfConcurrentTransactions)
4007	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message.	Send to ndbd node failed
4008	MySQL error.	DMEC
	NDB error type.	Unknown result error
	Error message.	Receive from NDB failed
4009	MySQL error.	HA_ERR_NO_CONNECTION
	NDB error type.	Unknown result error
	Error message.	Cluster Failure
4010	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4011	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Internal Error in NdbApi
4012	MySQL error.	DMEC
	NDB error type.	Unknown result error
	Error message. high load or	Request ndbd time-out, maybe due to communication problems
4013	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. failure	Request timed out in waiting for node
4021	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of Send Buffer space in NDB API
4022	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of Send Buffer space in NDB API

4023	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Transaction aborted due to node
4025	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4027	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4028	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4029	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4030	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Transaction aborted due to node
4031	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Node failure caused abort of
4032	MySQL error.	DMEC
	NDB error type.	Temporary Resource error

4033	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message.	Send to NDB failed
4034	MySQL error.	DMEC
	NDB error type.	Node shutdown
	Error message. shutdown	Transaction aborted due to node
4035	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message.	Cluster temporary unavailable
410	MySQL error.	DMEC
	NDB error type.	Overload error
		REDO log files overloaded eBetweenLocalCheckpoints or increase ogFiles)
4100	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Status Error in NDB
4101	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	No connections to NDB available and
4102	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Type in NdbTamper not correct
4103	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. and connect fa	No schema connections to NDB available ailed
4104	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. object and cre	Ndb Init in wrong state, destroy Ndb

4105	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Too many Ndb objects
4106	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. defined	All Not NULL attribute have not been
4107	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Simple Transaction and Not Start
4108	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Faulty operation type
4109	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Faulty primary key attribute length
4110	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Faulty length in ATTRINFO signal
4111	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Status Error in NdbConnection
4113	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Too many operations received
4114	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Transaction is already completed

4115	MySQL error. D	MEC
	NDB error type.	Node Recovery error
	Error message. information wa	Transaction was committed but all read s not received due to node crash
4116	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. probably missi	Operation was not defined correctly, ng a key
4117	MySQL error.	MEC
	NDB error type.	Application error
	Error message. configuration	Could not start transporter, error
4118	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Parameter error in API call
4119	MySQL error.	MEC
	NDB error type.	Node Recovery error
	Error message.	Simple/dirty read failed due to node
4120	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Scan already complete
4121	MySQL error.	MEC
	NDB error type.	Application error
	Error message. object	Cannot set name twice for an Ndb
4122	MySQL error.	MEC
	NDB error type.	Application error
	Error message. initialised	Cannot set name after Ndb object is

4123	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. range is 1-99	
414	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	414
416	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Bad state handling unlock request
417	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. unlock	Bad operation reference - double
418	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. increase Long	Out of transaction buffers in LQH, SignalMemory
419	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. LongSignalMem	
4200	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. operation	Status Error when defining an
4201	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Variable Arrays not yet supported
4202	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. not allowed	Set value on tuple key attribute is

4203	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trying to set a NOT NULL attribute to
4204	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. incompatible	Set value and Read/Delete Tuple is
4205	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	No Key attribute used to define tuple
4206	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. twice	Not allowed to equal key attribute
4207	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Key size is limited to 4092 bytes
4208	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trying to read a non-stored attribute
4209	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. incorrect	Length parameter in equal/setValue is
4210	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. specified	Ndb sent more info than the length he
4211	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. objects	Inconsistency in list of NdbRecAttr-

4212	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. attribute	Ndb reports NULL value on Not NULL
4213	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. received	Not all data of an attribute has been
4214	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Not all attributes have been received
4215	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. TCKEYCONF mess	More data received than reported in sage
4216	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	More than 8052 bytes in setValue
4217	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. other than uns	It is not allowed to increment any signed ints
4218	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NULL-able attr	
4219	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. attributes are	Maximum size of interpretative e 64 bits

4220	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. attributes ar	Maximum size of interpretative e 64 bits
4221	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trying to jump to a non-defined label
4222	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Label was not found, internal error
4223	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. yourself	Not allowed to create jumps to
4224	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. different sub	Not allowed to jump to a label in a routine
4225	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. setValue/getV	All primary keys defined, call alue
4226	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Bad number when defining a label
4227	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Bad number when defining a subroutine
4228	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. definition	Illegal interpreter function in scan
4229	MySQL error.	DMEC

	NDB error type.	Application error
	Error message. function defin	
4230	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. probably not a	
4231	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Illegal state when calling interpreter
4232	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. 240	Parallelism can only be between 1 and
4233	MySQL error.	DMEC
	NDB error type.	Application error
		Calling execute (synchronous) when red asynchronous transaction exists
4234	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Illegal to call setValue in this state
4235	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	No callback from execute
4236	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trigger name too long
4237	•	DMEC
	NDB error type.	
	Error message.	
4238	MySQL error.	DMEC

	NDB error type.	Application error
	Error message.	Trigger not found
4239	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trigger with given name already exists
4240	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Unsupported trigger type
4241	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Index name too long
4242	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Too many indexes
4243	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Index not found
4244	MySQL error.	HA_ERR_TABLE_EXIST
	NDB error type.	Schema object already exists
	Error message.	Index or table with given name already
4247	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. alter request	Illegal index/trigger create/drop/
4248	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Trigger/index name invalid
4249	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid table

4250	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. option	Invalid index type or index logging
4251	MySQL error.	HA_ERR_FOUND_DUPP_UNIQUE
	NDB error type.	Application error
	Error message. keys found	Cannot create unique index, duplicate
4252	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Failed to allocate space for index
4253	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Failed to create index table
4254	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Table not an index table
4255	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. specified in	Hash index attributes must be same order as table attributes
4256	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. function	Must call Ndb::init() before this
4257	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. getValue call	Tried to read too much - too many s
4258	MySQL error.	DMEC
	NDB error type.	Application error
	_	Cannot create unique index, duplicate und in definition

4259	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid set of range scan bounds
4260	MySQL error.	DMEC
	NDB error type.	User defined error
	Error message. in NdbScanFilt	NdbScanFilter: Operator is not defined er::Group
4261	MySQL error.	DMEC
	NDB error type.	User defined error
	Error message.	NdbScanFilter: Column is NULL
4262	MySQL error.	DMEC
	NDB error type.	User defined error
	Error message.	NdbScanFilter: Condition is out of
4263	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. blob parts tab	Invalid blob attributes or invalid ble
4264	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid usage of blob attribute
4265	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. blob state	The method is not valid in current
4266	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid blob seek position
4267	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Corrupted blob value
4268	MySQL error.	DMEC

	NDB error type.	Internal error
	Error message. rollback of tr	
4269	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	No connection to ndb management server
4270	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Unknown blob error
4271	MySQL error.	DMEC
	NDB error type.	Application error
	<pre>Error message. via getIndex()</pre>	Invalid index object, not retrieved
4272	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Table definition has undefined column
4273	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	No blob table in dict cache
4274	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. operation	Corrupted main table PK in blob
4275	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. operation type	
4276	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Missing NULL ptr in end of keyData
4277	MySQL error.	DMEC

	NDB error type.	Application error
	Error message.	Key part len is to small for column
4278	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Supplied buffer to small
4279	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Malformed string
4280	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Inconsistent key part length
4281	MySQL error.	MEC
	NDB error type.	Application error
	Error message. in scanIndex	Too many keys specified for key bound
4282	MySQL error.	MEC
	NDB error type.	Application error
	Error message. ordered multi-	range_no not strictly increasing in range index scan
4283	MySQL error.	MEC
	NDB error type.	Application error
	Error message. index ndbrecor	key_record in index scan is not an d
4284	MySQL error.	MEC
	NDB error type.	Application error
	Error message. methods in one	
4285	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	NULL NdbRecord pointer
4286	MySQL error.	MEC
	NDB error type.	Application error

	Error message.	<pre>Invalid range_no (must be < 4096)</pre>
4287	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. primary key op	The key_record and attribute_record in peration do not belong to the same table
4288	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Blob handle for column not available
4289	MySQL error.	DMEC
	NDB error type.	Application error
		API version mismatch or wrong ionary::RecordSpecification)
4290	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbDictionary:	Missing column specification in RecordSpecification
4291	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbDictionary:	Duplicate column specification in RecordSpecification
4292	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. index key NdbR	NdbRecord for tuple access is not an Record
4293	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. scanIndex() ca	
4294	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Scan filter is too large, discarded
4295	MySQL error.	DMEC
	NDB error type.	Application error

	Error message. structure	Column is NULL in Get/SetValueSpec
4296	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid AbortOption
4297	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. OperationOptic	Invalid or unsupported ons structure
4298	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. structure	Invalid or unsupported ScanOptions
4299	MySQL error.	DMEC
	NDB error type.	Application error
	_	Incorrect combination of ScanOption etValues ptr and numExtraGetValues
4300	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Tuple Key Type not correct
4301	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Fragment Type not correct
4302	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Minimum Load Factor not correct
4303	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Maximum Load Factor not correct

4304	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. Minimum	Maximum Load Factor smaller than
4305	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	K value must currently be set to 6
4306	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Memory Type not correct
4307	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid table name
4308	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Attribute Size not correct
4309	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. bytes	Fixed array too large, maximum 64000
4310	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Attribute Type not correct
4311	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Storage Mode not correct
4312	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Null Attribute Type not correct
4313	MySQL error.	DMEC
	NDB error type.	Application error

	Error message. attribute	Index only storage for non-key
4314	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Storage Type of attribute not correct
4315	MySQL error.	DMEC
	NDB error type.	Application error
	_	No more key attributes allowed after able length key attribute
4316	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NULL attribute	Key attributes are not allowed to be es
4317	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Too many primary keys defined in table
4318	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Invalid attribute name or number
4319	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	createAttribute called at erroneus
4320	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. create table	Cannot use the same object twice to
4321	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. transactions	Trying to start two schema
4322	MySQL error.	DMEC
	NDB error type.	Application error

	Error message. when not prepa	Attempt to define distribution key red to
4323	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. defined on fir	Distribution Key set on table but not st attribute
4324	MySQL error.	OMEC
	NDB error type.	Application error
	Error message. when not prepa	Attempt to define distribution group red to
4325	MySQL error.	DMEC
	NDB error type.	Application error
		Distribution Group set on table but first attribute
4326	MySQL error. D	OMEC
	NDB error type.	Application error
	Error message. number of bits	
4327	MySQL error. D	OMEC
	NDB error type.	Application error
	Error message. part of primar	Distribution key is only supported on y key
4328	MySQL error. D	OMEC
	NDB error type.	Application error
	Error message. supported	Disk memory attributes not yet
4329	MySQL error. D	OMEC
	NDB error type.	Application error
	Error message. supported	Variable stored attributes not yet
4335	MySQL error.	OMEC
	NDB error type.	Application error
	Error message. per table. Hav	Only one autoincrement column allowed ing a table without primary key uses

		ented hidden key, i.e. a table without a in not have an autoincremented column
4340	MySQL error.	DMEC
	NDB error type.	Application error
		Result or attribute record must be a precord, not an index ndbrecord
4341	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. SF_OrderBy	Not all keys read when using option
4342	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Scan defined but not prepared
4343	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Table with blobs does not support
4344	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Only DBDICT and TRIX can send requests
4345	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. probably due t	TRIX block is not available yet, o node failure
4346	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Internal error at index create/build
4347	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Bad state at alter index
4348	MySQL error.	DMEC
	NDB error type.	Internal error

	Error message.	Inconsistency detected at alter index
4349	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Inconsistency detected at index usage
4350	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Transaction already aborted
4351	MySQL error.	DMEC
	NDB error type.	Timeout expired
	Error message.	Timeout/deadlock during index build
4377	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. on Ndb object	Database and schema name must be set
4400	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Status Error in NdbSchemaCon
4401	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. transaction	Only one schema operation per schema
4402	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. calling execut	No schema operation defined before te
4410	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Schema transaction is already started
4411	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. upgrade comple	Schema transaction not possible until

4412	MySQL error.	OMEC
	NDB error type.	Application error
	Error message.	Schema transaction is not started
4501	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. getting table	Insert in hash table failed when information from Ndb
4502	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. operation	GetValue not allowed in Update
4503	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. operation	GetValue not allowed in Insert
4504	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	SetValue not allowed in Read operation
4505	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. search	NULL value not allowed in primary key
4506	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Missing getValue/setValue when calling
4507	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Missing operation request when calling

4508	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. defined operat	GetValue not allowed for NdbRecord
4509	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. more than one	Non SF_MultiRange scan cannot have bound
4510	MySQL error.	DMEC
	NDB error type.	Application error
		User specified partition id not can takeover operation
4511	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. result record	Blobs not allowed in NdbRecord delete
4512	MySQL error.	DMEC
	NDB error type.	Application error
		Incorrect combination of ons optionsPresent, extraGet/SetValues traGet/SetValues
4513	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbRecord set!	Only one scan bound allowed for non- Bound() API
4514	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbIndexScanOp	Can only call setBound/equal() for an peration
4515	MySQL error.	DMEC
	NDB error type.	Application error
		Method not allowed for NdbRecord, use ons or ScanOptions structure instead
4516	MySQL error.	DMEC

	NDB error type.	Application error
	Error message. program	Illegal instruction in interpreted
4517	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Bad label in branch instruction
4518	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. program	Too many instructions in interpreted
4519	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. called	NdbInterpretedCode::finalise() not
4520	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Call to undefined subroutine
4521	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Call to undefined subroutine, internal
4522	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	setBound() called twice for same key
4523	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbRecord	Pseudo columns not supported by
4524	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	NdbInterpretedCode is for different
4535	MySQL error.	DMEC

	NDB error type.	Application error
	Error message.	Attempt to set bound on non key column
4536	MySQL error.	DMEC
	NDB error type.	Application error
		NdbScanFilter constructor taking s not supported for NdbRecord
4537	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. NdbRecord oper	Wrong API. Use NdbInterpretedCode for ations
4538	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. requires that	NdbInterpretedCode instruction table is set
4539	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. operation type	NdbInterpretedCode not supported for
4540	MySQL error.	DMEC
	NDB error type.	Application error
	_	Attempt to pass an Index column to Use base table columns only
4542	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Unknown partition information type
4543	MySQL error.	OMEC
	NDB error type.	Application error
	Error message. supplied	Duplicate partitioning information
4544	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Wrong partitionInfo type for table
4545	MySQL error.	DMEC

NE	OB error type.	Application error
	ror message.	Invalid or Unsupported PartitionInfo
4546 My	/SQL error. DM	IEC
NE	OB error type.	Application error
	ror message.	Explicit partitioning info not allowed peration
4547 M y	/SQL error. DM	IEC
NE	OB error type.	Application error
	ror message.	RecordSpecification has overlapping
4548 My	/SQL error. DM	IEC
NE	OB error type.	Application error
	ror message.	RecordSpecification has too many
4549 My	/SQL error. DM	IEC
NE	OB error type.	Application error
	-	getLockHandle only supported for d with a lock
4550 My	/SQL error. DM	MEC
NC	OB error type.	Application error
	ror message. eration execu	Cannot releaseLockHandle until
4551 My	/SQL error. DM	MEC
NE	OB error type.	Application error
Eri	ror message.	NdbLockHandle already released
4552 My	/SQL error. DM	IEC
NE	OB error type.	Application error
	ror message.	NdbLockHandle does not belong to

4553	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. executed succe	NdbLockHandle original operation not essfully
4554	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	NdbBlob can only be closed from Active
4555	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	NdbBlob cannot be closed with pending
4556	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. in column_flag	RecordSpecification has illegal value
4557	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. comparing two	Column types must be identical when columns
4558	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. executed before	Pending Blob operations must be re this call
4600	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Transaction is already started
4601	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Transaction is not started

4602	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. executeScan	You must call getNdbOperation before
4603	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. scan transaction	There can only be ONE operation in a on
4604	MySQL error. D	MEC
	NDB error type.	Application error
	_	takeOverScanOp, to take over a scanned xplicitly request keyinfo on readTuples
4605	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. for each opera	You may only call readTuples() once tion
4607	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. scan transaction	There may only be one operation in a on
4608	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. have used open	You can not takeOverScan unless you ScanExclusive
4609	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. trying to take	You must call nextScanResult before OverScan
4707	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Too many event have been defined
4708	MySQL error. D	MEC
	NDB error type.	Application error

	Error message.	Event name is too long
4709	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Can't accept more subscribers
4710	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Event not found
4711	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Creation of event failed
4712	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. exist. Already	
4713	MySQL error. D	MEC
	NDB error type.	Schema error
	Error message. in table	Column defined in event does not exist
4714	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. NDB_INDEX_STAT	Index stats sys tables _PREFIX do not exist
4715	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Index stats for specified index do not
4716	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Index stats methods usage error
4717	MySQL error. D	MEC
	NDB error type.	Application error
	Error message.	Index stats cannot allocate memory

4718	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. cache is inval	Index stats samples data or memory
4719	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Index stats internal error
4720	MySQL error.	DMEC
	NDB error type.	Application error
	_	Index stats sys tables T_PREFIX partly missing or invalid
4721	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message. for requests	Mysqld: index stats thread not open
4722	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Mysqld: index stats entry unexpectedly
4723	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. due to recent	Mysqld: index stats request ignored error
4724	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. stats thread	Mysqld: index stats request aborted by
4725	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Index stats were deleted by another

4731	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Event not found
488	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Too many active scans
489	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. SharedGlobalM	
490	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Too many active scans
499	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Scan take over error, restart scan
5024	MySQL error.	DMEC
	NDB error type.	Timeout expired
	Error message. starting in t	
5025	MySQL error.	DMEC
	NDB error type.	Timeout expired
	Error message. completing in	
623	MySQL error.	HA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message.	623
624	MySQL error.	HA_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message.	624
625	MySQL error.	HA_ERR_INDEX_FILE_FULL

	NDB error type.	Insufficient space
	Error message. index part (in	Out of memory in Ndb Kernel, hash crease DataMemory)
626	MySQL error.	HA_ERR_KEY_NOT_FOUND
	NDB error type.	No data found
	Error message.	Tuple did not exist
630	MySQL error.	IA_ERR_FOUND_DUPP_KEY
	NDB error type.	Constraint violation
	Error message. to insert	Tuple already existed when attempting
631	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. transaction	Scan take over error, restart scan
632	MySQL error.	OMEC
	NDB error type.	Internal error
	Error message.	632
633	MySQL error.	IA_ERR_INDEX_FILE_FULL
	NDB error type.	Insufficient space
	Error message. maximum possib	
640	MySQL error.	OMEC
	NDB error type.	Insufficient space
	Error message. happen)	Too many hash indexes (should not
677	MySQL error.	DMEC
	NDB error type.	Overload error
	Error message. (increase Undo	Index UNDO buffers overloaded IndexBuffer)
701	MySQL error.	DMEC
	NDB error type.	Overload error
	Error message. operation	System busy with other schema

702	MySQL error.	DMEC
	NDB error type.	Internal temporary
	Error message.	Request to non-master
703	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid table format
704	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Attribute name too long
705	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Table name too long
706	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Inconsistency during table creation
707	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. (increase Max	
708	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. (increase Max	No more attribute metadata records xNoOfAttributes)
709	MySQL error.	HA_ERR_NO_SUCH_TABLE
	NDB error type.	Schema error
	Error message.	No such table existed
710	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. supported, us	-
711	MySQL error.	DMEC
	NDB error type.	Overload error

	essage. System busy with node restart, schema ions not allowed
712 MySQL	error. DMEC
NDB err	or type. Schema error
Error mo	essage. No more hashmap metadata records
720 MySQL	error. DMEC
NDB err	or type. Application error
Error me definit	essage. Attribute name reused in table tion
721 MySQL	error. HA_ERR_TABLE_EXIST
NDB err	or type. Schema object already exists
Error me exists	essage. Schema object with given name already
723 MySQL	error. HA_ERR_NO_SUCH_TABLE
NDB err	or type. Schema error
Error me	essage. No such table existed
736 MySQL 6	error. DMEC
NDB err	or type. Schema error
Error me	essage. Unsupported array size
737 MySQL	error. HA_WRONG_CREATE_OPTION
NDB err	or type. Schema error
Error me	essage. Attribute array size too big
738 MySQL	error. HA_WRONG_CREATE_OPTION
NDB err	or type. Schema error
Error me	essage. Record too big
739 MySQL (error. HA_WRONG_CREATE_OPTION
NDB err	or type. Schema error
Error me	essage. Unsupported primary key length
740 MySQL	error. HA_WRONG_CREATE_OPTION
NDB err	or type. Schema error
Error me	essage. Nullable primary key not supported

741	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Unsupported alter table
743	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message. index	Unsupported character set in table or
744	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. character set	_
745	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message. char attribut	Distribution key not supported for the (use binary attribute)
746	MySQL error.	DMEC
	NDB error type.	Schema object already exists
	Error message.	Event name already exists
747	MySQL error.	DMEC
	NDB error type.	Insufficient space
	Error message.	Out of event records
748	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Busy during read of event table
749	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Internal error
	Error message.	Primary Table in wrong state
750	MySQL error.	IE
	NDB error type.	Schema error
	Error message.	Invalid file type
751	MySQL error.	DMEC
	NDB error type.	Schema error

	Error message.	Out of file records
752	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid file format
753	MySQL error.	IE
	NDB error type.	Schema error
	Error message.	Invalid filegroup for file
754	MySQL error.	IE
	NDB error type.	Schema error
	Error message. creating file	
755	MySQL error.	HA_MISSING_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Invalid tablespace
756	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Index on disk column is not supported
757	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Varsize bitfield not supported
758	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Tablespace has changed
759	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid tablespace version
760	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	File already exists,
761	MySQL error.	DMEC

	NDB error type.	Schema error
	Error message. progress	Unable to drop table as backup is in
762	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. progress	Unable to alter table as backup is in
763	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. node versions	DDL is not supported with mixed data-
764	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Invalid extent size
765	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of filegroup records
766	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Cant drop file, no such file
767	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Cant drop filegroup, no such filegroup
768	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Cant drop filegroup, filegroup is used
769	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. logfile group	Drop undofile not supported, drop instead
770	MySQL error.	DMEC
	NDB error type.	Schema error

	Error message.	Cant drop file, file is used
771	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Application error
	Error message.	Given NODEGROUP doesn't exist in this
772	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Internal error
	Error message.	Given fragmentType doesn't exist
773	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. StringMemory	Out of string memory, please modify config parameter
774	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Invalid schema object for drop
775	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. Diskless=1	Create file is not supported when
776	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. itself be temp	Index created on temporary table must
777	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. non-temporary	——————————————————————————————————————
778	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. specified as a	A temporary table or index must be not logging
779	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error

	Error message.	Invalid undo buffer size
780	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Too many schema transactions
781	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Invalid schema transaction key from
782	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Invalid schema transaction id from NDB
783	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Too many schema operations
784	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Invalid schema transaction state
785	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Schema object is busy with another
786	MySQL error.	DMEC
	NDB error type.	Node Recovery error
	Error message. node-failure	Schema transaction aborted due to
787	MySQL error.	DMEC
	NDB error type.	Internal temporary
	Error message.	Schema transaction aborted

788	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message. of schema tra	_
789	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Application error
	Error message.	Logfile group not found
790	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Invalid hashmap
791	MySQL error.	HA_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message.	Too many total bits in bitfields
792	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	
793	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Object definition too big
794	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. upgrade	Schema feature requires data node
795	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	Out of LongMessageBuffer in DICT
796	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message.	Out of schema transaction memory
797	MySQL error.	DMEC
	NDB error type.	Function not implemented

	Error message. replicated tab	Wrong fragment count for fully le
798	MySQL error.	MEC
	NDB error type.	Application error
	Error message. no logging	A disk table must not be specified as
799	MySQL error. H	A_WRONG_CREATE_OPTION
	NDB error type.	Schema error
	Error message. partitions	Non default partitioning without
805	MySQL error. D	MEC
	NDB error type.	Temporary Resource error
	Error message. manager, incre	Out of attrinfo records in tuple ase LongSignalMemory
809	MySQL error. D	MEC
	NDB error type.	Internal error
	Error message.	809
812	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	812
823	MySQL error. D	MEC
	NDB error type.	Application error
	Error message. tuple manager	Too much attrinfo from application in
826	MySQL error. H	A_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message. (increase MaxN	Too many tables and attributes oOfAttributes or MaxNoOfTables)
827	MySQL error. H	A_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message. data (increase	-
829	MySQL error.	MEC

	NDB error type.	Application error
	Error message. update	Corrupt data received for insert/
830	MySQL error.	DMEC
	NDB error type.	Temporary Resource error
	Error message.	Out of add fragment operation records
831	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. definition	Too many nullable/bitfields in table
833	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	833
839	MySQL error.	DMEC
	NDB error type.	Constraint violation
	Error message.	Illegal null attribute
840	MySQL error.	DMEC
	NDB error type.	Constraint violation
	Error message.	Trying to set a NOT NULL attribute to
850	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	Too long or too short default value
851	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. max.Use VARCHA stored columns	AR or COLUMN_FORMAT DYNAMIC for memory-
871	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	871
873	MySQL error.	DMEC

	NDB error type.	Temporary Resource error
	•	Out of transaction memory in mager, ordered index data (increase memory)
874	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. for scan in t	Too much attrinfo (e.g. scan filter) tuple manager
876	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	876
877	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	877
878	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	878
879	MySQL error.	DMEC
	NDB error type.	Application error
	Error message.	879
880	MySQL error.	DMEC
	NDB error type.	Application error
	Error message. getValue call	Tried to read too much - too many .s
881	MySQL error.	DMEC
	NDB error type.	Schema error
	Error message. pages (increa	Unable to create table, out of data ase DataMemory)
882	MySQL error.	DMEC
	NDB error type.	Internal error
	Error message.	882
883	MySQL error.	DMEC

	NDB error type.	Internal error
	Error message.	883
884	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Stack overflow in interpreter
885	MySQL error.	MEC
	NDB error type.	Application error
	Error message.	Stack underflow in interpreter
886	MySQL error.	MEC
	NDB error type.	Application error
	Error message. in interpreter	More than 65535 instructions executed
887	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	887
888	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	888
889	MySQL error. H	A_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
		Table fragment fixed data reference ximum possible value (specify MAXROWS of partitions)
890	MySQL error.	MEC
	NDB error type.	Internal error
	Error message.	890
891	MySQL error.	MEC
	NDB error type.	Overload error
	Error message. UndoDataBuffer	Data UNDO buffers overloaded (increase)
892	MySQL error.	MEC
	NDB error type.	Application error

	Error message.	Unsupported type in scan filter
893	MySQL error. H	A_ERR_FOUND_DUPP_KEY
	NDB error type.	Constraint violation
	Error message. value in unique	Constraint violation e.g. duplicate e index
896	MySQL error. D	MEC
	NDB error type.	Internal error
		Tuple corrupted - wrong checksum or invalid format
897	MySQL error. D	MEC
	NDB error type.	Application error
	ndbcluster inte	Update attempt of primary key via ernal api (if this occurs via the MySQL bug, please report)
899	MySQL error. D	MEC
	NDB error type.	Temporary Resource error
	Error message.	Rowid already allocated
901	MySQL error. D	MEC
	NDB error type.	Internal error
	Error message. needs to be dro	Inconsistent ordered index. The index opped and recreated
902	MySQL error. H	A_ERR_RECORD_FILE_FULL
	NDB error type.	Insufficient space
	Error message. index data (index data)	Out of memory in Ndb Kernel, ordered crease DataMemory)
903	MySQL error. H	A_ERR_INDEX_FILE_FULL
	NDB error type.	Insufficient space
	Error message. MaxNoOfOrdered	
904	MySQL error. H	A_ERR_INDEX_FILE_FULL
	NDB error type.	Insufficient space
	Error message. MaxNoOfOrdered	Out of fragment records (increase Indexes)

905	MySQL error.	DMEC	
	NDB error type.	Insufficient space	
	Error message. Out of attribute records (increase MaxNoOfAttributes)		
906	MySQL error. DMEC		
	NDB error type.	Schema error	
	Error message.	Unsupported attribute type in index	
907	MySQL error. DMEC		
	NDB error type.	Schema error	
	Error message.	Unsupported character set in table or	
908	MySQL error.	DMEC	
	NDB error type.	Insufficient space	
	Error message.	Invalid ordered index tree node size	
909	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
	_	Out of transaction memory in local ordered scan operation (increase emory)	
910	MySQL error.	MySQL error. HA_ERR_NO_SUCH_TABLE	
	NDB error type.	Schema error	
	Error message.	Index is being dropped	
911	MySQL error. DMEC		
	NDB error type.	Schema error	
	Error message. with unsupport	Index stat scan requested on index ted key size	
912	MySQL error.	DMEC	
	NDB error type.	Application error	
	Error message. lock mode	Index stat scan requested with wrong	
913	MySQL error. DMEC		
	NDB error type.	Application error	
	Error message.	Invalid index for index stats update	

914	MySQL error.	DMEC	
	NDB error type.	Internal error	
	Error message.	Invalid index stats request	
915	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
	Error message.	No free index stats op	
916	MySQL error.	DMEC	
	NDB error type.	Internal error	
	Error message.	Invalid index stats sys tables	
917	MySQL error.	DMEC	
	NDB error type.	Internal error	
	Error message.	Invalid index stats sys tables data	
918	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
	Error message.	Cannot prepare index stats update	
919	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
	Error message.	Cannot execute index stats update	
920	MySQL error.	DMEC	
	NDB error type.	Application error	
	Error message. refreshTuple	_	
921	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
		Out of transaction memory in anager, copy tuples (increase Memory)	
923	MySQL error.	DMEC	
	NDB error type.	Temporary Resource error	
	Error message. UNDO_BUFFER_S	Out of UNDO buffer memory (increase SIZE)	
924	MySQL error.	DMEC	

NDB error type. Temporary Resource error

Error message. Out of transaction memory in local data manager, stored procedure record (increase

SharedGlobalMemory)

925 MySQL error. DMEC

NDB error type. Temporary Resource error

Error message. Out of transaction memory in local data manager, tup scan operation (increase

SharedGlobalMemory)

926 MySQL error. DMEC

NDB error type. Temporary Resource error

Error message. Out of transaction memory in local data manager, acc scan operation (increase SharedGlobalMemory)

INVALID_BLOCK_NAME MySQL error. DMEC

NDB error type. Application error

Error message. Invalid block name

INVALID_ERROR_NUMBER MySQL error. DMEC

NDB error type. Application error

Error message. Invalid error number. Should be >= 0.

INVALID_TRACE_NUMBER MySQL error. DMEC

NDB error type. Application error

Error message. Invalid trace number.

NODE_NOT_API_NODE MySQL error. DMEC

NDB error type. Application error

Error message. The specified node is not an API node.

NODE_SHUTDOWN_IN_PROGESS MySQL error. DMEC

NDB error type. Application error

Error message. Node shutdown in progress

NODE_SHUTDOWN_WOULD_CAUSE_MySQLMerrorSH DMEC

NDB error type. Application error

Error message. Node shutdown would cause system crash

 NDB error type. Application error

Error message. No contact with database nodes }

NO_CONTACT_WITH_PROCESS MySQL error. DMEC

NDB error type. Application error

Error message. No contact with the process (dead ?).

OPERATION_NOT_ALLOWED_STARMySQ1perror. DMEC

NDB error type. Application error

Error message. Operation not allowed while nodes are

starting or stopping.

QRY_BATCH_SIZE_TOO_SMALL MySQL error. DMEC

NDB error type. Application error

Error message. Batch size for sub scan cannot be

smaller than number of fragments.

QRY_CHAR_OPERAND_TRUNCATEDMySQL error. DMEC

NDB error type. Application error

Error message. Character operand was right truncated

QRY_CHAR_PARAMETER_TRUNCATMySQL error. DMEC

NDB error type. Application error

Error message. Character Parameter was right

truncated

QRY_DEFINITION_TOO_LARGE MySQL error. DMEC

NDB error type. Application error

Error message. Query definition too large.

QRY_EMPTY_PROJECTION MySQL error. DMEC

NDB error type. Application error

Error message. Query has operation with empty

projection.

QRY_HAS_ZERO_OPERATIONS MySQL error. DMEC

NDB error type. Application error

Error message. Query defintion should have at least

one operation.

QRY_ILLEGAL_STATE MySQL error. DMEC

NDB error type. Application error

Error message. Query is in illegal state for this

operation.

QRY_IN_ERROR_STATE MySQL error. DMEC

NDB error type. Application error

Error message. A previous query operation failed,

which you missed to catch.

QRY_MULTIPLE_PARENTS MySQL error. DMEC

NDB error type. Application error

Error message. Multiple 'parents' specified in

linkedValues for this operation

QRY_MULTIPLE_SCAN_SORTED MySQL error. DMEC

NDB error type. Application error

Error message. Query with multiple scans may not be

sorted.

QRY_NEST_NOT_SUPPORTED MySQL error. DMEC

NDB error type. Application error

Error message. FirstInner/Upper has to be an ancestor

or a sibling

QRY_NUM_OPERAND_RANGE MySQL error. DMEC

NDB error type. Application error

Error message. Numeric operand out of range

QRY_OJ_NOT_SUPPORTED MySQL error. DMEC

NDB error type. Application error

Error message. Outer joined scans not supported by

data nodes.

QRY_OPERAND_ALREADY_BOUND MySQL error. DMEC

NDB error type. Application error

Error message. Can't use same operand value to

specify different column values

QRY_OPERAND_HAS_WRONG_TYPEMySQL error. DMEC

NDB error type. Application error

Error message. Incompatible datatype specified in

operand argument

QRY_PARAMETER_HAS_WRONG_TYMYSQL error. DMEC

NDB error type. Application error

Error message. Parameter value has an incompatible

datatype

QRY_REQ_ARG_IS_NULL MySQL error. DMEC

NDB error type. Application error

Error message. Required argument is NULL

QRY_RESULT_ROW_ALREADY_DEFMySQL error. DMEC

NDB error type. Application error

Error message. Result row already defined for

NdbQueryOperation.

QRY_SCAN_ORDER_ALREADY_SETMySQL error. DMEC

NDB error type. Application error

Error message. Index scan order was already set in

query definition.

ORY SEQUENTIAL SCAN SORTEDMySQL error. DMEC

NDB error type. Application error

Error message. Parallelism cannot be restricted for

sorted scans.

QRY_TOO_FEW_KEY_VALUES MySQL error. DMEC

NDB error type. Application error

Error message. All required 'key' values was not

specified

QRY_TOO_MANY_KEY_VALUES MySQL error. DMEC

NDB error type. Application error

Error message. Too many 'key' or 'bound' values was

specified

QRY_UNKNOWN_PARENT MySQL error. DMEC

NDB error type. Application error

Error message. Unknown 'parent' specified in

linkedValue

QRY_UNRELATED_INDEX MySQL error. DMEC

NDB error type. Application error

Error message. Specified 'index' does not belong to

specified 'table'

QRY_WRONG_INDEX_TYPE MySQL error. DMEC

NDB error type. Application error

Error message. Wrong type of index specified for this

operation

QRY_WRONG_OPERATION_TYPE MySQL error. DMEC

NDB error type. Application error

Error message. This method cannot be invoked on this

type of operation (lookup/scan/index scan).

SEND_OR_RECEIVE_FAILED MySQL error. DMEG

NDB error type. Application error

Error message. Send to process or receive failed.

SYSTEM_SHUTDOWN_IN_PROGRESMYSQL error. DMEC

NDB error type. Application error

Error message. System shutdown in progress

UNSUPPORTED_NODE_SHUTDOWN MySQL error. DMEC

NDB error type. Application error

Error message. Unsupported multi node shutdown. Abort

option required.

WRONG_PROCESS_TYPE MySQL error. DMEC

NDB error type. Application error

Error message. The process has wrong type. Expected a

DB process.

2.4.4 NDB Error Classifications

The following table lists the classification codes used for NDB API errors, and their descriptions. These can also be found in the file /storage/ndb/src/ndbapi/ndberror.cpp (NDB 7.6 and earlier. ndberror.c).

Table 2.82 Classification codes for NDB API errors, with corresponding error status and description.

Classification Code	Error Status	Description
NE	Success	No error
AE	Permanent error	Application error
CE	Permanent error	Configuration or application error
ND	Permanent error	No data found
CV	Permanent error	Constraint violation
SE	Permanent error	Schema error
OE	Permanent error	Schema object already exists
UD	Permanent error	User defined error
IS	Permanent error	Insufficient space
TR	Temporary error	Temporary Resource error
NR	Temporary error	Node Recovery error
OL	Temporary error	Overload error
TO	Temporary error	Timeout expired
NS	Temporary error	Node shutdown
IT	Temporary error	Internal temporary
UR	Unknown result	Unknown result error
UE	Unknown result	Unknown error code
IE	Permanent error	Internal error
NI	Permanent error	Function not implemented
DMEC	Default MySQL error code	Used for NDB errors that are not otherwise mapped to MySQL error codes

In NDB 7.6.4 and later, you can also obtain the descriptions for the classification codes from the error_classification column of the ndbinfo.error_messages table.

2.5 NDB API Examples

This section provides code examples illustrating how to accomplish some basic tasks using the NDB API.

All of these examples can be compiled and run as provided, and produce sample output to demonstrate their effects.



Note

For an NDB API program to connect to the cluster, the cluster configuration file must have at least one <code>[api]</code> section that is not assigned to an SQL node and that can be accessed from the host where the NDB API application runs. You can also use an unassigned <code>[mysqld]</code> section for this purpose, although we recommend that you use <code>[mysqld]</code> sections for SQL nodes and <code>[api]</code> sections for NDB client programs. See NDB Cluster Configuration Files, and especially Defining SQL and Other API Nodes in an NDB Cluster, for more information.

2.5.1 NDB API Example Using Synchronous Transactions

This example illustrates the use of synchronous transactions in the NDB API. It first creates a database ndb_examples and a table api_simple (if these objects do not already exist) using the MySQL C API with an SQL node, then performs a series of basic data operations (insert, update, read, and select) on this table using the NDB API.

The compiled program takes two arguments:

- 1. The path to a MySQL socket file (mysqld --socket option)
- 2. An NDB Cluster connection string (see NDB Cluster Connection Strings)

The correct output from this program is as follows:

```
ATTR1 ATTR2
       10
1
       1
2
       12
Detected that deleted tuple doesn't exist!
       14
5
        5
6
       16
7
       7
8
       18
9
```

The source code for this example can be found in storage/ndb/ndbapi-examples/ndbapi_simple/
ndbapi_simple.cpp in the NDB Cluster source tree, and is reproduced here:

```
ndbapi_simple.cpp: Using synchronous transactions in NDB API
   Correct output from this program is:
   ATTR1 ATTR2
     0 10
           1
          12
   Detected that deleted tuple doesn't exist!
         14
     6
          16
     7
           7
     8
     9
           9
 */
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>
// Used for cout
#include <stdio.h>
#include <iostream>
static void run_application(MYSQL &, Ndb_cluster_connection &);
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
           << ", code: " << code \
           << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
  PRINT_ERROR(mysql_errno(&mysql), mysql_error(&mysql)); \
 exit(-1); }
```

```
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
int main(int argc, char** argv)
  if (argc != 3)
   std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(-1);
  // ndb_init must be called first
 ndb_init();
  // connect to mysql server and cluster and run application
   char * mysqld_sock = argv[1];
   const char *connection_string = argv[2];
   // Object representing the cluster
   Ndb_cluster_connection cluster_connection(connection_string);
    // Connect to cluster management server (ndb_mgmd)
   if (cluster_connection.connect(4 /* retries
                                                              */,
      5 /* delay between retries */,
      1 /* verbose
     std::cout << "Cluster management server was not ready within 30 secs.\n";
     exit(-1);
    // Optionally connect and wait for the storage nodes (ndbd's)
   if (cluster_connection.wait_until_ready(30,0) < 0)</pre>
     std::cout << "Cluster was not ready within 30 secs.\n";
     exit(-1);
   // connect to mysql server
   MYSQL mysql;
   if ( !mysql_init(&mysql) ) {
     std::cout << "mysql_init failed\n";</pre>
     exit(-1);
   if ( !mysql_real_connect(&mysql, "localhost", "root", "", "",
        0, mysqld_sock, 0))
     MYSQLERROR(mysql);
    // run the application code
   run_application(mysql, cluster_connection);
   mysql_close(&mysql);
 ndb_end(0);
 return 0;
static void create_table(MYSQL &);
static void do_insert(Ndb &);
static void do_update(Ndb &);
static void do_delete(Ndb &);
static void do_read(Ndb &);
static void run_application(MYSQL &mysql,
      Ndb_cluster_connection &cluster_connection)
  /*************
```

```
* Connect to database via mysql-c
 mysql_query(&mysql, "CREATE DATABASE ndb_examples");
 if (mysql_query(&mysql, "USE ndb_examples") != 0) MYSQLERROR(mysql);
 create_table(mysql);
 /************
  * Connect to database via NDB API
  ****************
 // Object representing the database
 Ndb myNdb( &cluster_connection, "ndb_examples" );
 if (myNdb.init()) APIERROR(myNdb.getNdbError());
  * Do different operations on database
 do_insert(myNdb);
 do_update(myNdb);
 do_delete(myNdb);
 do_read(myNdb);
/********************
* Create a table named api_simple if it does not exist *
*****************
static void create_table(MYSQL &mysql)
 while (mysql_query(&mysql,
   "CREATE TABLE"
    api simple"
       (ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY,"
       ATTR2 INT UNSIGNED NOT NULL)"
   " ENGINE=NDB"))
 {
   if (mysql_errno(&mysql) == ER_TABLE_EXISTS_ERROR)
     std::cout << "NDB Cluster already has example table: api_simple. "</pre>
     << "Dropping it..." << std::endl;
    mysql_query(&mysql, "DROP TABLE api_simple");
   else MYSQLERROR(mysql);
/************************
* Using 5 transactions, insert 10 tuples in table: (0,0),(1,1),\ldots,(9,9) *
************************
static void do_insert(Ndb &myNdb)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_simple");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 for (int i = 0; i < 5; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
   if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->insertTuple();
   myOperation->equal("ATTR1", i);
   myOperation->setValue("ATTR2", i);
   myOperation= myTransaction->getNdbOperation(myTable);
```

```
if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->insertTuple();
   myOperation->equal("ATTR1", i+5);
   myOperation->setValue("ATTR2", i+5);
   if (myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
* Update the second attribute in half of the tuples (adding 10) *
static void do_update(Ndb &myNdb)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_simple");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 for (int i = 0; i < 10; i+=2) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
   if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->updateTuple();
   myOperation->equal( "ATTR1", i );
   myOperation->setValue( "ATTR2", i+10);
   if( myTransaction->execute( NdbTransaction::Commit ) == -1 )
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
* Delete one tuple (the one with primary key 3) *
static void do_delete(Ndb &myNdb)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_simple");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTransaction= myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
 if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
 myOperation->deleteTuple();
 myOperation->equal( "ATTR1", 3 );
 if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
```

```
* Read and print all tuples *
static void do_read(Ndb &myNdb)
  const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_simple");
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
  std::cout << "ATTR1 ATTR2" << std::endl;
  for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
    if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->readTuple(NdbOperation::LM Read);
   myOperation->equal("ATTR1", i);
   NdbRecAttr *myRecAttr= myOperation->getValue("ATTR2", NULL);
    if (myRecAttr == NULL) APIERROR(myTransaction->getNdbError());
   if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
    if (myTransaction->getNdbError().classification == NdbError::NoDataFound)
      if (i == 3)
       std::cout << "Detected that deleted tuple doesn't exist!" << std::endl;</pre>
APIERROR(myTransaction->getNdbError());
    if (i != 3) {
      printf(" %2d
                      %2d\n", i, myRecAttr->u_32_value());
   myNdb.closeTransaction(myTransaction);
```

2.5.2 NDB API Example Using Synchronous Transactions and Multiple Clusters

This example demonstrates synchronous transactions and connecting to multiple clusters in a single NDB API application.

The source code for this program may be found in the NDB Cluster source tree, in the file storage/ndb/ndbapi-examples/ndbapi_simple_dual/main.cpp.



Note

The example file was formerly named ndbapi_simple_dual.cpp.

```
/*
 * ndbapi_simple_dual: Using synchronous transactions in NDB API
 *
 * Correct output from this program is:
 *
 * ATTR1 ATTR2
 * 0 10
 * 1 1
```

```
2
          12
   Detected that deleted tuple doesn't exist!
          14
     4
     5
          16
     6
          7
     8
          18
     9
          9
   ATTR1 ATTR2
     0
          10
          1
     1
     2
         12
   Detected that deleted tuple doesn't exist!
     4
         14
     5
         16
     6
    8
         18
     9
          9
 * /
#ifdef _WIN32
#include <winsock2.h>
#endif
#include <mysql.h>
#include <NdbApi.hpp>
#include <stdlib.h>
// Used for cout
#include <stdio.h>
#include <iostream>
static void run_application(MYSQL &, Ndb_cluster_connection &, const char* table, const char* db);
#define PRINT_ERROR(code,msg) \
 << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql), mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
int main(int argc, char** argv)
 if (argc != 5)
   std::cout << "Arguments are <socket mysqld1> <connect_string cluster 1> <socket mysqld2> <connect_string
  // ndb_init must be called first
 ndb_init();
   char * mysqld1_sock = argv[1];
   const char *connectstring1 = argv[2];
   char * mysqld2_sock = argv[3];
   const char *connectstring2 = argv[4];
   // Object representing the cluster 1
   Ndb_cluster_connection cluster1_connection(connectstring1);
   MYSQL mysql1;
   // Object representing the cluster 2
   Ndb_cluster_connection cluster2_connection(connectstring2);
   MYSQL mysql2;
```

```
// connect to mysql server and cluster 1 and run application
    // Connect to cluster 1 management server (ndb_mgmd)
    if (cluster1_connection.connect(4 /* retries
                                                                 */,
        5 /* delay between retries */,
        1 /* verbose
      std::cout << "Cluster 1 management server was not ready within 30 secs.\n";
      exit(-1);
    // Optionally connect and wait for the storage nodes (ndbd's)
    if (cluster1_connection.wait_until_ready(30,0) < 0)</pre>
      std::cout << "Cluster 1 was not ready within 30 secs.\n";</pre>
      exit(-1);
    // connect to mysql server in cluster 1
    if ( !mysql_init(&mysql1) ) {
      std::cout << "mysql_init failed\n";</pre>
      exit(-1);
    if ( !mysql_real_connect(&mysql1, "localhost", "root", "", "",
            0, mysqld1_sock, 0))
      MYSQLERROR(mysql1);
    // connect to mysql server and cluster 2 and run application
    // Connect to cluster management server (ndb_mgmd)
    if (cluster2_connection.connect(4 /* retries
                                                                 */,
        5 /* delay between retries */,
        1 /* verbose
      std::cout << "Cluster 2 management server was not ready within 30 secs.\n";
    // Optionally connect and wait for the storage nodes (ndbd's)
    if (cluster2_connection.wait_until_ready(30,0) < 0)</pre>
      std::cout << "Cluster 2 was not ready within 30 secs.\n";
      exit(-1);
    // connect to mysql server in cluster 2
    if ( !mysql_init(&mysql2) ) {
      std::cout << "mysql_init failed\n";</pre>
      exit(-1);
    if ( !mysql_real_connect(&mysql2, "localhost", "root", "", "",
            0, mysqld2_sock, 0))
     MYSQLERROR(mysql2);
    // run the application code
    \verb|run_application(mysql1, cluster1_connection, "api_simple_dual_1", "ndb_examples")|;\\
    run_application(mysql2, cluster2_connection, "api_simple_dual_2", "ndb_examples");
  // Note: all connections must have been destroyed before calling ndb_end()
 ndb_end(0);
 return 0;
static void create_table(MYSQL &, const char* table);
static void do_insert(Ndb &, const char* table);
static void do_update(Ndb &, const char* table);
static void do_delete(Ndb &, const char* table);
static void do_read(Ndb &, const char* table);
static void drop_table(MYSQL &,const char* table);
```

```
static void run_application(MYSQL &mysql,
      Ndb_cluster_connection &cluster_connection,
      const char* table,
      const char* db)
  /*************
  * Connect to database via mysql-c
char db_stmt[256];
sprintf(db_stmt, "CREATE DATABASE %s\n", db);
 mysql_query(&mysql, db_stmt);
sprintf(db_stmt, "USE %s", db);
 if (mysql_query(&mysql, db_stmt) != 0) MYSQLERROR(mysql);
 create_table(mysql, table);
  /************
  * Connect to database via NdbApi
  ***********
 // Object representing the database
 Ndb myNdb( &cluster_connection, db );
 if (myNdb.init()) APIERROR(myNdb.getNdbError());
  * Do different operations on database
 do_insert(myNdb, table);
 do_update(myNdb, table);
 do_delete(myNdb, table);
 do_read(myNdb, table);
  * Drop the table
 drop_table(mysql,table);
/***************
 * Create a table named by table if it does not exist *
 ***********************************
static void create_table(MYSQL &mysql, const char* table)
 char create_stmt[256];
 sprintf(create_stmt, "CREATE TABLE %s \
         (ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY,\
          ATTR2 INT UNSIGNED NOT NULL)\
         ENGINE=NDB", table);
 if (mysql_query(&mysql, create_stmt))
   MYSQLERROR(mysql);
* Using 5 transactions, insert 10 tuples in table: (0,0),(1,1),\ldots,(9,9) *
static void do_insert(Ndb &myNdb, const char* table)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable(table);
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 for (int i = 0; i < 5; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
```

```
if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->insertTuple();
    myOperation->equal("ATTR1", i);
    myOperation->setValue("ATTR2", i);
   myOperation= myTransaction->getNdbOperation(myTable);
    if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->insertTuple();
   myOperation->equal("ATTR1", i+5);
    myOperation->setValue("ATTR2", i+5);
    if (myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
 * Update the second attribute in half of the tuples (adding 10) *
static void do_update(Ndb &myNdb, const char* table)
  const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable(table);
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
  for (int i = 0; i < 10; i+=2) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
    if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
    if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->updateTuple();
   myOperation->equal( "ATTR1", i );
   myOperation->setValue( "ATTR2", i+10);
   if( myTransaction->execute( NdbTransaction::Commit ) == -1 )
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
/***************
* Delete one tuple (the one with primary key 3) *
static void do_delete(Ndb &myNdb, const char* table)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable(table);
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTransaction= myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
  if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
 myOperation->deleteTuple();
```

```
myOperation->equal( "ATTR1", 3 );
 if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
* Read and print all tuples *
**********
static void do_read(Ndb &myNdb, const char* table)
 const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable(table);
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "ATTR1 ATTR2" << std::endl;
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
   if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->readTuple(NdbOperation::LM_Read);
   myOperation->equal("ATTR1", i);
   NdbRecAttr *myRecAttr= myOperation->getValue("ATTR2", NULL);
   if (myRecAttr == NULL) APIERROR(myTransaction->getNdbError());
   if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     if (i == 3) {
std::cout << "Detected that deleted tuple doesn't exist!" << std::endl;</pre>
     } else {
APIERROR(myTransaction->getNdbError());
     }
   if (i != 3) {
     printf(" %2d
                     %2d\n", i, myRecAttr->u_32_value());
   myNdb.closeTransaction(myTransaction);
/********
* Drop table after usage *
**********
static void drop_table(MYSQL &mysql, const char* table)
 char drop_stmt[75];
 sprintf(drop_stmt, "DROP TABLE %s", table);
 if (mysql_query(&mysql,drop_stmt))
     MYSQLERROR(mysql);
```

Prior to NDB 8.0.1, this program could not be run more than once in succession during the same session (Bug #27009386).

2.5.3 NDB API Example: Handling Errors and Retrying Transactions

This program demonstrates handling errors and retrying failed transactions using the NDB API.

The source code for this example can be found in storage/ndb/ndbapi-examples/ndbapi_retries/ndbapi_retries.cpp in the NDB Cluster source tree.

There are many ways to program using the NDB API. In this example, we perform two inserts in the same transaction using NdbTransaction::execute(NoCommit).

In NDB API applications, there are two types of failures to be taken into account:

- 1. **Transaction failures**: If nonpermanent, these can be handled by re-executing the transaction.
- 2. **Application errors**: These are indicated by APIERROR; they must be handled by the application programmer.

```
ndbapi_retries.cpp: Error handling and transaction retries
11
   There are many ways to program using the NDB API. In this example
   we execute two inserts in the same transaction using
// NdbConnection::execute(NoCommit).
// Transaction failing is handled by re-executing the transaction
   in case of non-permanent transaction errors.
   Application errors (i.e. errors at points marked with APIERROR)
// should be handled by the application programmer.
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>
// Used for cout
#include <iostream>
// Used for sleep (use your own version of sleep)
#include <unistd.h>
#define TIME_TO_SLEEP_BETWEEN_TRANSACTION_RETRIES 1
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
           << ", code: " << code \
           << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql),mysql_error(&mysql)); \
 exit(-1); }
// APIERROR prints an NdbError object
#define APIERROR(error) \
  { std::cout << "API ERROR: " << error.code << " " << error.message \
             << std::endl \
                            " << "Status: " << error.status \
             << "
             << ", Classification: " << error.classification << std::endl\
             << "
                            " << "File: " << __FILE__ \
             << " (Line: " << __LINE__ << ")" << std::endl \
  }
   TRANSERROR prints all error info regarding an NdbTransaction
#define TRANSERROR(ndbTransaction) \
  { NdbError error = ndbTransaction->getNdbError(); \
   std::cout << "TRANS ERROR: " << error.code << " " << error.message \
             << std::endl \
```

```
" << "Status: " << error.status \
             << ", Classification: " << error.classification << std::endl \setminus
                           " << "File: " << __FILE__ \
             << " (Line: " << __LINE__ << ")" << std::endl \
             ; \
   printTransactionError(ndbTransaction); \
void printTransactionError(NdbTransaction *ndbTransaction) {
 const NdbOperation *ndbOp = NULL;
 int i=0;
  /*********************
   * Print NdbError object of every operations in the transaction *
 while ((ndbOp = ndbTransaction->getNextCompletedOperation(ndbOp)) != NULL) {
   NdbError error = ndbOp->getNdbError();
                          OPERATION " << i+1 << ": "
   std::cout << "
      << error.code << " " << error.message << std::endl
                    Status: " << error.status
      << ", Classification: " << error.classification << std::endl;
   i++;
 }
}
// Example insert
// @param myNdb Ndb object representing NDB Cluster
// @param myTransaction NdbTransaction used for transaction
                        Table to insert into
   @param myTable
// @param error
                        NdbError object returned in case of errors
// @return -1 in case of failures, 0 otherwise
int insert(int transactionId, NdbTransaction* myTransaction,
   const NdbDictionary::Table *myTable) {
 NdbOperation *myOperation;
                                    // For other operations
 myOperation = myTransaction->getNdbOperation(myTable);
 if (myOperation == NULL) return -1;
 if (myOperation->insertTuple() | |
     myOperation->equal("ATTR1", transactionId) ||
     myOperation->setValue("ATTR2", transactionId)) {
   APIERROR(myOperation->getNdbError());
   exit(-1);
 return myTransaction->execute(NdbTransaction::NoCommit);
// Execute function which re-executes (tries 10 times) the transaction
// if there are temporary errors (e.g. the NDB Cluster is overloaded).
// @return -1 failure, 1 success
11
int executeInsertTransaction(int transactionId, Ndb* myNdb,
      const NdbDictionary::Table *myTable) {
 int result = 0;
                                     // No result yet
 int noOfRetriesLeft = 10;
 NdbTransaction *myTransaction;
                                      // For other transactions
 NdbError ndberror;
 while (noOfRetriesLeft > 0 && !result) {
    /*********
```

```
* Start and execute transaction *
   myTransaction = myNdb->startTransaction();
   if (myTransaction == NULL) {
     APIERROR(myNdb->getNdbError());
     ndberror = myNdb->getNdbError();
     result = -1; // Failure
   } else if (insert(transactionId, myTransaction, myTable) ||
       insert(10000+transactionId, myTransaction, myTable) ||
       myTransaction->execute(NdbTransaction::Commit)) {
     TRANSERROR(myTransaction);
     ndberror = myTransaction->getNdbError();
     result = -1; // Failure
   } else {
     result = 1; // Success
    /**********
     * If failure, then analyze error *
    ***********
   if (result == -1) {
     switch (ndberror.status) {
     case NdbError::Success:
break;
     case NdbError::TemporaryError:
std::cout << "Retrying transaction..." << std::endl;</pre>
sleep(TIME_TO_SLEEP_BETWEEN_TRANSACTION_RETRIES);
 --noOfRetriesLeft;
result = 0; // No completed transaction yet
break;
     case NdbError::UnknownResult:
     case NdbError::PermanentError:
std::cout << "No retry of transaction..." << std::endl;
result = -1; // Permanent failure
break;
    /********
    * Close transaction *
    ********
   if (myTransaction != NULL) {
     myNdb->closeTransaction(myTransaction);
 }
 if (result != 1) exit(-1);
 return result;
* Create a table named api_retries if it does not exist *
static void create_table(MYSQL &mysql)
 while(mysql_query(&mysql,
   "CREATE TABLE "
    " api_retries"
       (ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY, "
        ATTR2 INT UNSIGNED NOT NULL)"
   " ENGINE=NDB"))
   if (mysql_errno(&mysql) == ER_TABLE_EXISTS_ERROR)
     std::cout << "NDB Cluster already has example table: api_scan. "
     << "Dropping it..." << std::endl;</pre>
```

```
mysql_query(&mysql, "DROP TABLE api_retries");
   else MYSQLERROR(mysql);
int main(int argc, char** argv)
 if (argc != 3)
   std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(-1);
 char * mysqld_sock = argv[1];
 const char *connection_string = argv[2];
 ndb_init();
 Ndb_cluster_connection *cluster_connection=
   new Ndb_cluster_connection(connection_string); // Object representing the cluster
 int r= cluster connection->connect(5 /* retries
                                                                */,
        3 /* delay between retries */,
        1 /* verbose
                                  */);
 if (r > 0)
   std::cout
     << "Cluster connect failed, possibly resolved with more retries.\n";</pre>
 else if (r < 0)
   std::cout
     << "Cluster connect failed.\n";</pre>
   exit(-1);
 if (cluster_connection->wait_until_ready(30,30))
   std::cout << "Cluster was not ready within 30 secs." << std::endl;</pre>
   exit(-1);
  // connect to mysql server
 MYSQL mysql;
 if ( !mysql_init(&mysql) ) {
   std::cout << "mysql_init failed\n";</pre>
   exit(-1);
 if ( !mysql_real_connect(&mysql, "localhost", "root", "", "",
     0, mysqld_sock, 0))
   MYSQLERROR(mysql);
  /*************
  * Connect to database via mysql-c
 mysql_query(&mysql, "CREATE DATABASE ndb_examples");
 if (mysql_query(&mysql, "USE ndb_examples") != 0) MYSQLERROR(mysql);
 create_table(mysql);
 mysql_close(&mysql);
 Ndb* myNdb= new Ndb( cluster_connection,
        "ndb_examples" ); // Object representing the database
 if (myNdb->init() == -1) {
   APIERROR(myNdb->getNdbError());
   exit(-1);
```

```
const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
const NdbDictionary::Table *myTable= myDict->getTable("api_retries");
if (myTable == NULL)
 APIERROR(myDict->getNdbError());
 return -1;
/***********
 * Execute some insert transactions *
 ***********
std::cout << "Ready to insert rows. You will see notices for temporary "
  "errors, permenant errors, and retries. \n";
for (int i = 10000; i < 20000; i++) {
  executeInsertTransaction(i, myNdb, myTable);
std::cout << "Done.\n";
delete myNdb;
delete cluster_connection;
ndb_end(0);
return 0;
```

2.5.4 NDB API Basic Scanning Example

This example illustrates how to use the NDB scanning API. It shows how to perform a scan, how to scan for an update, and how to scan for a delete, making use of the NdbScanFilter and NdbScanOperation classes.

The source code for this example may found in the NDB Cluster source tree, in the file storage/ndb/ndbapi_examples/ndbapi_scan/ndbapi_scan.cpp.

This example makes use of the following classes and methods:

```
• Ndb_cluster_connection:
```

- connect()
- wait_until_ready()
- Ndb:
 - init()
 - getDictionary()
 - startTransaction()
 - closeTransaction()
- NdbTransaction:
 - getNdbScanOperation()
 - execute()
- NdbOperation:
 - insertTuple()

```
• equal()
 • getValue()
 • setValue()
• NdbScanOperation:
 • readTuples()
 • nextResult()
 • deleteCurrentTuple()
 • updateCurrentTuple()
• NdbDictionary:
 • Dictionary::getTable()
 • Table::getColumn()
 • Column::getLength()
• NdbScanFilter:
 • begin()
 • eq()
  • end()
   Copyright (c) 2005, 2017, Oracle and/or its affiliates. All rights reserved.
  This program is free software; you can redistribute it and/or modify
   it under the terms of the GNU General Public License as published by
   the Free Software Foundation; version 2 of the License.
  This program is distributed in the hope that it will be useful,
  but WITHOUT ANY WARRANTY; without even the implied warranty of
  MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
  GNU General Public License for more details.
  You should have received a copy of the GNU General Public License
  along with this program; if not, write to the Free Software
   Foundation, Inc., 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA
 * ndbapi_scan.cpp:
 * Illustrates how to use the scan api in the NDBAPI.
 * The example shows how to do scan, scan for update and scan for delete
 * using NdbScanFilter and NdbScanOperation
 * Classes and methods used in this example:
   Ndb_cluster_connection
        connect()
        wait_until_ready()
```

```
Ndb
        init()
        getDictionary()
         startTransaction()
         closeTransaction()
   NdbTransaction
         getNdbScanOperation()
         execute()
   NdbScanOperation
        getValue()
        readTuples()
        nextResult()
         deleteCurrentTuple()
        updateCurrentTuple()
   const NdbDictionary::Dictionary
        getTable()
   const NdbDictionary::Table
        getColumn()
   const NdbDictionary::Column
        getLength()
   NdbOperation
        insertTuple()
         equal()
        setValue()
   NdbScanFilter
        begin()
   eq()
   end()
*/
#ifdef _WIN32
#include <winsock2.h>
#endif
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>
// Used for cout
#include <iostream>
#include <stdio.h>
#include <string.h>
#include <stdlib.h>
#include <config.h>
#ifdef HAVE_SYS_SELECT_H
#include <sys/select.h>
#endif
* Helper sleep function
* /
static void
milliSleep(int milliseconds){
 struct timeval sleeptime;
 sleeptime.tv_sec = milliseconds / 1000;
 sleeptime.tv_usec = (milliseconds - (sleeptime.tv_sec * 1000)) * 1000000;
 select(0, 0, 0, 0, &sleeptime);
```

```
* Helper debugging macros
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
           << ", code: " << code \
            << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql),mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
struct Car
   * Note memset, so that entire char-fields are cleared
      as all 20 bytes are significant (as type is char)
 Car() { memset(this, 0, sizeof(* this)); }
 unsigned int reg_no;
 char brand[20];
 char color[20];
* Function to drop table
void drop_table(MYSQL &mysql)
 if (mysql_query(&mysql, "DROP TABLE IF EXISTS api_scan"))
   MYSQLERROR(mysql);
* Function to create table
void create_table(MYSQL &mysql)
 while (mysql_query(&mysql,
   "CREATE TABLE"
   " api_scan"
        (REG_NO INT UNSIGNED NOT NULL,"
         BRAND CHAR(20) NOT NULL,"
         COLOR CHAR(20) NOT NULL,"
         PRIMARY KEY USING HASH (REG_NO))"
    " ENGINE=NDB"))
   if (mysql_errno(&mysql) != ER_TABLE_EXISTS_ERROR)
     MYSQLERROR(mysql);
   std::cout << "NDB Cluster already has example table: api_scan. "
      << "Dropping it..." << std::endl;
   drop_table(mysql);
int populate(Ndb * myNdb)
 int i;
 Car cars[15];
 const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_scan");
  if (myTable == NULL)
```

```
APIERROR(myDict->getNdbError());
  * Five blue mercedes
  for (i = 0; i < 5; i++)
   cars[i].reg_no = i;
   sprintf(cars[i].brand, "Mercedes");
sprintf(cars[i].color, "Blue");
  * Five black bmw
  for (i = 5; i < 10; i++)
   cars[i].reg_no = i;
   sprintf(cars[i].brand, "BMW");
   sprintf(cars[i].color, "Black");
  * Five pink toyotas
  for (i = 10; i < 15; i++)
   cars[i].reg_no = i;
    sprintf(cars[i].brand, "Toyota");
    sprintf(cars[i].color, "Pink");
 NdbTransaction* myTrans = myNdb->startTransaction();
  if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
  for (i = 0; i < 15; i++)
   NdbOperation* myNdbOperation = myTrans->getNdbOperation(myTable);
   if (myNdbOperation == NULL)
     APIERROR(myTrans->getNdbError());
   myNdbOperation->insertTuple();
    myNdbOperation->equal("REG_NO", cars[i].reg_no);
   myNdbOperation->setValue("BRAND", cars[i].brand);
    myNdbOperation->setValue("COLOR", cars[i].color);
  }
 int check = myTrans->execute(NdbTransaction::Commit);
 myTrans->close();
 return check != -1;
int scan_delete(Ndb* myNdb,
 int column,
 const char * color)
  // Scan all records exclusive and delete
  // them one by one
 int
                       retryAttempt = 0;
 const int
                       retryMax = 10;
  int deletedRows = 0;
  int check;
 NdbError
                        err;
```

```
NdbTransaction *myTrans;
NdbScanOperation *myScanOp;
const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
const NdbDictionary::Table *myTable= myDict->getTable("api_scan");
if (myTable == NULL)
  APIERROR(myDict->getNdbError());
  * Loop as long as :
  * retryMax not reached
  * failed operations due to TEMPORARY erros
  * Exit loop;
  * retyrMax reached
  * Permanent error (return -1)
  * /
while (true)
   if (retryAttempt >= retryMax)
    std::cout << "ERROR: has retried this operation " << retryAttempt
 << " times, failing!" << std::endl;
    return -1;
   myTrans = myNdb->startTransaction();
   if (myTrans == NULL)
     const NdbError err = myNdb->getNdbError();
     if (err.status == NdbError::TemporaryError)
milliSleep(50);
retryAttempt++;
continue;
    std::cout << err.message << std::endl;</pre>
    return -1;
   * Get a scan operation.
   myScanOp = myTrans->getNdbScanOperation(myTable);
   if (myScanOp == NULL)
    std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
    * Define a result set for the scan.
   if(myScanOp->readTuples(NdbOperation::LM_Exclusive) != 0)
    std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
    * Use NdbScanFilter to define a search critera
   NdbScanFilter filter(myScanOp) ;
```

```
if(filter.begin(NdbScanFilter::AND) < 0 ||</pre>
      filter.cmp(NdbScanFilter::COND_EQ, column, color, 20) < 0 ||
      filter.end() < 0)
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
    * Start scan
                    (NoCommit since we are only reading at this stage);
   if(myTrans->execute(NdbTransaction::NoCommit) != 0){
     err = myTrans->getNdbError();
     if(err.status == NdbError::TemporaryError){
std::cout << myTrans->getNdbError().message << std::endl;</pre>
myNdb->closeTransaction(myTrans);
milliSleep(50);
continue;
     }
     std::cout << err.code << std::endl;</pre>
     std::cout << myTrans->getNdbError().code << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
     return -1;
   * start of loop: nextResult(true) means that "parallelism" number of
   * rows are fetched from NDB and cached in NDBAPI
   while((check = myScanOp->nextResult(true)) == 0){
     do
     {
if (myScanOp->deleteCurrentTuple() != 0)
  std::cout << myTrans->getNdbError().message << std::endl;</pre>
 myNdb->closeTransaction(myTrans);
 return -1;
deletedRows++;
 * nextResult(false) means that the records
 * cached in the NDBAPI are modified before
 * fetching more rows from NDB.
     } while((check = myScanOp->nextResult(false)) == 0);
     /**
      * NoCommit when all cached tuple have been marked for deletion
      * /
     if(check != -1)
check = myTrans->execute(NdbTransaction::NoCommit);
     /**
      * Check for errors
     err = myTrans->getNdbError();
     if(check == -1)
if(err.status == NdbError::TemporaryError)
  std::cout << myTrans->getNdbError().message << std::endl;</pre>
  myNdb->closeTransaction(myTrans);
```

```
milliSleep(50);
   continue;
      /**
       * End of loop
     * Commit all prepared operations
    if(myTrans->execute(NdbTransaction::Commit) == -1)
     if(err.status == NdbError::TemporaryError){
std::cout << myTrans->getNdbError().message << std::endl;</pre>
myNdb->closeTransaction(myTrans);
milliSleep(50);
continue;
     }
    std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return 0;
 if(myTrans!=0)
    std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
 return -1;
int scan_update(Ndb* myNdb,
 int update_column,
 const char * before_color,
 const char * after_color)
  // Scan all records exclusive and update
  // them one by one
 int
                       retryAttempt = 0;
                       retryMax = 10;
 const int
 int updatedRows = 0;
  int check;
 NdbError
 NdbTransaction *myTrans;
 NdbScanOperation *myScanOp;
 const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_scan");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
   * Loop as long as :
   * retryMax not reached
   ^{\star} \, failed operations due to TEMPORARY erros
   * Exit loop;
   * retryMax reached
   * Permanent error (return -1)
```

```
while (true)
   if (retryAttempt >= retryMax)
    std::cout << "ERROR: has retried this operation " << retryAttempt</pre>
 << " times, failing!" << std::endl;
    return -1;
  myTrans = myNdb->startTransaction();
  if (myTrans == NULL)
     const NdbError err = myNdb->getNdbError();
     if (err.status == NdbError::TemporaryError)
milliSleep(50);
retryAttempt++;
continue;
    std::cout << err.message << std::endl;
    return -1;
  * Get a scan operation.
  myScanOp = myTrans->getNdbScanOperation(myTable);
   if (myScanOp == NULL)
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
   }
   * Define a result set for the scan.
   if( myScanOp->readTuples(NdbOperation::LM_Exclusive) )
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
     myNdb->closeTransaction(myTrans);
    return -1;
   }
    * Use NdbScanFilter to define a search critera
   NdbScanFilter filter(myScanOp) ;
   if(filter.begin(NdbScanFilter::AND) < 0 ||</pre>
      filter.cmp(NdbScanFilter::COND_EQ, update_column, before_color, 20) <0||
      filter.end() <0)
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
    * Start scan
                    (NoCommit since we are only reading at this stage);
   if(myTrans->execute(NdbTransaction::NoCommit) != 0)
     err = myTrans->getNdbError();
     if(err.status == NdbError::TemporaryError){
std::cout << myTrans->getNdbError().message << std::endl;</pre>
```

```
myNdb->closeTransaction(myTrans);
milliSleep(50);
continue;
     std::cout << myTrans->getNdbError().code << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
    return -1;
   /**
   * start of loop: nextResult(true) means that "parallelism" number of
   * rows are fetched from NDB and cached in NDBAPI
   while((check = myScanOp->nextResult(true)) == 0){
    do {
/**
* Get update operation
NdbOperation * myUpdateOp = myScanOp->updateCurrentTuple();
if (myUpdateOp == 0)
 std::cout << myTrans->getNdbError().message << std::endl;</pre>
 myNdb->closeTransaction(myTrans);
 return -1;
updatedRows++;
* do the update
myUpdateOp->setValue(update_column, after_color);
* nextResult(false) means that the records
* cached in the NDBAPI are modified before
 * fetching more rows from NDB.
     } while((check = myScanOp->nextResult(false)) == 0);
     * NoCommit when all cached tuple have been updated
     if(check != -1)
check = myTrans->execute(NdbTransaction::NoCommit);
     /**
     * Check for errors
     err = myTrans->getNdbError();
     if(check == -1)
if(err.status == NdbError::TemporaryError){
  std::cout << myTrans->getNdbError().message << std::endl;</pre>
 myNdb->closeTransaction(myTrans);
 milliSleep(50);
  continue;
     /**
      * End of loop
    * Commit all prepared operations
```

```
if(myTrans->execute(NdbTransaction::Commit) == -1)
     if(err.status == NdbError::TemporaryError){
std::cout << myTrans->getNdbError().message << std::endl;</pre>
myNdb->closeTransaction(myTrans);
milliSleep(50);
continue;
     }
   std::cout << myTrans->getNdbError().message << std::endl;</pre>
   myNdb->closeTransaction(myTrans);
   return 0;
  if(myTrans!=0)
    std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
 return -1;
int scan_print(Ndb * myNdb)
// Scan all records exclusive and update
 // them one by one
 int
                       retryAttempt = 0;
 const int
                       retryMax = 10;
 int fetchedRows = 0;
  int check;
 NdbError
                        err;
 NdbTransaction *myTrans;
 NdbScanOperation *myScanOp;
  /* Result of reading attribute value, three columns:
    REG_NO, BRAND, and COLOR
 NdbRecAttr *
                  myRecAttr[3];
 const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_scan");
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
   * Loop as long as :
   * retryMax not reached
   ^{\star} \, failed operations due to TEMPORARY erros
   * Exit loop;
   * retyrMax reached
   * Permanent error (return -1)
   * /
 while (true)
   if (retryAttempt >= retryMax)
      std::cout << "ERROR: has retried this operation " << retryAttempt</pre>
  << " times, failing!" << std::endl;
      return -1;
    }
```

```
myTrans = myNdb->startTransaction();
   if (myTrans == NULL)
     const NdbError err = myNdb->getNdbError();
     if (err.status == NdbError::TemporaryError)
milliSleep(50);
retryAttempt++;
continue;
    }
    std::cout << err.message << std::endl;</pre>
    return -1;
    * Define a scan operation.
    * NDBAPI.
   * /
   myScanOp = myTrans->getNdbScanOperation(myTable);
   if (myScanOp == NULL)
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
     return -1;
    * Read without locks, without being placed in lock queue
   if( myScanOp->readTuples(NdbOperation::LM_CommittedRead) == -1)
     std::cout << myTrans->getNdbError().message << std::endl;</pre>
    myNdb->closeTransaction(myTrans);
     return -1;
   * Define storage for fetched attributes.
   * E.g., the resulting attributes of executing
    * myOp->getValue("REG_NO") is placed in myRecAttr[0].
    * No data exists in myRecAttr until transaction has commited!
   myRecAttr[0] = myScanOp->getValue("REG_NO");
   myRecAttr[1] = myScanOp->getValue("BRAND");
   myRecAttr[2] = myScanOp->getValue("COLOR");
   if(myRecAttr[0] ==NULL | | myRecAttr[1] == NULL | | myRecAttr[2] ==NULL)
std::cout << myTrans->getNdbError().message << std::endl;</pre>
myNdb->closeTransaction(myTrans);
return -1;
   }
   /**
    * Start scan
                  (NoCommit since we are only reading at this stage);
   if(myTrans->execute(NdbTransaction::NoCommit) != 0){
     err = myTrans->getNdbError();
     if(err.status == NdbError::TemporaryError){
std::cout << myTrans->getNdbError().message << std::endl;</pre>
myNdb->closeTransaction(myTrans);
milliSleep(50);
continue;
     std::cout << err.code << std::endl;</pre>
     std::cout << myTrans->getNdbError().code << std::endl;</pre>
     myNdb->closeTransaction(myTrans);
     return -1;
```

```
* start of loop: nextResult(true) means that "parallelism" number of
    ^{\star} rows are fetched from NDB and cached in NDBAPI
   while((check = myScanOp->nextResult(true)) == 0){
 fetchedRows++;
 * print REG_NO unsigned int
std::cout << myRecAttr[0]->u_32_value() << "\t";</pre>
 * print BRAND character string
std::cout << myRecAttr[1]->aRef() << "\t";</pre>
 * print COLOR character string
std::cout << myRecAttr[2]->aRef() << std::endl;</pre>
 * nextResult(false) means that the records
 * cached in the NDBAPI are modified before
 * fetching more rows from NDB.
     } while((check = myScanOp->nextResult(false)) == 0);
   myNdb->closeTransaction(myTrans);
   return 1;
 return -1;
void mysql_connect_and_create(MYSQL & mysql, const char *socket)
 bool ok;
 ok = mysql_real_connect(&mysql, "localhost", "root", "", "", 0, socket, 0);
   mysql_query(&mysql, "CREATE DATABASE ndb_examples");
   ok = ! mysql_select_db(&mysql, "ndb_examples");
 if(ok) {
   create_table(mysql);
 if(! ok) MYSQLERROR(mysql);
void ndb_run_scan(const char * connectstring)
  /***********************
  * Connect to ndb cluster
  {\tt Ndb\_cluster\_connection\ cluster\_connection(connectstring);}
 if (cluster_connection.connect(4, 5, 1))
   std::cout << "Unable to connect to cluster within 30 secs." << std::endl;
   exit(-1);
```

```
// Optionally connect and wait for the storage nodes (ndbd's)
if (cluster_connection.wait_until_ready(30,0) < 0)</pre>
  std::cout << "Cluster was not ready within 30 secs.\n";</pre>
  exit(-1);
Ndb myNdb(&cluster_connection, "ndb_examples");
                                   // Set max 1024 parallel transactions
if (myNdb.init(1024) == -1) {
  APIERROR(myNdb.getNdbError());
  exit(-1);
}
 /*************
  * Check table definition
  **************
 int column_color;
  const NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
  const NdbDictionary::Table *t= myDict->getTable("api_scan");
  if(t == NULL)
    std::cout << "Dictionary::getTable() failed.";</pre>
    exit(-1);
  Car car;
  if (t->getColumn("COLOR")->getLength() != sizeof(car.color) ||
t->getColumn("BRAND")->getLength() != sizeof(car.brand))
    std::cout << "Wrong table definition" << std::endl;</pre>
    exit(-1);
  column_color= t->getColumn("COLOR")->getColumnNo();
}
if(populate(&myNdb) > 0)
  std::cout << "populate: Success!" << std::endl;</pre>
if(scan_print(&myNdb) > 0)
  std::cout << "scan_print: Success!" << std::endl << std::endl;</pre>
std::cout << "Going to delete all pink cars!" << std::endl;</pre>
   * Note! color needs to be of exact the same size as column defined
  Car tmp;
  sprintf(tmp.color, "Pink");
  if(scan_delete(&myNdb, column_color, tmp.color) > 0)
    std::cout << "scan_delete: Success!" << std::endl << std::endl;</pre>
if(scan_print(&myNdb) > 0)
  std::cout << "scan_print: Success!" << std::endl << std::endl;</pre>
   * Note! color1 & 2 need to be of exact the same size as column defined
  Car tmp1, tmp2;
  sprintf(tmp1.color, "Blue");
  sprintf(tmp2.color, "Black");
  std::cout << "Going to update all " << tmp1.color
     << " cars to " << tmp2.color << " cars!" << std::endl;</pre>
   if(scan_update(&myNdb, column_color, tmp1.color, tmp2.color) > 0)
```

```
std::cout << "scan_update: Success!" << std::endl << std::endl;</pre>
  if(scan_print(&myNdb) > 0)
    std::cout << "scan_print: Success!" << std::endl << std::endl;</pre>
int main(int argc, char** argv)
  if (argc != 3)
   std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(-1);
 char * mysqld_sock = argv[1];
  const char *connectstring = argv[2];
 MYSQL mysql;
 mysql_init(& mysql);
 mysql_connect_and_create(mysql, mysqld_sock);
 ndb_init();
 ndb_run_scan(connectstring);
 ndb_end(0);
 mysql_close(&mysql);
  return 0;
```

2.5.5 NDB API Example: Using Secondary Indexes in Scans

This program illustrates how to use secondary indexes in the NDB API.

The source code for this example may be found in the NDB Cluster source tree, in storage/ndb/ndbapi-examples/ndbapi_simple_index/main.cpp.



Note

This file was previously named ndbapi_simple_index.cpp.

The correct output from this program is shown here:

```
ATTR1 ATTR2
      10
0
       1
      12
Detected that deleted tuple doesn't exist!
4
      14
5
       5
6
      16
7
       7
      18
       9
```

The listing for this program is shown here:

```
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>

// Used for cout
#include <stdio.h>
#include <iostream>

#define PRINT_ERROR(code,msg) \
```

```
std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
           << ", code: " << code \
           << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql), mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
int main(int argc, char** argv)
 if (argc != 3)
   std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(-1);
 char * mysqld_sock = argv[1];
 const char *connection_string = argv[2];
 ndb_init();
 /****************
  * Connect to mysql server and create table
  *************************************
 MYSQL mysql;
   if ( !mysql_init(&mysql) ) {
     std::cout << "mysql_init failed\n";</pre>
     exit(-1);
   if ( !mysql_real_connect(&mysql, "localhost", "root", "", "",
       0, mysqld_sock, 0) )
     MYSOLERROR(mysql);
   mysql_query(&mysql, "CREATE DATABASE ndb_examples_1");
   if (mysql_query(&mysql, "USE ndb_examples") != 0) MYSQLERROR(mysql);
   while (mysql_query(&mysql,
     "CREATE TABLE"
     " api_simple_index"
         (ATTR1 INT UNSIGNED,"
           ATTR2 INT UNSIGNED NOT NULL, "
           PRIMARY KEY USING HASH (ATTR1),"
          UNIQUE MYINDEXNAME USING HASH (ATTR2))"
     " ENGINE=NDB"))
     if (mysql_errno(&mysql) == ER_TABLE_EXISTS_ERROR)
       std::cout << "NDB Cluster already has example table: api_scan. "</pre>
       << "Dropping it..." << std::endl;
       mysql_query(&mysql, "DROP TABLE api_simple_index");
     else MYSQLERROR(mysql);
   mysql_close(&mysql);
  /**********************************
  * Connect to ndb cluster
       ***********************************
 Ndb_cluster_connection *cluster_connection=
   new Ndb_cluster_connection(connection_string); // Object representing the cluster
 if (cluster_connection->connect(5,3,1))
   std::cout << "Connect to cluster management server failed.\n";</pre>
```

```
exit(-1);
}
if (cluster_connection->wait_until_ready(30,30))
 std::cout << "Cluster was not ready within 30 secs.\n";
Ndb* myNdb = new Ndb( cluster_connection,
 "ndb_examples" ); // Object representing the database
if (myNdb->init() == -1) {
 APIERROR(myNdb->getNdbError());
 exit(-1);
const NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
const NdbDictionary::Table *myTable= myDict->getTable("api_simple_index");
if (myTable == NULL)
 APIERROR(myDict->getNdbError());
const NdbDictionary::Index *myIndex= myDict->getIndex("MYINDEXNAME$unique","api_simple_index");
if (myIndex == NULL)
 APIERROR(myDict->getNdbError());
/****************************
 * Using 5 transactions, insert 10 tuples in table: (0,0),(1,1),\ldots,(9,9) *
 *****************
for (int i = 0; i < 5; i++) {
 NdbTransaction *myTransaction= myNdb->startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
 NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
 if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
 myOperation->insertTuple();
 myOperation->equal("ATTR1", i);
 myOperation->setValue("ATTR2", i);
 myOperation = myTransaction->getNdbOperation(myTable);
 if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
 myOperation->insertTuple();
 myOperation->equal("ATTR1", i+5);
 myOperation->setValue("ATTR2", i+5);
 if (myTransaction->execute( NdbTransaction::Commit ) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
 * Read and print all tuples using index *
 ************
std::cout << "ATTR1 ATTR2" << std::endl;
for (int i = 0; i < 10; i++) {
 NdbTransaction *myTransaction= myNdb->startTransaction();
  if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
 NdbIndexOperation *myIndexOperation=
   myTransaction->getNdbIndexOperation(myIndex);
 if (myIndexOperation == NULL) APIERROR(myTransaction->getNdbError());
 myIndexOperation->readTuple(NdbOperation::LM_Read);
 myIndexOperation->equal("ATTR2", i);
```

```
NdbRecAttr *myRecAttr= myIndexOperation->getValue("ATTR1", NULL);
 if (myRecAttr == NULL) APIERROR(myTransaction->getNdbError());
 if(myTransaction->execute( NdbTransaction::Commit,
                           NdbOperation::AbortOnError ) != -1)
                  %2d\n", myRecAttr->u_32_value(), i);
   printf(" %2d
 myNdb->closeTransaction(myTransaction);
 * Update the second attribute in half of the tuples (adding 10) *
       ***********************************
for (int i = 0; i < 10; i+=2) {
 NdbTransaction *myTransaction= myNdb->startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
 NdbIndexOperation *myIndexOperation=
   myTransaction->getNdbIndexOperation(myIndex);
 if (myIndexOperation == NULL) APIERROR(myTransaction->getNdbError());
 myIndexOperation->updateTuple();
 myIndexOperation->equal( "ATTR2", i );
 myIndexOperation->setValue( "ATTR2", i+10);
 if( myTransaction->execute( NdbTransaction::Commit ) == -1 )
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
/***************
 * Delete one tuple (the one with primary key 3) *
       *************
 NdbTransaction *myTransaction= myNdb->startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
 NdbIndexOperation *myIndexOperation=
   myTransaction->getNdbIndexOperation(myIndex);
 if (myIndexOperation == NULL) APIERROR(myTransaction->getNdbError());
 myIndexOperation->deleteTuple();
 myIndexOperation->equal( "ATTR2", 3 );
 if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
 * Read and print all tuples *
 **********
 std::cout << "ATTR1 ATTR2" << std::endl;
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb->startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
   NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
   if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
   myOperation->readTuple(NdbOperation::LM_Read);
   myOperation->equal("ATTR1", i);
```

2.5.6 NDB API Example: Using NdbRecord with Hash Indexes

This program illustrates how to use secondary indexes in the NDB API with the aid of the NdbRecord interface.

The source code for this example may be found in the NDB Cluster source trees, in the file storage/ndb/ndbapi-examples/ndbapi_s_i_ndbrecord/main.cpp.

When run on a cluster having 2 data nodes, the correct output from this program is as shown here:

```
ATTR1 ATTR2
 0
       0 (frag=0)
 1
       1 (frag=1)
       2 (frag=1)
 2
 3
          (frag=0)
       4 (frag=1)
 4
       5 (frag=1)
 5
 6
       6 (frag=0)
 7
       7 (frag=0)
 8
       8
          (frag=1)
 9
      9
          (frag=0)
ATTR1 ATTR2
 0 10
 1
      1
 2
     12
Detected that deleted tuple doesn't exist!
     14
 5
       5
 6
     16
 7
      7
 8
      18
```

The program listing is shown here:

```
//
// ndbapi_simple_index_ndbrecord.cpp: Using secondary unique hash indexes
// in NDB API, utilising the NdbRecord interface.
//
// Correct output from this program is (from a two-node cluster):
//
```

```
// ATTR1 ATTR2
   0
          0 (frag=0)
             (frag=1)
          1
11
    1
          2
              (frag=1)
   3
          3 (frag=0)
          4
             (frag=1)
   5
         5 (frag=1)
   6
             (frag=0)
          6
          7
              (frag=0)
              (frag=1)
    8
          8
    9
         9
              (frag=0)
11
// ATTR1 ATTR2
   0 10
//
//
    1
          1
11
    2
         12
// Detected that deleted tuple doesn't exist!
        14
    5
         5
         16
11
    6
    7
          7
         18
    8
    9
          9
#include <mysql.h>
#include <NdbApi.hpp>
// Used for cout
#include <stdio.h>
#include <iostream>
#define PRINT_ERROR(code,msg) \
  std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
           << ", code: " << code \
           << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
  PRINT_ERROR(mysql_errno(&mysql),mysql_error(&mysql)); \
  exit(1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
  exit(1); }
/* C struct representing layout of data from table
 * api_s_i_ndbrecord in memory
 * This can make it easier to work with rows in the application,
 * but is not necessary - NdbRecord can map columns to any
 * pattern of offsets.
 * In this program, the same row offsets are used for columns
 * specified as part of a key, and as part of an attribute or
 * result. This makes the example simpler, but is not
 * essential.
*/
struct MyTableRow
 unsigned int attrl;
 unsigned int attr2;
int main(int argc, char** argv)
  if (argc != 3)
    std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(1);
  char * mysqld_sock = argv[1];
  const char *connection_string = argv[2];
  ndb_init();
```

```
MYSQL mysql;
/*********************
 * Connect to mysql server and create table
 if ( !mysql_init(&mysql) ) {
   std::cout << "mysql_init failed\n";</pre>
   exit(1);
 if ( !mysql_real_connect(&mysql, "localhost", "root", "", "",
                         0, mysqld_sock, 0) )
   MYSQLERROR(mysql);
 mysql_query(&mysql, "CREATE DATABASE ndb_examples");
  if (mysql_query(&mysql, "USE ndb_examples") != 0)
   MYSQLERROR(mysql);
 mysql_query(&mysql, "DROP TABLE api_s_i_ndbrecord");
  if (mysql_query(&mysql,
                 "CREATE TABLE"
                 " api s i ndbrecord"
                     (ATTR1 INT UNSIGNED,"
                      ATTR2 INT UNSIGNED NOT NULL,"
                      PRIMARY KEY USING HASH (ATTR1),"
                      UNIQUE MYINDEXNAME USING HASH (ATTR2))"
                 " ENGINE=NDB"))
   MYSQLERROR(mysql);
}
/********************
 * Connect to ndb cluster
          ******************
Ndb_cluster_connection *cluster_connection=
 new Ndb_cluster_connection(connection_string); // Object representing the cluster
if (cluster_connection->connect(5,3,1))
 std::cout << "Connect to cluster management server failed.\n";
 exit(1);
if (cluster_connection->wait_until_ready(30,30))
 std::cout << "Cluster was not ready within 30 secs.\n";</pre>
 exit(1);
Ndb* myNdb = new Ndb( cluster_connection,
                    "ndb_examples" ); // Object representing the database
if (myNdb->init() == -1) {
 APIERROR(myNdb->getNdbError());
 exit(1);
NdbDictionary::Dictionary* myDict= myNdb->getDictionary();
const NdbDictionary::Table *myTable= myDict->getTable("api_s_i_ndbrecord");
if (myTable == NULL)
 APIERROR(myDict->getNdbError());
const NdbDictionary::Index *myIndex= myDict->qetIndex("MYINDEXNAME$unique", "api_s_i_ndbrecord");
if (myIndex == NULL)
 APIERROR(myDict->getNdbError());
/* Create NdbRecord descriptors. */
const NdbDictionary::Column *col1= myTable->getColumn("ATTR1");
if (col1 == NULL)
```

```
APIERROR(myDict->getNdbError());
const NdbDictionary::Column *col2= myTable->getColumn("ATTR2");
if (col2 == NULL)
  APIERROR(myDict->getNdbError());
/* NdbRecord for primary key lookup. */
NdbDictionary::RecordSpecification spec[2];
spec[0].column= col1;
spec[0].offset= offsetof(MyTableRow, attr1);
  // So that it goes nicely into the struct
spec[0].nullbit_byte_offset= 0;
spec[0].nullbit_bit_in_byte= 0;
const NdbRecord *pk_record=
 myDict->createRecord(myTable, spec, 1, sizeof(spec[0]));
if (pk_record == NULL)
 APIERROR(myDict->getNdbError());
/* NdbRecord for all table attributes (insert/read). */
spec[0].column= col1;
spec[0].offset= offsetof(MyTableRow, attr1);
spec[0].nullbit_byte_offset= 0;
spec[0].nullbit_bit_in_byte= 0;
spec[1].column= col2;
spec[1].offset= offsetof(MyTableRow, attr2);
spec[1].nullbit_byte_offset= 0;
spec[1].nullbit_bit_in_byte= 0;
const NdbRecord *attr_record=
 myDict->createRecord(myTable, spec, 2, sizeof(spec[0]));
if (attr_record == NULL)
  APIERROR(myDict->getNdbError());
/* NdbRecord for unique key lookup. */
spec[0].column= col2;
spec[0].offset= offsetof(MyTableRow, attr2);
spec[0].nullbit_byte_offset= 0;
spec[0].nullbit_bit_in_byte= 0;
const NdbRecord *key_record=
 myDict->createRecord(myIndex, spec, 1, sizeof(spec[0]));
if (key_record == NULL)
  APIERROR(myDict->getNdbError());
MyTableRow row;
 * Using 5 transactions, insert 10 tuples in table: (0,0),(1,1),...,(9,9) *
 *************************
for (int i = 0; i < 5; i++) {
  NdbTransaction *myTransaction= myNdb->startTransaction();
  if (myTransaction == NULL) APIERROR(myNdb->getNdbError());
   We initialise the row data and pass to each insertTuple operation
   The data is copied in the call to insertTuple and so the original
    row object can be reused for the two operations.
  row.attr1= row.attr2= i;
  const NdbOperation *myOperation=
   myTransaction->insertTuple(attr_record, (const char*)&row);
  if (myOperation == NULL)
   APIERROR(myTransaction->getNdbError());
  row.attr1= row.attr2= i+5;
  myOperation=
    myTransaction->insertTuple(attr_record, (const char*)&row);
  if (myOperation == NULL)
    APIERROR(myTransaction->getNdbError());
```

```
if (myTransaction->execute( NdbTransaction::Commit ) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
* Read and print all tuples using index *
std::cout << "ATTR1 ATTR2" << std::endl;
for (int i = 0; i < 10; i++) {
 NdbTransaction *myTransaction= myNdb->startTransaction();
  if (myTransaction == NULL)
   APIERROR(myNdb->getNdbError());
  /* The optional OperationOptions parameter to NdbRecord methods
  ^{\star} can be used to specify extra reads of columns which are not in
  * the NdbRecord specification, which need to be stored somewhere
  ^{\star} other than specified in the NdbRecord specification, or
  * which cannot be specified as part of an NdbRecord (pseudo
  * /
 Uint32 frag;
 NdbOperation::GetValueSpec getSpec[1];
 getSpec[0].column=NdbDictionary::Column::FRAGMENT;
 getSpec[0].appStorage=&frag;
 NdbOperation::OperationOptions options;
 options.optionsPresent = NdbOperation::OperationOptions::OO_GETVALUE;
 options.extraGetValues = &getSpec[0];
 options.numExtraGetValues = 1;
  /* We're going to read using the secondary unique hash index
  * Set the value of its column
 row.attr2= i;
 MyTableRow resultRow;
 unsigned char mask[1] = \{ 0x01 \};
                                     // Only read ATTR1 into resultRow
  const NdbOperation *myOperation=
   myTransaction->readTuple(key_record, (const char*) &row,
                            attr_record, (char*) &resultRow,
                            NdbOperation::LM_Read, mask,
                            &options,
                            sizeof(NdbOperation::OperationOptions));
 if (myOperation == NULL)
   APIERROR(myTransaction->getNdbError());
  if (myTransaction->execute( NdbTransaction::Commit,
                             NdbOperation::AbortOnError ) != -1)
   printf(" %2d
                 %2d (frag=%u)\n", resultRow.attrl, i, frag);
 myNdb->closeTransaction(myTransaction);
/***********************
* Update the second attribute in half of the tuples (adding 10) *
for (int i = 0; i < 10; i+=2) {
 NdbTransaction *myTransaction= myNdb->startTransaction();
 if (myTransaction == NULL)
   APIERROR(myNdb->getNdbError());
```

```
/* Specify key column to lookup in secondary index */
 row.attr2= i;
 /* Specify new column value to set */
 MyTableRow newRowData;
 newRowData.attr2= i+10;
 unsigned char mask[1] = \{ 0x02 \};
                                          // Only update ATTR2
 const NdbOperation *myOperation=
   myTransaction->updateTuple(key_record, (const char*)&row,
                             attr_record,(char*) &newRowData, mask);
 if (myOperation == NULL)
   APIERROR(myTransaction->getNdbError());
 if ( myTransaction->execute( NdbTransaction::Commit ) == -1 )
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
* Delete one tuple (the one with unique key 3) *
**************
 NdbTransaction *myTransaction= myNdb->startTransaction();
 if (myTransaction == NULL)
   APIERROR(myNdb->getNdbError());
 row.attr2= 3;
 const NdbOperation *myOperation=
   myTransaction->deleteTuple(key_record, (const char*) &row,
                             attr_record);
 if (myOperation == NULL)
   APIERROR(myTransaction->getNdbError());
 if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb->closeTransaction(myTransaction);
/*********
* Read and print all tuples *
**********
 std::cout << "ATTR1 ATTR2" << std::endl;</pre>
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb->startTransaction();
   if (myTransaction == NULL)
     APIERROR(myNdb->getNdbError());
   row.attrl= i;
   /* Read using pk. Note the same row space is used as
    * key and result storage space
   const NdbOperation *myOperation=
    myTransaction->readTuple(pk_record, (const char*) &row,
                             attr_record, (char*) &row);
   if (myOperation == NULL)
     APIERROR(myTransaction->getNdbError());
   if (myTransaction->execute( NdbTransaction::Commit,
                              NdbOperation::AbortOnError ) == -1)
     if (i == 3) {
```

```
std::cout << "Detected that deleted tuple doesn't exist!\n";
} else {
    APIERROR(myTransaction->getNdbError());
}

if (i != 3)
    printf(" %2d  %2d\n", row.attr1, row.attr2);

myNdb->closeTransaction(myTransaction);
}
}

delete myNdb;
delete cluster_connection;

ndb_end(0);
return 0;
}
```

2.5.7 NDB API Example Comparing RecAttr and NdbRecord

This example illustrates the key differences between the old-style NdbRecAttr API and the newer approach using NdbRecord when performing some common tasks in an NDB API application.

The source code can be found can be found in the file storage/ndb/ndbapi-examples/ndbapi_recattr_vs_record/main.cpp in the NDB Cluster source tree.

```
#include <mysql.h>
#include <NdbApi.hpp>
// Used for cout
#include <stdio.h>
#include <iostream>
// Do we use old-style (NdbRecAttr?) or new style (NdbRecord?)
enum ApiType {api_attr, api_record};
static void run_application(MYSQL &, Ndb_cluster_connection &, ApiType);
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__
           << ", line: " << __LINE_
           << ", code: " << code \
           << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql),mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
int main(int argc, char** argv)
  if (argc != 4)
   std::cout << "Arguments are <socket mysqld> "
             << "<connect_string cluster> <attr|record>.\n";
   exit(-1);
  // ndb_init must be called first
 ndb_init();
  // connect to mysql server and cluster and run application
   char * mysqld_sock = argv[1];
    const char *connection_string = argv[2];
```

```
ApiType accessType=api_attr;
    // Object representing the cluster
    Ndb_cluster_connection cluster_connection(connection_string);
    // Connect to cluster management server (ndb_mgmd)
    if (cluster_connection.connect(4 /* retries
                                                                */,
       5 /* delay between retries */,
       1 /* verbose
      std::cout << "Management server not ready within 30 sec.\n";
    // Optionally connect and wait for the storage nodes (ndbd's)
    if (cluster_connection.wait_until_ready(30,0) < 0)</pre>
      std::cout << "Cluster not ready within 30 sec.\n";</pre>
      exit(-1);
    // connect to mysql server
    MYSQL mysql;
    if ( !mysql_init(&mysql) ) {
      std::cout << "mysql_init failed\n";</pre>
      exit(-1);
    if ( !mysql_real_connect(&mysql, "localhost", "root", "", "",
       0, mysqld_sock, 0))
      MYSQLERROR(mysql);
    if (0==strncmp("attr", argv[3], 4))
      accessType=api_attr;
    else if (0==strncmp("record", argv[3], 6))
      accessType=api_record;
    else
      std::cout << "Bad access type argument : "
                << argv[3] << "\n";
      exit(-1);
    // run the application code
    run_application(mysql, cluster_connection, accessType);
  ndb_end(0);
  return 0;
static void init_ndbrecord_info(Ndb &);
static void create_table(MYSQL &);
static void do_insert(Ndb &, ApiType);
static void do_update(Ndb &, ApiType);
static void do_delete(Ndb &, ApiType);
static void do_read(Ndb &, ApiType);
static void do_mixed_read(Ndb &);
static void do_mixed_update(Ndb &);
static void do_scan(Ndb &, ApiType);
static void do_mixed_scan(Ndb &);
static void do_indexScan(Ndb &, ApiType);
static void do_mixed_indexScan(Ndb&);
```

```
static void do_read_and_delete(Ndb &);
static void do_scan_update(Ndb&, ApiType);
static void do_scan_delete(Ndb&, ApiType);
static void do_scan_lock_reread(Ndb&, ApiType);
static void do_all_extras_read(Ndb &myNdb);
static void do_secondary_indexScan(Ndb &myNdb, ApiType accessType);
static void do_secondary_indexScanEqual(Ndb &myNdb, ApiType accessType);
static void do_interpreted_update(Ndb &myNdb, ApiType accessType);
static void do_interpreted_scan(Ndb &myNdb, ApiType accessType);
static void do_read_using_default(Ndb &myNdb);
/* This structure is used describe how we want data read using
^{\star} NDBRecord to be placed into memory. This can make it easier
 * to work with data, but is not essential.
struct RowData
 int attr1;
 int attr2;
 int attr3;
/* Handy struct for representing the data in the
* secondary index
struct IndexRow
 unsigned int attr3;
 unsigned int attr2;
static void run_application(MYSQL &mysql,
      Ndb_cluster_connection &cluster_connection,
                          ApiType accessType)
  /*************
  * Connect to database via mysql-c
   *************
 mysql_query(&mysql, "CREATE DATABASE ndb_examples");
 if (mysql_query(&mysql, "USE ndb_examples") != 0) MYSQLERROR(mysql);
 create_table(mysql);
  * Connect to database via NDB API
  // Object representing the database
 Ndb myNdb( &cluster_connection, "ndb_examples" );
 if (myNdb.init()) APIERROR(myNdb.getNdbError());
 init_ndbrecord_info(myNdb);
  * Do different operations on database
 do_insert(myNdb, accessType);
 do_update(myNdb, accessType);
 do_delete(myNdb, accessType);
 do_read(myNdb, accessType);
 do_mixed_read(myNdb);
 do_mixed_update(myNdb);
 do_read(myNdb, accessType);
 do_scan(myNdb, accessType);
 do_mixed_scan(myNdb);
 do_indexScan(myNdb, accessType);
 do_mixed_indexScan(myNdb);
 do_read_and_delete(myNdb);
 do_scan_update(myNdb, accessType);
```

```
do_scan_delete(myNdb, accessType);
 do_scan_lock_reread(myNdb, accessType);
 do_all_extras_read(myNdb);
 do_secondary_indexScan(myNdb, accessType);
 do_secondary_indexScanEqual(myNdb, accessType);
 do_scan(myNdb, accessType);
 do_interpreted_update(myNdb, accessType);
 do_interpreted_scan(myNdb, accessType);
 do_read_using_default(myNdb);
 do_scan(myNdb, accessType);
/****************
 * Create a table named api recattr vs record if it does not exist *
static void create_table(MYSQL &mysql)
  if (mysql_query(&mysql,
    "DROP TABLE IF EXISTS"
    " api_recattr_vs_record"))
   MYSQLERROR(mysql);
  if (mysql_query(&mysql,
    "CREATE TABLE"
    " api_recattr_vs_record"
        (ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY, "
         ATTR2 INT UNSIGNED NOT NULL,"
                 ...
                       ATTR3 INT UNSIGNED NOT NULL)"
   " ENGINE=NDB"))
   MYSQLERROR(mysql);
  /* Add ordered secondary index on 2 attributes, in reverse order */
 if (mysql_query(&mysql,
                  "CREATE INDEX"
                  " MYINDEXNAME"
                  " ON api_recattr_vs_record"
                    (ATTR3, ATTR2)"))
   MYSQLERROR(mysql);
/* Clunky statics for shared NdbRecord stuff */
static const NdbDictionary::Column *pattr1Col;
static const NdbDictionary::Column *pattr2Col;
static const NdbDictionary::Column *pattr3Col;
static const NdbRecord *pkeyColumnRecord;
static const NdbRecord *pallColsRecord;
static const NdbRecord *pkeyIndexRecord;
static const NdbRecord *psecondaryIndexRecord;
static int attr1ColNum;
static int attr2ColNum;
static int attr3ColNum;
* Initialise NdbRecord structures for table and index access *
static void init_ndbrecord_info(Ndb &myNdb)
  /* Here we create various NdbRecord structures for accessing
  * data using the tables and indexes on api_recattr_vs_record
  * We could use the default NdbRecord structures, but then
   * we wouldn't have the nice ability to read and write rows
   * to and from the RowData and IndexRow structs
   * /
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
```

```
const NdbDictionary::Table *myTable=
                  myDict->getTable("api_recattr_vs_record");
NdbDictionary::RecordSpecification recordSpec[3];
if (myTable == NULL)
  APIERROR(myDict->getNdbError());
pattr1Col = myTable->getColumn("ATTR1");
if (pattrlCol == NULL) APIERROR(myDict->getNdbError());
pattr2Col = myTable->getColumn("ATTR2");
if (pattr2Col == NULL) APIERROR(myDict->getNdbError());
pattr3Col = myTable->getColumn("ATTR3");
if (pattr3Col == NULL) APIERROR(myDict->getNdbError());
attr1ColNum = pattr1Col->getColumnNo();
attr2ColNum = pattr2Col->getColumnNo();
attr3ColNum = pattr3Col->getColumnNo();
// ATTR 1
recordSpec[0].column = pattr1Col;
recordSpec[0].offset = offsetof(RowData, attrl);
recordSpec[0].nullbit_byte_offset = 0; // Not nullable
recordSpec[0].nullbit_bit_in_byte = 0;
// ATTR 2
recordSpec[1].column = pattr2Col;
recordSpec[1].offset = offsetof(RowData, attr2);
recordSpec[1].nullbit_byte_offset = 0;  // Not nullable
recordSpec[1].nullbit_bit_in_byte = 0;
// ATTR 3
recordSpec[2].column = pattr3Col;
recordSpec[2].offset = offsetof(RowData, attr3);
recordSpec[2].nullbit_byte_offset = 0;  // Not nullable
recordSpec[2].nullbit_bit_in_byte = 0;
/* Create table record with just the primary key column */
pkeyColumnRecord =
  myDict->createRecord(myTable, recordSpec, 1, sizeof(recordSpec[0]));
if (pkeyColumnRecord == NULL) APIERROR(myDict->getNdbError());
/* Create table record with all the columns */
pallColsRecord =
  myDict->createRecord(myTable, recordSpec, 3, sizeof(recordSpec[0]));
if (pallColsRecord == NULL) APIERROR(myDict->getNdbError());
/* Create NdbRecord for primary index access */
const NdbDictionary::Index *myPIndex=
                  myDict->getIndex("PRIMARY", "api_recattr_vs_record");
if (myPIndex == NULL)
  APIERROR(myDict->getNdbError());
pkeyIndexRecord =
  myDict->createRecord(myPIndex, recordSpec, 1, sizeof(recordSpec[0]));
if (pkeyIndexRecord == NULL) APIERROR(myDict->getNdbError());
/* Create Index NdbRecord for secondary index access
 ^{\star} Note that we use the columns from the table to define the index
 * access record
const NdbDictionary::Index *mySIndex=
              myDict->getIndex("MYINDEXNAME", "api_recattr_vs_record");
```

```
recordSpec[0].column= pattr3Col;
 recordSpec[0].offset= offsetof(IndexRow, attr3);
 recordSpec[0].nullbit_byte_offset=0;
 recordSpec[0].nullbit_bit_in_byte=0;
 recordSpec[1].column= pattr2Col;
 recordSpec[1].offset= offsetof(IndexRow, attr2);
 recordSpec[1].nullbit_byte_offset=0;
 recordSpec[1].nullbit_bit_in_byte=1;
  /* Create NdbRecord for accessing via secondary index */
 psecondaryIndexRecord =
   myDict->createRecord(mySIndex,
                         recordSpec,
                         2.
                         sizeof(recordSpec[0]));
 if (psecondaryIndexRecord == NULL)
   APIERROR(myDict->getNdbError());
* Using 5 transactions, insert 10 tuples in table: (0,0),(1,1),\ldots,(9,9) *
static void do_insert(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                            myDict->getTable("api_recattr_vs_record");
 std::cout << "Running do_insert\n";</pre>
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 for (int i = 0; i < 5; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   switch (accessType)
   case api_attr :
       NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
       if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
       myOperation->insertTuple();
       myOperation->equal("ATTR1", i);
       myOperation->setValue("ATTR2", i);
       myOperation->setValue("ATTR3", i);
       myOperation= myTransaction->getNdbOperation(myTable);
       if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
       myOperation->insertTuple();
       myOperation->equal("ATTR1", i+5);
       myOperation->setValue("ATTR2", i+5);
       myOperation->setValue("ATTR3", i+5);
       break;
   case api_record :
       RowData row;
```

```
row.attr1= row.attr2= row.attr3= i;
       const NdbOperation *pop1=
         myTransaction->insertTuple(pallColsRecord, (char *) &row);
       if (pop1 == NULL) APIERROR(myTransaction->getNdbError());
       row.attr1= row.attr2= row.attr3= i+5;
       const NdbOperation *pop2=
         myTransaction->insertTuple(pallColsRecord, (char *) &row);
       if (pop2 == NULL) APIERROR(myTransaction->getNdbError());
       break;
   default :
       std::cout << "Bad branch : " << accessType << "\n";
       exit(-1);
    if (myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Update the second attribute in half of the tuples (adding 10) *
      ******************
static void do_update(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                           myDict->getTable("api_recattr_vs_record");
 std::cout << "Running do_update\n";</pre>
  for (int i = 0; i < 10; i+=2) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   switch (accessType)
     case api_attr :
       NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
       if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
       myOperation->updateTuple();
       myOperation->equal( "ATTR1", i );
       myOperation->setValue( "ATTR2", i+10);
       myOperation->setValue( "ATTR3", i+20);
       break;
     case api_record :
       RowData row;
       row.attrl=i;
       row.attr2=i+10;
       row.attr3=i+20;
        /* Since we're using an NdbRecord with all columns in it to
```

```
* specify the updated columns, we need to create a mask to
         * indicate that we are only updating attr2 and attr3.
       unsigned char attrMask=(1<<attr2ColNum) | (1<<attr3ColNum);</pre>
       const NdbOperation *pop =
         myTransaction->updateTuple(pkeyColumnRecord, (char*) &row,
                                    pallColsRecord, (char*) &row,
                                    &attrMask);
       if (pop==NULL) APIERROR(myTransaction->getNdbError());
   default :
       std::cout << "Bad branch : " << accessType << "\n";
       exit(-1);
   if( myTransaction->execute( NdbTransaction::Commit ) == -1 )
     APIERROR(myTransaction->getNdbError());
   myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
};
/**************
* Delete one tuple (the one with primary key 3) *
static void do_delete(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                           myDict->getTable("api_recattr_vs_record");
 std::cout << "Running do_delete\n";</pre>
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTransaction= myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 switch (accessType)
 case api_attr :
     NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
     if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
     myOperation->deleteTuple();
     myOperation->equal( "ATTR1", 3 );
     break;
 case api_record :
     RowData keyInfo;
     keyInfo.attr1=3;
     const NdbOperation *pop=
       myTransaction->deleteTuple(pkeyColumnRecord,
                                   (char*) &keyInfo,
                                  pallColsRecord);
```

```
if (pop==NULL) APIERROR(myTransaction->getNdbError());
     break;
  default :
     std::cout << "Bad branch : " << accessType << "\n";
     exit(-1);
  if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
 * Update the second attribute in half of the tuples (adding 10) *
*******************
static void do_mixed_update(Ndb &myNdb)
  /* This method performs an update using a mix of NdbRecord
  * supplied attributes, and extra setvalues provided by
  * the OperationOptions structure.
 std::cout << "Running do_mixed_update (NdbRecord only)\n";</pre>
  for (int i = 0; i < 10; i+=2) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   RowData row;
    row.attr1=i;
   row.attr2=i+30;
    /* Only attr2 is updated vian NDBRecord */
   unsigned char attrMask= (1<<attr2ColNum);</pre>
   NdbOperation::SetValueSpec setvalspecs[1];
    /* Value to set attr3 to */
   Uint32 dataSource= i + 40;
    setvalspecs[0].column = pattr3Col;
   setvalspecs[0].value = &dataSource;
   NdbOperation::OperationOptions opts;
   opts.optionsPresent= NdbOperation::OperationOptions::OO_SETVALUE;
   opts.extraSetValues= &setvalspecs[0];
    opts.numExtraSetValues= 1;
    // Define mixed operation in one call to NDBAPI
   const NdbOperation *pop =
     myTransaction->updateTuple(pkeyColumnRecord, (char*) &row,
                                pallColsRecord, (char*) &row,
                                &attrMask,
                                &opts);
    if (pop==NULL) APIERROR(myTransaction->getNdbError());
    if( myTransaction->execute( NdbTransaction::Commit ) == -1 )
     APIERROR(myTransaction->getNdbError());
```

```
myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read and print all tuples using PK access *
static void do_read(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                            myDict->getTable("api_recattr_vs_record");
 std::cout << "Running do_read\n";</pre>
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   RowData rowData;
   NdbRecAttr *myRecAttr;
   NdbRecAttr *myRecAttr2;
   switch (accessType)
     case api_attr :
       NdbOperation *myOperation= myTransaction->getNdbOperation(myTable);
       if (myOperation == NULL) APIERROR(myTransaction->getNdbError());
       myOperation->readTuple(NdbOperation::LM_Read);
       myOperation->equal("ATTR1", i);
       myRecAttr= myOperation->getValue("ATTR2", NULL);
       if (myRecAttr == NULL) APIERROR(myTransaction->getNdbError());
       myRecAttr2=myOperation->getValue("ATTR3", NULL);
       if (myRecAttr2 == NULL) APIERROR(myTransaction->getNdbError());
       break;
     case api_record :
       rowData.attr1=i;
       const NdbOperation *pop=
         myTransaction->readTuple(pkeyColumnRecord,
                                   (char*) &rowData,
                                   pallColsRecord, // Read PK+ATTR2+ATTR3
                                   (char*) &rowData);
       if (pop==NULL) APIERROR(myTransaction->getNdbError());
       break;
   default :
      std::cout << "Bad branch : " << accessType << "\n";
      exit(-1);
```

```
if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   if (myTransaction->qetNdbError().classification == NdbError::NoDataFound)
     if (i == 3)
       std::cout << "Deleted tuple does not exist." << std::endl;</pre>
APIERROR(myTransaction->getNdbError());
   switch (accessType)
     case api_attr :
       if (i != 3) {
         printf(" %2d
                       %2d %2d\n",
                i,
                myRecAttr->u_32_value(),
                myRecAttr2->u_32_value());
       break;
     case api_record :
       if (i !=3) {
                       %2d %2d\n",
         printf(" %2d
                rowData.attr2,
                rowData.attr3);
       break;
     default :
       std::cout << "Bad branch : " << accessType << "\n";
       exit(-1);
   myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/********
* Read and print all tuples *
 **********
static void do_mixed_read(Ndb &myNdb)
 std::cout << "Running do_mixed_read (NdbRecord only)\n";</pre>
 std::cout << "ATTR1 ATTR2 ATTR3 COMMIT_COUNT" << std::endl;</pre>
  for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   RowData rowData;
   NdbRecAttr *myRecAttr3, *myRecAttrCC;
    /* Start with NdbRecord read of ATTR2, and then add
    * getValue NdbRecAttr read of ATTR3 and Commit count
   NdbOperation::GetValueSpec extraCols[2];
```

```
extraCols[0].column=pattr3Col;
   extraCols[0].appStorage=NULL;
   extraCols[0].recAttr=NULL;
   extraCols[1].column=NdbDictionary::Column::COMMIT_COUNT;
   extraCols[1].appStorage=NULL;
   extraCols[1].recAttr=NULL;
   NdbOperation::OperationOptions opts;
   opts.optionsPresent = NdbOperation::OperationOptions::OO_GETVALUE;
   opts.extraGetValues= &extraCols[0];
   opts.numExtraGetValues= 2;
    /* We only read attr2 using the normal NdbRecord access */
   unsigned char attrMask= (1<<attr2ColNum);</pre>
   // Set PK search criteria
   rowData.attr1= i;
   const NdbOperation *pop=
     myTransaction->readTuple(pkeyColumnRecord,
                               (char*) &rowData,
                               pallColsRecord, // Read all with mask
                               (char*) &rowData,
                               NdbOperation::LM_Read,
                               &attrMask, // result_mask
                               &opts);
   if (pop==NULL) APIERROR(myTransaction->getNdbError());
   myRecAttr3= extraCols[0].recAttr;
   myRecAttrCC= extraCols[1].recAttr;
   if (myRecAttr3 == NULL) APIERROR(myTransaction->getNdbError());
   if (myRecAttrCC == NULL) APIERROR(myTransaction->getNdbError());
   if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   if (myTransaction->qetNdbError().classification == NdbError::NoDataFound)
      if (i == 3)
        std::cout << "Deleted tuple does not exist." << std::endl;
      else
APIERROR(myTransaction->getNdbError());
   if (i !=3) {
     printf(" %2d
                   %2d %2d %d\n",
            rowData.attr1,
            rowData.attr2,
            myRecAttr3->u_32_value(),
            myRecAttrCC->u_32_value()
            );
   }
   myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read and print all tuples via table scan *
static void do_scan(Ndb &myNdb, ApiType accessType)
```

```
NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
const NdbDictionary::Table *myTable=
                          myDict->getTable("api_recattr_vs_record");
std::cout << "Running do_scan\n";</pre>
if (myTable == NULL)
  APIERROR(myDict->getNdbError());
std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
NdbTransaction *myTransaction=myNdb.startTransaction();
if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
NdbScanOperation *psop;
NdbRecAttr *recAttrAttr1;
NdbRecAttr *recAttrAttr2;
NdbRecAttr *recAttrAttr3;
switch (accessType)
  case api_attr :
    psop=myTransaction->getNdbScanOperation(myTable);
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    if (psop->readTuples(NdbOperation::LM_Read) != 0)
     APIERROR (myTransaction->getNdbError());
    recAttrAttr1=psop->getValue("ATTR1");
    recAttrAttr2=psop->getValue("ATTR2");
    recAttrAttr3=psop->getValue("ATTR3");
    break;
  case api_record :
    /* Note that no row ptr is passed to the NdbRecord scan operation
     * The scan will fetch a batch and give the user a series of pointers
     * to rows in the batch in nextResult() below
     * /
    psop=myTransaction->scanTable(pallColsRecord,
                                  NdbOperation::LM_Read);
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    break;
default :
  std::cout << "Bad branch : " << accessType << "\n";</pre>
  exit(-1);
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
  APIERROR(myTransaction->getNdbError());
switch (accessType)
case api_attr :
  while (psop->nextResult(true) == 0)
    printf(" %2d
                  %2d
                         %2d\n",
           recAttrAttr1->u_32_value(),
```

```
recAttrAttr2->u_32_value(),
            recAttrAttr3->u_32_value());
   }
   psop->close();
   break;
 case api_record :
   RowData *prowData; // Ptr to point to our data
   int rc=0;
   /* Ask nextResult to update out ptr to point to the next
    * row from the scan
   while ((rc = psop->nextResult((const char**) &prowData,
                                  true,
                                  false)) == 0)
     printf(" %2d %2d %2d\n",
            prowData->attr1,
            prowData->attr2,
            prowData->attr3);
   if (rc != 1) APIERROR(myTransaction->getNdbError());
   psop->close(true);
   break;
 default :
   std::cout << "Bad branch : " << accessType << "\n";
   exit(-1);
 if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read and print all tuples via table scan and mixed read *
static void do_mixed_scan(Ndb &myNdb)
 std::cout << "Running do_mixed_scan(NdbRecord only)\n";</pre>
 std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbScanOperation *psop;
 NdbRecAttr *recAttrAttr3;
  /* Set mask so that NdbRecord scan reads attr1 and attr2 only */
 unsigned char attrMask=((1<<attr1ColNum) | (1<<attr2ColNum));</pre>
  /* Define extra get value to get attr3 */
```

```
NdbOperation::GetValueSpec extraGets[1];
  extraGets[0].column = pattr3Col;
  extraGets[0].appStorage= 0;
  extraGets[0].recAttr= 0;
 NdbScanOperation::ScanOptions options;
 options.optionsPresent= NdbScanOperation::ScanOptions::SO_GETVALUE;
  options.extraGetValues= &extraGets[0];
 options.numExtraGetValues= 1;
 psop=myTransaction->scanTable(pallColsRecord,
                                NdbOperation::LM_Read,
                                &attrMask,
                                &options,
                                sizeof(NdbScanOperation::ScanOptions));
  if (psop == NULL) APIERROR(myTransaction->getNdbError());
  /* RecAttr for the extra get has been set by the operation definition */
 recAttrAttr3 = extraGets[0].recAttr;
  if (recAttrAttr3 == NULL) APIERROR(myTransaction->getNdbError());
  if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
   APIERROR(myTransaction->getNdbError());
 RowData *prowData; // Ptr to point to our data
  int rc=0;
  while ((rc = psop->nextResult((const char**) &prowData,
                                true,
                                false)) == 0)
   printf(" %2d %2d %2d\n",
          prowData->attr1,
          prowData->attr2,
           recAttrAttr3->u_32_value());
  if (rc != 1) APIERROR(myTransaction->getNdbError());
 psop->close(true);
  if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
  std::cout << "----\n";
 * Read and print all tuples via primary ordered index scan *
static void do_indexScan(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Index *myPIndex=
                  myDict->getIndex("PRIMARY", "api_recattr_vs_record");
 std::cout << "Running do_indexScan\n";</pre>
  if (myPIndex == NULL)
   APIERROR(myDict->getNdbError());
```

```
std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
NdbTransaction *myTransaction=myNdb.startTransaction();
if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
NdbIndexScanOperation *psop;
/* RecAttrs for NdbRecAttr Api */
NdbRecAttr *recAttrAttr1;
NdbRecAttr *recAttrAttr2;
NdbRecAttr *recAttrAttr3;
switch (accessType)
  case api_attr :
    psop=myTransaction->getNdbIndexScanOperation(myPIndex);
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    /* Multi read range is not supported for the NdbRecAttr scan
    * API, so we just read one range.
    * /
    Uint32 scanFlags=
     NdbScanOperation::SF_OrderBy |
      NdbScanOperation::SF_MultiRange
      NdbScanOperation::SF_ReadRangeNo;
    if (psop->readTuples(NdbOperation::LM_Read,
                         scanFlags,
                         (Uint32) 0, // batch
(Uint32) 0) != 0) // parallel
     APIERROR (myTransaction->getNdbError());
    /* Add a bound
     * Tuples where ATTR1 >=2 and < 4
     * 2,[3 deleted]
    Uint32 low=2;
    Uint32 high=4;
    if (psop->setBound("ATTR1",
                      NdbIndexScanOperation::BoundLE, (char*)&low))
      APIERROR(myTransaction->getNdbError());
    if (psop->setBound("ATTR1",
                      NdbIndexScanOperation::BoundGT, (char*)&high))
      APIERROR(myTransaction->getNdbError());
    if (psop->end_of_bound(0))
     APIERROR(psop->getNdbError());
    /* Second bound
     * Tuples where ATTR1 > 5 and \leq 9
     * 6,7,8,9
    * /
    low=5;
    high=9;
    if (psop->setBound("ATTR1",
                     NdbIndexScanOperation::BoundLT, (char*)&low))
      APIERROR(myTransaction->getNdbError());
    if (psop->setBound("ATTR1",
                      NdbIndexScanOperation::BoundGE, (char*)&high))
      APIERROR(myTransaction->getNdbError());
    if (psop->end_of_bound(1))
```

```
APIERROR(psop->getNdbError());
  /* Read all columns */
  recAttrAttr1=psop->getValue("ATTR1");
  recAttrAttr2=psop->getValue("ATTR2");
  recAttrAttr3=psop->getValue("ATTR3");
  break;
case api_record :
  /* NdbRecord supports scanning multiple ranges using a
  * single index scan operation
  Uint32 scanFlags =
   NdbScanOperation::SF_OrderBy |
   NdbScanOperation::SF_MultiRange
   NdbScanOperation::SF_ReadRangeNo;
  NdbScanOperation::ScanOptions options;
  options.optionsPresent=NdbScanOperation::ScanOptions::SO_SCANFLAGS;
  options.scan_flags=scanFlags;
  psop=myTransaction->scanIndex(pkeyIndexRecord,
                                pallColsRecord,
                                NdbOperation::LM_Read,
                                NULL, // no mask; read all columns
                                      // in result record
                                NULL, // bound defined later
                                &options,
                                sizeof(NdbScanOperation::ScanOptions));
  if (psop == NULL) APIERROR(myTransaction->getNdbError());
  /* Add a bound
   * Tuples where ATTR1 >=2 and <4
   * 2,[3 deleted]
  Uint32 low=2;
  Uint32 high=4;
  NdbIndexScanOperation::IndexBound bound;
  bound.low_key=(char*)&low;
  bound.low_key_count=1;
  bound.low_inclusive=true;
  bound.high_key=(char*)&high;
  bound.high_key_count=1;
  bound.high_inclusive=false;
  bound.range_no=0;
  if (psop->setBound(pkeyIndexRecord, bound))
   APIERROR(myTransaction->getNdbError());
  /* Second bound
   * Tuples where ATTR1 > 5 and <=9
   * 6,7,8,9
  * /
  low=5;
  high=9;
  bound.low_key=(char*)&low;
  bound.low_key_count=1;
  bound.low_inclusive=false;
  bound.high_key=(char*)&high;
  bound.high_key_count=1;
  bound.high_inclusive=true;
  bound.range_no=1;
```

```
if (psop->setBound(pkeyIndexRecord, bound))
     APIERROR(myTransaction->getNdbError());
   break;
default :
 {
   std::cout << "Bad branch : " << accessType << "\n";
   exit(-1);
}
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
 APIERROR(myTransaction->getNdbError());
if (myTransaction->getNdbError().code != 0)
 APIERROR(myTransaction->getNdbError());
switch (accessType)
 case api_attr :
   while (psop->nextResult(true) == 0)
     printf(" %2d
                   %2d
                         %2d
                                Range no : %2d\n",
           recAttrAttr1->u_32_value(),
            recAttrAttr2->u_32_value(),
            recAttrAttr3->u_32_value(),
            psop->get_range_no());
   psop->close();
   break;
 case api_record :
   RowData *prowData; // Ptr to point to our data
   int rc=0;
   while ((rc = psop->nextResult((const char**) &prowData,
                                true,
                                false)) == 0)
     // printf(" PTR : %d\n", (int) prowData);
     prowData->attr1,
            prowData->attr2,
            prowData->attr3,
            psop->get_range_no());
   if (rc != 1) APIERROR(myTransaction->getNdbError());
   psop->close(true);
   break;
 default :
   std::cout << "Bad branch : " << accessType << "\n";
   exit(-1);
```

```
if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read and print all tuples via index scan using mixed NdbRecord access *
***********************
static void do_mixed_indexScan(Ndb &myNdb)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Index *myPIndex=
                   myDict->getIndex("PRIMARY", "api_recattr_vs_record");
 std::cout << "Running do_mixed_indexScan\n";</pre>
 if (myPIndex == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbIndexScanOperation *psop;
 NdbRecAttr *recAttrAttr3;
 Uint32 scanFlags =
   NdbScanOperation::SF_OrderBy |
   NdbScanOperation::SF_MultiRange
   NdbScanOperation::SF_ReadRangeNo;
  /* We'll get Attr3 via ScanOptions */
 unsigned char attrMask=((1<<attr1ColNum) | (1<<attr2ColNum));</pre>
 NdbOperation::GetValueSpec extraGets[1];
 extraGets[0].column= pattr3Col;
 extraGets[0].appStorage= NULL;
 extraGets[0].recAttr= NULL;
 NdbScanOperation::ScanOptions options;
 options.optionsPresent=
   NdbScanOperation::ScanOptions::SO_SCANFLAGS |
   NdbScanOperation::ScanOptions::SO_GETVALUE;
 options.scan_flags= scanFlags;
 options.extraGetValues= &extraGets[0];
 options.numExtraGetValues= 1;
 psop=myTransaction->scanIndex(pkeyIndexRecord,
                               pallColsRecord,
                               NdbOperation::LM_Read,
                               &attrMask, // mask
                               NULL, // bound defined below
                               &options,
                               sizeof(NdbScanOperation::ScanOptions));
 if (psop == NULL) APIERROR(myTransaction->getNdbError());
  /* Grab RecAttr now */
 recAttrAttr3= extraGets[0].recAttr;
 /* Add a bound
```

```
* ATTR1 >= 2, < 4
 * 2,[3 deleted]
 * /
Uint32 low=2;
Uint32 high=4;
NdbIndexScanOperation::IndexBound bound;
bound.low_key=(char*)&low;
bound.low_key_count=1;
bound.low_inclusive=true;
bound.high_key=(char*)&high;
bound.high_key_count=1;
bound.high_inclusive=false;
bound.range no=0;
if (psop->setBound(pkeyIndexRecord, bound))
 APIERROR(myTransaction->getNdbError());
/* Second bound
 * ATTR1 > 5, <= 9
 * 6,7,8,9
 * /
low=5;
high=9;
bound.low_key=(char*)&low;
bound.low_key_count=1;
bound.low_inclusive=false;
bound.high_key=(char*)&high;
bound.high_key_count=1;
bound.high_inclusive=true;
bound.range_no=1;
if (psop->setBound(pkeyIndexRecord, bound))
 APIERROR(myTransaction->getNdbError());
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
 APIERROR(myTransaction->getNdbError());
RowData *prowData; // Ptr to point to our data
int rc=0;
while ((rc = psop->nextResult((const char**) &prowData,
                              true,
                              false)) == 0)
  printf(" %2d %2d %2d
                              Range no : %2d\n",
        prowData->attr1,
         prowData->attr2,
         recAttrAttr3->u_32_value(),
         psop->get_range_no());
if (rc != 1) APIERROR(myTransaction->getNdbError());
psop->close(true);
if(myTransaction->execute( NdbTransaction::Commit ) !=0)
 APIERROR(myTransaction->getNdbError());
myNdb.closeTransaction(myTransaction);
std::cout << "----\n";
```

```
/*****************
* Read + Delete one tuple (the one with primary key 8) *
static void do_read_and_delete(Ndb &myNdb)
  /* This procedure performs a single operation, single round
  * trip read and then delete of a tuple, specified by
  * primary key
 std::cout << "Running do_read_and_delete (NdbRecord only)\n";</pre>
 NdbTransaction *myTransaction= myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 RowData row;
 row.attr1=8;
  row.attr2=0; // Don't care
 row.attr3=0; // Don't care
  /* We'll also read some extra columns while we're
  * reading + deleting
  * /
 NdbOperation::OperationOptions options;
 NdbOperation::GetValueSpec extraGets[2];
  extraGets[0].column = pattr3Col;
  extraGets[0].appStorage = NULL;
 extraGets[0].recAttr = NULL;
  extraGets[1].column = NdbDictionary::Column::COMMIT_COUNT;
  extraGets[1].appStorage = NULL;
  extraGets[1].recAttr = NULL;
 options.optionsPresent= NdbOperation::OperationOptions::OO_GETVALUE;
 options.extraGetValues= &extraGets[0];
 options.numExtraGetValues= 2;
 unsigned char attrMask = (1<<attr2ColNum); // Only read Col2 into row
  const NdbOperation *pop=
   myTransaction->deleteTuple(pkeyColumnRecord, // Spec of key used
                              (char*) &row, // Key information
                              pallColsRecord, // Spec of columns to read
                              (char*) &row, // Row to read values into
                              &attrMask, // Cols to read as part of delete
                              sizeof(NdbOperation::OperationOptions));
  if (pop==NULL) APIERROR(myTransaction->getNdbError());
  if (myTransaction->execute(NdbTransaction::Commit) == -1)
   APIERROR(myTransaction->getNdbError());
  std::cout << "ATTR1 ATTR2 ATTR3 COMMITS" << std::endl;
  printf(" %2d
               %2d
                      %2d %2d\n",
        row.attr1,
        row.attr2,
        extraGets[0].recAttr->u_32_value(),
        extraGets[1].recAttr->u_32_value());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/* Some handy consts for scan control */
static const int GOT_ROW= 0;
static const int NO_MORE_ROWS= 1;
```

```
static const int NEED_TO_FETCH_ROWS= 2;
 * Read and update all tuples via table scan *
static void do_scan_update(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                              myDict->getTable("api_recattr_vs_record");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "Running do_scan_update\n";</pre>
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbScanOperation *psop;
 NdbRecAttr *recAttrAttr1;
 NdbRecAttr *recAttrAttr2;
 NdbRecAttr *recAttrAttr3;
 switch (accessType)
   case api_attr :
      psop=myTransaction->getNdbScanOperation(myTable);
      if (psop == NULL) APIERROR(myTransaction->getNdbError());
      /* When we want to operate on the tuples returned from a
       * scan, we need to request the tuple's keyinfo is
       * returned, with SF_KeyInfo
      if (psop->readTuples(NdbOperation::LM_Read,
                          NdbScanOperation::SF_KeyInfo) != 0)
       APIERROR (myTransaction->getNdbError());
      recAttrAttr1=psop->getValue("ATTR1");
      recAttrAttr2=psop->getValue("ATTR2");
      recAttrAttr3=psop->getValue("ATTR3");
     break;
   case api_record :
      NdbScanOperation::ScanOptions options;
      options.optionsPresent= NdbScanOperation::ScanOptions::SO_SCANFLAGS;
      options.scan_flags= NdbScanOperation::SF_KeyInfo;
      psop=myTransaction->scanTable(pallColsRecord,
                                    NdbOperation::LM_Read,
                                    NULL, // mask - read all columns
                                    &options,
                                    sizeof(NdbScanOperation::ScanOptions));
      if (psop == NULL) APIERROR(myTransaction->getNdbError());
      break;
 default :
      std::cout << "Bad branch : " << accessType << "\n";
      exit(-1);
```

```
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
 APIERROR(myTransaction->getNdbError());
switch (accessType)
 case api_attr :
   int result= NEED_TO_FETCH_ROWS;
   Uint32 processed= 0;
   while (result == NEED_TO_FETCH_ROWS)
      bool fetch=true;
     while ((result = psop->nextResult(fetch)) == GOT_ROW)
        fetch= false;
       Uint32 col2Value=recAttrAttr2->u_32_value();
       NdbOperation *op=psop->updateCurrentTuple();
       if (op==NULL)
         APIERROR(myTransaction->getNdbError());
       op->setValue("ATTR2", (10*col2Value));
       processed++;
      if (result < 0)
       APIERROR(myTransaction->getNdbError());
      if (processed !=0)
        // Need to execute
        if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
         APIERROR(myTransaction->getNdbError());
       processed=0;
   psop->close();
   break;
 case api_record :
   RowData *prowData; // Ptr to point to our data
   int result= NEED_TO_FETCH_ROWS;
   Uint32 processed=0;
   while (result == NEED_TO_FETCH_ROWS)
     bool fetch= true;
     while ((result = psop->nextResult((const char**) &prowData,
                                       fetch, false)) == GOT_ROW)
       fetch= false;
        /* Copy row into a stack variable */
       RowData r= *prowData;
        /* Modify attr2 */
       r.attr2*= 10;
```

```
/* Update it */
         const NdbOperation *op = psop->updateCurrentTuple(myTransaction,
                                                             pallColsRecord,
                                                             (char*) &r);
          if (op==NULL)
           APIERROR(myTransaction->getNdbError());
         processed ++;
        if (result < 0)
         APIERROR(myTransaction->getNdbError());
       if (processed !=0)
          /* To get here, there are no more cached scan results,
           * and some row updates that we've not sent yet.
           * Send them before we try to get another batch, or
           * finish.
          * /
         if (myTransaction->execute( NdbTransaction::NoCommit ) != 0)
           APIERROR(myTransaction->getNdbError());
         processed=0;
     psop->close(true);
     break;
   default :
     std::cout << "Bad branch : " << accessType << "\n";
     exit(-1);
 if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read all and delete some tuples via table scan *
static void do_scan_delete(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                              myDict->getTable("api_recattr_vs_record");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "Running do_scan_delete\n";</pre>
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbScanOperation *psop;
 NdbRecAttr *recAttrAttr1;
```

```
/* Scan, retrieving first column.
* Delete particular records, based on first column
* Read third column as part of delete
switch (accessType)
  case api_attr :
    psop=myTransaction->getNdbScanOperation(myTable);
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    /* Need KeyInfo when performing scanning delete */
    if (psop->readTuples(NdbOperation::LM_Read,
                         NdbScanOperation::SF_KeyInfo) != 0)
      APIERROR (myTransaction->getNdbError());
    recAttrAttr1=psop->getValue("ATTR1");
    break;
 case api_record :
    NdbScanOperation::ScanOptions options;
    \verb"options.optionsPresent=NdbScanOperation": \verb"ScanOptions": \verb"SO_SCANFLAGS"; \\
    /* Need KeyInfo when performing scanning delete */
    options.scan_flags=NdbScanOperation::SF_KeyInfo;
    psop=myTransaction->scanTable(pkeyColumnRecord,
                                   NdbOperation::LM_Read,
                                   NULL, // mask
                                   &options,
                                   sizeof(NdbScanOperation::ScanOptions));
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
   break;
default :
    std::cout << "Bad branch : " << accessType << "\n";
    exit(-1);
}
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
 APIERROR(myTransaction->getNdbError());
switch (accessType)
  case api_attr :
    int result= NEED_TO_FETCH_ROWS;
    Uint32 processed=0;
    while (result == NEED_TO_FETCH_ROWS)
      bool fetch=true;
      while ((result = psop->nextResult(fetch)) == GOT_ROW)
        fetch= false;
        Uint32 col1Value=recAttrAttr1->u_32_value();
        if (col1Value == 2)
```

```
/* Note : We cannot do a delete pre-read via
         * the NdbRecAttr interface. We can only
         * delete here.
        if (psop->deleteCurrentTuple())
         APIERROR(myTransaction->getNdbError());
        processed++;
    if (result < 0)
      APIERROR(myTransaction->getNdbError());
   if (processed !=0)
      /* To get here, there are no more cached scan results,
       * and some row deletes that we've not sent yet.
       * Send them before we try to get another batch, or
      * finish.
      if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
        APIERROR(myTransaction->getNdbError());
      processed=0;
 psop->close();
 break;
case api_record :
  RowData *prowData; // Ptr to point to our data
  int result= NEED_TO_FETCH_ROWS;
  Uint32 processed=0;
  while (result == NEED_TO_FETCH_ROWS)
   bool fetch=true;
   const NdbOperation* theDeleteOp;
   RowData readRow;
   NdbRecAttr* attr3;
   NdbRecAttr* commitCount;
   while ((result = psop->nextResult((const char**) &prowData,
                                      fetch,
                                      false)) == GOT_ROW)
      fetch = false;
      /* Copy latest row to a stack local */
      RowData r;
      r= *prowData;
      if (r.attr1 == 2)
        /* We're going to perform a read+delete on this
        * row. We'll read attr1 and attr2 vian NDBRecord
         * and Attr3 and the commit count via extra
         * get values.
        * /
        NdbOperation::OperationOptions options;
        NdbOperation::GetValueSpec extraGets[2];
        extraGets[0].column = pattr3Col;
        extraGets[0].appStorage = NULL;
        extraGets[0].recAttr = NULL;
```

```
extraGets[1].column = NdbDictionary::Column::COMMIT_COUNT;
        extraGets[1].appStorage = NULL;
        extraGets[1].recAttr = NULL;
        options.optionsPresent= NdbOperation::OperationOptions::OO_GETVALUE;
        options.extraGetValues= &extraGets[0];
        options.numExtraGetValues= 2;
        // Read cols 1 + 2 vian NDBRecord
        unsigned char attrMask =
                (1<<attr1ColNum) | (1<<attr2ColNum);</pre>
        theDeleteOp =
          psop->deleteCurrentTuple(myTransaction,
                                      pallColsRecord,
                                      (char*) &readRow,
                                      &attrMask,
                                      &options,
                                      sizeof(NdbOperation::OperationOptions)
        if (theDeleteOp==NULL)
          APIERROR(myTransaction->getNdbError());
        /* Store extra Get RecAttrs */
        attr3= extraGets[0].recAttr;
        commitCount= extraGets[1].recAttr;
        processed ++;
    if (result < 0)
      APIERROR(myTransaction->getNdbError());
    if (processed !=0)
      /* To get here, there are no more cached scan results,
      * and some row deletes that we've not sent yet.
      * Send them before we try to get another batch, or
       * finish.
      if (myTransaction->execute( NdbTransaction::NoCommit ) != 0)
       APIERROR(myTransaction->getNdbError());
      processed=0;
      // Let's look at the data just read
      printf("Deleted data\n");
      printf("ATTR1 ATTR2 ATTR3 COMMITS\n");
      printf(" %2d %2d
                             %2d
                                    %2d\n",
            readRow.attr1,
             readRow.attr2,
             attr3->u_32_value(),
             commitCount->u_32_value());
  psop->close(true);
  break;
default :
  std::cout << "Bad branch : " << accessType << "\n";
  exit(-1);
```

```
if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/*****************
* Read all tuples via scan, reread one with lock takeover *
static void do_scan_lock_reread(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                             myDict->getTable("api_recattr_vs_record");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "Running do_scan_lock_reread\n";</pre>
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbScanOperation *psop;
 NdbRecAttr *recAttrAttr1;
 switch (accessType)
   case api_attr :
     psop=myTransaction->getNdbScanOperation(myTable);
     if (psop == NULL) APIERROR(myTransaction->getNdbError());
     /* Need KeyInfo for lock takeover */
     if (psop->readTuples(NdbOperation::LM_Read,
                          NdbScanOperation::SF_KeyInfo) != 0)
       APIERROR (myTransaction->getNdbError());
     recAttrAttr1=psop->getValue("ATTR1");
     break;
   case api_record :
     NdbScanOperation::ScanOptions options;
     options.optionsPresent= NdbScanOperation::ScanOptions::SO_SCANFLAGS;
      /* Need KeyInfo for lock takeover */
     options.scan_flags= NdbScanOperation::SF_KeyInfo;
     psop=myTransaction->scanTable(pkeyColumnRecord,
                                   NdbOperation::LM_Read,
                                   NULL, // mask
                                   &options,
                                   sizeof(NdbScanOperation::ScanOptions));
     if (psop == NULL) APIERROR(myTransaction->getNdbError());
     break;
  default :
```

```
std::cout << "Bad branch : " << accessType << "\n";</pre>
   exit(-1);
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
 APIERROR(myTransaction->getNdbError());
switch (accessType)
 case api_attr :
   int result= NEED_TO_FETCH_ROWS;
   Uint32 processed=0;
   NdbRecAttr *attr1, *attr2, *attr3, *commitCount;
   while (result == NEED_TO_FETCH_ROWS)
      bool fetch=true;
      while ((result = psop->nextResult(fetch)) == GOT_ROW)
        fetch= false;
       Uint32 col1Value=recAttrAttr1->u_32_value();
        if (col1Value == 9)
         /* Let's read the rest of the info for it with
          * a separate operation
         NdbOperation *op= psop->lockCurrentTuple();
         if (op==NULL)
           APIERROR(myTransaction->getNdbError());
         attr1=op->getValue("ATTR1");
         attr2=op->getValue("ATTR2");
         attr3=op->getValue("ATTR3");
         commitCount=op->getValue(NdbDictionary::Column::COMMIT_COUNT);
         processed++;
      if (result < 0)
       APIERROR(myTransaction->getNdbError());
      if (processed !=0)
        // Need to execute
       if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
         APIERROR(myTransaction->getNdbError());
       processed=0;
       // Let's look at the whole row...
       printf("Locked and re-read data:\n");
       printf("ATTR1 ATTR2 ATTR3 COMMITS\n");
       printf(" %2d %2d
                              %2d
              attr1->u_32_value(),
              attr2->u_32_value(),
              attr3->u_32_value(),
               commitCount->u_32_value());
   psop->close();
   break;
```

```
case api_record :
  RowData *prowData; // Ptr to point to our data
  int result= NEED_TO_FETCH_ROWS;
  Uint32 processed=0;
  RowData rereadData;
  NdbRecAttr *attr3, *commitCount;
  while (result == NEED_TO_FETCH_ROWS)
   bool fetch=true;
   while ((result = psop->nextResult((const char**) &prowData,
                                      fetch,
                                       false)) == GOT_ROW)
      fetch = false;
      /* Copy row to stack local */
      RowData r;
      r=*prowData;
      if (r.attr1 == 9)
        /* Perform extra read of this row via lockCurrentTuple
        * Read all columns using NdbRecord for attr1 + attr2,
         * and extra get values for attr3 and the commit count
        NdbOperation::OperationOptions options;
        NdbOperation::GetValueSpec extraGets[2];
        extraGets[0].column = pattr3Col;
        extraGets[0].appStorage = NULL;
        extraGets[0].recAttr = NULL;
        extraGets[1].column = NdbDictionary::Column::COMMIT_COUNT;
        extraGets[1].appStorage = NULL;
        extraGets[1].recAttr = NULL;
        options.optionsPresent=NdbOperation::OperationOptions::OO_GETVALUE;
        options.extraGetValues=&extraGets[0];
        options.numExtraGetValues=2;
        // Read cols 1 + 2 vian NDBRecord
        unsigned char attrMask =
                    (1<<attr1ColNum) | (1<<attr2ColNum);</pre>
        const NdbOperation *lockOp =
            psop->lockCurrentTuple(myTransaction,
                                      pallColsRecord,
                                       (char *) &rereadData,
                                      &attrMask,
                                      &options,
                                      sizeof(NdbOperation::OperationOptions)
        if (lockOp == NULL)
          APIERROR(myTransaction->getNdbError());
        attr3= extraGets[0].recAttr;
        commitCount= extraGets[1].recAttr;
        processed++;
    if (result < 0)
      APIERROR(myTransaction->getNdbError());
```

```
if (processed !=0)
         // Need to execute
         if (myTransaction->execute( NdbTransaction::NoCommit ) != 0)
          APIERROR(myTransaction->getNdbError());
         processed=0;
         // Let's look at the whole row...
         printf("Locked and re-read data:\n");
         printf("ATTR1 ATTR2 ATTR3 COMMITS\n");
         printf(" %2d %2d %2d\n",
               rereadData.attr1,
               rereadData.attr2,
                attr3->u_32_value(),
                commitCount->u_32_value());
     psop->close(true);
     break;
   default :
     std::cout << "Bad branch : " << accessType << "\n";
     exit(-1);
 if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/*********************
 * Read all tuples via primary key, using only extra getValues *
 ***********************
static void do_all_extras_read(Ndb &myNdb)
 std::cout << "Running do_all_extras_read(NdbRecord only)\n";</pre>
 std::cout << "ATTR1 ATTR2 ATTR3 COMMIT_COUNT" << std::endl;</pre>
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   RowData rowData;
   NdbRecAttr *myRecAttr1, *myRecAttr2, *myRecAttr3, *myRecAttrCC;
   /* We read nothing vian NDBRecord, and everything via
    * 'extra' reads
   NdbOperation::GetValueSpec extraCols[4];
   extraCols[0].column=pattr1Col;
   extraCols[0].appStorage=NULL;
   extraCols[0].recAttr=NULL;
   extraCols[1].column=pattr2Col;
   extraCols[1].appStorage=NULL;
   extraCols[1].recAttr=NULL;
```

```
extraCols[2].column=pattr3Col;
   extraCols[2].appStorage=NULL;
   extraCols[2].recAttr=NULL;
   extraCols[3].column=NdbDictionary::Column::COMMIT_COUNT;
   extraCols[3].appStorage=NULL;
   extraCols[3].recAttr=NULL;
   NdbOperation::OperationOptions opts;
   opts.optionsPresent = NdbOperation::OperationOptions::OO_GETVALUE;
   opts.extraGetValues=&extraCols[0];
   opts.numExtraGetValues=4;
   unsigned char attrMask= 0; // No row results required.
   // Set PK search criteria
   rowData.attrl= i;
   const NdbOperation *pop=
     myTransaction->readTuple(pkeyColumnRecord,
                             (char*) &rowData,
                             pkeyColumnRecord,
                             NULL, // null result row
                             NdbOperation::LM_Read,
                             &attrMask,
                             &opts);
   if (pop==NULL) APIERROR(myTransaction->getNdbError());
   myRecAttr1=extraCols[0].recAttr;
   myRecAttr2=extraCols[1].recAttr;
   myRecAttr3=extraCols[2].recAttr;
   myRecAttrCC=extraCols[3].recAttr;
   if (myRecAttr1 == NULL) APIERROR(myTransaction->getNdbError());
   if (myRecAttr2 == NULL) APIERROR(myTransaction->getNdbError());
   if (myRecAttr3 == NULL) APIERROR(myTransaction->getNdbError());
   if (myRecAttrCC == NULL) APIERROR(myTransaction->getNdbError());
   if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   bool deleted= (myTransaction->getNdbError().classification ==
                 NdbError::NoDataFound);
   if (deleted)
     printf("Detected that deleted tuple %d doesn't exist!\n", i);
   else
     printf(" %2d
                  %2d %2d
                                %d\n",
            myRecAttr1->u_32_value(),
            myRecAttr2->u_32_value(),
            myRecAttr3->u_32_value(),
            myRecAttrCC->u_32_value()
            );
   }
   myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/*********************
 * Read and print some tuples via bounded scan of secondary index *
 *********************
static void do_secondary_indexScan(Ndb &myNdb, ApiType accessType)
```

```
NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
const NdbDictionary::Index *mySIndex=
              myDict->getIndex("MYINDEXNAME", "api_recattr_vs_record");
std::cout << "Running do_secondary_indexScan\n";</pre>
std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
NdbTransaction *myTransaction=myNdb.startTransaction();
if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
NdbIndexScanOperation *psop;
NdbRecAttr *recAttrAttr1;
NdbRecAttr *recAttrAttr2;
NdbRecAttr *recAttrAttr3;
Uint32 scanFlags =
  NdbScanOperation::SF_OrderBy |
  NdbScanOperation::SF_Descending
  NdbScanOperation::SF_MultiRange
  NdbScanOperation::SF_ReadRangeNo;
switch (accessType)
  case api_attr :
    psop=myTransaction->getNdbIndexScanOperation(mySIndex);
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    if (psop->readTuples(NdbOperation::LM_Read,
                          scanFlags,
                          (Uint32) 0,
                                               // batch
                          (Uint32) 0) != 0)
                                               // parallel
      APIERROR (myTransaction->getNdbError());
    /* Bounds :
     * > ATTR3=6
     * < ATTR3=42
     * /
    Uint32 low=6;
    Uint32 high=42;
    if (psop->setBound("ATTR3",
                      NdbIndexScanOperation::BoundLT, (char*)&low))
      APIERROR(psop->getNdbError());
    if (psop->setBound("ATTR3",
                      NdbIndexScanOperation::BoundGT, (char*)&high))
      APIERROR(psop->getNdbError());
    recAttrAttr1=psop->getValue("ATTR1");
    recAttrAttr2=psop->getValue("ATTR2");
    recAttrAttr3=psop->getValue("ATTR3");
  case api_record :
    NdbScanOperation::ScanOptions options;
    options.optionsPresent=NdbScanOperation::ScanOptions::SO_SCANFLAGS;
    options.scan_flags=scanFlags;
    psop=myTransaction->scanIndex(psecondaryIndexRecord,
                                   pallColsRecord,
                                   NdbOperation::LM_Read,
```

```
NULL, // mask
                                  NULL, // bound
                                  &options,
                                  sizeof(NdbScanOperation::ScanOptions));
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    /* Bounds :
     * > ATTR3=6
     * < ATTR3=42
     * /
    Uint32 low=6;
    Uint32 high=42;
    NdbIndexScanOperation::IndexBound bound;
    bound.low_key=(char*)&low;
    bound.low_key_count=1;
    bound.low_inclusive=false;
    bound.high_key=(char*)&high;
    bound.high_key_count=1;
    bound.high_inclusive=false;
    bound.range_no=0;
    if (psop->setBound(psecondaryIndexRecord, bound))
      APIERROR(myTransaction->getNdbError());
   break;
default :
    std::cout << "Bad branch : " << accessType << "\n";
    exit(-1);
}
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
  APIERROR(myTransaction->getNdbError());
// Check rc anyway
if (myTransaction->getNdbError().status != NdbError::Success)
  APIERROR(myTransaction->getNdbError());
switch (accessType)
  case api_attr :
    while (psop->nextResult(true) == 0)
      printf(" %2d %2d %2d
                                  Range no : %2d\n",
            recAttrAttr1->u_32_value(),
             recAttrAttr2->u_32_value(),
            recAttrAttr3->u_32_value(),
             psop->get_range_no());
    psop->close();
   break;
  case api_record :
    RowData *prowData; // Ptr to point to our data
    int rc=0;
    while ((rc = psop->nextResult((const char**) &prowData,
                                  true,
```

```
false)) == 0)
        // printf(" PTR : %d\n", (int) prowData);
       printf(" %2d %2d %2d
                                    Range no : %2d\n",
              prowData->attr1,
              prowData->attr2,
               prowData->attr3,
               psop->get_range_no());
     if (rc != 1) APIERROR(myTransaction->getNdbError());
      psop->close(true);
     break;
   default :
      std::cout << "Bad branch : " << accessType << "\n";
  if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
 * Index scan to read tuples from secondary index using equality bound *
static void do_secondary_indexScanEqual(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Index *mySIndex=
               myDict->getIndex("MYINDEXNAME", "api_recattr_vs_record");
  std::cout << "Running do_secondary_indexScanEqual\n";</pre>
 std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;</pre>
 NdbTransaction *myTransaction=myNdb.startTransaction();
 if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
 NdbIndexScanOperation *psop;
 NdbRecAttr *recAttrAttr1;
 NdbRecAttr *recAttrAttr2;
 NdbRecAttr *recAttrAttr3;
 Uint32 scanFlags = NdbScanOperation::SF_OrderBy;
 Uint32 attr3Eq= 44;
  switch (accessType)
   case api_attr :
     psop=myTransaction->getNdbIndexScanOperation(mySIndex);
      if (psop == NULL) APIERROR(myTransaction->getNdbError());
      if (psop->readTuples(NdbOperation::LM_Read,
                           scanFlags,
                           (Uint32) 0,
                                                // batch
```

```
(Uint32) 0) != 0)
                                              // parallel
      APIERROR (myTransaction->getNdbError());
    if (psop->setBound("ATTR3",
                     NdbIndexScanOperation::BoundEQ, (char*)&attr3Eq))
      APIERROR(myTransaction->getNdbError());
    recAttrAttr1=psop->getValue("ATTR1");
    recAttrAttr2=psop->getValue("ATTR2");
    recAttrAttr3=psop->getValue("ATTR3");
    break;
  case api_record :
    NdbScanOperation::ScanOptions options;
    options.optionsPresent= NdbScanOperation::ScanOptions::SO_SCANFLAGS;
    options.scan_flags=scanFlags;
    psop=myTransaction->scanIndex(psecondaryIndexRecord,
                                  pallColsRecord, // Read all table rows back
                                  NdbOperation::LM_Read,
                                  NULL, // mask
                                  NULL, // bound specified below
                                  &options,
                                  sizeof(NdbScanOperation::ScanOptions));
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
    /* Set equality bound via two inclusive bounds */
    NdbIndexScanOperation::IndexBound bound;
    bound.low_key= (char*)&attr3Eq;
    bound.low_key_count= 1;
    bound.low_inclusive= true;
    bound.high_key= (char*)&attr3Eq;
    bound.high_key_count= 1;
    bound.high_inclusive= true;
    bound.range_no= 0;
    if (psop->setBound(psecondaryIndexRecord, bound))
      APIERROR(myTransaction->getNdbError());
   break;
default :
    std::cout << "Bad branch : " << accessType << "\n";</pre>
    exit(-1);
}
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
  APIERROR(myTransaction->getNdbError());
// Check rc anyway
if (myTransaction->getNdbError().status != NdbError::Success)
  APIERROR(myTransaction->getNdbError());
switch (accessType)
  case api_attr :
    int res;
    while ((res= psop->nextResult(true)) == GOT_ROW)
```

```
printf(" %2d %2d
                             %2d\n",
              recAttrAttr1->u_32_value(),
              recAttrAttr2->u_32_value(),
              recAttrAttr3->u_32_value());
     if (res != NO_MORE_ROWS)
       APIERROR(psop->getNdbError());
     psop->close();
     break;
   case api_record :
     RowData *prowData; // Ptr to point to our data
     int rc=0;
     while ((rc = psop->nextResult((const char**) &prowData,
                                   true, // fetch
                                   false)) // forceSend
             == GOT_ROW)
       printf(" %2d %2d %2d\n",
              prowData->attr1,
              prowData->attr2,
              prowData->attr3);
     if (rc != NO_MORE_ROWS)
       APIERROR(myTransaction->getNdbError());
     psop->close(true);
     break;
   default :
     std::cout << "Bad branch : " << accessType << "\n";
     exit(-1);
  if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
 * Interpreted update *
static void do_interpreted_update(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                             myDict->getTable("api_recattr_vs_record");
 const NdbDictionary::Index *myPIndex=
                       myDict->getIndex("PRIMARY", "api_recattr_vs_record");
 std::cout << "Running do_interpreted_update\n";</pre>
```

```
if (myTable == NULL)
  APIERROR(myDict->getNdbError());
if (myPIndex == NULL)
 APIERROR(myDict->getNdbError());
std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
NdbTransaction *myTransaction=myNdb.startTransaction();
if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
NdbRecAttr *recAttrAttr1;
NdbRecAttr *recAttrAttr2;
NdbRecAttr *recAttrAttr3;
NdbRecAttr *recAttrAttr11;
NdbRecAttr *recAttrAttr12;
NdbRecAttr *recAttrAttr13;
RowData rowData;
RowData rowData2;
/* Register aliases */
const Uint32 R1=1, R2=2, R3=3, R4=4, R5=5, R6=6;
switch (accessType)
  case api_attr :
    NdbOperation *pop;
    pop=myTransaction->getNdbOperation(myTable);
    if (pop == NULL) APIERROR(myTransaction->getNdbError());
    if (pop->interpretedUpdateTuple())
      APIERROR (pop->getNdbError());
    /* Interpreted update on row where ATTR1 == 4 */
    if (pop->equal("ATTR1", 4) != 0)
      APIERROR (pop->getNdbError());
    /* First, read the values of all attributes in the normal way */
    recAttrAttr1=pop->getValue("ATTR1");
    recAttrAttr2=pop->getValue("ATTR2");
    recAttrAttr3=pop->getValue("ATTR3");
    /* Now define interpreted program which will run after the
     * values have been read
     * This program is rather tortuous and doesn't achieve much other
     * than demonstrating control flow, register and some column
     * operations
     * /
    // R5 = 3
    if (pop->load_const_u32(R5, 3) != 0)
      APIERROR (pop->getNdbError());
    // R1= *ATTR1; R2= *ATTR2; R3= *ATTR3
    if (pop->read_attr("ATTR1", R1) != 0)
     APIERROR (pop->getNdbError());
    if (pop->read_attr("ATTR2", R2) != 0)
      APIERROR (pop->getNdbError());
    if (pop->read_attr("ATTR3", R3) != 0)
      APIERROR (pop->getNdbError());
    // R3= R3-R5
    if (pop->sub_reg(R3, R5, R3) != 0)
      APIERROR (pop->getNdbError());
    // R2= R1+R2
```

```
if (pop->add_reg(R1, R2, R2) != 0)
  APIERROR (pop->getNdbError());
// *ATTR2= R2
if (pop->write_attr("ATTR2", R2) != 0)
 APIERROR (pop->getNdbError());
// *ATTR3= R3
if (pop->write_attr("ATTR3", R3) != 0)
 APIERROR (pop->getNdbError());
// *ATTR3 = *ATTR3 - 30
if (pop->subValue("ATTR3", (Uint32)30) != 0)
 APIERROR (pop->getNdbError());
Uint32 comparisonValue= 10;
// if *ATTR3 > comparisonValue, goto Label 0
if (pop->branch_col_lt(pattr3Col->getColumnNo(),
                       &comparisonValue,
                       sizeof(Uint32),
                       false,
                       0) != 0)
 APIERROR (pop->getNdbError());
// assert(false)
// Fail the operation with error 627 if we get here.
if (pop->interpret_exit_nok(627) != 0)
  APIERROR (pop->getNdbError());
// Label 0
if (pop->def_label(0) != 0)
  APIERROR (pop->getNdbError());
Uint32 comparisonValue2= 344;
// if *ATTR2 == comparisonValue, goto Label 1
if (pop->branch_col_eq(pattr2Col->getColumnNo(),
                       &comparisonValue2,
                       sizeof(Uint32),
                       false,
                       1) != 0)
 APIERROR (pop->getNdbError());
// assert(false)
// Fail the operation with error 628 if we get here
if (pop->interpret_exit_nok(628) != 0)
  APIERROR (pop->getNdbError());
// Label 1
if (pop->def_label(1) != 1)
 APIERROR (pop->getNdbError());
// Optional infinite loop
//if (pop->branch_label(0) != 0)
// APIERROR (pop->getNdbError());
// R1 = 10
if (pop->load_const_u32(R1, 10) != 0)
 APIERROR (pop->getNdbError());
// R3 = 2
if (pop->load_const_u32(R3, 2) != 0)
  APIERROR (pop->getNdbError());
// Now call subroutine 0
if (pop->call_sub(0) != 0)
```

```
APIERROR (pop->getNdbError());
// *ATTR2= R2
if (pop->write_attr("ATTR2", R2) != 0)
 APIERROR (pop->getNdbError());
// Return ok, we'll move onto an update.
if (pop->interpret_exit_ok() != 0)
 APIERROR (pop->getNdbError());
/* Define a final read of the columns after the update */
recAttrAttr11= pop->getValue("ATTR1");
recAttrAttr12= pop->getValue("ATTR2");
recAttrAttr13= pop->getValue("ATTR3");
// Define any subroutines called by the 'main' program
// Subroutine 0
if (pop->def_subroutine(0) != 0)
 APIERROR (pop->getNdbError());
// R4= 1
if (pop->load_const_u32(R4, 1) != 0)
 APIERROR (pop->getNdbError());
// Label 2
if (pop->def_label(2) != 2)
 APIERROR (pop->getNdbError());
// R3= R3-R4
if (pop->sub_reg(R3, R4, R3) != 0)
 APIERROR (pop->getNdbError());
// R2 = R2 + R1
if (pop->add_reg(R2, R1, R2) != 0)
 APIERROR (pop->getNdbError());
// Optional infinite loop
// if (pop->branch_label(2) != 0)
// APIERROR (pop->getNdbError());
// Loop, subtracting 1 from R4 until R4 < 1 \,
if (pop->branch_ge(R4, R3, 2) != 0)
 APIERROR (pop->getNdbError());
// Jump to label 3
if (pop->branch_label(3) != 0)
 APIERROR (pop->getNdbError());
// assert(false)
// Fail operation with error 629
if (pop->interpret_exit_nok(629) != 0)
 APIERROR (pop->getNdbError());
// Label 3
if (pop->def_label(3) != 3)
 APIERROR (pop->getNdbError());
// Nested subroutine call to sub 2
if (pop->call_sub(2) != 0)
 APIERROR (pop->getNdbError());
// Return from subroutine 0
if (pop->ret_sub() !=0)
 APIERROR (pop->getNdbError());
// Subroutine 1
if (pop->def_subroutine(1) != 1)
```

```
APIERROR (pop->getNdbError());
  // R6= R1+R2
  if (pop->add_reg(R1, R2, R6) != 0)
    APIERROR (pop->getNdbError());
  // Return from subrouine 1
  if (pop->ret_sub() !=0)
    APIERROR (pop->getNdbError());
  // Subroutine 2
  if (pop->def_subroutine(2) != 2)
    APIERROR (pop->getNdbError());
  // Call backward to subroutine 1
  if (pop->call_sub(1) != 0)
    APIERROR (pop->getNdbError());
  // Return from subroutine 2
  if (pop->ret_sub() !=0)
    APIERROR (pop->getNdbError());
 break;
case api_record :
  const NdbOperation *pop;
 rowData.attr1= 4;
  /* NdbRecord does not support an updateTuple pre-read or post-read, so
   * we use separate operations for these.
   ^{\star} Note that this assumes that a operations are executed in
   * the order they are defined by NDBAPI, which is not guaranteed. To
   * ensure execution order, the application should perform a NoCommit
   * execute between operations.
  const NdbOperation *op0= myTransaction->readTuple(pkeyColumnRecord,
                                                      (char*) &rowData,
                                                     pallColsRecord,
                                                      (char*) &rowData);
  if (op0 == NULL)
    APIERROR (myTransaction->getNdbError());
  /* Allocate some space to define an Interpreted program */
  const Uint32 numWords= 64;
  Uint32 space[numWords];
  NdbInterpretedCode stackCode(myTable,
                                &space[0],
                                numWords);
  NdbInterpretedCode *code= &stackCode;
  /* Similar program as above, with tortuous control flow and little
   * purpose. Note that for NdbInterpretedCode, some instruction
   \mbox{\ensuremath{\star}} arguments are in different orders
   * /
  // R5= 3
  if (code->load_const_u32(R5, 3) != 0)
   APIERROR(code->getNdbError());
  // R1= *ATTR1; R2= *ATTR2; R3= *ATTR3
  if (code->read_attr(R1, pattr1Col) != 0)
    APIERROR (code->getNdbError());
  if (code->read_attr(R2, pattr2Col) != 0)
```

```
APIERROR (code->getNdbError());
if (code->read_attr(R3, pattr3Col) != 0)
 APIERROR (code->getNdbError());
// R3= R3-R5
if (code->sub_reg(R3, R3, R5) != 0)
 APIERROR (code->getNdbError());
// R2= R1+R2
if (code->add_reg(R2, R1, R2) != 0)
 APIERROR (code->getNdbError());
// *ATTR2= R2
if (code->write_attr(pattr2Col, R2) != 0)
 APIERROR (code->getNdbError());
// *ATTR3= R3
if (code->write_attr(pattr3Col, R3) != 0)
 APIERROR (code->getNdbError());
// *ATTR3 = *ATTR3 - 30
if (code->sub_val(pattr3Col->getColumnNo(), (Uint32)30) != 0)
 APIERROR (code->getNdbError());
Uint32 comparisonValue= 10;
// if comparisonValue < *ATTR3, goto Label 0
if (code->branch_col_lt(&comparisonValue,
                        sizeof(Uint32),
                        pattr3Col->getColumnNo(),
                        0) != 0)
 APIERROR (code->getNdbError());
// assert(false)
// Fail operation with error 627
if (code->interpret_exit_nok(627) != 0)
 APIERROR (code->getNdbError());
// Label 0
if (code->def_label(0) != 0)
 APIERROR (code->getNdbError());
Uint32 comparisonValue2= 344;
// if *ATTR2 == comparisonValue, goto Label 1
if (code->branch_col_eq(&comparisonValue2,
                        sizeof(Uint32),
                        pattr2Col->getColumnNo(),
                        1) != 0)
 APIERROR (code->getNdbError());
// assert(false)
// Fail operation with error 628
if (code->interpret_exit_nok(628) != 0)
 APIERROR (code->getNdbError());
// Label 1
if (code->def_label(1) != 0)
 APIERROR (code->getNdbError());
if (code->load_const_u32(R1, 10) != 0)
 APIERROR (code->getNdbError());
// R3 = 2
if (code->load_const_u32(R3, 2) != 0)
  APIERROR (code->getNdbError());
```

```
// Call subroutine 0 to effect
// R2 = R2 + (R1*R3)
if (code->call_sub(0) != 0)
 APIERROR (code->getNdbError());
// *ATTR2= R2
if (code->write_attr(pattr2Col, R2) != 0)
  APIERROR (code->getNdbError());
// Return ok
if (code->interpret_exit_ok() != 0)
 APIERROR (code->getNdbError());
// Subroutine 0
if (code->def_sub(0) != 0)
 APIERROR (code->getNdbError());
// R4 = 1
if (code->load_const_u32(R4, 1) != 0)
  APIERROR (code->getNdbError());
// Label 2
if (code->def_label(2) != 0)
 APIERROR (code->getNdbError());
// R3= R3-R4
if (code->sub_reg(R3, R3, R4) != 0)
  APIERROR (code->getNdbError());
// R2= R2+R1
if (code->add_reg(R2, R2, R1) != 0)
  APIERROR (code->getNdbError());
// Loop, subtracting 1 from R4 until R4>1
if (code->branch_ge(R3, R4, 2) != 0)
  APIERROR (code->getNdbError());
// Jump to label 3
if (code->branch_label(3) != 0)
  APIERROR (code->getNdbError());
// Fail operation with error 629
if (code->interpret_exit_nok(629) != 0)
  APIERROR (code->getNdbError());
// Label 3
if (code->def_label(3) != 0)
 APIERROR (code->getNdbError());
// Call sub 2
if (code->call_sub(2) != 0)
  APIERROR (code->getNdbError());
// Return from sub 0
if (code->ret_sub() != 0)
 APIERROR (code->getNdbError());
// Subroutine 1
if (code->def_sub(1) != 0)
  APIERROR (code->getNdbError());
// R6= R1+R2
if (code->add_reg(R6, R1, R2) != 0)
  APIERROR (code->getNdbError());
// Return from subroutine 1
```

```
if (code->ret_sub() !=0)
      APIERROR (code->getNdbError());
    // Subroutine 2
    if (code->def_sub(2) != 0)
      APIERROR (code->getNdbError());
    // Call backward to subroutine 1
    if (code->call_sub(1) != 0)
      APIERROR (code->getNdbError());
    // Return from subroutine 2
    if (code->ret_sub() !=0)
      APIERROR (code->getNdbError());
    /* Finalise code object
     * This step is essential for NdbInterpretedCode objects
     * and must be done before they can be used.
    if (code->finalise() !=0)
      APIERROR (code->getNdbError());
    /* Time to define the update operation to use the
     * InterpretedCode object. The same finalised object
     * could be used with multiple operations or even
     * multiple threads
    NdbOperation::OperationOptions oo;
    oo.optionsPresent=
     NdbOperation::OperationOptions::OO_INTERPRETED;
    oo.interpretedCode= code;
    unsigned char mask= 0;
    pop= myTransaction->updateTuple(pkeyColumnRecord,
                                    (char*) &rowData,
                                    pallColsRecord,
                                     (char*) &rowData,
                                     (const unsigned char *) &mask,
                                               // mask - update nothing
                                    . 00%
                                    sizeof(NdbOperation::OperationOptions));
    if (pop == NULL)
      APIERROR (myTransaction->getNdbError());
    // NoCommit execute so we can read the 'after' data.
    if (myTransaction->execute( NdbTransaction::NoCommit ) != 0)
      APIERROR(myTransaction->getNdbError());
    /* Second read op as we can't currently do a 'read after
     * 'interpreted code' read as part of NdbRecord.
     * We are assuming that the order of op definition == order
     * of execution on a single row, which is not guaranteed.
    const NdbOperation *pop2=
      myTransaction->readTuple(pkeyColumnRecord,
                               (char*) &rowData,
                               pallColsRecord,
                               (char*) &rowData2);
    if (pop2 == NULL)
      APIERROR (myTransaction->getNdbError());
    break;
default :
    std::cout << "Bad branch : " << accessType << "\n";
```

```
exit(-1);
   }
 }
 if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
   APIERROR(myTransaction->getNdbError());
 // Check return code
 if (myTransaction->getNdbError().status != NdbError::Success)
   APIERROR(myTransaction->getNdbError());
 switch (accessType)
   case api_attr :
     printf(" %2d
                  %2d %2d Before\n"
            " %2d
                  %2d %2d After\n",
           recAttrAttr1->u_32_value(),
            recAttrAttr2->u_32_value(),
            recAttrAttr3->u_32_value(),
            recAttrAttr11->u_32_value(),
            recAttrAttr12->u_32_value(),
            recAttrAttr13->u_32_value());
     break;
   case api_record :
     rowData.attr1,
            rowData.attr2,
            rowData.attr3.
            rowData2.attr1,
            rowData2.attr2,
            rowData2.attr3);
     break;
   default :
     std::cout << "Bad branch : " << accessType << "\n";
     exit(-1);
 }
 if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
* Read and print selected rows with interpreted code *
 ************************************
static void do_interpreted_scan(Ndb &myNdb, ApiType accessType)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                            myDict->getTable("api_recattr_vs_record");
 std::cout << "Running do_interpreted_scan\n";</pre>
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
```

```
std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
NdbTransaction *myTransaction=myNdb.startTransaction();
if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
NdbScanOperation *psop;
NdbRecAttr *recAttrAttr1;
NdbRecAttr *recAttrAttr2;
NdbRecAttr *recAttrAttr3;
/* Create some space on the stack for the program */
const Uint32 numWords= 64;
Uint32 space[numWords];
NdbInterpretedCode stackCode(myTable,
                             &space[0],
                             numWords);
NdbInterpretedCode *code= &stackCode;
/* RecAttr and NdbRecord scans both use NdbInterpretedCode
 * Let's define a small scan filter of sorts
Uint32 comparisonValue= 10;
// Return rows where 10 > ATTR3 (ATTR3 <10)
if (code->branch_col_gt(&comparisonValue,
                        sizeof(Uint32),
                        pattr3Col->getColumnNo(),
                        0) != 0)
  APIERROR (myTransaction->getNdbError());
/* If we get here then we don't return this row */
if (code->interpret_exit_nok() != 0)
 APIERROR (myTransaction->getNdbError());
/* Label 0 */
if (code->def_label(0) != 0)
  APIERROR (myTransaction->getNdbError());
/* Return this row */
if (code->interpret_exit_ok() != 0)
  APIERROR (myTransaction->getNdbError());
/* Finalise the Interpreted Program */
if (code->finalise() != 0)
  APIERROR (myTransaction->getNdbError());
switch (accessType)
  case api_attr :
    psop=myTransaction->getNdbScanOperation(myTable);
    if (psop == NULL)
      APIERROR(myTransaction->getNdbError());
    if (psop->readTuples(NdbOperation::LM_Read) != 0)
      APIERROR (myTransaction->getNdbError());
    if (psop->setInterpretedCode(code) != 0)
      APIERROR (myTransaction->getNdbError());
    recAttrAttr1=psop->getValue("ATTR1");
    recAttrAttr2=psop->getValue("ATTR2");
    recAttrAttr3=psop->getValue("ATTR3");
```

```
break;
  case api_record :
   NdbScanOperation::ScanOptions so;
    so.optionsPresent = NdbScanOperation::ScanOptions::SO_INTERPRETED;
    so.interpretedCode= code;
    psop=myTransaction->scanTable(pallColsRecord,
                                  NdbOperation::LM_Read,
                                  NULL, // mask
                                  &so,
                                  sizeof(NdbScanOperation::ScanOptions));
    if (psop == NULL) APIERROR(myTransaction->getNdbError());
   break;
default :
   std::cout << "Bad branch : " << accessType << "\n";
    exit(-1);
if(myTransaction->execute( NdbTransaction::NoCommit ) != 0)
  APIERROR(myTransaction->getNdbError());
switch (accessType)
  case api_attr :
    while (psop->nextResult(true) == 0)
     printf(" %2d
                   %2d %2d\n",
            recAttrAttr1->u_32_value(),
            recAttrAttr2->u_32_value(),
            recAttrAttr3->u_32_value());
    psop->close();
   break;
  case api_record :
    RowData *prowData; // Ptr to point to our data
    int rc=0;
    while ((rc = psop->nextResult((const char**) &prowData,
                                  true,
                                  false)) == GOT_ROW)
                    %2d
      printf(" %2d
                           %2d\n",
            prowData->attr1,
             prowData->attr2,
             prowData->attr3);
    if (rc != NO_MORE_ROWS) APIERROR(myTransaction->getNdbError());
    psop->close(true);
    break;
```

```
default :
     std::cout << "Bad branch : " << accessType << "\n";</pre>
     exit(-1);
 }
 if(myTransaction->execute( NdbTransaction::Commit ) !=0)
   APIERROR(myTransaction->getNdbError());
 myNdb.closeTransaction(myTransaction);
 std::cout << "----\n";
/****************
* Read some data using the default NdbRecord objects *
static void do_read_using_default(Ndb &myNdb)
 NdbDictionary::Dictionary* myDict= myNdb.getDictionary();
 const NdbDictionary::Table *myTable=
                             myDict->getTable("api_recattr_vs_record");
 const NdbRecord* tableRec= myTable->getDefaultRecord();
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 std::cout << "Running do_read_using_default_record (NdbRecord only)\n";</pre>
 std::cout << "ATTR1 ATTR2 ATTR3" << std::endl;
  /* Allocate some space for the rows to be read into */
 char* buffer= (char*)malloc(NdbDictionary::getRecordRowLength(tableRec));
 if (buffer == NULL)
   printf("Allocation failed\n");
   exit(-1);
 for (int i = 0; i < 10; i++) {
   NdbTransaction *myTransaction= myNdb.startTransaction();
   if (myTransaction == NULL) APIERROR(myNdb.getNdbError());
   char* attr1= NdbDictionary::getValuePtr(tableRec,
                                           attr1ColNum);
   *((unsigned int*)attrl)= i;
   const NdbOperation *pop=
     myTransaction->readTuple(tableRec,
                              buffer,
                              tableRec, // Read everything
                              buffer);
   if (pop==NULL) APIERROR(myTransaction->getNdbError());
   if(myTransaction->execute( NdbTransaction::Commit ) == -1)
     APIERROR(myTransaction->getNdbError());
   NdbError err= myTransaction->getNdbError();
   if (err.code != 0)
     if (err.classification == NdbError::NoDataFound)
       std::cout << "Tuple " << i
```

```
<< " does not exist." << std::endl;
   else
     APIERROR(myTransaction->getNdbError());
 else
   printf(" %2d
                   %2d
                        %2d\n",
          i,
           *((unsigned int*) NdbDictionary::getValuePtr(tableRec,
                                                        attr2ColNum)),
           *((unsigned int*) NdbDictionary::getValuePtr(tableRec,
                                                       buffer,
                                                        attr3ColNum)));
 myNdb.closeTransaction(myTransaction);
free(buffer);
std::cout << "----\n";
```

2.5.8 NDB API Event Handling Example

This example demonstrates NDB API event handling.

The source code for this program may be found in the NDB Cluster source tree, in the file storage/ndb/ndbapi_examples/ndbapi_event/ndbapi_event.cpp.

```
#include <NdbApi.hpp>
// Used for cout
#include <stdio.h>
#include <iostream>
#include <unistd.h>
#ifdef VM_TRACE
#include <my_global.h>
#endif
#ifndef assert
#include <assert.h>
#endif
* Assume that there is a table which is being updated by
 * another process (e.g. flexBench -1 0 -stdtables).
 * We want to monitor what happens with column values.
 * Or using the mysql client:
 * shell> mysql -u root
 * mysql> create database ndb_examples;
 * mysql> use ndb_examples;
 * mysql> create table t0
          (c0 int, c1 int, c2 char(4), c3 char(4), c4 text,
          primary key(c0, c2)) engine ndb charset latin1;
 * In another window start ndbapi_event, wait until properly started
   insert into t0 values (1, 2, 'a', 'b', null); insert into t0 values (3, 4, 'c', 'd', null);
   update t0 set c3 = 'e' where c0 = 1 and c2 = 'a'; -- use pk
   update t0 set c3 = 'f'; -- use scan
   update t0 set c3 = 'F'; -- use scan update to 'same'
```

```
update t0 set c2 = 'g' where c0 = 1; -- update pk part
  update t0 set c2 = 'G' where c0 = 1; -- update pk part to 'same'
  update t0 set c0 = 5, c2 = 'H' where c0 = 3; -- update full PK
  delete from t0;
  insert ...; update ...; -- see events w/ same pk merged (if -m option)
  delete ...; insert ...; -- there are 5 combinations ID IU DI UD UU
  update ...; update ...;
  -- text requires -m flag
  set @a = repeat('a',256); -- inline size
  set @b = repeat('b',2000); -- part size
  set @c = repeat('c',2000*30); -- 30 parts
   -- update the text field using combinations of @a, @b, @c ...
* you should see the data popping up in the example window
* /
#define APIERROR(error) \
  { std::cout << "Error in " << __FILE__ << ", line:" << __LINE__ << ", code:" \
             << error.code << ", msg: " << error.message << "." << std::endl; \</pre>
   exit(-1); }
int myCreateEvent(Ndb* myNdb,
   const char *eventName,
   const char *eventTableName,
   const char **eventColumnName,
   const int noEventColumnName,
                 bool merge_events);
int main(int argc, char** argv)
 if (argc < 3)
   std::cout << "Arguments are <connect_string cluster> <timeout> [m(merge events) | d(debug)].\n";
   exit(-1);
 const char *connection_string = argv[1];
 int timeout = atoi(argv[2]);
 ndb_init();
 bool merge_events = argc > 3 && strchr(argv[3], 'm') != 0;
#ifdef VM TRACE
 bool dbug = argc > 3 && strchr(argv[3], 'd') != 0;
 if (dbug) DBUG_PUSH("d:t:");
 if (dbug) putenv("API_SIGNAL_LOG=-");
#endif
 Ndb_cluster_connection *cluster_connection=
   new Ndb_cluster_connection(connection_string); // Object representing the cluster
 int r= cluster_connection->connect(5 /* retries
                                                                 */,
         3 /* delay between retries */,
                                   */);
        1 /* verbose
 if (r > 0)
   std::cout
     << "Cluster connect failed, possibly resolved with more retries.\n";
   exit(-1);
 else if (r < 0)
   std::cout
     << "Cluster connect failed.\n";</pre>
   exit(-1);
```

```
if (cluster_connection->wait_until_ready(30,30))
 std::cout << "Cluster was not ready within 30 secs." << std::endl;</pre>
  exit(-1);
Ndb* myNdb= new Ndb(cluster_connection,
      "ndb_examples"); // Object representing the database
if (myNdb->init() == -1) APIERROR(myNdb->getNdbError());
const char *eventName= "CHNG_IN_t0";
const char *eventTableName= "t0";
const int noEventColumnName= 5;
const char *eventColumnName[noEventColumnName]=
  {"c0",
   "c1",
   "c2",
   "c3",
   "c4"
 };
// Create events
myCreateEvent(myNdb,
eventName,
eventTableName,
eventColumnName,
noEventColumnName,
             merge_events);
// Normal values and blobs are unfortunately handled differently..
typedef union { NdbRecAttr* ra; NdbBlob* bh; } RA_BH;
int i, j, k, l;
j = 0;
while (j < timeout) {
  // Start "transaction" for handling events
  NdbEventOperation* op;
  printf("create EventOperation\n");
  if ((op = myNdb->createEventOperation(eventName)) == NULL)
   APIERROR(myNdb->getNdbError());
  op->mergeEvents(merge_events);
  printf("get values\n");
  RA_BH recAttr[noEventColumnName];
  RA_BH recAttrPre[noEventColumnName];
  // primary keys should always be a part of the result
  for (i = 0; i < noEventColumnName; i++) {</pre>
   if (i < 4) {
     recAttr[i].ra
                     = op->getValue(eventColumnName[i]);
      recAttrPre[i].ra = op->getPreValue(eventColumnName[i]);
    } else if (merge_events) {
     recAttr[i].bh = op->getBlobHandle(eventColumnName[i]);
      recAttrPre[i].bh = op->getPreBlobHandle(eventColumnName[i]);
  }
  // set up the callbacks
  printf("execute\n");
  // This starts changes to "start flowing"
  if (op->execute())
    APIERROR(op->getNdbError());
  NdbEventOperation* the_op = op;
```

```
i= 0;
   while (i < timeout) {</pre>
     // printf("now waiting for event...\n");
     int r = myNdb - pollEvents(1000); // wait for event or 1000 ms
    if (r > 0) {
// printf("got data! %d\n", r);
while ((op= myNdb->nextEvent())) {
         assert(the_op == op);
  switch (op->getEventType()) {
  case NdbDictionary::Event::TE_INSERT:
   printf("%u INSERT", i);
   break;
  case NdbDictionary::Event::TE_DELETE:
    printf("%u DELETE", i);
    break;
  case NdbDictionary::Event::TE_UPDATE:
    printf("%u UPDATE", i);
    break;
  default:
    abort(); // should not happen
         printf(" gci=%d\n", (int)op->getGCI());
         for (k = 0; k \le 1; k++) {
           printf(k == 0 ? "post: " : "pre : ");
           for (1 = 0; 1 < noEventColumnName; 1++) {</pre>
             if (1 < 4) {
               NdbRecAttr* ra = k == 0 ? recAttr[1].ra : recAttrPre[1].ra;
               if (ra->isNULL() >= 0) { // we have a value}
                 if (ra->isNULL() == 0) { // we have a non-null value}
                   if (1 < 2)
                     printf("%-5u", ra->u_32_value());
                   else
                     printf("%-5.4s", ra->aRef());
                 } else
                   printf("%-5s", "NULL");
               } else
                 printf("%-5s", "-"); // no value
             } else if (merge_events) {
               int isNull;
               NdbBlob* bh = k == 0 ? recAttr[1].bh : recAttrPre[1].bh;
               bh->getDefined(isNull);
               if (isNull >= 0) { // we have a value
                 if (! isNull) \{\ //\ \mbox{we have a non-null value}
                   Uint64 length = 0;
                   bh->getLength(length);
                   // read into buffer
                   unsigned char* buf = new unsigned char [length];
                   memset(buf, 'X', length);
                   Uint32 n = length;
                   bh->readData(buf, n); // n is in/out
                   assert(n == length);
                   // pretty-print
                   bool first = true;
                   Uint32 i = 0;
                   while (i < n) {
                     unsigned char c = buf[i++];
                     Uint32 m = 1;
                     while (i < n \&\& buf[i] == c)
                       i++, m++;
                     if (! first)
                      printf("+");
                     printf("%u%c", m, c);
                     first = false;
                   printf("[%u]", n);
                   delete [] buf;
```

```
} else
                    printf("%-5s", "NULL");
                } else
                  printf("%-5s", "-"); // no value
            printf("\n");
      } // else printf("timed out (%i)\n", timeout);
    // don't want to listen to events anymore
   if (myNdb->dropEventOperation(the_op)) APIERROR(myNdb->getNdbError());
   the_op = 0;
    j++;
   NdbDictionary::Dictionary *myDict = myNdb->getDictionary();
   if (!myDict) APIERROR(myNdb->getNdbError());
   // remove event from database
    if (myDict->dropEvent(eventName)) APIERROR(myDict->getNdbError());
  }
 delete myNdb;
 delete cluster_connection;
 ndb_end(0);
 return 0;
int myCreateEvent(Ndb* myNdb,
   const char *eventName,
   const char *eventTableName,
   const char **eventColumnNames,
   const int noEventColumnNames,
                 bool merge_events)
 NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
  if (!myDict) APIERROR(myNdb->getNdbError());
  const NdbDictionary::Table *table= myDict->getTable(eventTableName);
  if (!table) APIERROR(myDict->getNdbError());
 NdbDictionary::Event myEvent(eventName, *table);
 myEvent.addTableEvent(NdbDictionary::Event::TE_ALL);
  // myEvent.addTableEvent(NdbDictionary::Event::TE_INSERT);
  // myEvent.addTableEvent(NdbDictionary::Event::TE_UPDATE);
  // myEvent.addTableEvent(NdbDictionary::Event::TE_DELETE);
 myEvent.addEventColumns(noEventColumnNames, eventColumnNames);
 myEvent.mergeEvents(merge_events);
  // Add event to database
  if (myDict->createEvent(myEvent) == 0)
   myEvent.print();
  else if (myDict->getNdbError().classification ==
   NdbError::SchemaObjectExists) {
   printf("Event creation failed, event exists\n");
   printf("dropping Event...\n");
   if (myDict->dropEvent(eventName)) APIERROR(myDict->getNdbError());
   // try again
    // Add event to database
   if ( myDict->createEvent(myEvent)) APIERROR(myDict->getNdbError());
   APIERROR(myDict->getNdbError());
```

```
return 0;
```

2.5.9 NDB API Example: Basic BLOB Handling

This example illustrates the manipulation of a BLOB column in the NDB API. It demonstrates how to perform insert, read, and update operations, using both inline value buffers as well as read and write methods.

The source code can be found can be found in the file storage/ndb/ndbapi-examples/ndbapi blob/ndbapi blob.cpp in the NDB Cluster source tree.



Note

While the MySQL data type used in the example is actually $\ensuremath{\mathtt{TEXT}}$, the same principles apply

```
ndbapi_blob.cpp:
 Illustrates the manipulation of BLOB (actually TEXT in this example).
 Shows insert, read, and update, using both inline value buffer and
 read/write methods.
#ifdef _WIN32
#include <winsock2.h>
#endif
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>
#include <stdlib.h>
#include <string.h>
/* Used for cout. */
#include <iostream>
#include <stdio.h>
#include <ctype.h>
* Helper debugging macros
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
            << ", code: " << code \
            << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql),mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
/* Quote taken from Project Gutenberg. */
const char *text_quote=
"Just at this moment, somehow or other, they began to run.\n"
"\n"
" Alice never could quite make out, in thinking it over\n"
"afterwards, how it was that they began: all she remembers is, \n"
"that they were running hand in hand, and the Queen went so fast\n"
"that it was all she could do to keep up with her: and still the\n"
"Queen kept crying 'Faster! Faster!' but Alice felt she COULD NOT\n"
"go faster, though she had not breath left to say so.\n"
"\n"
" The most curious part of the thing was, that the trees and the \n"
```

```
"other things round them never changed their places at all:\n"
"however fast they went, they never seemed to pass anything. 'I\n"
"wonder if all the things move along with us?' thought poor\n"
"puzzled Alice. And the Queen seemed to guess her thoughts, for\n"
"she cried, 'Faster! Don't try to talk!'\n"
"\n"
" Not that Alice had any idea of doing THAT. She felt as if she \n"
"would never be able to talk again, she was getting so much out of \n"
"breath: and still the Queen cried 'Faster! Faster!' and dragged\n" her along. 'Are we nearly there?' Alice managed to pant out at\n"
"last.\n"
"\n"
  'Nearly there!' the Queen repeated. 'Why, we passed it ten\n"
"minutes ago! Faster!' And they ran on for a time in silence,\n"
"with the wind whistling in Alice's ears, and almost blowing her\n"
"hair off her head, she fancied.\n"
"\n"
" 'Now! Now!' cried the Queen. 'Faster! Faster!' And they\n"
"went so fast that at last they seemed to skim through the air,\n"
"hardly touching the ground with their feet, till suddenly, just\n"
"as Alice was getting quite exhausted, they stopped, and she found\n"
"herself sitting on the ground, breathless and giddy.\n"
" The Queen propped her up against a tree, and said kindly, 'You\n"
"may rest a little now.'\n"
"\n"
" Alice looked round her in great surprise. 'Why, I do believe\n"
"we've been under this tree the whole time! Everything's just as\n"
"it was!'\n"
"\n"
" 'Of course it is,' said the Queen, 'what would you have it?'\n"
"\n"
" 'Well, in OUR country,' said Alice, still panting a little,\n"
"'you'd generally get to somewhere else--if you ran very fast\n"
"for a long time, as we've been doing.'\n"
"\n"
" 'A slow sort of country!' said the Queen. 'Now, HERE, you see,\n"
"it takes all the running YOU can do, to keep in the same place.\n"
"If you want to get somewhere else, you must run at least twice as\n"
"fast as that!'\n"
" 'I'd rather not try, please!' said Alice. 'I'm quite content\n"
"to stay here--only I AM so hot and thirsty!'\n"
"\n"
" -- Lewis Carroll, 'Through the Looking-Glass'.";
Function to drop table.
void drop_table(MYSQL &mysql)
 if (mysql_query(&mysql, "DROP TABLE api_blob"))
    MYSQLERROR(mysql);
 Functions to create table.
int try_create_table(MYSQL &mysql)
  return mysql_query(&mysql,
                      "CREATE TABLE"
                        api_blob"
                          (my_id INT UNSIGNED NOT NULL, "
                           my_text TEXT NOT NULL,"
                           PRIMARY KEY USING HASH (my_id))"
```

```
ENGINE=NDB");
void create_table(MYSQL &mysql)
 if (try_create_table(mysql))
   if (mysql_errno(&mysql) != ER_TABLE_EXISTS_ERROR)
     MYSQLERROR(mysql);
   std::cout << "NDB Cluster already has example table: api_blob. "
             << "Dropping it..." << std::endl;</pre>
    * Recreate table *
     ************
   drop_table(mysql);
   if (try_create_table(mysql))
     MYSQLERROR(mysql);
int populate(Ndb *myNdb)
 const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbOperation *myNdbOperation= myTrans->getNdbOperation(myTable);
 if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 myNdbOperation->insertTuple();
 myNdbOperation->equal("my_id", 1);
 NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
 if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
 myBlobHandle->setValue(text_quote, strlen(text_quote));
 int check= myTrans->execute(NdbTransaction::Commit);
 myTrans->close();
 return check != -1;
int update_key(Ndb *myNdb)
   Uppercase all characters in TEXT field, using primary key operation.
   Use piece-wise read/write to avoid loading entire data into memory
   at once.
 const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbOperation *myNdbOperation= myTrans->getNdbOperation(myTable);
 if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 myNdbOperation->updateTuple();
```

```
myNdbOperation->equal("my_id", 1);
  NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
  if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
  /* Execute NoCommit to make the blob handle active. */
  if (-1 == myTrans->execute(NdbTransaction::NoCommit))
   APIERROR(myTrans->getNdbError());
 Uint64 length= 0;
 if (-1 == myBlobHandle->getLength(length))
   APIERROR(myBlobHandle->getNdbError());
   A real application should use a much larger chunk size for
   efficiency, preferably much larger than the part size, which
   defaults to 2000. 64000 might be a good value.
#define CHUNK_SIZE 100
  int chunk;
  char buffer[CHUNK_SIZE];
  for (chunk= (length-1)/CHUNK_SIZE; chunk >=0; chunk--)
   Uint64 pos= chunk*CHUNK_SIZE;
   Uint32 chunk_length= CHUNK_SIZE;
   if (pos + chunk_length > length)
      chunk_length= length - pos;
    /* Read from the end back, to illustrate seeking. */
   if (-1 == myBlobHandle->setPos(pos))
      APIERROR(myBlobHandle->getNdbError());
   if (-1 == myBlobHandle->readData(buffer, chunk_length))
     APIERROR(myBlobHandle->getNdbError());
    int res= myTrans->execute(NdbTransaction::NoCommit);
   if (-1 == res)
     APIERROR(myTrans->getNdbError());
    /* Uppercase everything. */
   for (Uint64 j= 0; j < chunk_length; j++)</pre>
      buffer[j] = toupper(buffer[j]);
    if (-1 == myBlobHandle->setPos(pos))
      APIERROR(myBlobHandle->getNdbError());
   if (-1 == myBlobHandle->writeData(buffer, chunk_length))
     APIERROR(myBlobHandle->getNdbError());
    /* Commit on the final update. */
    if (-1 == myTrans->execute(chunk ?
                               NdbTransaction::NoCommit :
                               NdbTransaction::Commit))
      APIERROR(myTrans->getNdbError());
  }
 myNdb->closeTransaction(myTrans);
 return 1;
int update_scan(Ndb *myNdb)
   Lowercase all characters in TEXT field, using a scan with
   updateCurrentTuple().
  char buffer[10000];
 const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
```

```
const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbScanOperation *myScanOp= myTrans->getNdbScanOperation(myTable);
 if (myScanOp == NULL)
   APIERROR(myTrans->getNdbError());
 myScanOp->readTuples(NdbOperation::LM_Exclusive);
 NdbBlob *myBlobHandle= myScanOp->getBlobHandle("my_text");
  if (myBlobHandle == NULL)
   APIERROR(myScanOp->getNdbError());
  if (myBlobHandle->getValue(buffer, sizeof(buffer)))
   APIERROR(myBlobHandle->getNdbError());
  /* Start the scan. */
 if (-1 == myTrans->execute(NdbTransaction::NoCommit))
   APIERROR(myTrans->getNdbError());
  int res;
 for (;;)
   res= myScanOp->nextResult(true);
   if (res==1)
      break;
                                                // Scan done.
    else if (res)
     APIERROR(myScanOp->getNdbError());
   Uint64 length= 0;
   if (myBlobHandle->getLength(length) == -1)
      APIERROR(myBlobHandle->getNdbError());
    /* Lowercase everything. */
   for (Uint64 j= 0; j < length; j++)
     buffer[j] = tolower(buffer[j]);
   NdbOperation *myUpdateOp= myScanOp->updateCurrentTuple();
   if (myUpdateOp == NULL)
      APIERROR(myTrans->getNdbError());
   NdbBlob *myBlobHandle2= myUpdateOp->getBlobHandle("my_text");
   if (myBlobHandle2 == NULL)
      APIERROR(myUpdateOp->getNdbError());
   if (myBlobHandle2->setValue(buffer, length))
      APIERROR(myBlobHandle2->getNdbError());
   if (-1 == myTrans->execute(NdbTransaction::NoCommit))
      APIERROR(myTrans->getNdbError());
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 return 1;
struct ActiveHookData {
 char buffer[10000];
 Uint32 readLength;
int myFetchHook(NdbBlob* myBlobHandle, void* arg)
```

```
ActiveHookData *ahd= (ActiveHookData *)arg;
  ahd->readLength= sizeof(ahd->buffer) - 1;
  return myBlobHandle->readData(ahd->buffer, ahd->readLength);
int fetch_key(Ndb *myNdb)
   Fetch and show the blob field, using setActiveHook().
  const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
  const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
    APIERROR(myNdb->getNdbError());
 NdbOperation *myNdbOperation= myTrans->getNdbOperation(myTable);
  if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 myNdbOperation->readTuple();
  myNdbOperation->equal("my_id", 1);
 NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
  if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
  struct ActiveHookData ahd;
  if (myBlobHandle->setActiveHook(myFetchHook, &ahd) == -1)
    APIERROR(myBlobHandle->getNdbError());
   Execute Commit, but calling our callback set up in setActiveHook()
   before actually committing.
  if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
  /* Our fetch callback will have been called during the execute(). */
 ahd.buffer[ahd.readLength] = '\0';
 std::cout << "Fetched data:" << std::endl << ahd.buffer << std::endl;</pre>
 return 1;
int update2_key(Ndb *myNdb)
 char buffer[10000];
  /* Simple setValue() update. */
 const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
  const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
  if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
  if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbOperation *myNdbOperation= myTrans->getNdbOperation(myTable);
  if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
```

```
myNdbOperation->updateTuple();
 myNdbOperation->equal("my_id", 1);
 NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
 if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
 memset(buffer, ' ', sizeof(buffer));
 if (myBlobHandle->setValue(buffer, sizeof(buffer)) == -1)
   APIERROR(myBlobHandle->getNdbError());
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 return 1;
int delete_key(Ndb *myNdb)
  /* Deletion of blob row. */
 const NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_blob");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbOperation *myNdbOperation= myTrans->getNdbOperation(myTable);
 if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 myNdbOperation->deleteTuple();
 myNdbOperation->equal("my_id", 1);
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 return 1;
void mysql_connect_and_create(const char *socket)
 MYSQL mysql;
 bool ok;
 mysql_init(&mysql);
 ok = mysql_real_connect(&mysql, "localhost", "root", "", "", 0, socket, 0);
 if(ok) {
   mysql_query(&mysql, "CREATE DATABASE ndb_examples");
   ok = ! mysql_select_db(&mysql, "ndb_examples");
 if(ok) {
   create_table(mysql);
 mysql_close(&mysql);
 if(! ok) MYSQLERROR(mysql);
void ndb_run_blob_operations(const char *connectstring)
  /* Connect to ndb cluster. */
 Ndb_cluster_connection cluster_connection(connectstring);
 if (cluster_connection.connect(4, 5, 1))
```

```
std::cout << "Unable to connect to cluster within 30 secs." << std::endl;
    exit(-1);
  ^{\prime} Optionally connect and wait for the storage nodes (ndbd's). */
  if (cluster_connection.wait_until_ready(30,0) < 0)</pre>
    std::cout << "Cluster was not ready within 30 secs.\n";</pre>
    exit(-1);
 Ndb myNdb(&cluster_connection, "ndb_examples");
 if (myNdb.init(1024) == -1) { // Set max 1024 parallel transactions
   APIERROR(myNdb.getNdbError());
    exit(-1);
  if(populate(&myNdb) > 0)
    std::cout << "populate: Success!" << std::endl;</pre>
  if(update_key(&myNdb) > 0)
    std::cout << "update_key: Success!" << std::endl;</pre>
  if(update_scan(&myNdb) > 0)
    std::cout << "update_scan: Success!" << std::endl;</pre>
  if(fetch_key(&myNdb) > 0)
   std::cout << "fetch_key: Success!" << std::endl;</pre>
 if(update2_key(&myNdb) > 0)
    std::cout << "update2_key: Success!" << std::endl;</pre>
  if(delete_key(&myNdb) > 0)
    std::cout << "delete_key: Success!" << std::endl;</pre>
int main(int argc, char**argv)
  if (argc != 3)
    std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
 char *mysqld_sock = argv[1];
 const char *connectstring = argv[2];
 mysql_connect_and_create(mysqld_sock);
 ndb_init();
 ndb_run_blob_operations(connectstring);
 ndb_end(0);
 return 0;
```

2.5.10 NDB API Example: Handling BLOB Columns and Values Using NdbRecord

This example illustrates the manipulation of a BLOB column in the NDB API using the NdbRecord interface. It demonstrates how to perform insert, read, and update operations, using both inline value buffers as well as read and write methods. It can be found in the file storage/ndb/ndbapi-examples/ndbapi_blob_ndbrecord/main.cpp in the NDB Cluster source trees.



Note

While the MySQL data type used in the example is actually TEXT, the same principles apply

```
ndbapi_blob_ndbrecord
 Illustrates the manipulation of BLOB (actually TEXT in this example).
 This example uses the NdbRecord style way of accessing tuples.
 Shows insert, read, and update, using both inline value buffer and
 read/write methods.
#ifdef _WIN32
#include <winsock2.h>
#endif
#include <mysql.h>
#include <mysqld_error.h>
#include <NdbApi.hpp>
/* Used for cout. */
#include <iostream>
#include <stdio.h>
#include <ctype.h>
#include <stdlib.h>
#include <stddef.h>
#include <string.h>
* Helper debugging macros
#define PRINT_ERROR(code,msg) \
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__ \
            << ", code: " << code \
            << ", msg: " << msg << "." << std::endl
#define MYSQLERROR(mysql) { \
 PRINT_ERROR(mysql_errno(&mysql), mysql_error(&mysql)); \
 exit(-1); }
#define APIERROR(error) { \
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
/* Quote taken from Project Gutenberg. */
const char *text_quote=
"Just at this moment, somehow or other, they began to run.\n"
"\n"
" Alice never could quite make out, in thinking it over\n"
"afterwards, how it was that they began: all she remembers is,\n"
"that they were running hand in hand, and the Queen went so fast\n"
"that it was all she could do to keep up with her: and still the\n"
"Queen kept crying 'Faster! Faster!' but Alice felt she COULD NOT\n"
"go faster, though she had not breath left to say so.\n"
"\n"
" The most curious part of the thing was, that the trees and the \n"
"other things round them never changed their places at all:\n"
"however fast they went, they never seemed to pass anything. \label{eq:local_local_local}
"wonder if all the things move along with us?' thought poor\n"
"puzzled Alice. And the Queen seemed to guess her thoughts, for\n"
"she cried, 'Faster! Don't try to talk!'\n"
"\n"
Not that Alice had any idea of doing THAT. She felt as if she\n"
"would never be able to talk again, she was getting so much out of\n"
"breath: and still the Queen cried 'Faster! Faster!' and dragged\n"
"her along. 'Are we nearly there?' Alice managed to pant out at\n"
"last.\n"
```

```
"\n"
" 'Nearly there!' the Queen repeated. 'Why, we passed it ten\n"
"minutes ago! Faster!' And they ran on for a time in silence,\n"
"with the wind whistling in Alice's ears, and almost blowing her\n"
"hair off her head, she fancied.\n"
" 'Now! Now!' cried the Queen. 'Faster! Faster!' And they\n"
"went so fast that at last they seemed to skim through the air,\n"
"hardly touching the ground with their feet, till suddenly, just\n"
"as Alice was getting quite exhausted, they stopped, and she found\n"
"herself sitting on the ground, breathless and giddy.\n"
" The Queen propped her up against a tree, and said kindly, 'You\n"
"may rest a little now.'\n"
"\n"
" Alice looked round her in great surprise. 'Why, I do believe\n"
"we've been under this tree the whole time! Everything's just as\n"
"it was!'\n"
"\n"
" 'Of course it is,' said the Queen, 'what would you have it?'\n"
" 'Well, in OUR country,' said Alice, still panting a little,\n"
"'you'd generally get to somewhere else--if you ran very fast\n"
"for a long time, as we've been doing.'\n"
"\n"
" 'A slow sort of country!' said the Queen. 'Now, HERE, you see,\n"
"it takes all the running YOU can do, to keep in the same place.\n"
"If you want to get somewhere else, you must run at least twice as\n"
"fast as that!'\n"
" 'I'd rather not try, please!' said Alice. 'I'm quite content\n"
"to stay here--only I AM so hot and thirsty!'\n"
"\n"
" -- Lewis Carroll, 'Through the Looking-Glass'.";
/* NdbRecord objects. */
const NdbRecord *key_record;
                                                // For specifying table key
const NdbRecord *blob_record;
                                                // For accessing blob
const NdbRecord *full_record;
                                                // All columns, for insert
/* C struct representing the row layout */
struct MyRow
 unsigned int myId;
  /* Pointer to Blob handle for operations on the blob column
   * Space must be left for it in the row, but a pointer to the
   ^{\star} blob handle can also be obtained via calls to
   * NdbOperation::getBlobHandle()
  */
 NdbBlob* myText;
static void setup_records(Ndb *myNdb)
 NdbDictionary::RecordSpecification spec[2];
 NdbDictionary::Dictionary *myDict= myNdb->getDictionary();
 const NdbDictionary::Table *myTable= myDict->getTable("api_blob_ndbrecord");
 if (myTable == NULL)
   APIERROR(myDict->getNdbError());
  const NdbDictionary::Column *col1= myTable->getColumn("my_id");
  if (col1 == NULL)
   APIERROR(myDict->getNdbError());
  const NdbDictionary::Column *col2= myTable->getColumn("my_text");
 if (col2 == NULL)
```

```
APIERROR(myDict->getNdbError());
 spec[0].column= col1;
 spec[0].offset= offsetof(MyRow, myId);
 spec[0].nullbit_byte_offset= 0;
 spec[0].nullbit_bit_in_byte= 0;
 spec[1].column= col2;
 spec[1].offset= offsetof(MyRow, myText);
 spec[1].nullbit_byte_offset= 0;
 spec[1].nullbit_bit_in_byte= 0;
 key_record= myDict->createRecord(myTable, &spec[0], 1, sizeof(spec[0]));
 if (key_record == NULL)
   APIERROR(myDict->getNdbError());
 blob_record= myDict->createRecord(myTable, &spec[1], 1, sizeof(spec[0]));
 if (blob_record == NULL)
   APIERROR(myDict->getNdbError());
 full_record= myDict->createRecord(myTable, &spec[0], 2, sizeof(spec[0]));
 if (full_record == NULL)
   APIERROR(myDict->getNdbError());
 Function to drop table.
void drop_table(MYSQL &mysql)
 if (mysql_query(&mysql, "DROP TABLE api_blob_ndbrecord"))
   MYSQLERROR(mysql);
 Functions to create table.
int try_create_table(MYSQL &mysql)
 return mysql_query(&mysql,
                     "CREATE TABLE"
                     " api_blob_ndbrecord"
                         (my_id INT UNSIGNED NOT NULL,"
                           my_text TEXT NOT NULL, "
                           PRIMARY KEY USING HASH (my_id))"
                       ENGINE=NDB");
void create_table(MYSQL &mysql)
 if (try_create_table(mysql))
   if (mysql_errno(&mysql) != ER_TABLE_EXISTS_ERROR)
     MYSQLERROR(mysql);
   std::cout << "NDB Cluster already has example table: api_blob_ndbrecord. "
              << "Dropping it..." << std::endl;</pre>
    * Recreate table *
   drop_table(mysql);
   if (try_create_table(mysql))
     MYSQLERROR(mysql);
int populate(Ndb *myNdb)
 MyRow row;
```

```
NdbTransaction *myTrans= myNdb->startTransaction();
  if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 row.myId= 1;
 const NdbOperation *myNdbOperation= myTrans->insertTuple(full_record, (const char*) &row);
  if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
 if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
 myBlobHandle->setValue(text_quote, strlen(text_quote));
  int check= myTrans->execute(NdbTransaction::Commit);
 myTrans->close();
 return check != -1;
int update_key(Ndb *myNdb)
 MyRow row;
   Uppercase all characters in TEXT field, using primary key operation.
   Use piece-wise read/write to avoid loading entire data into memory
   at once.
 NdbTransaction *myTrans= myNdb->startTransaction();
  if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 row.myId= 1;
 const NdbOperation *myNdbOperation=
   myTrans->updateTuple(key_record,
                         (const char*) &row,
                         blob_record,
                         (const char*) &row);
  if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
 if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
  /* Execute NoCommit to make the blob handle active so
   * that we can determine the actual Blob length
  if (-1 == myTrans->execute(NdbTransaction::NoCommit))
   APIERROR(myTrans->getNdbError());
 Uint64 length= 0;
  if (-1 == myBlobHandle->getLength(length))
   APIERROR(myBlobHandle->getNdbError());
   A real application should use a much larger chunk size for
   efficiency, preferably much larger than the part size, which
   defaults to 2000. 64000 might be a good value.
#define CHUNK_SIZE 100
  int chunk;
 char buffer[CHUNK_SIZE];
 for (chunk= (length-1)/CHUNK_SIZE; chunk >=0; chunk--)
```

```
Uint64 pos= chunk*CHUNK_SIZE;
   Uint32 chunk_length= CHUNK_SIZE;
   if (pos + chunk_length > length)
     chunk_length= length - pos;
    /* Read from the end back, to illustrate seeking. */
   if (-1 == myBlobHandle->setPos(pos))
     APIERROR(myBlobHandle->getNdbError());
   if (-1 == myBlobHandle->readData(buffer, chunk_length))
     APIERROR(myBlobHandle->getNdbError());
   int res= myTrans->execute(NdbTransaction::NoCommit);
   if (-1 == res)
     APIERROR(myTrans->getNdbError());
   /* Uppercase everything. */
   for (Uint64 j= 0; j < chunk_length; j++)</pre>
     buffer[j]= toupper(buffer[j]);
   if (-1 == myBlobHandle->setPos(pos))
     APIERROR(myBlobHandle->getNdbError());
   if (-1 == myBlobHandle->writeData(buffer, chunk_length))
     APIERROR(myBlobHandle->getNdbError());
    /* Commit on the final update. */
   if (-1 == myTrans->execute(chunk ?
                               NdbTransaction::NoCommit :
                               NdbTransaction::Commit))
     APIERROR(myTrans->getNdbError());
 }
 myNdb->closeTransaction(myTrans);
 return 1;
int update_scan(Ndb *myNdb)
   Lowercase all characters in TEXT field, using a scan with
   updateCurrentTuple().
 char buffer[10000];
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 NdbScanOperation *myScanOp=
   myTrans->scanTable(blob_record, NdbOperation::LM_Exclusive);
 if (myScanOp == NULL)
   APIERROR(myTrans->getNdbError());
 NdbBlob *myBlobHandle= myScanOp->getBlobHandle("my_text");
 if (myBlobHandle == NULL)
   APIERROR(myScanOp->getNdbError());
 if (myBlobHandle->getValue(buffer, sizeof(buffer)))
   APIERROR(myBlobHandle->getNdbError());
  /* Start the scan. */
 if (-1 == myTrans->execute(NdbTransaction::NoCommit))
   APIERROR(myTrans->getNdbError());
 const MyRow *out_row;
  int res;
 for (;;)
   res= myScanOp->nextResult((const char**)&out_row, true, false);
```

```
if (res==1)
                                                 // Scan done.
     break;
    else if (res)
     APIERROR(myScanOp->getNdbError());
    Uint64 length= 0;
    if (myBlobHandle->getLength(length) == -1)
      APIERROR(myBlobHandle->getNdbError());
    /* Lowercase everything. */
    for (Uint64 j= 0; j < length; j++)
      buffer[j] = tolower(buffer[j]);
    /* 'Take over' the row locks from the scan to a separate
     * operation for updating the tuple
    const NdbOperation *myUpdateOp=
     myScanOp->updateCurrentTuple(myTrans,
                                   blob_record,
                                   (const char*)out_row);
    if (myUpdateOp == NULL)
      APIERROR(myTrans->getNdbError());
    NdbBlob *myBlobHandle2= myUpdateOp->getBlobHandle("my_text");
    if (myBlobHandle2 == NULL)
     APIERROR(myUpdateOp->getNdbError());
    if (myBlobHandle2->setValue(buffer, length))
     APIERROR(myBlobHandle2->getNdbError());
    if (-1 == myTrans->execute(NdbTransaction::NoCommit))
      APIERROR(myTrans->getNdbError());
  if (-1 == myTrans->execute(NdbTransaction::Commit))
    APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
  return 1;
struct ActiveHookData {
 char buffer[10000];
 Uint32 readLength;
int myFetchHook(NdbBlob* myBlobHandle, void* arg)
 ActiveHookData *ahd= (ActiveHookData *)arg;
 ahd->readLength= sizeof(ahd->buffer) - 1;
 return myBlobHandle->readData(ahd->buffer, ahd->readLength);
int fetch_key(Ndb *myNdb)
  /* Fetch a blob without specifying how many bytes
   * to read up front, in one execution using
   * the 'ActiveHook' mechanism.
   * The supplied ActiveHook procedure is called when
   * the Blob handle becomes 'active'. At that point
   * the length of the Blob can be obtained, and buffering
   \mbox{\scriptsize *} arranged, and the data read requested.
  /* Separate rows used to specify key and hold result */
 MyRow key_row;
```

```
MyRow out_row;
   Fetch and show the blob field, using setActiveHook().
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 key_row.myId= 1;
 out_row.myText= NULL;
 const NdbOperation *myNdbOperation=
   myTrans->readTuple(key_record,
                       (const char*) &key_row,
                       blob_record,
                       (char*) &out_row);
 if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
  /* This time, we'll get the blob handle from the row, because
   * we can. Alternatively, we could use the normal mechanism
  * of calling getBlobHandle().
 NdbBlob *myBlobHandle= out_row.myText;
 if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
 struct ActiveHookData ahd;
 if (myBlobHandle->setActiveHook(myFetchHook, &ahd) == -1)
   APIERROR(myBlobHandle->getNdbError());
   Execute Commit, but calling our callback set up in setActiveHook()
   before actually committing.
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 /* Our fetch callback will have been called during the execute(). */
 ahd.buffer[ahd.readLength] = '\0';
 std::cout << "Fetched data:" << std::endl << ahd.buffer << std::endl;</pre>
 return 1;
int update2_key(Ndb *myNdb)
 char buffer[10000];
 MyRow row;
  /* Simple setValue() update specified before the
   * Blob handle is made active
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 row.myId= 1;
 const NdbOperation *myNdbOperation=
   myTrans->updateTuple(key_record,
                         (const char*)&row,
                         blob_record,
                         (char*) &row);
```

```
if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
  NdbBlob *myBlobHandle= myNdbOperation->getBlobHandle("my_text");
  if (myBlobHandle == NULL)
   APIERROR(myNdbOperation->getNdbError());
 memset(buffer, ' ', sizeof(buffer));
  if (myBlobHandle->setValue(buffer, sizeof(buffer)) == -1)
   APIERROR(myBlobHandle->getNdbError());
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 return 1;
int delete_key(Ndb *myNdb)
  MyRow row;
  /* Deletion of row containing blob via primary key. */
 NdbTransaction *myTrans= myNdb->startTransaction();
 if (myTrans == NULL)
   APIERROR(myNdb->getNdbError());
 row.myId= 1;
 const NdbOperation *myNdbOperation= myTrans->deleteTuple(key_record,
                                                            (const char*)&row,
                                                            full_record);
  if (myNdbOperation == NULL)
   APIERROR(myTrans->getNdbError());
 if (-1 == myTrans->execute(NdbTransaction::Commit))
   APIERROR(myTrans->getNdbError());
 myNdb->closeTransaction(myTrans);
 return 1;
void mysql_connect_and_create(const char *socket)
 MYSQL mysql;
 bool ok;
 mysql_init(&mysql);
 ok = mysql_real_connect(&mysql, "localhost", "root", "", "", 0, socket, 0);
   mysql_query(&mysql, "CREATE DATABASE ndb_examples");
   ok = ! mysql_select_db(&mysql, "ndb_examples");
  if(ok) {
   create_table(mysql);
 mysql_close(&mysql);
  if(! ok) MYSQLERROR(mysql);
void ndb_run_ndbrecord_blob_operations(const char * connectstring)
  /* Connect to ndb cluster. */
 Ndb_cluster_connection cluster_connection(connectstring);
 if (cluster_connection.connect(4, 5, 1))
```

```
std::cout << "Unable to connect to cluster within 30 secs." << std::endl;
   exit(-1);
  ^{\prime} * Optionally connect and wait for the storage nodes (ndbd's). */
 if (cluster_connection.wait_until_ready(30,0) < 0)</pre>
   std::cout << "Cluster was not ready within 30 secs.\n";
   exit(-1);
 Ndb myNdb(&cluster_connection, "ndb_examples");
 if (myNdb.init(1024) == -1) {
                                      // Set max 1024 parallel transactions
   APIERROR(myNdb.getNdbError());
   exit(-1);
 setup_records(&myNdb);
 if(populate(&myNdb) > 0)
   std::cout << "populate: Success!" << std::endl;</pre>
 if(update_key(&myNdb) > 0)
   std::cout << "update_key: Success!" << std::endl;</pre>
 if(update_scan(&myNdb) > 0)
   std::cout << "update_scan: Success!" << std::endl;</pre>
 if(fetch_key(&myNdb) > 0)
   std::cout << "fetch_key: Success!" << std::endl;</pre>
 if(update2_key(&myNdb) > 0)
   std::cout << "update2_key: Success!" << std::endl;</pre>
 if(delete_key(&myNdb) > 0)
   std::cout << "delete_key: Success!" << std::endl;</pre>
int main(int argc, char**argv)
 if (argc != 3)
   std::cout << "Arguments are <socket mysqld> <connect_string cluster>.\n";
   exit(-1);
 char *mysqld_sock = argv[1];
 const char *connectstring = argv[2];
 mysql_connect_and_create(mysqld_sock);
 ndb_init();
 ndb_run_ndbrecord_blob_operations(connectstring);
 ndb_end(0);
 return 0;
```

2.5.11 NDB API Simple Array Example

This program inserts CHAR, VARCHAR, and BINARY column data into a table by constructing aRef objects using local functions. It then reads the columns back and extracts the data from them using local functions.

This example assumes you have a table named api_array_simple, created as follows:

```
CREATE TABLE api_array_simple (
ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY,
```

```
ATTR2 CHAR(20) NOT NULL,
ATTR3 VARCHAR(20) NOT NULL,
ATTR4 VARCHAR(500) NOT NULL,
ATTR5 BINARY(20) NOT NULL,
ATTR6 VARBINARY(20) NOT NULL,
ATTR7 VARBINARY(500) NOT NULL)
```



Note

This program uses a number of utilities which can be found in storage/ndb/
ndbapi-examples/common/. See Section 2.5.14, "Common Files for NDB API
Array Examples", for listings of these.

The example file can be found as ndbapi_array_simple/ndbapi_array_simple.cpp in the NDB 7.3.8, NDB 7.4.3, or later NDB Cluster source distribution's storage/ndb/ndbapi-examples directory. (Bug #70550, Bug #17592990)

```
#include <NdbApi.hpp>
#include <iostream>
#include <vector>
#include <cstdlib>
#include <cstring>
 See Section 2.5.14, "Common Files for NDB API Array Examples",
 for listings of these utilities.
#include "../common/error_handling.hpp"
#include "../common/ndb_util.hpp"
#include "../common/util.hpp"
using namespace std;
/* structure to help in insertion */
struct RowData
  /* id */
 int attr1;
  /* CHAR(20)- fixed length, no additional length bytes */
 char attr2[20];
  /* VARCHAR(20) - requires one additional length byte (length < 256 ) */
 char attr3[1 + 20];
  /* VARCHAR(500) - requires two additional length bytes (length > 256 ) */
 char attr4[2 + 500];
  /* BINARY(20) - fixed length, requires no additional length byte */
 char attr5[20];
  /* VARBINARY(20) - requires one additional length byte (length < 256 ) */
 char attr6[1 + 20];
  /* VARBINARY(20) - requires one additional length byte (length > 256 ) */
 char attr7[2 + 500];
};
/* extracts the length and the start byte of the data stored */
static int get_byte_array(const NdbRecAttr* attr,
                          const char*& first_byte,
                          size_t& bytes)
 const NdbDictionary::Column::ArrayType array_type =
   attr->getColumn()->getArrayType();
 const size_t attr_bytes = attr->get_size_in_bytes();
  const char* aRef = attr->aRef();
 string result;
  switch (array_type) {
 case NdbDictionary::Column::ArrayTypeFixed:
```

```
No prefix length is stored in aRef. Data starts from aRef's first byte
    data might be padded with blank or null bytes to fill the whole column
   first_byte = aRef;
   bytes = attr_bytes;
   return 0;
 case NdbDictionary::Column::ArrayTypeShortVar:
    First byte of aRef has the length of data stored
    Data starts from second byte of aRef
   first_byte = aRef + 1;
   bytes = (size_t)(aRef[0]);
   return 0;
 case NdbDictionary::Column::ArrayTypeMediumVar:
    First two bytes of aRef has the length of data stored
    Data starts from third byte of aRef
     * /
   first_byte = aRef + 2;
   bytes = (size_t)(aRef[1]) * 256 + (size_t)(aRef[0]);
 default:
   first_byte = NULL;
   bytes = 0;
   return -1;
Extracts the string from given NdbRecAttr
Uses get_byte_array internally
static int get_string(const NdbRecAttr* attr, string& str)
 size_t attr_bytes;
 const char* data_start_ptr = NULL;
  /* get stored length and data using get_byte_array */
 if(get_byte_array(attr, data_start_ptr, attr_bytes) == 0)
    /* we have length of the string and start location */
   str= string(data_start_ptr, attr_bytes);
   if(attr->getType() == NdbDictionary::Column::Char)
     /* Fixed Char : remove blank spaces at the end */
     size_t endpos = str.find_last_not_of(" ");
     if( string::npos != endpos )
       str = str.substr(0, endpos+1);
 return 0;
// Do a cleanup of all inserted tuples
static void do_cleanup(Ndb& ndb)
 const NdbDictionary::Dictionary* dict = ndb.getDictionary();
 const NdbDictionary::Table *table = dict->getTable("api_array_simple");
 if (table == nullptr) APIERROR(dict->getNdbError());
 NdbTransaction *transaction= ndb.startTransaction();
 if (transaction == nullptr) APIERROR(ndb.getNdbError());
```

```
for (int i = 0; i \le 20; i++)
   NdbOperation* myOperation = transaction->getNdbOperation(table);
   if (myOperation == nullptr) APIERROR(transaction->getNdbError());
   myOperation->deleteTuple();
   myOperation->equal("ATTR1", i);
 if (transaction->execute(NdbTransaction::Commit) != 0)
   APIERROR(transaction->getNdbError());
 ndb.closeTransaction(transaction);
/********************
* Use one transaction and insert 21 rows in one batch *
****************
static void do_insert(Ndb& ndb)
 const NdbDictionary::Dictionary* dict = ndb.getDictionary();
 const NdbDictionary::Table *table = dict->getTable("api_array_simple");
 if (table == NULL) APIERROR(dict->getNdbError());
 NdbTransaction *transaction= ndb.startTransaction();
 if (transaction == NULL) APIERROR(ndb.getNdbError());
 /* Create and initialize sample data */
 const string meter = 50 * string("'''-,,,,|");
 const string space = 20 * string(" ");
 unsigned char binary_meter[500];
 for (unsigned i = 0; i < 500; i++)
   binary_meter[i] = (unsigned char)(i % 256);
 vector<NdbOperation*> operations;
 for (int i = 0; i \le 20; i++)
   RowData data;
   NdbOperation* myOperation = transaction->getNdbOperation(table);
   if (myOperation == NULL) APIERROR(transaction->getNdbError());
   data.attr1 = i;
   // Fill CHAR(20) with 'i' chars from meter
   strncpy (data.attr2, meter.c_str(), i);
   // Pad it with space up to 20 chars
   strncpy (data.attr2 + i, space.c_str(), 20 - i);
   // Fill VARCHAR(20) with 'i' chars from meter. First byte is
   // reserved for length field. No padding is needed.
   strncpy (data.attr3 + 1, meter.c_str(), i);
   // Set the length byte
   data.attr3[0] = (char)i;
   // Fill VARCHAR(500) with 20*i chars from meter. First two bytes
   // are reserved for length field. No padding is needed.
   strncpy (data.attr4 + 2, meter.c_str(), 20*i);
   // Set the length bytes
   data.attr4[0] = (char)(20*i % 256);
   data.attr4[1] = (char)(20*i / 256);
   // Fill BINARY(20) with 'i' bytes from binary_meter.
   memcpy(data.attr5, binary_meter, i);
   // Pad with 0 up to 20 bytes.
```

```
memset(data.attr5 + i, 0, 20 - i);
   // Fill VARBINARY(20) with 'i' bytes from binary_meter. First byte
   // is reserved for length field. No padding is needed.
   memcpy(data.attr6 + 1, binary_meter, i);
   // Set the length byte
   data.attr6[0] = (char)i;
   // Fill VARBINARY(500) with 'i' bytes from binary_meter. First two
   // bytes are reserved for length filed. No padding is needed.
   memcpy(data.attr7 + 2, binary_meter, 20*i);
   // Set the length bytes
   data.attr7[0] = (char)(20*i % 256);
   data.attr7[1] = (char)(20*i / 256);
   myOperation->insertTuple();
   myOperation->equal("ATTR1", data.attr1);
   myOperation->setValue("ATTR2", data.attr2);
   myOperation->setValue("ATTR3", data.attr3);
   myOperation->setValue("ATTR4", data.attr4);
   myOperation->setValue("ATTR5", data.attr5);
   myOperation->setValue("ATTR6", data.attr6);
   myOperation->setValue("ATTR7", data.attr7);
   operations.push_back(myOperation);
  // Now execute all operations in one batch, and check for errors.
 if (transaction->execute( NdbTransaction::Commit ) != 0)
   for (size_t i = 0; i < operations.size(); i++)</pre>
     const NdbError err= operations[i]->getNdbError();
     if(err.code != NdbError::Success)
       cout << "Error inserting Row : " << i << endl;</pre>
        PRINT_ERROR(err.code, err.message);
   APIERROR(transaction->getNdbError());
 ndb.closeTransaction(transaction);
Reads the row with id = 17
Retrieves an prints value of the [VAR]CHAR/BINARY
static void do_read(Ndb& ndb)
 const NdbDictionary::Dictionary* dict= ndb.getDictionary();
 const NdbDictionary::Table* table= dict->getTable("api_array_simple");
 if (table == NULL) APIERROR(dict->getNdbError());
 NdbTransaction *transaction= ndb.startTransaction();
 if (transaction == NULL) APIERROR(ndb.getNdbError());
 NdbOperation *operation= transaction->getNdbOperation(table);
 if (operation == NULL) APIERROR(transaction->getNdbError());
  /* create and execute a read operation */
 operation->readTuple(NdbOperation::LM_Read);
 operation->equal("ATTR1", 17);
 vector<NdbRecAttr*> attr;
 const int column_count= table->getNoOfColumns();
```

```
attr.reserve(column_count);
  attr.push back(nullptr);
  for (int i= 1; i < column_count; i++)</pre>
   attr.push_back(operation->getValue(i, NULL));
   if (attr[i] == NULL) APIERROR(transaction->getNdbError());
  if(transaction->execute( NdbTransaction::Commit ) == -1)
   APIERROR(transaction->getNdbError());
  /* print the fetched data */
  cout << "Row ID : 17\n";
  for (int i= 1; i < column_count; i++)</pre>
   if (attr[i] != NULL)
     NdbDictionary::Column::Type column_type = attr[i]->getType();
     cout << "Column id: " << i << ", name: " << attr[i]->getColumn()->getName()
          << ", size: " << attr[i]->get_size_in_bytes()
          << ", type: " << column_type_to_string(attr[i]->getType());
     switch (column_type) {
     case NdbDictionary::Column::Char:
     case NdbDictionary::Column::Varchar:
     case NdbDictionary::Column::Longvarchar:
          /* for char columns the actual string is printed */
         string str;
         get_string(attr[i], str);
          cout << ", stored string length: " << str.length()</pre>
              << ", value: " << str << endl;
       break;
     case NdbDictionary::Column::Binary:
     case NdbDictionary::Column::Varbinary:
     case NdbDictionary::Column::Longvarbinary:
          /* for binary columns the sum of all stored bytes is printed */
         const char* first;
         size_t count;
          get_byte_array(attr[i], first, count);
         int sum = 0;
         for (const char* byte = first; byte < first + count; byte++)</pre>
           sum += (int)(*byte);
          cout << ", stored bytes length: " << count
              << ", sum of byte array: " << sum << endl;
       break;
     default:
        cout << ", column type \"" << column_type_to_string(attr[i]->getType())
            << "\" not covered by this example" << endl;
 ndb.closeTransaction(transaction);
static void run_application(Ndb_cluster_connection &cluster_connection,
                            const char* database_name)
```

```
* Connect to database via NdbApi
  // Object representing the database
 Ndb ndb( &cluster_connection, database_name);
 if (ndb.init()) APIERROR(ndb.getNdbError());
   * Do different operations on database
 do_insert(ndb);
 do read(ndb);
 do_cleanup(ndb);
int main(int argc, char** argv)
 if (argc != 3)
   std::cout << "Arguments are <connect_string cluster> <database_name>.\n";
  /* ndb init must be called first */
   /* connect to cluster */
   const char *connectstring = argv[1];
   Ndb_cluster_connection cluster_connection(connectstring);
   if (cluster_connection.connect(30 /* retries */,
                                   1 /* delay between retries */,
                                   0 /* verbose */))
     std::cout << "Cluster management server was not ready within 30 secs.\n";</pre>
     exit(-1);
    /* Connect and wait for the storage nodes */
   if (cluster_connection.wait_until_ready(30,10) < 0)</pre>
     std::cout << "Cluster was not ready within 30 secs.\n";
     exit(-1);
    /* run the application code */
   const char* dbname = arqv[2];
   run_application(cluster_connection, dbname);
 ndb_end(0);
 return 0;
```

Prior to NDB 8.0.1, this program could not be run more than once in succession during the same session (Bug #27009386).

2.5.12 NDB API Simple Array Example Using Adapter

This program inserts CHAR, VARCHAR, and BINARY column data into a table by constructing aRef objects using array adapters of the type defined in common/array_adapter.hpp (see Section 2.5.14, "Common Files for NDB API Array Examples"). It then reads the columns back and extracts the data, again using array adapters.

The example uses the table shown here:

```
CREATE TABLE api_array_using_adapter (
ATTR1 INT UNSIGNED NOT NULL PRIMARY KEY,
```

```
ATTR2 CHAR(20) NOT NULL,
ATTR3 VARCHAR(20) NOT NULL,
ATTR4 VARCHAR(500) NOT NULL,
ATTR5 BINARY(20) NOT NULL,
ATTR6 VARBINARY(20) NOT NULL,
ATTR7 VARBINARY(500) NOT NULL
) ENGINE NDB CHARSET latin1;
```

The example file can be found as ndbapi_array_using_adapter/

ndbapi_array_using_adapter.cpp in the NDB 7.3.8, NDB 7.4.3, or later NDB Cluster source distribution's storage/ndb/ndbapi-examples directory. (Bug #70550, Bug #17592990)

```
#include <NdbApi.hpp&gt;
#include <iostream&gt;
#include <vector&gt;
#include <cstdlib&qt;
#include <cstring&gt;
using namespace std;
 See Section 2.5.14, "Common Files for NDB API Array Examples",
 for listings of these utilities.
#include "../common/error_handling.hpp"
#include "../common/array_adapter.hpp"
#include "../common/ndb_util.hpp"
#include "../common/util.hpp"
// Do a cleanup of all inserted rows
static void do_cleanup(Ndb& ndb)
 const NdbDictionary::Dictionary* dict = ndb.getDictionary();
 const NdbDictionary::Table *table = dict->getTable("api_array_using_adapter");
 if (table == nullptr) APIERROR(dict->getNdbError());
 NdbTransaction *transaction= ndb.startTransaction();
 if (transaction == nullptr) APIERROR(ndb.getNdbError());
  // Delete all 21 rows using a single transaction
  for (int i = 0; i <= 20; i++)
   NdbOperation* myOperation = transaction->getNdbOperation(table);
   if (myOperation == nullptr) APIERROR(transaction->getNdbError());
   myOperation->deleteTuple();
   myOperation->equal("ATTR1", i);
  if (transaction->execute(NdbTransaction::Commit) != 0)
   APIERROR(transaction->getNdbError());
 ndb.closeTransaction(transaction);
// Use one transaction and insert 21 rows in one batch.
static void do_insert(Ndb& ndb)
 const NdbDictionary::Dictionary* dict = ndb.getDictionary();
 const NdbDictionary::Table *table = dict->getTable("api_array_using_adapter");
  if (table == NULL)
   APIERROR(dict->getNdbError());
```

```
// Get a column object for each CHAR/VARCHAR/BINARY/VARBINARY column
// to insert into.
const NdbDictionary::Column *column2 = table->getColumn("ATTR2");
if (column2 == NULL)
  APIERROR(dict->getNdbError());
const NdbDictionary::Column *column3 = table->getColumn("ATTR3");
if (column3 == NULL)
 APIERROR(dict->getNdbError());
const NdbDictionary::Column *column4 = table->getColumn("ATTR4");
if (column4 == NULL)
  APIERROR(dict->getNdbError());
const NdbDictionary::Column *column5 = table->getColumn("ATTR5");
if (column5 == NULL)
  APIERROR(dict->getNdbError());
const NdbDictionary::Column *column6 = table->getColumn("ATTR6");
if (column6 == NULL)
 APIERROR(dict->getNdbError());
const NdbDictionary::Column *column7 = table->getColumn("ATTR7");
if (column7 == NULL)
  APIERROR(dict->getNdbError());
// Create a read/write attribute adapter to be used for all
// CHAR/VARCHAR/BINARY/VARBINARY columns.
ReadWriteArrayAdapter attr_adapter;
// Create and initialize sample data.
const string meter = 50 * string("'''-,,,,|");
unsigned char binary_meter[500];
for (unsigned i = 0; i < 500; i++)
  binary_meter[i] = (unsigned char)(i % 256);
NdbTransaction *transaction= ndb.startTransaction();
if (transaction == NULL) APIERROR(ndb.getNdbError());
// Create 21 operations and put a reference to them in a vector to
// be able to find failing operations.
vector<NdbOperation*> operations;
for (int i = 0; i \le 20; i++)
  NdbOperation* operation = transaction->getNdbOperation(table);
  if (operation == NULL) APIERROR(transaction->getNdbError());
  operation->insertTuple();
  operation->equal("ATTR1", i);
  /* use ReadWrite Adapter to convert string to aRefs */
  ReadWriteArrayAdapter::ErrorType error;
```

```
char *attr2_aRef;
   attr2_aRef= attr_adapter.make_aRef(column2, meter.substr(0,i), error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "make_aRef failed for ATTR2");
   operation->setValue("ATTR2", attr2_aRef);
   char *attr3_aRef;
   attr3_aRef= attr_adapter.make_aRef(column3, meter.substr(0,i), error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "make_aRef failed for ATTR3");
   operation->setValue("ATTR3", attr3_aRef);
   char *attr4 aRef;
   attr4_aRef= attr_adapter.make_aRef(column4, meter.substr(0,20*i), error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "make_aRef failed for ATTR4");
   operation->setValue("ATTR4", attr4_aRef);
   char* attr5_aRef;
   char* attr5_first;
   attr_adapter.allocate_in_bytes(column5, attr5_aRef, attr5_first, i, error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "allocate_in_bytes failed for ATTR5");
   memcpy(attr5_first, binary_meter, i);
   operation->setValue("ATTR5", attr5_aRef);
   char* attr6_aRef;
   char* attr6_first;
   attr_adapter.allocate_in_bytes(column6, attr6_aRef, attr6_first, i, error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "allocate_in_bytes failed for ATTR6");
   memcpy(attr6_first, binary_meter, i);
   operation->setValue("ATTR6", attr6_aRef);
   char* attr7_aRef;
   char* attr7_first;
   attr_adapter.allocate_in_bytes(column7, attr7_aRef, attr7_first, 20*i, error);
   PRINT_IF_NOT_EQUAL(error, ReadWriteArrayAdapter::Success,
                      "allocate_in_bytes failed for ATTR7");
   memcpy(attr7_first, binary_meter, 20*i);
   operation->setValue("ATTR7", attr7_aRef);
   operations.push_back(operation);
 // Now execute all operations in one batch, and check for errors.
 if (transaction->execute( NdbTransaction::Commit ) != 0)
   for (size_t i = 0; i < operations.size(); i++)</pre>
     const NdbError err= operations[i]->getNdbError();
     if(err.code != NdbError::Success)
      cout << "Error inserting Row : " << i << endl;</pre>
       PRINT_ERROR(err.code, err.message);
   APIERROR(transaction->getNdbError());
 ndb.closeTransaction(transaction);
Reads the row with id = 17
Retrieves an prints value of the [VAR]CHAR/BINARY using array_adapter
*/
```

```
static void do_read(Ndb& ndb)
 const NdbDictionary::Dictionary* dict= ndb.getDictionary();
 const NdbDictionary::Table* table= dict->getTable("api_array_using_adapter");
 if (table == NULL) APIERROR(dict->getNdbError());
 NdbTransaction *transaction= ndb.startTransaction();
 if (transaction == NULL) APIERROR(ndb.getNdbError());
 NdbOperation *operation= transaction->getNdbOperation(table);
 if (operation == NULL) APIERROR(transaction->getNdbError());
 operation->readTuple(NdbOperation::LM Read);
 operation->equal("ATTR1", 17);
 vector<NdbRecAttr*> attr;
 const int column_count= table->getNoOfColumns();
 attr.reserve(column_count);
 attr.push_back(nullptr);
  for (int i= 1; i < column_count; i++)</pre>
    attr.push_back(operation->getValue(i, NULL));
    if (attr[i] == NULL) APIERROR(transaction->getNdbError());
  if(transaction->execute( NdbTransaction::Commit ) == -1)
    APIERROR(transaction->getNdbError());
  /* Now use an array adapter to read the data from columns */
 const ReadOnlyArrayAdapter attr_adapter;
 ReadOnlyArrayAdapter::ErrorType error;
  /* print the fetched data */
 cout << "Row ID : 17\n";
  for (int i= 1; i < column_count; i++)</pre>
    if (attr[i] != NULL)
      NdbDictionary::Column::Type column_type = attr[i]->getType();
      cout << "Column id: " << i
           << ", name: " << attr[i]->getColumn()->getName()
           << ", size: " << attr[i]->get_size_in_bytes()
           << ", type: " << column_type_to_string(attr[i]->getType());
      if(attr_adapter.is_binary_array_type(column_type))
        /* if column is [VAR]BINARY, get the byte array and print their sum */
        const char* data_ptr;
        size_t data_length;
        attr_adapter.get_byte_array(attr[i], data_ptr,
                                     data_length, error);
        if(error == ReadOnlyArrayAdapter::Success)
          int sum = 0;
         for (size_t j = 0; j < data_length; j++)</pre>
           sum += (int)(data_ptr[j]);
          cout << ", stored bytes length: " << data_length</pre>
               << ", sum of byte array: " << sum << endl;
        }
        else
          cout << ", error fetching value." << endl;</pre>
      else
        /* if the column is [VAR]CHAR, retrieve the string and print */
```

```
std::string value= attr_adapter.get_string(attr[i], error);
        if(error == ReadOnlyArrayAdapter::Success)
          cout << ", stored string length: " << value.length()</pre>
               << ", value: " << value
               << endl;
        }
        else
          cout << ", error fetching value." << endl;</pre>
  }
 ndb.closeTransaction(transaction);
static void run_application(Ndb_cluster_connection &cluster_connection,
                            const char* database_name)
  /************
   * Connect to database via NdbApi
  // Object representing the database
 Ndb ndb( &cluster_connection, database_name);
  if (ndb.init()) APIERROR(ndb.getNdbError());
  * Do different operations on database
  * /
 do_insert(ndb);
 do_read(ndb);
 do_cleanup(ndb);
int main(int argc, char** argv)
  if (argc != 3)
   std::cout << "Arguments are <connect_string cluster> <database_name>.\n";
    exit(-1);
  /* ndb_init must be called first */
  ndb_init();
    /* connect to cluster */
    const char *connectstring = argv[1];
    Ndb_cluster_connection cluster_connection(connectstring);
    if (cluster_connection.connect(30 /\ast retries \ast/ , $1 \ /\ast$ delay between retries \ast/ ,
                                    0 /* verbose */))
      std::cout << "Cluster management server was not ready within 30 secs.\n";
      exit(-1);
    /* Connect and wait for the storage nodes */
   if (cluster_connection.wait_until_ready(30,10) < 0)</pre>
     std::cout << "Cluster was not ready within 30 secs.\n";</pre>
      exit(-1);
    /* run the application code */
    const char* dbname = argv[2];
    run_application(cluster_connection, dbname);
 ndb_end(0);
```

```
return 0;
}
```

Prior to NDB 8.0.1, this program could not be run more than once in succession during the same session (Bug #27009386).

2.5.13 Timestamp2 Example

The file timestamp2.cpp reproduced in this section provides an example of working in NDB API applications with the "new" MySQL temporal data types supporting fractional seconds that were implemented in MySQL 5.6, and in NDB 7.3 and NDB 7.4.

For more information working with MySQL temporal and other data types in the NDB API, see Section 2.1.3.2, "NDB API Handling of MySQL Data Types".

```
#include <stdio.h>
#include <stdlib.h>
#include <iostream>
#include <NdbApi.hpp>
#include <string>
#include <unistd.h>
//no binlog value
#define NDB_ANYVALUE_FOR_NOLOGGING 0x8000007f
using namespace std;
int setTimestamp(NdbOperation* op,
                const NdbDictionary::Column* col,
                unsigned int value)
 if (col->getType() == NDB_TYPE_TIMESTAMP)
    /* Set as 32-bit int in host layout */
   return op->setValue(col->getName(), value);
 else if (col->getType() == NDB_TYPE_TIMESTAMP2)
   /* Set as 64 bit big-endian value */
   //assert(col->getPrecision() == 0);
   Uint64 ts = 0;
   unsigned char* bytes = (unsigned char*) &ts;
   bytes[0] = value >> 24 & 0xff;
   bytes[1] = value >> 16 & 0xff;
   bytes[2] = value >> 8 & 0xff;
   return op->setValue(col->getName(), ts);
 else
   cout << "Bad type for column " << col->getType()
        << std::endl;
   exit(1);
unsigned int readTimestamp(NdbRecAttr* recAttr)
 if (recAttr->getType() == NDB_TYPE_TIMESTAMP)
    /* Timestamp is in native 32 bit layout */
   return recAttr->u_32_value();
 else if (recAttr->getType() == NDB_TYPE_TIMESTAMP2)
```

```
/* Timestamp is in big-endian layout */
    //assert(recAttr->getColumn()->getPrecision() == 0);
    Uint64 ts2 = recAttr->u_64_value();
    const unsigned char* bytes = (const unsigned char*) &ts2;
    const unsigned int ts =
      (Uint64(bytes[0]) << 24) +
      (Uint64(bytes[1]) << 16) +
      (Uint64(bytes[2]) << 8) +
      (Uint64(bytes[3]));
   return ts;
 else
    cout << "Error with timestamp column type : "</pre>
         << recAttr->getType()
         << endl;
    exit(1);
void insert(string connectString)
    Ndb_cluster_connection *cluster_connection = new Ndb_cluster_connection(connectString.c_str());
    if(cluster_connection->connect(5,5,1)) {
       cout << "Cannot connect to Cluster using connectstring: "<< connectString << endl;</pre>
        exit(1);
    }
    if(cluster_connection->wait_until_ready(30,0) < 0) {</pre>
        cout << "Cluster was not ready within 30 seconds" << endl;</pre>
    Ndb *myNdb = new Ndb(cluster_connection, "myndb_user_data");
    if(myNdb->init(1024) == -1){
        cout << "Error: Cannot initialize NDB object" << endl;</pre>
        exit(-1);
    }
    const NdbDictionary::Dictionary *dict = myNdb->getDictionary();
    if (dict == NULL) {
        cout << "Error: Cannot fetch NndDictionary" << endl;</pre>
        exit(0);
    }
    const NdbDictionary::Table *timestampTable = dict->getTable("TIMESTAMP_TEST");
    if (timestampTable == NULL) {
        cout << "Error: Cannot fetch MYNDB table" << endl;</pre>
        exit(0);
    NdbTransaction *trans = myNdb->startTransaction();
    if (trans == NULL) {
      cout << "Error: Cannot start new transaction" << endl;</pre>
      exit(1);
    NdbOperation *myOperation = trans->getNdbOperation(timestampTable);
    if ( myOperation == NULL) {
      cout << "Error: Cannot get new operation" << endl;</pre>
      exit(1);
    myOperation->insertTuple();
```

```
Uint64 value;
   myNdb->getAutoIncrementValue(timestampTable, value, (Uint32)32);
   myOperation->setValue("KEY_COL", value);
   time_t timestamp= time(NULL);
   setTimestamp(myOperation,
                 timestampTable->getColumn("createTimestamp"),
                 timestamp);
   setTimestamp(myOperation,
                 timestampTable->getColumn("modifyTimestamp"),
    //disable binlogging
   myOperation->setAnyValue(NDB_ANYVALUE_FOR_NOLOGGING);
   if(trans->execute(NdbTransaction::Commit) != 0) {
     cout << "Error: " << trans->getNdbError().message << endl;</pre>
      exit(1);
   myNdb->closeTransaction(trans);
   delete myNdb;
   delete cluster_connection;
void fetch_from_database(string connectString)
   Ndb_cluster_connection *cluster_connection = new Ndb_cluster_connection(connectString.c_str());
   if(cluster_connection->connect(5,5,1)) {
       cout << "Cannot connect to Cluster using connectstring: "<< connectString << endl;</pre>
       exit(1);
   if(cluster_connection->wait_until_ready(30,0) < 0) {</pre>
       cout << "Cluster was not ready within 30 seconds" << endl;</pre>
   Ndb *myNdb = new Ndb(cluster_connection, "myndb_user_data");
   if(myNdb->init(1024) == -1){
       cout << "Error: Cannot initialize NDB object" << endl;</pre>
        exit(-1);
   const NdbDictionary::Dictionary *dict = myNdb->getDictionary();
   if (dict == NULL) {
       cout << "Error: Cannot fetch NndDictionary" << endl;</pre>
        exit(0);
    const NdbDictionary::Table *timestampTable = dict->getTable("TIMESTAMP_TEST");
   if (timestampTable == NULL) {
       cout << "Error: Cannot fetch MYNDB table" << endl;</pre>
        exit(0);
   NdbTransaction *trans = myNdb->startTransaction();
   if (trans == NULL) {
      cout << "Error: Cannot start new transaction" << endl;</pre>
      exit(1);
   NdbScanOperation *myOperation = trans->getNdbScanOperation(timestampTable);
   if ( myOperation == NULL) {
```

```
cout << "Error: Cannot get new operation" << endl;</pre>
      exit(1);
    }
    if (myOperation->readTuples(NdbOperation::LM_Exclusive) == -1){
      cout << "Error: " << trans->getNdbError().message << endl;</pre>
      exit(0);
   NdbRecAttr *recAttrs[3];
    recAttrs[0] = myOperation->getValue("KEY_COL");
    recAttrs[1] = myOperation->getValue("createTimestamp");
    recAttrs[2] = myOperation->getValue("modifyTimestamp");
    if (recAttrs[0] == NULL | recAttrs[1] == NULL | recAttrs[2] == NULL) {
        cout << "Error: " << trans->getNdbError().message << endl;</pre>
        exit(0);
    }
    if(trans->execute(NdbTransaction::NoCommit) != 0) {
      cout << "Error: " << trans->getNdbError().message << endl;</pre>
      exit(1);
    int check;
    while((check = myOperation->nextResult(true)) == 0){
     do {
     cout << recAttrs[0]->u_32_value() << "\t";</pre>
           cout << readTimestamp(recAttrs[1]) << "\t";</pre>
     cout << readTimestamp(recAttrs[2]) << std::endl;</pre>
        while((check = myOperation->nextResult(false)) == 0);
    myNdb->closeTransaction(trans);
    delete myNdb;
    delete cluster_connection;
int main(int argc, char **argv) {
cout << "Timestamp test application!!!!" << endl;</pre>
//fetch parameters
   string connectString;
    if (argc < 2) {
        cout<<"Please provide connect string for PLDB"<<endl;</pre>
        exit(1);
    connectString = argv[1];
ndb_init();
    insert(connectString);
    fetch_from_database(connectString);
ndb_end(0);
return EXIT_SUCCESS;
```

2.5.14 Common Files for NDB API Array Examples

In NDB 7.3.8, NDB 7.4.3, or later NDB Cluster source distribution, the storage/ndb/ndbapi-examples directory storage/ndb/ndbapi-examples/common contains four header files with utilities for use in example NDB API programs. (Bug #70550, Bug #17592990) The names of these files are listed here:

- array_adapter.hpp: Contains utility classes for converting between C++ style strings or byte arrays and the format used by NDB internally for VARCHAR, CHAR, and VARBINARY types.
- error_handling.hpp: Contains error handling functions.
- ndb_util.hpp: Defines a column_type_to_string() function which handles NDB column types.
- util.hpp: Provides a method for generating strings of arbitrary length.

Following in this section are source listings for each of the header files.

array_adapter.hpp

```
#ifndef ARRAY_ADAPTER_HPP
#define ARRAY_ADAPTER_HPP
#include <algorithm>
#include <assert.h>
Utility classes to convert between C++ strings/byte arrays and the
 internal format used for [VAR]CHAR/BINARY types.
Base class that can be used for read operations. The column type is
taken from the NdbRecAttr object, so only one object is needed to
convert from different [VAR]CHAR/BINARY types. No additional memory
is allocated.
class ReadOnlyArrayAdapter {
public:
 ReadOnlyArrayAdapter() {}
 enum ErrorType {Success,
                  InvalidColumnType,
                  InvalidArrayType,
                  InvalidNullColumn,
                  InvalidNullAttribute,
                  InvalidNullaRef,
                  BytesOutOfRange,
                  UnknownError);
   Return a C++ string from the aRef() value of attr. This value
   will use the column and column type from attr. The advantage is
   for reading; the same ArrayAdapter can be used for multiple
   columns. The disadvantage is; passing an attribute not of
   [VAR]CHAR/BINARY type will result in a traditional exit(-1)
 std::string get_string(const NdbRecAttr* attr,
                         ErrorType& error) const;
  /* Calculate the first_byte and number of bytes in aRef for attr */
 void get_byte_array(const NdbRecAttr* attr,
                      const char*& first_byte,
                      size_t& bytes,
                      ErrorType& error) const;
  /* Check if a column is of type [VAR]BINARY */
 bool is_binary_array_type(const NdbDictionary::Column::Type t) const;
```

```
/* Check if a column is of type [VAR]BINARY or [VAR]CHAR */
     bool is_array_type(const NdbDictionary::Column::Type t) const;
private:
     /* Disable copy constructor */
     ReadOnlyArrayAdapter(const ReadOnlyArrayAdapter& a) {}
};
     Extension to ReadOnlyArrayAdapter to be used together with
      insert/write/update operations. Memory is allocated for each
     call to make_aRef or allocate_in_bytes. The memory allocated will
     be deallocated by the destructor. To save memory, the scope of an % \left( 1\right) =\left( 1\right) +\left( 1\right) +
      instance of this class should not be longer than the life time of
      the transaction. On the other hand, it must be long enough for the
     usage of all references created
      * /
class ReadWriteArrayAdapter : public ReadOnlyArrayAdapter {
     ReadWriteArrayAdapter() {}
      /* Destructor, the only place where memory is deallocated */
      ~ReadWriteArrayAdapter();
         Create a binary representation of the string 's' and return a
         pointer to it. This pointer can later be used as argument to for
          example setValue
      char* make_aRef(const NdbDictionary::Column* column,
                                                             std::string s,
                                                             ErrorType& error);
         Allocate a number of bytes suitable for this column type. aRef
          can later be used as argument to for example setValue. first_byte
          is the first byte to store data to. bytes is the number of bytes
          to allocate
      void allocate_in_bytes(const NdbDictionary::Column* column,
                                                                                     char*& aRef,
                                                                                     char*& first_byte,
                                                                                     size_t bytes,
                                                                                     ErrorType& error);
private:
       /* Disable copy constructor */
     ReadWriteArrayAdapter(const ReadWriteArrayAdapter& a)
             :ReadOnlyArrayAdapter() {}
      /* Record of allocated char arrays to delete by the destructor */
     std::vector<char*> aRef_created;
inline ReadWriteArrayAdapter::~ReadWriteArrayAdapter()
      for (std::vector<char*>::iterator i = aRef_created.begin();
                      i != aRef_created.end();
                        ++i) {
             delete [] *i;
char*
```

```
ReadWriteArrayAdapter::
make_aRef(const NdbDictionary::Column* column,
          std::string input,
          ErrorType& error)
  char* new_ref;
  char* data_start;
  Allocate bytes and push them into the aRef_created vector.
  After this operation, new_ref has a complete aRef to use in insertion
   and data_start has ptr from which data is to be written.
  The new_aref returned is padded completely with blank spaces.
  allocate_in_bytes(column, new_ref, data_start, input.length(), error);
  if(error != Success)
   return NULL;
  Copy the input string into aRef's data pointer
  without affecting remaining blank spaces at end.
  strncpy(data_start, input.c_str(), input.length());
  return new_ref;
void
ReadWriteArrayAdapter::
allocate_in_bytes(const NdbDictionary::Column* column,
                  char*& aRef,
                  char*& first_byte,
                  size_t bytes,
                  ErrorType& error)
  bool is_binary;
  char zero_char;
  NdbDictionary::Column::ArrayType array_type;
  size_t max_length;
  /* unless there is going to be any problem */
  error = Success;
  if (column == NULL)
    error = InvalidNullColumn;
   aRef = NULL;
   first_byte = NULL;
   return;
  if (!is_array_type(column->getType()))
    error = InvalidColumnType;
    aRef = NULL;
   first_byte = NULL;
   return;
  is_binary = is_binary_array_type(column->getType());
  zero_char = (is_binary ? 0 : ' ');
  array_type = column->getArrayType();
  max_length = column->getLength();
```

```
if (bytes > max_length)
   error = BytesOutOfRange;
   aRef = NULL;
   first_byte = NULL;
   return;
  switch (array_type) {
 case NdbDictionary::Column::ArrayTypeFixed:
   /* no need to store length bytes */
   aRef = new char[max_length];
   first_byte = aRef;
    /* pad the complete string with blank space (or) null bytes */
   for (size_t i=0; i < max_length; i++) {</pre>
     aRef[i] = zero_char;
   break;
  case NdbDictionary::Column::ArrayTypeShortVar:
    /* byte length stored over first byte. no padding required */
   aRef = new char[1 + bytes];
   first_byte = aRef + 1;
   aRef[0] = (char)bytes;
   break;
  case NdbDictionary::Column::ArrayTypeMediumVar:
   /* byte length stored over first two bytes. no padding required */
   aRef = new char[2 + bytes];
   first_byte = aRef + 2;
   aRef[0] = (char)(bytes % 256);
   aRef[1] = (char)(bytes / 256);
   break;
 aRef_created.push_back(aRef);
std::string ReadOnlyArrayAdapter::get_string(const NdbRecAttr* attr,
                                             ErrorType& error) const
 size_t attr_bytes= 0;
 const char* data_ptr= NULL;
 std::string result= "";
  /* get the beginning of data and its size.. */
 get_byte_array(attr, data_ptr, attr_bytes, error);
  if(error != Success)
   return result;
  /* ..and copy the value into result */
 result = string(data_ptr, attr_bytes);
  /* special treatment for FixedArrayType to eliminate padding characters */
  if(attr->getColumn()->getArrayType() == NdbDictionary::Column::ArrayTypeFixed)
   char padding_char = ' ';
   std::size_t last = result.find_last_not_of(padding_char);
   result = result.substr(0, last+1);
 return result;
```

```
void
ReadOnlyArrayAdapter::
get_byte_array(const NdbRecAttr* attr,
               const char*& data_ptr,
               size_t& bytes,
               ErrorType& error) const
  /* unless there is a problem */
  error= Success;
  if (attr == NULL)
   error = InvalidNullAttribute;
   return;
  if (!is_array_type(attr->getType()))
    error = InvalidColumnType;
    return;
  const NdbDictionary::Column::ArrayType array_type =
    attr->getColumn()->getArrayType();
  const size_t attr_bytes = attr->get_size_in_bytes();
  const char* aRef = attr->aRef();
  if(aRef == NULL)
    error= InvalidNullaRef;
  switch (array_type) {
  case NdbDictionary::Column::ArrayTypeFixed:
   /* no length bytes stored with aRef */
    data_ptr = aRef;
   bytes = attr_bytes;
   break;
  case NdbDictionary::Column::ArrayTypeShortVar:
    /* first byte of aRef has length of the data */
    data_ptr = aRef + 1;
   bytes = (size_t)(aRef[0]);
   break;
  case NdbDictionary::Column::ArrayTypeMediumVar:
   /* first two bytes of aRef has length of the data */
    data_ptr = aRef + 2;
   bytes = (size_t)(aRef[1]) * 256 + (size_t)(aRef[0]);
   break;
    /* should never reach here */
   data_ptr = NULL;
   bytes = 0;
    error = InvalidArrayType;
    break;
bool
ReadOnlyArrayAdapter::
is_binary_array_type(const NdbDictionary::Column::Type t) const
  bool is_binary;
  switch (t)
```

```
case NdbDictionary::Column::Binary:
 case NdbDictionary::Column::Varbinary:
 case NdbDictionary::Column::Longvarbinary:
   is_binary = true;
   break;
 default:
   is_binary = false;
 return is_binary;
bool
ReadOnlyArrayAdapter::
is_array_type(const NdbDictionary::Column::Type t) const
 bool is_array;
 switch (t)
 case NdbDictionary::Column::Binary:
 case NdbDictionary::Column::Varbinary:
 case NdbDictionary::Column::Longvarbinary:
 case NdbDictionary::Column::Char:
 case NdbDictionary::Column::Varchar:
 case NdbDictionary::Column::Longvarchar:
   is_array = true;
   break;
 default:
   is_array = false;
  return is_array;
#endif // #ifndef ARRAY_ADAPTER_HPP
```

error_handling.hpp

```
#ifndef ERROR_HANDLING_HPP
#define ERROR_HANDLING_HPP
template <typename T>
inline static void print_if_not_equal(T got,
                                     T expected,
                                      const char* msg,
                                      const char* file,
                                      int line)
 std::cout << "Got value " << got << " instead of expected value " << expected
            << " in " << file << ":" << line;
#define PRINT_IF_NOT_EQUAL(got, expected, msg) {
   if (got != expected) {
     print_if_not_equal(got, expected, msg, __FILE__, __LINE__);
      exit(-1);
#define PRINT_ERROR(code,msg)
 std::cout << "Error in " << __FILE__ << ", line: " << __LINE__
           << ", code: " << code
            << ", msg: " << msg << "." << std::endl
#define APIERROR(error) {
 PRINT_ERROR(error.code,error.message); \
 exit(-1); }
```

#endif

ndb_util.hpp

```
#ifndef NDB_UTIL_HPP
#define NDB_UTIL_HPP
#include <NdbApi.hpp>
#include <string>
#include <sstream>
static const std::string column_type_to_string(NdbDictionary::Column::Type type)
 switch (type)
 case NdbDictionary::Column::Undefined:
   return "Undefined";
 case NdbDictionary::Column::Tinyint:
   return "Tinyint";
 case NdbDictionary::Column::Tinyunsigned:
   return "Tinyunsigned";
 case NdbDictionary::Column::Smallint:
   return "Smallint";
 case NdbDictionary::Column::Smallunsigned:
   return "Smallunsigned";
 case NdbDictionary::Column::Mediumint:
   return "Mediumint";
 case NdbDictionary::Column::Mediumunsigned:
   return "Mediumunsigned";
 case NdbDictionary::Column::Int:
   return "Int";
 case NdbDictionary::Column::Unsigned:
   return "Unsigned";
 case NdbDictionary::Column::Bigint:
   return "Bigint";
 case NdbDictionary::Column::Bigunsigned:
   return "Bigunsigned";
 case NdbDictionary::Column::Float:
   return "Float";
 case NdbDictionary::Column::Double:
   return "Double";
 case NdbDictionary::Column::Olddecimal:
   return "Olddecimal";
 case NdbDictionary::Column::Olddecimalunsigned:
   return "Olddecimalunsigned";
 case NdbDictionary::Column::Decimal:
   return "Decimal";
 case NdbDictionary::Column::Decimalunsigned:
   return "Decimalunsigned";
 case NdbDictionary::Column::Char:
   return "Char";
 case NdbDictionary::Column::Varchar:
   return "Varchar";
 case NdbDictionary::Column::Binary:
   return "Binary";
 case NdbDictionary::Column::Varbinary:
   return "Varbinary";
 case NdbDictionary::Column::Datetime:
   return "Datetime";
 case NdbDictionary::Column::Date:
   return "Date";
 case NdbDictionary::Column::Blob:
   return "Blob";
 case NdbDictionary::Column::Text:
   return "Text";
 case NdbDictionary::Column::Bit:
```

```
return "Bit";
 case NdbDictionary::Column::Longvarchar:
   return "Longvarchar";
 case NdbDictionary::Column::Longvarbinary:
   return "Longvarbinary";
 case NdbDictionary::Column::Time:
   return "Time";
 case NdbDictionary::Column::Year:
   return "Year";
 case NdbDictionary::Column::Timestamp:
  return "Timestamp";
 case NdbDictionary::Column::Time2:
   return "Time2";
 case NdbDictionary::Column::Datetime2:
   return "Datetime2";
 case NdbDictionary::Column::Timestamp2:
   return "Timestamp2";
 default:
     std::string str;
     std::stringstream s(str);
     s << "Unknown type: " << type;
     return s.str();
#endif
```

util.hpp

```
#include <string>

/* Return a string containing 'n' copies of the string 's'. */
static std::string operator * (unsigned n, const std::string& s)
{
   std::string result;
   result.reserve(n * s.length());
   for (unsigned i = 0; i < n; i++)
   {
      result.append(s);
   }
   return result;
}
#endif // #ifndef UTIL_HPP</pre>
```

Chapter 3 The MGM API

Table of Contents

3.1 N	MGM API Concepts	599
3.2 N	MGM API Function Listing	601
	3.2.1 Log Event Functions	
	3.2.2 MGM API Error Handling Functions	604
	3.2.3 Management Server Handle Functions	606
	3.2.4 Management Server Connection Functions	607
	3.2.5 Cluster Status Functions	613
	3.2.6 Functions for Starting & Stopping Nodes	615
	3.2.7 Cluster Log Functions	621
	3.2.8 Backup Functions	623
	3.2.9 Single-User Mode Functions	627
3.3 N	MGM API Data Types	
3.4 N	MGM API Data Structures	636
3.5 N	MGM API Errors	643
3.6 N	MGM API Examples	645
	3.6.1 Basic MGM API Event Logging Example	645
	3.6.2 MGM API Event Handling with Multiple Clusters	

This chapter discusses the NDB Cluster Management API, a C language API that is used for administrative tasks such as starting and stopping Cluster nodes, backups, and logging. It also covers MGM API concepts, programming constructs, and event types.

3.1 MGM API Concepts

This section describes concepts basic to the NDB Cluster MGM API.

- NdbMgmHandle
- · Working with Log Events
- Structured Log Events

NdbMgmHandle

Each MGM API function needs a management server handle of type NdbMgmHandle. This handle is created by calling the function ndb_mgm_create_handle() and freed by calling ndb_mgm_destroy_handle().

See ndb_mgm_create_handle(), and ndb_mgm_destroy_handle(), for more information about these two functions.



Important

You should not share an NdbMgmHandle between threads. While it is possible to do so (if you implement your own locks), this is not recommended; each thread should use its own management server handle.

A function can return any of the following:

An integer value, with a value of -1 indicating an error.

- A nonconstant pointer value. A NULL value indicates an error; otherwise, the return value must be freed by the programmer.
- A constant pointer value, with a NULL value indicating an error. The returned value should not be freed.

Error conditions can be identified by using the appropriate error-reporting functions ndb_mgm_get_latest_error() and ndb_mgm_error().

Here is an example using the MGM API (without error handling for brevity's sake):

```
NdbMgmHandle handle= ndb_mgm_create_handle();
ndb_mgm_connect(handle,0,0,0);
struct ndb_mgm_cluster_state *state= ndb_mgm_get_status(handle);
for(int i=0; i < state->no_of_nodes; i++)
{
    struct ndb_mgm_node_state *node_state= &state->node_states[i];
    printf("node with ID=%d ", node_state->node_id);

    if(node_state->version != 0)
        printf("connected\n");
    else
        printf("not connected\n");
}
free((void*)state);
ndb_mgm_destroy_handle(&handle);
```

Working with Log Events

Data nodes and management servers both regularly and on specific occasions report on various log events that occur in the cluster. These log events are written to the cluster log. Optionally an MGM API client may listen to these events using the method ndb_mgm_listen_event(). Each log event belongs to a category ndb_mgm_event_category) and has a severity ndb_mgm_event_severity associated with it. Each log event also has a level (0-15) associated with it.

```
Which log events that come out is controlled with ndb_mgm_listen_event(), ndb_mgm_set_clusterlog_loglevel(), and ndb_mgm_set_clusterlog_severity_filter().
```

This is an example showing how to listen to events related to backup:

```
int filter[] = { 15, NDB_MGM_EVENT_CATEGORY_BACKUP, 0 };
int fd = ndb_mgm_listen_event(handle, filter);
```

Structured Log Events

Handling of structured log events in the MGM API involves the following steps:

- 1. Create an NdbLogEventHandle using ndb_mgm_create_logevent_handle().
- 2. Wait for and store log events using ndb_logevent_get_next().
- 3. The log event data is available in the structure ndb_logevent. The data which is specific to a particular event is stored in a union between structures; use ndb_logevent::type to decide which structure is valid.

The following sample code demonstrates listening to events related to backups:

```
int filter[] = { 15, NDB_MGM_EVENT_CATEGORY_BACKUP, 0 };
NdbLogEventHandle le_handle= ndb_mgm_create_logevent_handle(handle, filter);
struct ndb_logevent le;
int r= ndb_logevent_get_next(le_handle, &le, 0);
if(r < 0)
    /* error */</pre>
```

```
else if(r == 0)
    /* no event */

switch(le.type)
{
    case NDB_LE_BackupStarted:
        ... le.BackupStarted.starting_node;
        ... le.BackupStarted.backup_id;
        break;
    case NDB_LE_BackupFailedToStart:
        ... le.BackupFailedToStart.error;
        break;
    case NDB_LE_BackupCompleted:
        ... le.BackupCompleted.stop_gci;
        break;
    case NDB_LE_BackupAborted:
        ... le.BackupStarted.backup_id;
        break;
    default:
        break;
}
```

For more information, see Section 3.2.1, "Log Event Functions".

Available log event types are listed in The Ndb_logevent_type Type, as well as in the file /storage/ndb/include/mgmapi/ndb_logevent.h in the NDB Cluster sources.

3.2 MGM API Function Listing

The next few sections provide information about the functions and data structures used by the MGM API. These listings are grouped by purpose or use.

3.2.1 Log Event Functions

This section provides information about MGM API functions used for listening to log events.

- ndb_mgm_listen_event()
- ndb_mgm_create_logevent_handle()
- ndb_mgm_destroy_logevent_handle()
- ndb_logevent_get_fd()
- ndb_logevent_get_next()
- ndb_logevent_get_next2()
- ndb_logevent_get_latest_error()
- ndb_logevent_get_latest_error_msg()

ndb_mgm_listen_event()

Description

This function is used to listen to log events, which are read from the return file descriptor. Events use a text-based format, the same as in the cluster log.

Signature

```
int ndb_mgm_listen_event
    (
        NdbMgmHandle handle,
        const int filter[]
```

Parameters

This function takes two arguments:

- An NdbMgmHandle handle.
- A filter which consists of a series of {level, ndb_mgm_event_category} pairs (in a single array) that are pushed to a file descriptor. Use 0 for the level to terminate the list.

Return value

The file descriptor from which events are to be read.

ndb_mgm_create_logevent_handle()

Description

This function is used to create a log event handle.

Signature

```
NdbLogEventHandle ndb_mgm_create_logevent_handle
   (
     NdbMgmHandle handle,
     const int filter[]
)
```

Parameters

This function takes two arguments:

- An NdbMgmHandle handle.
- A filter which consists of a series of {level, ndb_mgm_event_category} pairs (in a single array) that are pushed to a file descriptor. Use 0 for the level to terminate the list.

Return value

A log event handle.

ndb_mgm_destroy_logevent_handle()

Description

Use this function to destroy a log event handle when there is no further need for it.

Signature

```
void ndb_mgm_destroy_logevent_handle
    (
        NdbLogEventHandle* handle
    )
```

Parameters

A pointer to a log event *handle*.

Return value

None.

ndb_logevent_get_fd()

Description

This function retrieves a file descriptor from an NdbMgmLogEventHandle; this descriptor can be used in (for example) an application select() call.



Warning

Do not attempt to read from the file descriptor returned by this function; this can cause the descriptor to become corrupted.

Signature

```
int ndb_logevent_get_fd
    (
        const NdbLogEventHandle handle
    )
```

A LogEventHandle.

Return value

A file descriptor. In the event of failure, -1 is returned.

ndb_logevent_get_next()

Description

This function is used to retrieve the next log event, using data from the event to fill in the supplied ndb_logevent structure.

Signature

```
int ndb_logevent_get_next
   (
        const NdbLogEventHandle handle,
        struct ndb_logevent* logevent,
        unsigned timeout
   )
```



Important

Prior to NDB 7.3.2, the log event's ndb_mgm_event_category was cast to an enum type. This behavior, although incorrect, interfered with existing applications and was reinstated in NDB 7.3.7; a new function exhibiting the corrected behavior ndb_logevent_get_next2() was added in these releases.

Parameters

Three parameters are expected by this function:

- An NdbLogEventHandle
- A pointer to an ndb_logevent data structure
- The number of milliseconds to wait for the event before timing out; passing 0 for this parameter causes the function to block until the next log event is received

Return value

The value returned by this function is interpreted as follows: If the return value is less than or equal to zero, then the *logevent* is not altered or affected in any way.

- > 0: The event exists, and it data was retrieved into the *logevent*
- 0: A timeout occurred while waiting for the event (more than timeout milliseconds elapsed)
- < 0: An error occurred.

ndb_logevent_get_next2()

Description

This function is used to retrieve the next log event, using data from the event to fill in the supplied ndb_logevent structure.

ndb_logevent_get_next2() was added in NDB 7.3.7. It is intended to serve as a replacement for ndb_logevent_get_next() which corrects that function's handling of the structure's ndb_mgm_event_category, for applications which do not require backward compatibility. It is otherwise identical to ndb_logevent_get_next().

```
int ndb_logevent_get_next2
   (
      const NdbLogEventHandle handle,
      struct ndb_logevent* logevent,
      unsigned timeout
)
```

Three parameters are expected by this function:

- An NdbLogEventHandle
- A pointer to an ndb_logevent data structure
- The number of milliseconds to wait for the event before timing out; passing 0 for this parameter causes the function to block until the next log event is received

Return value

The value returned by this function is interpreted as follows: If the return value is less than or equal to zero, then the *logevent* is not altered or affected in any way.

- > 0: The event exists, and it data was retrieved into the *logevent*
- 0: A timeout occurred while waiting for the event (more than timeout milliseconds elapsed)
- < 0: An error occurred.

ndb_logevent_get_latest_error()

Description

This function retrieves the error code from the most recent error.



Note

You may prefer to use $ndb_logevent_get_latest_error_msg()$ instead. See $ndb_logevent_get_latest_error_msg()$

Signature

int ndb_logevent_get_latest_error
 (
 const NdbLogEventHandle handle
)

Parameters

A log event handle.

Return value

An error code.

ndb_logevent_get_latest_error_msg()

Description

Retrieves the text of the most recent error obtained while trying to read log events.

Signature

const char* ndb_logevent_get_latest_error_msg
 (
 const NdbLogEventHandle handle
)

Parameters

A log event handle.

Return value

The text of the error message.

3.2.2 MGM API Error Handling Functions

This section provides information about MGM API functions used for error handling.

Each MGM API error is characterised by an error code and an error message. There may also be an error description that provides additional information about the error. The MGM API includes functions to obtain this information in the event of an error.

- ndb_mgm_get_latest_error()
- ndb_mgm_get_latest_error_msg()
- ndb_mgm_get_latest_error_desc()
- ndb_mgm_set_error_stream()

ndb_mgm_get_latest_error()

Description

This function is used to get the latest error code associated with a given management server handle.

Prior to NDB 7.4.8, this function was not safe for use with NULL. In later versions, ndb_mgm_get_latest_error() is null-safe but returns an arbitrary value. (Bug #78130, Bug #21651706)

Signature

```
int ndb_mgm_get_latest_error
    (
        const NdbMgmHandle handle
    )
```

Parameters

An NdbMgMHandle.

Return value

An error code corresponding to an ndb_mgm_error value. You can obtain the related error message using ndb_mgm_get_latest_error_msg().

ndb_mgm_get_latest_error_msg()

Description

This function is used to obtain the latest general error message associated with an NdbMgmHandle.

Prior to NDB 7.4.8, this function was not safe for use with NULL. In later versions, ndb_mgm_get_latest_error_msg() is null-safe but returns an arbitrary value. (Bug #78130, Bug #21651706)

Signature

```
const char* ndb_mgm_get_latest_error_msg
    (
        const NdbMgmHandle handle
    )
```

Parameters

An NdbMgmHandle.

Return value

The error message text. More specific information can be obtained using ndb_mgm_get_latest_error_desc()-

ndb_mgm_get_latest_error_desc()

Description

Get the most recent error description associated with an NdbMgmHandle; this description provides additional information regarding the error message.

Prior to NDB 7.4.8, this function was not safe for use with NULL. In later versions, ndb_mgm_get_latest_error_desc() is null-safe but returns an arbitrary value. (Bug #78130, Bug #21651706)

```
const char* ndb_mgm_get_latest_error_desc
  (
    const NdbMgmHandle handle
)
```

Parameters An NdbMgmHandle.

Return value The error description text.

ndb_mgm_set_error_stream()

Description The function can be used to set the error output stream.

Signature void ndb_mgm_set_error_stream

(
NdbMgmHandle handle,
FILE* file

Parameters This function requires two parameters:

• An NdbMgmHandle

• A pointer to the file to which errors are to be sent.

Return value None.

3.2.3 Management Server Handle Functions

This section provides information about MGM API functions used to create and destroy management server handles (see NdbMgmHandle).

- ndb_mgm_create_handle()
- ndb_mgm_set_name()
- ndb_mgm_set_ignore_sigpipe()
- ndb_mgm_destroy_handle()

ndb_mgm_create_handle()

Description This function is used to create a handle to a management server.

Signature NdbMgmHandle ndb_mgm_create_handle

(
 void
)

Parameters None.

Return value An NdbMgmHandle.

ndb_mgm_set_name()

Description This function can be used to set a name for the management server

handle, which is then reported in the Cluster log.

Signature void ndb_mgm_set_name

Void ndb_mgm_set_name
(

NdbMgmHandle handle,

const char* name
)

Parameters This function takes two arguments:

• A management server handle.

• The desired name for the handle.

Return value

None.

ndb_mgm_set_ignore_sigpipe()

Description

The MGM API by default installs a signal handler that ignores all SIGPIPE signals that might occur when writing to asocket that has been closed or reset. An application that provides its own handler for SIGPIPE should call this function after creating the management server handle and before using the handle to connect to the management server. (In other words, call this function after using ndb_mgm_create_handle() but before calling ndb_mgm_connect(), which causes the MGM API's SIGPIPE handler to be installed unless overridden.)

Signature

```
int ndb_mgm_set_ignore_sigpipe
    (
        NdbMgmHandle handle,
        int ignore = 1
    )
```

Parameters

This function takes two parameters:

- A management server handle
- An integer value which determines whether to *ignore* SIGPIPE errors. Set this to 1 (the default) to cause the MGM API to ignore SIGPIPE; set to zero if you wish for SIGPIPE to propagate to your MGM API application.

Return value

None.

ndb_mgm_destroy_handle()

Description

This function destroys a management server handle

Signature

```
void ndb_mgm_destroy_handle
(
NdbMgmHandle* handle
```

Parameters

A pointer to the NdbMgmHandle to be destroyed.

Return value None.

3.2.4 Management Server Connection Functions

This section provides information about MGM API functions that are used to initiate, configure, and terminate connections to an NDB management server.

- ndb_mgm_get_connectstring()
- ndb_mgm_get_configuration_nodeid()
- ndb_mgm_get_connected_port()
- ndb_mgm_get_connected_host()

- ndb_mgm_get_version()
- ndb_mgm_is_connected()
- ndb_mgm_check_connection()
- ndb_mgm_number_of_mgmd_in_connect_string()
- ndb_mgm_set_bindaddress()
- ndb_mgm_set_connectstring()
- ndb_mgm_set_configuration_nodeid()
- ndb_mgm_set_timeout()
- ndb_mgm_connect()
- ndb_mgm_disconnect()

ndb_mgm_get_connectstring()

Description

This function retrieves the connection string used for a connection.



Note

This function returns the default connection string if no call to ndb_mgm_set_connectstring() has been performed. In addition, the returned connection string may be formatted slightly differently than the original in that it may contain specifiers not present in the original.

The connection string format is the same as that discussed for ndb_mgm_set_connectstring().

Signature

```
const char* ndb_mgm_get_connectstring
   (
     NdbMgmHandle handle,
     char* buffer,
     int size
)
```

Parameters

This function takes three arguments:

- An NdbMgmHandle.
- A pointer to a *buffer* in which to place the result.
- The size of the buffer.

Return value

The connection string—this is the same value that is pushed to the *buffer*.

ndb_mgm_get_configuration_nodeid()

Description

This function gets the ID of the node to which the connection is being (or was) made.

```
int ndb_mgm_get_configuration_nodeid
   (
     NdbMgmHandle handle
   )
```

Parameters A management server handle.

Return value A node ID.

ndb_mgm_get_connected_port()

Description This function retrieves the number of the port used by the connection.

Signature int ndb_mgm_get_connected_port

NdbMgmHandle handle

Parameters An NdbMgmHandle.

Return value A port number.

ndb_mgm_get_connected_host()

Description This function is used to obtain the name of the host to which the

connection is made.

Signature const char* ndb_mgm_get_connected_host

(
NdbMgmHandle handle

Parameters A management server *handle*.

Return value A host name.

ndb_mgm_get_version()

Description Given a management server handle, this function gets NDB engine

and MySQL Server version information for the indicated management

server.

Signature int ndb_mgm_get_version

```
(
NdbMgmHandle handle,
int* major,
int* minor,
int* build,
int length,
char* string
```

Parameters

An NdbMgmHandle, and pointers to the NDB engine major, minor, and build version values, as well as a pointer to the version string (along

with the strength's *length*).

The version string uses the format mysql-x.x.x ndb-y.y.y-status, where x.x.x is the three-part MySQL Server version, and y.y.y is the three-part NDB storage engine version. The status string indicates the release level or status; usually this is one of beta, rc, or ga, but other values are sometimes possible.

Return value ndb_mgm_get_version() returns an integer: 0 on success; any

nonzero value indicates an error.

ndb_mgm_is_connected()

Description Used to determine whether a connection has been established.



Note

This function does not determine whether or not there is a "live" management server at the other end of the connection. Use ndb_mgm_check_connection() to accomplish that task.

Signature

```
int ndb_mgm_is_connected
    (
        NdbMgmHandle handle
    )
```

Parameters

A management server *handle*.

Return value

This function returns an integer, whose value is interpreted as follows:

- 0: Not connected to the management node.
- Any nonzero value: A connection has been established with the management node.

ndb_mgm_check_connection()

Description

This function can be used to determine whether a management server is running on a given connection from a management client.

Signature

```
int ndb_mgm_check_connection
    (
        NdbMgmHandle handle
    )
```

Parameters

An NdbMgmHandle (see Section 3.1, "MGM API Concepts").

Return value

In NDB 7.5 and later, this function returns 0 on success, -1 when the handle is null, and -2 when not connected.

In NDB 7.4 and earlier, this function returned -1 in the event of an error; otherwise it returned 0, even when the management server handle was NULL, or when the connection check failed (Bug #53242, Bug #11760802).

ndb_mgm_number_of_mgmd_in_connect_string()

Description

This is a convenience function which provides an easy way to determine the number of management servers referenced in a connection string as set using ndb_mgm_set_connectstring().

Signature

```
int ndb_mgm_number_of_mgmd_in_connect_string
    (
      NdbMgmHandle handle
    )
```

Parameters

A management handle (NdbMgmHandle).

Return value

On success, a nonnegative integer; a negative integer indicates failure.

ndb_mgm_set_bindaddress()

Description

This function makes it possible to set a local bind address for the management server. If used, it must be called before connecting to the management server.

Signature

int ndb_mgm_set_bindaddress

```
(
   NdbMgmHandle handle,
   const char* address
)
```

This function takes two parameters:

- A management handle (NdbMgmHandle).
- A string address of the form host[:port].

Return value

Returns an integer:

- · 0 indicates success
- Any nonzero value indicates failure (the address was not valid)



Important

Errors caused by binding an otherwise valid local address are not reported until the connection to the management is actually attempted.

ndb_mgm_set_connectstring()

Description

This function is used to set the connection string for a management server connection to a node.

Signature

```
int ndb_mgm_set_connectstring
   (
      NdbMgmHandle handle,
      const char* connection_string
)
```

Parameters

ndb mgm set connectstring() takes two parameters:

- A management server handle.
- A connection_string whose format is shown here:

```
connection_string :=
   [nodeid-specification,]host-specification[,host-specification]
```

It is possible to establish connections with multiple management servers using a single connection string.

```
nodeid-specification := nodeid=id
host-specification := host[:port]
```

id, port, and host are defined as follows:

- id: An integer greater than 0 identifying a node in config.ini.
- port: An integer referring to a standard Unix port.
- host: A string containing a valid network host address.

Return value

This function returns -1 in the event of failure.

ndb_mgm_set_configuration_nodeid()

Description

This function sets the connection node ID.

Signature

```
int ndb_mgm_set_configuration_nodeid
   (
     NdbMgmHandle handle,
     int id
)
```

Parameters

This function requires two parameters:

- An NdbMgmHandle.
- The id of the node to connect to.

Return value

This function returns -1 in the event of failure.

ndb_mgm_set_timeout()

Description

Normally, network operations time out after 60 seconds. This function permits you to vary this time.



Important

The timeout set by this function applies not only to establishing network connections, but to *every* operation requiring communication using a network connection. This includes each network read or write performed by any MGM API function, NDB API method call, or ndb_mgm client command.

Signature

```
int ndb_mgm_set_timeout
   (
      NdbMgmHandle handle,
      unsigned int timeout
   )
```

Parameters

This function takes two parameters:

- A management server handle (NdbMgmHandle).
- An amount of time to wait before timing out, expressed in milliseconds.

Return value

Returns 0 on success, with any other value representing failure.

ndb_mgm_connect()

Description

This function establishes a connection to a management server specified by the connection string set by ndb_mgm_set_connectstring().

```
int ndb_mgm_connect
   (
     NdbMgmHandle handle,
     int retries,
     int delay,
     int verbose
)
```

This function takes 4 arguments:

- A management server handle.
- The number of retries to make when attempting to connect. 0 for this value means that one connection attempt is made.
- The number of seconds to *delay* between connection attempts.
- If *verbose* is 1, then a message is printed for each connection attempt.

Return value

This function returns -1 in the event of failure.

ndb_mgm_disconnect()

Description

This function terminates a management server connection.

Signature

```
int ndb_mgm_disconnect
    (
         NdbMgmHandle handle
    )
```

Parameters

An NdbMqmHandle.

Return value

Returns -1 if unable to disconnect.

3.2.5 Cluster Status Functions

This section provides information about MGM API functions used to obtain status information from NDB Cluster nodes.

- ndb_mgm_get_status()
- ndb_mgm_get_status2()
- ndb_mgm_dump_state()

ndb_mgm_get_status()

Description

This function is used to obtain the status of the nodes in an NDB Cluster.



Note

The caller must free the pointer returned by this function.

Signature

```
struct ndb_mgm_cluster_state* ndb_mgm_get_status
    (
        NdbMgmHandle handle
)
```

Parameters

This function takes a single parameter, a management server *handle*.

Return value

A pointer to an ndb_mgm_cluster_state data structure.

ndb_mgm_get_status2()

Description

This function is similar to ndb_mgm_get_status(), in that it is used to obtain the status of the nodes in an NDB Cluster. However, ndb_mgm_get_status2() allows one to specify the type or types of nodes (ndb_mgm_node_type) to be checked.



Note

The caller must free the pointer returned by this function.

Signature

Parameters

This function takes two parameters:

- A management server handle
- A pointer to array of the node types to be checked. These are ndb_mgm_node_type values. The array should be terminated by an element of type NDB_MGM_NODE_TYPE_UNKNOWN.

Return value

A pointer to an ndb_mgm_cluster_state data structure.

ndb_mgm_dump_state()

Description

This function can be used to dump debugging information to the cluster log. The NDB Cluster management client DUMP command is a wrapper for this function.

ndb_mgm_dump_state(), like the DUMP command, can cause a running NDB Cluster to malfunction or even to fail completely if it is used improperly. Be sure to consult the relevant documentation before using this function. For more information on the DUMP command, and for a listing of current DUMP codes and their effects, see NDB Cluster Management Client DUMP Commands.

Signature

```
int ndb_mgm_dump_state
   (
      NdbMgmHandle handle,
      int nodeId,
      const int* arguments,
      int numberOfArguments,
      struct ndb_mgm_reply* reply
   )
```

Parameters

This function takes the following pararemeters:

- A management server handle (NdbMgmHandle)
- The nodeId of a cluster data node.
- An array of arguments. The first of these is the DUMP code to be executed. Subsequent arguments can be passed in this array if needed by or desired for the corresponding DUMP command.
- The numberOfArguments to be passed.

 An ndb_mgm_reply, which contains a return code along with a response or error message.

Return value

on success; otherwise, an error code.

Example. The following example has the same result as running 2 DUMP 1000 in the management client:

```
// [...]
#include <mgmapi_debug.h>
// [...]
struct ndb_mgm_reply reply;
int args[1];
int stat, arg_count, node_id;

args[0] = 1000;
arg_count = 1;
node_id = 2;
stat = ndb_mgm_dump_state(h, node_id, args, arg_count, &reply);
```

3.2.6 Functions for Starting & Stopping Nodes

The MGM API provides several functions which can be used to start, stop, and restart one or more Cluster data nodes. These functions are described in this section.

Starting, Stopping, and Restarting Nodes. You can start, stop, and restart Cluster nodes using the following functions, which are described in more detail in the next few sections.

- Starting Nodes. Use ndb_mgm_start().
- **Stopping Nodes.** Use ndb_mgm_stop(), ndb_mgm_stop2(), ndb_mgm_stop3(), or ndb_mgm_stop4().

Normally, you cannot use any of these functions to stop a node while other nodes are starting. You can override this restriction using ndb_mgm_stop4() with the *force* parameter set to 1.

• **Restarting Nodes.** Use ndb_mgm_restart(), ndb_mgm_restart2(), ndb_mgm_restart3(), or ndb_mgm_restart4().

Normally, you cannot use any of these functions to restart a node while other nodes are starting. You can override this restriction using ndb_mgm_restart4() with the force parameter set to 1.

- ndb_mgm_start()
- ndb_mgm_stop()
- ndb_mgm_stop2()
- ndb_mgm_stop3()
- ndb_mgm_stop4()
- ndb_mgm_restart()
- ndb_mgm_restart2()
- ndb_mgm_restart3()
- ndb_mgm_restart4()

ndb_mgm_start()

Description

This function can be used to start one or more Cluster nodes. The nodes to be started must have been started with the no-start option (-n), meaning that the data node binary was started and is waiting for a START management command which actually enables the node.

Signature

```
int ndb_mgm_start
   (
    NdbMgmHandle handle,
    int number,
    const int* list
)
```

Parameters

ndb_mgm_start() takes 3 parameters:

- An NdbMgmHandle.
- A number of nodes to be started. Use 0 to start all of the data nodes in the cluster.
- A list of the node IDs of the nodes to be started.

Return value

The number of nodes actually started; in the event of failure, -1 is returned.

ndb_mgm_stop()

Description

This function stops one or more data nodes.

Signature

```
int ndb_mgm_stop
   (
    NdbMgmHandle handle,
    int number,
    const int* list
)
```

Parameters

 $\label{limiting_model} $$ ndb_mgm_stop() $ takes 3 parameters: Calling this function is $$ equivalent to calling ndb_mgm_stop2(handle, number, list, 0). $$$

- An NdbMgmHandle.
- The *number* of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.

Return value

The number of nodes actually stopped; in the event of failure, -1 is returned.

ndb_mgm_stop2()

Description

Like $ndb_mgm_stop()$, this function stops one or more data nodes. However, it offers the ability to specify whether or not the nodes shut down gracefully.

```
NdbMgmHandle handle,
int number,
const int* list,
int abort
)
```

ndb_mgm_stop2() takes 4 parameters:

- An NdbMgmHandle.
- The number of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A list of the node IDs of the nodes to be stopped.
- The value of *abort* determines how the nodes will be shut down. 1 indicates the nodes will shut down immediately; 0 indicates that the nodes will stop gracefully.

Return value

The number of nodes actually stopped; in the event of failure, -1 is returned.

ndb_mgm_stop3()

Description

Like ndb_mgm_stop() and ndb_mgm_stop2(), this function stops one or more data nodes. Like ndb_mgm_stop2(), it offers the ability to specify whether the nodes should shut down gracefully. In addition, it provides for a way to check to see whether disconnection is required prior to stopping a node.

Signature

```
int ndb_mgm_stop3
   (
    NdbMgmHandle handle,
    int number,
    const int* list,
    int abort,
    int* disconnect
)
```

Parameters

ndb mgm stop3() takes 5 parameters:

- An NdbMgmHandle.
- The number of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A list of the node IDs of the nodes to be stopped.
- The value of abort determines how the nodes will be shut down. 1 indicates the nodes will shut down immediately; 0 indicates that the nodes will stop gracefully.
- If disconnect returns 1 (true), this means the you must disconnect before you can apply the command to stop. For example, disconnecting is required when stopping the management server to which the handle is connected.

Return value

The number of nodes actually stopped; in the event of failure, -1 is returned.

ndb_mgm_stop4()

Description

Like the other ndb_mgm_stop*() functions, this function stops one or more data nodes. Like ndb_mgm_stop2(), it offers the ability to specify whether the nodes should shut down gracefully; like ndb_mgm_stop3() it provides for a way to check to see whether disconnection is required prior to stopping a node. In addition, it is possible to force the node to shut down even if this would cause the cluster to become nonviable.

Signature

```
int ndb_mgm_stop4
   (
     NdbMgmHandle handle,
     int number,
     const int* list,
     int abort,
     int force,
     int* disconnect
)
```

Parameters

ndb_mgm_stop4() takes 6 parameters:

- An NdbMgmHandle.
- The *number* of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.
- The value of abort determines how the nodes will be shut down. 1
 indicates the nodes will shut down immediately; 0 indicates that the
 nodes will stop gracefully.
- The value of force determines the action to be taken in the event that the shutdown of a given node would cause an incomplete cluster.
 1 causes the node—and the entire cluster—to be shut down in such cases. 0 means the node will not be shut down.

Setting *force* equal to 1 also makes it possible to stop a node even while other nodes are starting. (Bug #58451)

• If disconnect returns 1 (true), this means the you must disconnect before you can apply the command to stop. For example, disconnecting is required when stopping the management server to which the handle is connected.

The number of nodes actually stopped; in the event of failure, -1 is returned.

Return value

ndb_mgm_restart()

Description

Signature

This function can be used to restart one or more Cluster data nodes.

```
int ndb_mgm_restart
    (
         NdbMgmHandle handle,
         int number,
         const int* list
)
```

ndb_mgm_restart() takes 3 parameters:

- An NdbMgmHandle.
- The number of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.

Calling this function is equivalent to calling

```
ndb_mgm_restart2(handle, number, list, 0, 0, 0);
```

See ndb_mgm_restart2(), for more information.

Return value

The number of nodes actually restarted; -1 on failure.

ndb_mgm_restart2()

Description

Like ndb_mgm_restart(), this function can be used to restart one or more Cluster data nodes. However, ndb_mgm_restart2() provides additional restart options, including initial restart, waiting start, and immediate (forced) restart.

Signature

Parameters

ndb mgm restart2() takes 6 parameters:

- An NdbMgmHandle.
- The *number* of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.
- If *initial* is true (1), then each node undergoes an initial restart—that is, its file system is removed.
- If nostart is true, then the nodes are not actually started, but instead are left ready for a start command.
- If abort is true, then the nodes are restarted immediately, bypassing any graceful restart.

Return value

The number of nodes actually restarted; -1 on failure.

ndb_mgm_restart3()

Description

Like ndb_mgm_restart2(), this function can be used to cause an initial restart, waiting restart, and immediate (forced) restart on one or more Cluster data nodes. However, ndb_mgm_restart3() provides

the additional options of checking whether disconnection is required prior to the restart.

Signature

Parameters

ndb_mgm_restart3() takes 7 parameters:

- An NdbMgmHandle.
- The number of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.
- If initial is true (1), then each node undergoes an initial restart that is, its file system is removed.
- If nostart is true, then the nodes are not actually started, but instead are left ready for a start command.
- If abort is true, then the nodes are forced to restart immediately without performing a graceful restart.
- If disconnect returns 1 (true), this means the you must disconnect before you can apply the command to restart. For example, disconnecting is required when stopping the management server to which the handle is connected.

Return value

The number of nodes actually restarted; -1 on failure.

ndb_mgm_restart4()

Description

Like the other ndb_mgm_restart*() functions, this function restarts one or more data nodes. Like ndb_mgm_restart2(), it can be used to cause an initial restart, waiting restart, and immediate (forced) restart on one or more NDB Cluster data nodes; like ndb_mgm_stop3() it provides for a way to check to see whether disconnection is required prior to stopping a node. In addition, it is possible to force the node to restart even if this would cause a restart of the cluster.

ndb_mgm_restart4() takes 7 parameters:

- An NdbMgmHandle.
- The number of nodes to be stopped. Use 0 to stop all of the data nodes in the cluster.
- A *list* of the node IDs of the nodes to be stopped.
- If initial is true (1), then each node undergoes an initial restart—that is, its file system is removed.
- If nostart is true, then the nodes are not actually started, but instead are left ready for a start command.
- If abort is true, then the nodes are forced to restart immediately without performing a graceful restart.
- The value of force determines the action to be taken in the event that the loss of a given node due to restarting would cause an incomplete cluster.
 - 1 causes the node—and the entire cluster—to be restarted in such cases, 0 means that the node will not be restarted.

Setting *force* equal to 1 also makes it possible to restart a node even while other nodes are starting. (Bug #58451)

• If disconnect returns 1 (true), this means the you must disconnect before you can apply the command to restart. For example, disconnecting is required when stopping the management server to which the handle is connected.

Return value

The number of nodes actually restarted; -1 on failure.

3.2.7 Cluster Log Functions

This section provides information about the functions available in the MGM API for controlling the output of the cluster log.

- ndb mgm get clusterlog severity filter()
- ndb_mgm_set_clusterlog_severity_filter()
- ndb_mgm_get_clusterlog_loglevel()
- ndb_mgm_set_clusterlog_loglevel()

ndb_mgm_get_clusterlog_severity_filter()

Description

This function is used to retrieve the cluster log severity filter currently in force.

```
int ndb_mgm_get_clusterlog_severity_filter
    (
        NdbMgmHandle handle,
        struct ndb_mgm_severity* severity,
        unsigned int size
)
```

- An NdbMgmHandle.
- A vector <code>severity</code> of seven (NDB_MGM_EVENT_SEVERITY_ALL) elements, each of which is an <code>ndb_mgm_severity</code> structure, where each element contains 1 if a severity indicator is enabled and 0 if not. A severity level is stored at position <code>ndb_mgm_clusterlog_level</code>; for example the error level is stored at position <code>NDB_MGM_EVENT_SEVERITY_ERROR</code>. The first element (position <code>NDB_MGM_EVENT_SEVERITY_ON</code>) in the vector signals whether the cluster log is disabled or enabled.
- The size of the vector (NDB_MGM_EVENT_SEVERITY_ALL).

Return value

The number of returned severities, or -1 in the event of an error.

ndb_mgm_set_clusterlog_severity_filter()

Description

This function is used to set a cluster log severity filter.

Signature

Parameters

This function takes 4 parameters:

- A management server handle.
- A cluster log severity to filter.
- A flag to enable or disable the filter; 1 enables and 0 disables the filter.
- A pointer to an ndb_mgm_reply structure for a reply message.

Return value

The function returns -1 in the event of failure.

ndb_mgm_get_clusterlog_loglevel()

Description

This function is used to obtain log category and level information, and is thread-safe.

Signature

```
int ndb_mgm_get_clusterlog_loglevel
    (
        NdbMgmHandle handle,
        struct ndb_mgm_loglevel* loglevel,
        unsigned int size
)
```

Parameters

ndb_mgm_get_clusterlog_loglevel() takes the following
parameters:

- A management handle (NdbMgmHandle).
- A loglevel (log level) vector consisting of twelve elements, each of which is an ndb_mgm_loglevel structure and which represents a log level of the corresponding category.

• The size of the vector (MGM_LOGLEVELS).

Return value

This function returns the number of returned loglevels or -1 in the event of an error.

ndb_mgm_set_clusterlog_loglevel()

Description

This function is used to set the log category and levels for the cluster log.

Signature

Parameters

This function takes 5 parameters:

- An NdbMgmHandle.
- The id of the node affected.
- An event categorymdash; this is one of the values listed in The ndb_mgm_event_category Type.
- A logging *level*.
- A pointer to an ndb_mgm_reply structure for the reply message.

Return value

In the event of an error, this function returns -1.

3.2.8 Backup Functions

This section provides information about the functions provided in the MGM API for starting and stopping NDB Cluster backups.

- ndb_mgm_start_backup()
- ndb_mgm_start_backup2()
- ndb_mgm_start_backup3()
- ndb_mgm_start_backup4()
- ndb_mgm_abort_backup()

ndb_mgm_start_backup()

Description

This function is used to initiate a backup of an NDB Cluster.

Signature

Parameters

This function requires the four parameters listed here:

int ndb_mgm_start_backup

NdbMgmHandle

unsigned int

unsigned int*

int

- A management server handle (an NdbMgmHandle).
- A wait flag, with the following possible values:
 - 0: Do not wait for confirmation of the backup.
 - 1: Wait for the backup to be started.
 - 2: Wait for the backup to be completed.
- Create the backup having backup ID id. (This is also the function's return value.)

No backup id is returned if wait is set equal to 0.

specifies a value to be used for the next backup taken.

• A pointer to an ndb_mgm_reply structure to accommodate a reply.

On success, the backup ID (id). In the event of failure, the function returns -1.

This function is used to initiate a backup of an NDB Cluster. It is the same as ndb_mgm_start_backup(), except that it additionally

handle,

nextBackupId

wait,

Return value

ndb_mgm_start_backup2()

Description

Signature

Parameters

This function requires the five parameters listed here:

- A management server handle (an NdbMgmHandle).
- A wait flag, with the following possible values:
 - 0: Do not wait for confirmation of the backup.
 - 1: Wait for the backup to be started.

struct ndb_mgm_reply* reply,

- 2: Wait for the backup to be completed.
- Create the backup having backup ID id. (This is also the function's return value.)

No backup id is returned if wait is set equal to 0.

- A pointer to an ndb_mgm_reply structure to accommodate a reply.
- The ID of the next backup taken is set to the value of nextBackupID

On success, the backup ID passed as id. Otherwise, the function returns -1.

Return value

ndb_mgm_start_backup3()

Description

This function is used to initiate a backup of an NDB Cluster. It is the same as ndb_mgm_start_backup2(), but adds an argument for specifying whether the state of the backup matches that of the cluster when the backup is started, or when it is completed.

Signature

Parameters

This function requires the six parameters listed here:

- A management server handle (an NdbMgmHandle).
- A wait flag, with the following possible values:
 - 0: Do not wait for confirmation of the backup.
 - 1: Wait for the backup to be started.
 - 2: Wait for the backup to be completed.
- Create the backup having backup ID id. (This is also the function's return value.)

No backup *id* is returned if *wait* is set equal to 0.

- A pointer to an ndb_mgm_reply structure to accommodate a reply.
- The ID of the next backup taken is set to the value of nextBackupID
 + 1.
- backupPoint is 1 if the state of the backup should reflect that of the cluster the time when the backup is started, or 0 if its state should reflect that of the cluster when the backup is complete. Using 1 is equivalent to invoking the ndb_mgm client START BACKUP command with SNAPSHOTSTART; 0 is equivalent to invoking the command with SNAPSHOTEND.

Return value

On success, the backup ID passed as *id*. Otherwise, the function returns -1.

ndb_mgm_start_backup4()

Description

This function is used to initiate a backup of an NDB Cluster. It is the same as ndb_mgm_start_backup3(), except that it produces an encrypted backup using the password provided of the length specified.

This function was added in NDB 8.0.22.

```
int ndb_mgm_start_backup (
```

```
NdbMgmHandle handle,
int wait,
unsigned int* id,
struct ndb_mgm_reply* reply,
unsigned int nextBackupId,
unsigned int backupPoint,
const char* password,
unsigned int password_length
)
```

This function requires the eight parameters listed here:

- A management server handle (an NdbMgmHandle).
- A wait flag, with the following possible values:
 - 0: Do not wait for confirmation of the backup.
 - 1: Wait for the backup to be started.
 - 2: Wait for the backup to be completed.
- Create the backup having backup ID id. (This is also the function's return value.)

No backup *id* is returned if *wait* is set equal to 0.

- A pointer to an ndb_mgm_reply structure to accommodate a reply.
- The ID of the next backup taken is set to the value of nextBackupID
 + 1.
- backupPoint is 1 if the state of the backup should reflect that of the cluster the time when the backup is started, or 0 if its state should reflect that of the cluster when the backup is complete. Using 1 is equivalent to invoking the ndb_mgm client START BACKUP command with SNAPSHOTSTART; 0 is equivalent to invoking the command with SNAPSHOTEND.
- A password used to protect the encrypted backup. This is a string of up to 256 characters in length; any printable ASCII characters can be used in the password string with the exception of !, ', ", \$, \$, \, and
- The length of the password.

It is possible to specify an empty password, but this is not recommended.

On success, the backup ID passed as id. Otherwise, the function returns -1.

Return value

ndb_mgm_abort_backup()

Description

Signature

This function is used to stop an NDB Cluster backup.

This function takes 3 parameters:

- An NdbMgmHandle.
- The *id* of the backup to be aborted.
- A pointer to an ndb_mgm_reply structure.

Return value

In case of an error, this function returns -1.

3.2.9 Single-User Mode Functions

The MGM API makes it possible for the programmer to put the cluster into single-user mode—and to return it to normal mode again—from within an application. This section covers the functions that are used for these operations.

- ndb_mgm_enter_single_user()
- ndb_mgm_exit_single_user()

ndb_mgm_enter_single_user()

Description

This function is used to enter single-user mode on a given node.

Signature

Parameters

This function takes 3 parameters:

- An NdbMgmHandle.
- The *id* of the node to be used in single-user mode.
- A pointer to an ndb_mgm_reply structure, used for a reply message.

Return value

Returns -1 in the event of failure.

ndb_mgm_exit_single_user()

Description

This function is used to exit single-user mode and to return to normal operation.

Signature

Parameters

This function requires 2 arguments:

- An NdbMgmHandle.
- A pointer to an ndb_mgm_reply.

Return value

Returns -1 in case of an error.

3.3 MGM API Data Types

This section provides information about the data types defined by the MGM API.

The types described in this section are all defined in the file /storage/ndb/include/mgmapi/mgmapi.h, with the exception of Ndb_logevent_type, ndb_mgm_event_severity, ndb_mgm_logevent_handle_error, and ndb_mgm_event_category, which are defined in /storage/ndb/include/mgmapi/ndb_logevent.h.

- The ndb_mgm_node_type Type
- The ndb_mgm_node_status Type
- The ndb_mgm_error Type
- The Ndb_logevent_type Type
- The ndb_mgm_event_severity Type
- The ndb_logevent_handle_error Type
- The ndb_mgm_event_category Type

The ndb_mgm_node_type Type

Description

This is used to classify the different types of nodes in an NDB Cluster.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 3.1 Type ndb mgm node type values and descriptions.

Value	Description
NDB_MGM_NODE_TYPE_UNK	ndnkmown
NDB_MGM_NODE_TYPE_API	API Node (SQL node)
NDB_MGM_NODE_TYPE_NDB	Data node
NDB_MGM_NODE_TYPE_MGM	Management node

The ndb_mgm_node_status Type

Description

This type describes a Cluster node's status.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 3.2 Type ndb_mgm_node_status values and descriptions.

Value	Description
NDB_MGM_NODE_STATUS_UNKNOW	The node's status is not known
NDB_MGM_NODE_STATUS_NO_CON	The node cannot be contacted
NDB_MGM_NODE_STATUS_NOT_STA	The node has not yet executed the startup protocol

Value	Description
NDB_MGM_NODE_STATUS_STARTI	The node is executing the startup protocol
NDB_MGM_NODE_STATUS_STARTE	The node is running
NDB_MGM_NODE_STATUS_SHUTTI	งไร <u>่ก</u> อาจังd e is shutting down
NDB_MGM_NODE_STATUS_RESTAR	The node is restarting
NDB_MGM_NODE_STATUS_SINGLE	The node is running in single-user (maintenance) mode
NDB_MGM_NODE_STATUS_RESUME	The node is in resume mode
NDB_MGM_NODE_STATUS_CONNEC	The node is connected

The ndb_mgm_error Type

Description

The values for this type are the error codes that may be generated by MGM API functions. These may be found in Section 3.5, "MGM API Errors".

See also ndb_mgm_get_latest_error(), for more information.

The Ndb_logevent_type Type

Description

These are the types of log events available in the MGM API, grouped by event category. (See The ndb_mgm_event_category Type.)

Most of these log event types have one or more corresponding log event messages; these are listed in NDB Cluster Log Messages.

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 3.3 Type Ndb_logevent_type values, descriptions, and event categories

Туре	Description	Category	
NDB_LE_Connected	The node has connected	NDB_MGM_EVENT_CATEGOR	RY_C
NDB_LE_Disconnecte	The node was disconnected	NDB_MGM_EVENT_CATEGOR	RY_C
NDB_LE_Communicati	Communication with the node has been closed	NDB_MGM_EVENT_CATEGOR	RY_C
NDB_LE_Communicati	Communication with the node has been started	NDB_MGM_EVENT_CATEGOR	RY_C
NDB_LE_ConnectedAp	The APowersion used by an API node; in the case of a MySQL server (SQL node), this is the same	NDB_MGM_EVENT_CATEGOR	RY_C

Туре	Description	Category	
	as displayed by SELECT VERSION()		
NDB_LE_GlobalCheck	A globat sheckpoint has been started	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_GlobalCheck	A global chēckpoint has been completed	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_LocalCheckpo	Tine node has begun a local checkpoint	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_LocalCheckpd	oTine rode has ed completed a local checkpoint	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_LCPStoppedI	was aborted, but the last global checkpoint was preserved	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_LCPFragment	Gopying of a table fragment was completed	NDB_MGM_EVENT_CATE	GORY_CHECI
NDB_LE_NDBStartSta	The node has begun to start	NDB_MGM_EVENT_CATE(GORY_STAR!
NDB_LE_NDBStartComp	The node has completed the startup process	NDB_MGM_EVENT_CATE	GORY_STAR!
NDB_LE_STTORRYReci	an STTORRY signal, indicating that the reading of configuration data is underway; see Configuration Read Phase (STTOR Phase -1), and STTOR Phase 0, for more information	NDB_MGM_EVENT_CATE(GORY_STAR
NDB_LE_StartPhaseCo	Annode start phase has been completed	NDB_MGM_EVENT_CATE	GORY_STAR
NDB_LE_CM_REGCONF	The node has received a CM_REGCONF signal; see STTOR Phase 1, for more information	NDB_MGM_EVENT_CATE	GORY_STAR'
NDB_LE_CM_REGREF	The node has received a CM_REGREF	NDB_MGM_EVENT_CATE	GORY_STAR

Туре	Description	Category	
	signal; see STTOR Phase 1, for more information		
NDB_LE_FIND_NEIGHB	oThesnode has discovered its neighboring nodes in the cluster	NDB_MGM_EVENT_CATE	GORY_S'
NDB_LE_NDBStopStar	Effice node is beginning to shut down	NDB_MGM_EVENT_CATE	GORY_S'
NDB_LE_NDBStopComp	Node shutdown completed	NDB_MGM_EVENT_CATE	GORY_S
NDB_LE_NDBStopForc	eThe node is being forced to shut down (usually indicates a severe problem in the cluster)	NDB_MGM_EVENT_CATE(GORY_S
NDB_LE_NDBStopAbor	The started to shut down, but was forced to continue running; this happens, for example, when a STOP command was issued in the management client for a node such that the cluster would no longer be able to keep all data available if the node were shut down	NDB_MGM_EVENT_CATE	GORY_S'
NDB_LE_StartREDOLo	Redo logging has been started	NDB_MGM_EVENT_CATE(GORY_S
NDB_LE_StartLog	Logging has started	NDB_MGM_EVENT_CATE(GORY_S
NDB_LE_UNDORecords	The node has read and executed all records from the redo log	NDB_MGM_EVENT_CATE	GORY_S
NDB_LE_StartReport	The node is issuing a start report	NDB_MGM_EVENT_CATE	GORY_S'
NDB_LE_NR_CopyDict	The node is copying the data dictionary	NDB_MGM_EVENT_CATE	GORY_NO
NDB_LE_NR_CopyDist	The node is copying data distribution information	NDB_MGM_EVENT_CATE	GORY_N

Туре	Description	Category	
NDB_LE_NR_CopyFrag	sThe node is copying table fragments	NDB_MGM_EVENT_CATEGOR	RY_NODE
NDB_LE_NR_CopyFrag	The node has completed copying a table fragment	NDB_MGM_EVENT_CATEGOI	RY_NODE
NDB_LE_NR_CopyFrag	The pode has completed copying all necessary table fragments	NDB_MGM_EVENT_CATEGO	RY_NODE
NDB_LE_NodeFailCom	Alle(remaining) nodes has been notified of the failure of a data node	NDB_MGM_EVENT_CATEGOR	RY_NODE
NDB_LE_NODE_FAILRE	A data node has failed	NDB_MGM_EVENT_CATEGOR	RY_NODE
NDB_LE_ArbitState	This event is used to report on the current state of arbitration in the cluster	NDB_MGM_EVENT_CATEGOR	RY_NODE_
NDB_LE_ArbitResult	This event is used to report on the outcome of node arbitration	NDB_MGM_EVENT_CATEGOI	RY_NODE
NDB_LE_GCP_Takeove	The node is attempting to become the master node (to assume responsibility for GCPs)	NDB_MGM_EVENT_CATEGO	RY_NODE
NDB_LE_GCP_Takeove	The pode has become the master (and assumed responsibility for GCPs)	NDB_MGM_EVENT_CATEGOR	RY_NODE
NDB_LE_LCP_Takeove	The node is attempting to become the master node (to assume responsibility for LCPs)	NDB_MGM_EVENT_CATEGOI	RY_NODE_
NDB_LE_LCP_Takeove	The pode has become the master (and assumed responsibility for LCPs)	NDB_MGM_EVENT_CATEGO	RY_NODE_
NDB_LE_TransReport	This indicates a report of transaction	NDB_MGM_EVENT_CATEGOR	RY_STAT:

Туре	Description	Category	I
	activity, which is given approximately once every 10 seconds		
NDB_LE_OperationRe	on the number of operations performed by this node (also provided approximately once every 10 seconds)	NDB_MGM_EVENT_CATE	GORY_S
NDB_LE_TableCreated	A new table has been created	NDB_MGM_EVENT_CATE	GORY_S'
NDB_LE_UndoLogBloc	dendo logging is blocked because the log buffer is close to overflowing	NDB_MGM_EVENT_CATE	GORY_S
NDB_LE_JobStatistic	c	NDB_MGM_EVENT_CATE	GORY_S
NDB_LE_SendBytesSta	Indicates a report of the average number of bytes transmitted per send operation by this node	NDB_MGM_EVENT_CATE	€ORY_S
NDB_LE_ReceiveByte:	sadicates: a report of the average number of bytes received per send operation to this node	NDB_MGM_EVENT_CATE	FORY_S
NDB_LE_MemoryUsage	A DUMP 1000 command has been issued to this node, and it is reporting its memory usage in turn	NDB_MGM_EVENT_CATE(GORY_S
NDB_LE_Transporter	A transporter error has occurred; see NDB Transporter Errors, for transporter error codes and messages	NDB_MGM_EVENT_CATE	GORY_EI
NDB_LE_Transporter	A potential problem is occurring in the transporter; see NDB Transporter Errors, for transporter error codes and messages	NDB_MGM_EVENT_CATE	GORY_E

Туре	Description	Category	
NDB_LE_MissedHeart	Hedicates a data node has missed a hreatbeat expected from another data node	NDB_MGM_EVENT_CATE(ORY_ERRO
NDB_LE_DeadDueToHe	A data node has missed at least 3 heartbeats in succession from another data node, and is reporting that it can no longer communicate with that data node	NDB_MGM_EVENT_CATE	ORY_ERRO
NDB_LE_WarningEver	Indicates a warning message	NDB_MGM_EVENT_CATE	ORY_ERRO
NDB_LE_SentHeartbe	A node heartbeat has been sent	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_CreateLogBy	rtes	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_InfoEvent	Indicates an informational message	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_SingleUser	The cluster has entered or exited single user mode	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_EventBuffer	sThis type of event indicates potentially excessive usage of the event buffer	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_EventBuffer	Provides improved reporting of event buffer status; added in NDB 7.5.1	NDB_MGM_EVENT_CATE	ORY_INFO
NDB_LE_BackupStart	A backup has been started	NDB_MGM_EVENT_CATE(GORY_BACK
NDB_LE_BackupFaile	dA backup has failed to start	NDB_MGM_EVENT_CATE(GORY_BACK
NDB_LE_BackupCompl	A backup has been completed successfully	NDB_MGM_EVENT_CATE	GORY_BACK
NDB_LE_BackupAbort	A backup in progress was terminated by the user	NDB_MGM_EVENT_CATE	ORY_BACK

The ndb_mgm_event_severity Type

Description These are the log event severities used to filter the cluster log by

 $\verb|ndb_mgm_set_clusterlog_severity_filter()|, \verb|and to filter||$

listening to events by ndb_mgm_listen_event().

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 3.4 Type ndb_mgm_event_severity values and descriptions

Value	Description
NDB_MGM_ILLEGAL_EVENT_SEVE	Invalid event severity specified
NDB_MGM_EVENT_SEVERITY_ON	Cluster logging is enabled
NDB_MGM_EVENT_SEVERITY_DEB	dsed for NDB Cluster development only
NDB_MGM_EVENT_SEVERITY_INF	Informational messages
NDB_MGM_EVENT_SEVERITY_WAR	Conditions that are not errors as such, but that might require special handling
NDB_MGM_EVENT_SEVERITY_ERR	Nonfatal error conditions that should be corrected
NDB_MGM_EVENT_SEVERITY_CRI	Critical conditions such as device errors or out of memory errors
NDB_MGM_EVENT_SEVERITY_ALE	Conditions that require immediate attention, such as corruption of the cluster
NDB_MGM_EVENT_SEVERITY_ALL	All severity levels

See ndb_mgm_set_clusterlog_severity_filter(), and ndb_mgm_listen_event(), for information on how this type is used by those functions.

The ndb_logevent_handle_error Type

Description This type is used to describe log event errors.

Enumeration values Possible values are shown, along with descriptions, in the following

table:

Table 3.5 Type ndb_logevent_handle_error values and descriptions

Value	Description
NDB_LEH_NO_ERROR	No error
NDB_LEH_READ_ERROR	Read error
NDB_LEH_MISSING_EVENT_SPEC	Invalid, incomplete, or missing log event specification
NDB_LEH_UNKNOWN_EVENT_TYPE	Unknown log event type
NDB_LEH_UNKNOWN_EVENT_VARIA	⊎nknown log event variable
NDB_LEH_INTERNAL_ERROR	Internal error

Value	Description
NDB_LEH_CONNECTION_ERROR	Connection error, or lost connection with management server

NDB_LEH_CONNECTION_ERROR was added in NDB 7.4.13 and NDB 7.5.4. (BUG #19474782)

The ndb_mgm_event_category Type

Description These are the log event categories referenced in The

Ndb_logevent_type Type. They are also used by the MGM API functions ndb_mgm_set_clusterlog_loglevel() and

ndb_mgm_listen_event().

Enumeration values

Possible values are shown, along with descriptions, in the following table:

Table 3.6 Type ndb_mgm_event_category values and descriptions

Value	Description
NDB_MGM_ILLEGAL_EVENT_CATEGOR	nvalid log event category
NDB_MGM_EVENT_CATEGORY_STARTU	Log events occurring during startup
NDB_MGM_EVENT_CATEGORY_SHUTDC	uog events occurring during shutdown
NDB_MGM_EVENT_CATEGORY_STATIS	Statistics log events
NDB_MGM_EVENT_CATEGORY_CHECKF	d_og events related to checkpoints
NDB_MGM_EVENT_CATEGORY_NODE_R	±sgzevents occurring during node restart
NDB_MGM_EVENT_CATEGORY_CONNEC	Logrevents relating to connections between cluster nodes
NDB_MGM_EVENT_CATEGORY_BACKUP	Log events relating to backups
NDB_MGM_EVENT_CATEGORY_CONGES	Log revents relating to congestion
NDB_MGM_EVENT_CATEGORY_INFO	Uncategorised log events (severity level INFO)
NDB_MGM_EVENT_CATEGORY_ERROR	Uncategorised log events (severity level WARNING, ERROR, CRITICAL, or ALERT)

See ndb_mgm_set_clusterlog_loglevel(), and ndb_mgm_listen_event(), for more information.

3.4 MGM API Data Structures

This section provides information about the data structures defined by the MGM API.

- The ndb_logevent Structure
- The ndb_mgm_node_state Structure

- The ndb_mgm_cluster_state Structure
- The ndb_mgm_reply Structure

The ndb_logevent Structure

Description

This structure models a Cluster log event, and is used for storing and retrieving log event information.

Definition. ndb_logevent has 8 members, the first 7 of which are shown in the following list:

- void* handle: An NdbLogEventHandle, set by ndb_logevent_get_next(). This handle is used only for purposes of comparison.
- type: Tells which type of event (Ndb_logevent_type) this is.
- unsigned time: The time at which the log event was registered with the management server.
- category: The log event category (ndb_mgm_event_category).
- severity: The log event severity (ndb_mgm_event_severity).
- unsigned level: The log event level. This is a value in the range of 0 to 15, inclusive.
- unsigned source_nodeid: The node ID of the node that reported this event.

The 8^{th} member of this structure contains data specific to the log event, and is dependent on its type. It is defined as the union of a number of data structures, each corresponding to a log event type. Which structure to use is determined by the value of type, and is shown in the following table:

Table 3.7 Type Ndb_logevent_type values and structures used

Ndb_logevent_type Value	Structure
NDB_LE_Connected	Connected:
	unsigned node
NDB_LE_Disconnected	Disconnected:
	unsigned node
NDB_LE_CommunicationClosed	CommunicationClosed:
	unsigned node
NDB_LE_CommunicationOpened	CommunicationOpened:
	unsigned node
NDB_LE_ConnectedApiVersion	ConnectedApiVersion:
	unsigned node unsigned version
NDB_LE_GlobalCheckpointStarted	GlobalCheckpointStarted:
	unsigned gci
NDB_LE_GlobalCheckpointCompleted	GlobalCheckpointCompleted:
	unsigned gci
NDB_LE_LocalCheckpointStarted	LocalCheckpointStarted:
	unsigned <i>lci</i> unsigned <i>keep_gci</i>

Ndb_logevent_type Value	Structure
	unsigned restore_gci
NDB_LE_LocalCheckpointCompleted	LocalCheckpointCompleted:
	unsigned lci
NDB_LE_LCPStoppedInCalcKeepGci	LCPStoppedInCalcKeepGci:
	unsigned data
NDB_LE_LCPFragmentCompleted	LCPFragmentCompleted:
	<pre>unsigned node unsigned table_id unsigned fragment_id</pre>
NDB_LE_UndoLogBlocked	UndoLogBlocked:
	unsigned acc_count unsigned tup_count
NDB_LE_NDBStartStarted	NDBStartStarted:
	unsigned version
NDB_LE_NDBStartCompleted	NDBStartCompleted:
	unsigned version
NDB_LE_STTORRYRecieved	STTORRYRecieved:
	[NONE]
NDB_LE_StartPhaseCompleted	StartPhaseCompleted:
	unsigned phase unsigned starttype
NDB_LE_CM_REGCONF	CM_REGCONF:
	unsigned own_id
	unsigned president_id unsigned dynamic_id
NDB_LE_CM_REGREF	CM_REGREF:
	unsigned own_id
	unsigned other_id unsigned cause
NDB_LE_FIND_NEIGHBOURS	FIND_NEIGHBOURS:
	unsigned own_id
	unsigned left_id
	unsigned right_id unsigned dynamic_id
NDB_LE_NDBStopStarted	NDBStopStarted:
	unsigned stoptype
NDB_LE_NDBStopCompleted	NDBStopCompleted:
	unsigned action unsigned signum
NDB_LE_NDBStopForced	NDBStopForced:
	unsigned action

Ndb_logevent_type Value	Structure
	unsigned signum unsigned error
	unsigned sphase
	unsigned extra
NDB_LE_NDBStopAborted	NDBStopAborted:
	[NONE]
NDB_LE_StartREDOLog	StartREDOLog:
	unsigned node
	unsigned keep_gci unsigned completed_gci
	unsigned restorable_gci
NDB_LE_StartLog	StartLog:
	unsigned log_part
	unsigned start_mb unsigned stop_mb
	unsigned gci
NDB_LE_UNDORecordsExecuted	UNDORecordsExecuted:
	unsigned block
	unsigned data1
	unsigned data2 unsigned data3
	unsigned data4
	unsigned data5 unsigned data6
	unsigned data7
	unsigned data8 unsigned data9
	unsigned data10
NDB_LE_NR_CopyDict	NR_CopyDict:
	[NONE]
NDB_LE_NR_CopyDistr	NR_CopyDistr:
	[NONE]
NDB_LE_NR_CopyFragsStarted	NR_CopyFragsStarted:
	unsigned dest_node
NDB_LE_NR_CopyFragDone	NR_CopyFragDone:
	unsigned dest_node
	unsigned table_id unsigned fragment_id
NDB_LE_NR_CopyFragsCompleted	NR_CopyFragsCompleted:
	unsigned dest_node
NDB_LE_NodeFailCompleted	NodeFailCompleted:
	unsigned block
	unsigned failed_node unsigned completing_node
	(For block and completing_node, 0 is interpreted as "all".)

Ndb_logevent_type Value	Structure
NDB_LE_NODE_FAILREP	NODE_FAILREP:
	unsigned failed_node unsigned failure_state
NDB_LE_ArbitState	ArbitState:
	<pre>unsigned code unsigned arbit_node unsigned ticket_0 unsigned ticket_1</pre>
NDB_LE_ArbitResult	ArbitResult:
	<pre>unsigned code unsigned arbit_node unsigned ticket_0 unsigned ticket_1</pre>
NDB_LE_GCP_TakeoverStarted	GCP_TakeoverStarted:
	[NONE]
NDB_LE_GCP_TakeoverCompleted	GCP_TakeoverCompleted:
	[NONE]
NDB_LE_LCP_TakeoverStarted	LCP_TakeoverStarted:
	[NONE]
NDB_LE_TransReportCounters	TransReportCounters:
	unsigned trans_count unsigned commit_count unsigned read_count unsigned simple_read_count unsigned write_count unsigned attrinfo_count unsigned conc_op_count unsigned abort_count unsigned scan_count unsigned range_scan_count
NDB_LE_OperationReportCounters	OperationReportCounters:
	unsigned ops
NDB_LE_TableCreated	TableCreated:
	unsigned table_id
NDB_LE_JobStatistic	JobStatistic:
	unsigned mean_loop_count
NDB_LE_SendBytesStatistic	SendBytesStatistic:
	unsigned to_node unsigned mean_sent_bytes
NDB_LE_ReceiveBytesStatistic	ReceiveBytesStatistic:
	unsigned from_node unsigned mean_received_bytes
NDB_LE_MemoryUsage	MemoryUsage:

Ndb_logevent_type Value	Structure
	int gth unsigned page_size_kb unsigned pages_used unsigned pages_total unsigned block
NDB_LE_TransporterError	TransporterError: unsigned to_node
	unsigned code
NDB_LE_TransporterWarning	TransporterWarning: unsigned to_node
	unsigned code
NDB_LE_MissedHeartbeat	MissedHeartbeat:
	unsigned node unsigned count
NDB_LE_DeadDueToHeartbeat	DeadDueToHeartbeat:
	unsigned node
NDB_LE_WarningEvent	WarningEvent:
	[NOT YET IMPLEMENTED]
NDB_LE_SentHeartbeat	SentHeartbeat:
	unsigned node
NDB_LE_CreateLogBytes	CreateLogBytes:
	unsigned <i>node</i>
NDB_LE_InfoEvent	InfoEvent:
	[NOT YET IMPLEMENTED]
NDB_LE_EventBufferStatus (NDB 7.5.0 and earlier)	EventBufferStatus::
	unsigned usage unsigned alloc unsigned max unsigned apply_gci_1 unsigned apply_gci_h unsigned latest_gci_l unsigned latest_gci_h
NDB_LE_EventBufferStatus2 (NDB 7.5.1 and later)	EventBufferStatus2:
	unsigned usage unsigned alloc unsigned max unsigned latest_consumed_epoch_l unsigned latest_buffered_epoch_l unsigned latest_buffered_epoch_l unsigned latest_buffered_epoch_h unsigned ndb_reference unsigned report_reason report_reason is one of NO_REPORT, COMPLETELY_BUFFERING, PARTIALLY_DISCARDING, COMPLETELY_DISCARDING,

Ndb_logevent_type Value	Structure
	PARTIALLY_BUFFERING, BUFFERED_EPOCHS_OVER_THRESHOLD, ENOUGH_FREE_EVENTBUFFER, or LOW_FREE_EVENTBUFFER; see Event Buffer Reporting in the Cluster Log, for descriptions of these values
NDB_LE_BackupStarted	BackupStarted: unsigned starting_node unsigned backup_id
NDB_LE_BackupFailedToStart	BackupFailedToStart: unsigned starting_node unsigned error
NDB_LE_BackupCompleted	BackupCompleted: unsigned starting_node unsigned backup_id unsigned start_gci unsigned stop_gci unsigned n_records unsigned n_log_records unsigned n_bytes unsigned n_log_bytes
NDB_LE_BackupAborted	BackupAborted: unsigned starting_node unsigned backup_id unsigned error
NDB_LE_SingleUser	SingleUser: unsigned type unsigned node_id
NDB_LE_StartReport	StartReport: unsigned report_type unsigned remaining_time unsigned bitmask_size unsigned bitmask_data[1]

The ndb_mgm_node_state Structure

Description

Provides information on the status of a Cluster node.

Definition. This structure contains the following members:

- int node_id: The cluster node's node ID.
- enum ndb_mgm_node_type node_type: The node type.

See The ndb_mgm_node_type Type, for permitted values.

• enum ndb_mgm_node_status node_status: The node's status.

See The ndb_mgm_node_status Type, for permitted values.

• int start_phase: The start phase.

This is valid only if the node_type is NDB_MGM_NODE_TYPE_NDB and the node_status is NDB MGM NODE STATUS STARTING.

• int dynamic_id: The ID for heartbeats and master takeover.

Valid only for data (ndbd) nodes.

• int node_group: The node group to which the node belongs.

Valid only for data (ndbd) nodes.

- int version: Internal version number.
- int connect_count: The number of times this node has connected to or disconnected from the management server.
- char connect_address[]: The IP address of this node as seen by the other nodes in the cluster.
- int *mysql_version*: The MySQL version number, expressed as an integer (for example: 80025). Applies only to SQL nodes.
- int is_single_user: The node ID of the API or SQL node having exclusive access when the cluster is in single user mode. Does not otherwise apply. Added in NDB 8.0.17.

The ndb_mgm_cluster_state Structure

Description

Provides information on the status of all Cluster nodes. This structure is returned by $ndb_mgm_get_status()$.

Definition. This structure has the following two members:

- int no_of_nodes: The number of elements in the node_states array.
- struct ndb_mgm_node_state node_states[]: An array containing the states of the nodes.

Each element of this array is an ndb_mgm_node_state structure.

See ndb_mgm_get_status().

The ndb_mgm_reply Structure

Description

Contains response information, consisting of a response code and a corresponding message, from the management server.

Definition. This structure contains two members, as shown here:

• int return_code: For a successful operation, this value is 0; otherwise, it contains an error code.

For error codes, see The ndb_mgm_error Type.

• char message[256]: contains the text of the response or error message.

See ndb_mgm_get_latest_error(), and ndb_mgm_get_latest_error_msg().

3.5 MGM API Errors

This section provides information about each of the six types MGM errors, with the listings that follow ordered by type.

- Request Errors
- Node ID Allocation Errors
- Service Errors
- Backup Errors
- Single User Mode Errors
- General Usage Errors

Request Errors

These are errors generated by failures to connect to a management server.

Table 3.8 Request errors generated by management server connection failures.

Value	Description
NDB_MGM_ILLEGAL_CONNECT_STRING	Invalid connection string
NDB_MGM_ILLEGAL_SERVER_HANDLE	Invalid management server handle
NDB_MGM_ILLEGAL_SERVER_REPLY	Invalid response from management server
NDB_MGM_ILLEGAL_NUMBER_OF_NODES	Invalid number of nodes
NDB_MGM_ILLEGAL_NODE_STATUS	Invalid node status
NDB_MGM_OUT_OF_MEMORY	Memory allocation error
NDB_MGM_SERVER_NOT_CONNECTED	Management server not connected
NDB_MGM_COULD_NOT_CONNECT_TO_SOCKET	Not able to connect to socket

Node ID Allocation Errors

These errors result from a failure to assign a node ID to a cluster node.

Table 3.9 Node ID allocation errors resulting from failure to assign a node ID

Value	Description
	Generic error; may be possible to retry and recover
NDB_MGM_ALLOCID_CONFIG_MISMATCH	Non-recoverable generic error

Service Errors

These errors result from the failure of a node or cluster to start, shut down, or restart.

Table 3.10 Service errors resulting from failure of a node or cluster to start, shut down, or restart

Value	Description
NDB_MGM_START_FAILED	Startup failure
NDB_MGM_STOP_FAILED	Shutdown failure
NDB_MGM_RESTART_FAILED	Restart failure

Backup Errors

These are errors which result from problems with initiating or aborting backups.

Table 3.11 Backup errors resulting from problems initiating or aborting backups.

Value	Description
NDB_MGM_COULD_NOT_START_BACKUP	Unable to initiate backup
NDB_MGM_COULD_NOT_ABORT_BACKUP	Unable to abort backup

Single User Mode Errors

These errors result from failures to enter or exit single user mode.

Table 3.12 Single user mode errors resulting from failure to enter or exit single user mode.

Value	Description
NDB_MGM_COULD_NOT_ENTER_SINGLE_USER_MOD	Unable to enter single-user mode
NDB_MGM_COULD_NOT_EXIT_SINGLE_USER_MODE	Unable to exit single-user mode

General Usage Errors

This is a general error type for errors which are otherwise not classifiable. There is one general usage error

Table 3.13 General usage errors, otherwise not classified.

Value	Description
NDB_MGM_USAGE_ERROR	General usage error

3.6 MGM API Examples

This section provides MGM API coding examples.

3.6.1 Basic MGM API Event Logging Example

This example shows the basics of handling event logging using the MGM API.

The source code for this program may be found in the NDB Cluster source tree, in the file storage/ndb/ndbapi-examples/mgmapi_logevent/main.cpp.

```
exit(-1); \
#define make_uint64(a,b) (((Uint64)(a)) + (((Uint64)(b)) << 32))</pre>
int main(int argc, char** argv)
 NdbMomHandle h;
 NdbLogEventHandle le;
  int filter[] = { 15, NDB_MGM_EVENT_CATEGORY_BACKUP,
     15, NDB_MGM_EVENT_CATEGORY_CONNECTION,
     15, NDB_MGM_EVENT_CATEGORY_NODE_RESTART,
     15, NDB_MGM_EVENT_CATEGORY_STARTUP,
     15, NDB_MGM_EVENT_CATEGORY_ERROR,
     0 };
  struct ndb_logevent event;
  if (argc < 2)
    printf("Arguments are <connect_string cluster> [<iterations>].\n");
    exit(-1);
 const char *connectstring = argv[1];
  int iterations = -1;
  if (argc > 2)
   iterations = atoi(argv[2]);
 ndb_init();
 h= ndb_mgm_create_handle();
 if (h == 0)
   printf("Unable to create handle\n");
    exit(-1);
  if (ndb_mgm_set_connectstring(h, connectstring) == -1)
   printf("Unable to set connection string\n");
    exit(-1);
  if (ndb_mgm_connect(h,0,0,0)) MGMERROR(h);
  le= ndb_mgm_create_logevent_handle(h, filter);
  if ( le == 0 ) MGMERROR(h);
  while (iterations -- != 0)
   int timeout= 1000;
    int r= ndb_logevent_get_next(le,&event,timeout);
   if (r == 0)
     printf("No event within %d milliseconds\n", timeout);
    else if (r < 0)
     LOGEVENTERROR(le)
      switch (event.type) {
      case NDB_LE_BackupStarted:
printf("Node %d: BackupStarted\n", event.source_nodeid);
\label{local_printf}  \mbox{printf("Starting node ID: $d\n", event.BackupStarted.starting_node);} 
printf(" Backup ID: %d\n", event.BackupStarted.backup_id);
break;
      case NDB_LE_BackupStatus:
printf("Node %d: BackupStatus\n", event.source_nodeid);
printf("Starting node ID: $d\n", event.BackupStarted.starting\_node);
printf(" Backup ID: %d\n", event.BackupStarted.backup_id);
printf(" Data written: %llu bytes (%llu records)\n",
               make_uint64(event.BackupStatus.n_bytes_lo,
                           event.BackupStatus.n_bytes_hi),
```

```
make_uint64(event.BackupStatus.n_records_lo,
                          event.BackupStatus.n_records_hi));
printf(" Log written: %llu bytes (%llu records)\n",
              make_uint64(event.BackupStatus.n_log_bytes_lo,
                          event.BackupStatus.n_log_bytes_hi),
              make_uint64(event.BackupStatus.n_log_records_lo,
                          event.BackupStatus.n_log_records_hi));
break;
     case NDB_LE_BackupCompleted:
printf("Node %d: BackupCompleted\n", event.source_nodeid);
printf(" Backup ID: %d\n", event.BackupStarted.backup_id);
printf(" Data written: %llu bytes (%llu records)\n",
              make_uint64(event.BackupCompleted.n_bytes,
                          event.BackupCompleted.n bytes hi),
              make_uint64(event.BackupCompleted.n_records,
                          event.BackupCompleted.n_records_hi));
printf(" Log written: %llu bytes (%llu records)\n",
              make_uint64(event.BackupCompleted.n_log_bytes,
                          event.BackupCompleted.n_log_bytes_hi),
              make_uint64(event.BackupCompleted.n_log_records,
                          event.BackupCompleted.n_log_records_hi));
break;
     case NDB_LE_BackupAborted:
printf("Node %d: BackupAborted\n", event.source_nodeid);
     case NDB_LE_BackupFailedToStart:
printf("Node %d: BackupFailedToStart\n", event.source_nodeid);
break;
     case NDB LE NodeFailCompleted:
printf("Node %d: NodeFailCompleted\n", event.source_nodeid);
break;
     case NDB LE ArbitResult:
printf("Node %d: ArbitResult\n", event.source_nodeid);
printf(" code %d, arbit_node %d\n",
      event.ArbitResult.code & 0xffff,
       event.ArbitResult.arbit_node);
break;
     case NDB_LE_DeadDueToHeartbeat:
printf("Node %d: DeadDueToHeartbeat\n", event.source_nodeid);
printf(" node %d\n", event.DeadDueToHeartbeat.node);
break;
     case NDB_LE_Connected:
printf("Node %d: Connected\n", event.source_nodeid);
printf(" node %d\n", event.Connected.node);
     case NDB_LE_Disconnected:
printf("Node %d: Disconnected\n", event.source_nodeid);
printf(" node %d\n", event.Disconnected.node);
break;
     case NDB_LE_NDBStartCompleted:
printf("Node %d: StartCompleted\n", event.source_nodeid);
printf(" version %d.%d.%d\n",
       event.NDBStartCompleted.version >> 16 & 0xff,
       event.NDBStartCompleted.version >> 8 & 0xff,
       event.NDBStartCompleted.version >> 0 & 0xff);
break;
     case NDB_LE_ArbitState:
printf("Node %d: ArbitState\n", event.source_nodeid);
printf(" code %d, arbit_node %d\n",
       event.ArbitState.code & 0xffff,
       event.ArbitResult.arbit_node);
break;
    default:
```

```
}
}

ndb_mgm_destroy_logevent_handle(&le);
ndb_mgm_destroy_handle(&h);
ndb_end(0);
return 0;
}
```

3.6.2 MGM API Event Handling with Multiple Clusters

This example shown in this section illustrates the handling of log events using the MGM API on multiple clusters in a single application.

The source code for this program may be found in the NDB Cluster source tree, in the file storage/ndb/ndbapi-examples/mgmapi_logevent2/main.cpp.



Note

This file was previously named mgmapi_logevent2.cpp.

```
#include <mysql.h>
#include <ndbapi/NdbApi.hpp>
#include <mgmapi.h>
#include <stdio.h>
#include <stdlib.h>
* export LD_LIBRARY_PATH=../../../libmysql_r/.libs:../../ndb/src/.libs
#define MGMERROR(h) \
 fprintf(stderr, "code: %d msg: %s\n", \
         ndb_mgm_get_latest_error(h), \
         ndb_mgm_get_latest_error_msg(h)); \
  exit(-1); \
#define LOGEVENTERROR(h) \
  fprintf(stderr, "code: %d msg: %s\n", \
         ndb_logevent_get_latest_error(h), \
         ndb_logevent_get_latest_error_msg(h)); \
 exit(-1); \
int main(int argc, char** argv)
 NdbMgmHandle h1,h2;
 NdbLogEventHandle le1,le2;
  int filter[] = { 15, NDB_MGM_EVENT_CATEGORY_BACKUP,
     15, NDB_MGM_EVENT_CATEGORY_CONNECTION,
    15, NDB_MGM_EVENT_CATEGORY_NODE_RESTART,
     15, NDB_MGM_EVENT_CATEGORY_STARTUP,
     15, NDB_MGM_EVENT_CATEGORY_ERROR,
     0 };
 struct ndb_logevent event1, event2;
  if (argc < 3)
    printf("Arguments are <connect_string cluster 1>",
           "<connect_string cluster 2> [<iterations>].\n");
    exit(-1);
```

```
const char *connectstring1 = argv[1];
const char *connectstring2 = argv[2];
 int iterations = -1;
if (argc > 3)
  iterations = atoi(argv[3]);
ndb_init();
h1= ndb_mgm_create_handle();
h2= ndb_mgm_create_handle();
if ( h1 == 0 || h2 == 0 )
  printf("Unable to create handle\n");
   exit(-1);
 if (ndb_mgm_set_connectstring(h1, connectstring1) == -1 ||
    ndb_mgm_set_connectstring(h2, connectstring1))
   printf("Unable to set connection string\n");
   exit(-1);
 if (ndb_mgm_connect(h1,0,0,0)) MGMERROR(h1);
if (ndb_mgm_connect(h2,0,0,0)) MGMERROR(h2);
if ((le1= ndb_mgm_create_logevent_handle(h1, filter)) == 0) MGMERROR(h1);
if ((le2= ndb_mgm_create_logevent_handle(h1, filter)) == 0) MGMERROR(h2);
while (iterations-- != 0)
   int timeout= 1000;
   int r1= ndb_logevent_get_next(le1,&event1,timeout);
   if (r1 == 0)
    printf("No event within %d milliseconds\n", timeout);
   else if (r1 < 0)
    LOGEVENTERROR(le1)
   else
     switch (event1.type) {
     case NDB_LE_BackupStarted:
printf("Node %d: BackupStarted\n", event1.source_nodeid);
printf(" Starting node ID: %d\n", event1.BackupStarted.starting_node);
printf(" Backup ID: %d\n", event1.BackupStarted.backup_id);
     case NDB_LE_BackupCompleted:
printf("Node %d: BackupCompleted\n", event1.source_nodeid);
printf(" Backup ID: %d\n", event1.BackupStarted.backup_id);
     case NDB_LE_BackupAborted:
printf("Node %d: BackupAborted\n", event1.source_nodeid);
break;
     case NDB_LE_BackupFailedToStart:
printf("Node %d: BackupFailedToStart\n", event1.source_nodeid);
break;
     case NDB_LE_NodeFailCompleted:
printf("Node %d: NodeFailCompleted\n", event1.source_nodeid);
break;
    case NDB_LE_ArbitResult:
printf("Node %d: ArbitResult\n", event1.source_nodeid);
printf(" code %d, arbit_node %d\n",
      event1.ArbitResult.code & 0xffff,
       event1.ArbitResult.arbit_node);
break;
     case NDB_LE_DeadDueToHeartbeat:
printf("Node %d: DeadDueToHeartbeat\n", event1.source_nodeid);
printf(" node %d\n", event1.DeadDueToHeartbeat.node);
```

```
case NDB_LE_Connected:
printf("Node %d: Connected\n", event1.source_nodeid);
printf(" node %d\n", event1.Connected.node);
break;
     case NDB_LE_Disconnected:
printf("Node %d: Disconnected\n", event1.source_nodeid);
printf(" node %d\n", event1.Disconnected.node);
break;
     case NDB_LE_NDBStartCompleted:
printf("Node %d: StartCompleted\n", event1.source_nodeid);
printf(" version %d.%d.%d\n",
       event1.NDBStartCompleted.version >> 16 & 0xff,
       event1.NDBStartCompleted.version >> 8 & 0xff,
       event1.NDBStartCompleted.version >> 0 & 0xff);
break;
     case NDB_LE_ArbitState:
printf("Node %d: ArbitState\n", event1.source_nodeid);
printf(" code %d, arbit_node %d\n",
       event1.ArbitState.code & 0xffff,
       event1.ArbitResult.arbit_node);
break;
    default:
break;
   int r2= ndb_logevent_get_next(le1,&event2,timeout);
   if (r2 == 0)
     printf("No event within %d milliseconds\n", timeout);
   else if (r2 < 0)
    LOGEVENTERROR(1e2)
     switch (event2.type) {
     case NDB_LE_BackupStarted:
printf("Node %d: BackupStarted\n", event2.source_nodeid);
printf(" Starting node ID: %d\n", event2.BackupStarted.starting_node);
printf(" Backup ID: %d\n", event2.BackupStarted.backup_id);
break;
     case NDB_LE_BackupCompleted:
printf("Node %d: BackupCompleted\n", event2.source_nodeid);
printf(" Backup ID: %d\n", event2.BackupStarted.backup_id);
     case NDB_LE_BackupAborted:
printf("Node %d: BackupAborted\n", event2.source_nodeid);
     case NDB_LE_BackupFailedToStart:
printf("Node %d: BackupFailedToStart\n", event2.source_nodeid);
     case NDB_LE_NodeFailCompleted:
printf("Node %d: NodeFailCompleted\n", event2.source_nodeid);
break;
     case NDB_LE_ArbitResult:
printf("Node %d: ArbitResult\n", event2.source_nodeid);
printf(" code %d, arbit_node %d\n",
       event2.ArbitResult.code & 0xffff,
       event2.ArbitResult.arbit_node);
break;
     case NDB_LE_DeadDueToHeartbeat:
printf("Node %d: DeadDueToHeartbeat\n", event2.source_nodeid);
printf(" node %d\n", event2.DeadDueToHeartbeat.node);
break;
     case NDB_LE_Connected:
```

```
printf("Node %d: Connected\n", event2.source_nodeid);
printf(" node %d\n", event2.Connected.node);
break;
     case NDB_LE_Disconnected:
printf("Node %d: Disconnected\n", event2.source_nodeid);
printf(" node %d\n", event2.Disconnected.node);
break;
     case NDB_LE_NDBStartCompleted:
printf("Node %d: StartCompleted\n", event2.source_nodeid);
printf(" version %d.%d.%d\n",
      event2.NDBStartCompleted.version >> 16 & 0xff,
       event2.NDBStartCompleted.version >> 8 & 0xff,
       event2.NDBStartCompleted.version >> 0 & 0xff);
break;
     case NDB_LE_ArbitState:
printf("Node %d: ArbitState\n", event2.source_nodeid);
printf(" code %d, arbit_node %d\n",
       event2.ArbitState.code & 0xffff,
       event2.ArbitResult.arbit_node);
break;
    default:
break;
}
ndb_mgm_destroy_logevent_handle(&le1);
ndb_mgm_destroy_logevent_handle(&le2);
ndb_mgm_destroy_handle(&h1);
ndb_mgm_destroy_handle(&h2);
ndb_end(0);
return 0;
```

Chapter 4 MySQL NDB Cluster Connector for Java

Table of Contents

4.1 MySQL NDB Cluster Connector for Java: Overview	653
4.1.1 MySQL NDB Cluster Connector for Java Architecture	653
4.1.2 Java and NDB Cluster	653
4.1.3 The ClusterJ API and Data Object Model	655
4.2 Using MySQL NDB Cluster Connector for Java	657
4.2.1 Getting, Installing, and Setting Up MySQL NDB Cluster Connector for Java	657
4.2.2 Using ClusterJ	659
4.2.3 Using Connector/J with NDB Cluster	
4.3 ClusterJ API Reference	
4.3.1 com.mysql.clusterj	668
4.3.2 com.mysql.clusterj.annotation	717
4.3.3 com.mysql.clusterj.query	725
4.3.4 Constant field values	732
4.4 MySQL NDB Cluster Connector for Java: Limitations and Known Issues	733

This chapter discusses using NDB Cluster with MySQL NDB Cluster Connector for Java, also known as ClusterJ.

ClusterJ is a high level database API that is similar in style and concept to object-relational mapping persistence frameworks such as Hibernate and JPA. Because ClusterJ does not use the MySQL Server to access data in NDB Cluster, it can perform some operations much more quickly than can be done using JDBC. ClusterJ supports primary key and unique key operations and single-table queries; it does not support multi-table operations, including joins.

4.1 MySQL NDB Cluster Connector for Java: Overview

This section provides a conceptual and architectural overview of the APIs available using the MySQL NDB Cluster Connector for Java.

4.1.1 MySQL NDB Cluster Connector for Java Architecture

MySQL NDB Cluster Connector for Java, also known as ClusterJ, is a Java API for writing applications against NDB Cluster. It is one among different access paths and styles of access to NDB Cluster data. Section 4.1.2, "Java and NDB Cluster", describes each of those APIs in more detail.

MySQL NDB Cluster Connector for Java is included with all NDB Cluster source and binary releases. Building MySQL NDB Cluster Connector for Java from source can be done as part of building NDB Cluster; however, it can also be built with Maven.

4.1.2 Java and NDB Cluster

A NDB Cluster is defined as one or more MySQL Servers providing access to an NDBCLUSTER storage engine—that is, to a set of NDB Cluster data nodes (ndbd processes). There are three main access paths from Java to NDBCLUSTER, listed here:


• JDBC and mysqld. JDBC works by sending SQL statements to the MySQL Server and returning result sets. When using JDBC, you must write the SQL, manage the connection, and copy any data from

the result set that you want to use in your program as objects. The JDBC implementation most often used with the MySQL Server is MySQL Connector/J.

- Java Persistence API (JPA) and JDBC. JPA uses JDBC to connect to the MySQL Server. Unlike JDBC, JPA provides an object view of the data in the database.
- ClusterJ. ClusterJ uses a JNI bridge to the NDB API for direct access to NDBCLUSTER. It employs a style of data access that is based on a domain object model, similar in many ways to that employed by JPA. ClusterJ does not depend on the MySQL Server for data access.

These paths are shown in the following API stack diagram:

Figure 4.1 Java Access Paths To NDB



JDBC and mysqld. Connector/J provides standard access through the MySQL JDBC driver. Using Connector/J, JDBC applications can be written to work with a MySQL server acting as an NDB Cluster SQL node in much the same way that other Connector/J applications work with any other MySQL Server instance.

For more information, see Section 4.2.3, "Using Connector/J with NDB Cluster".

ClusterJ. ClusterJ is a native Java Connector for NDBCLUSTER (or NDB), the storage engine for NDB Cluster, in the style of Hibernate, JPA, and JDO. Like other persistence frameworks, ClusterJ uses the Data Mapper pattern, in which data is represented as domain objects, separate from business logic, mapping Java classes to database tables stored in the NDBCLUSTER storage engine.



Note

The NDBCLUSTER storage engine is often referred to (in MySQL documentation and elsewhere) simply as NDB. The terms NDB and NDBCLUSTER are synonymous, and you can use either ENGINE=NDB or ENGINE=NDBCLUSTER in a CREATE TABLE statement to create a clustered table.

ClusterJ does not need to connect to a mysqld process, having direct access to NDBCLUSTER using a JNI bridge that is included in the dynamic library libnbdclient. However, unlike JDBC, ClusterJ does not support table creation and other data definition operations; these must be performed by some other

means, such as JDBC or the mysql client. Also, ClusterJ is limited to queries on single tables, and does not support relations or inheritance; you should use another kind of access paths if you need support for those features in your applications.

4.1.3 The ClusterJ API and Data Object Model

This section discusses the ClusterJ API and the object model used to represent the data handled by the application.

Application Programming Interface. The ClusterJ API depends on 4 main interfaces: Session, SessionFactory, Transaction, and QueryBuilder.

Session interface. All access to NDB Cluster data is done in the context of a session. The Session interface represents a user's or application's individual connection to an NDB Cluster. It contains methods for the following operations:

- · Finding persistent instances by primary key
- Creating, updating, and deleting persistent instances
- Getting a query builder (see com.mysql.clusterj.query.QueryBuilder)
- Getting the current transaction (see com.mysql.clusterj.Transaction).

SessionFactory interface. Sessions are obtained from a SessionFactory, of which there is typically a single instance for each NDB Cluster that you want to access from the Java VM. SessionFactory stores configuration information about the cluster, such as the hostname and port number of the NDB Cluster management server. It also stores parameters regarding how to connect to the cluster, including connection delays and timeouts. For more information about SessionFactory and its use in a ClusterJ application, see Getting the SessionFactory and getting a Session.

Transaction interface. Transactions are not managed by the Session interface; like other modern application frameworks, ClusterJ separates transaction management from other persistence methods. Transaction demarcation might be done automatically by a container or in a web server servlet filter. Removing transaction completion methods from Session facilitates this separation of concerns.

The Transaction interface supports the standard begin, commit, and rollback behaviors required by a transactional database. In addition, it enables the user to mark a transaction as being rollback-only, which makes it possible for a component that is not responsible for completing a transaction to indicate that—due to an application or database error—the transaction must not be permitted to complete normally.

QueryBuilder interface. The <code>QueryBuilder</code> interface makes it possible to construct criteria queries dynamically, using domain object model properties as query modeling elements. Comparisons between parameters and database column values can be specified, including equal, greater and less than, between, and in operations. These comparisons can be combined using methods corresponding to the Boolean operators AND, OR, and NOT. Comparison of values to <code>NULL</code> is also supported.

Data model. ClusterJ provides access to data in NDB Cluster using domain objects, similar in many ways to the way that JPA models data.

In ClusterJ, the domain object mapping has the following characteristics:

All tables map to persistent interfaces. For every NDB table in the cluster, ClusterJ uses one or more
interfaces. In many cases, a single interface is used; but for cases where different columns are needed
by different parts of the application, multiple interfaces can be mapped to the same table.

However, the classes themselves are not persistent.

• Users map a subset of columns to persistent properties in interfaces. Thus, all properties map to columns; however, not all columns necessarily map to properties.

All ClusterJ property names default to column names. The interface provides getter and setter methods for each property, with predictable corresponding method names.

Annotations on interfaces define mappings.

The user view of the application environment and domain objects is illustrated in the following diagram, which shows the logical relationships among the modeling elements of the ClusterJ interfaces:

Session and Transaction

SessionFactory

Configuration Properties

Figure 4.2 ClusterJ User View Of Application And Environment

The SessionFactory is configured by a properties object that might have been loaded from a file or constructed dynamically by the application using some other means (see Section 4.2.2.1, "Executing ClusterJ Applications and Sessions").

The application obtains Session instances from the SessionFactory, with at most one thread working with a Session at a time. A thread can manage multiple Session instances if there is some application requirement for multiple connections to the database.

Each session has its own collection of domain objects, each of which represents the data from one row in the database. The domain objects can represent data in any of the following states:

- · New; not yet stored in the database
- Retrieved from the database; available to the application
- · Updated; to be stored back in the database
- · To be deleted from the database

4.2 Using MySQL NDB Cluster Connector for Java

This section provides basic information about building and running Java applications using MySQL NDB Cluster Connector for Java (ClusterJ).

4.2.1 Getting, Installing, and Setting Up MySQL NDB Cluster Connector for Java

This section discusses how to obtain ClusterJ sources and binaries, and how to compile, install, and get started with ClusterJ.

Obtaining and Installing MySQL NDB Cluster Connector for Java. You can obtain the most recent NDB Cluster release, which includes ClusterJ, from downloads.mysql.com. The installation instructions given in NDB Cluster Installation also install ClusterJ.

Building and installing MySQL NDB Cluster Connector for Java from source. You can build and install ClusterJ as part of building and installing NDB Cluster, which always requires you to configure the build using the CMake option WITH_NDBCLUSTER_STORAGE_ENGINE (or its alias WITH_NDBCLUSTER).

A typical CMake command for configuring a build for NDB Cluster that supports ClusterJ might look like this:

```
cmake .. -DWITH_BOOST=/usr/local/boost_1_59_0 -DWITH_NDBCLUSTER=ON
```

The WITH_NDB_JAVA option is enabled by default, which means ClusterJ is be built together with NDB Cluster by the above command. However, if CMake cannot find the location of Java on your system, the configuration process is going to fail; use the WITH_CLASSPATH option to provide the Java classpath if needed. Also, because ClusterJ uses the ucs2 character set for internal storage and ClusterJ cannot be built without it, if you ever use the WITH_EXTRA_CHARSETS CMake option and change its value from the default setting of all, you should make sure that ucs2 is specified in the character set list passed to the option. For information about other CMake options that can be used, see option_cmake_with_ndbcluster.

After configuring the build with CMake, run make and make install as you normally would to compile and install the NDB Cluster software.

MySQL NDB Cluster Connector for Java jar files. Following the installation, these ClusterJ jar files can be found in the folder share/java under the MySQL installation directory (which is /usr/local/mysql by default for Linux platforms):

- clusterj-api-version. jar: This is the compile-time jar file, required for compiling ClusterJ application code.
- clusterj-version. jar: This is the runtime library required for executing ClusterJ applications.
- clusterj-test-version.jar: This is the ClusterJ test suite, required for testing your ClusterJ installation.

Building ClusterJ with Maven

The source files for ClusterJ are configured as Maven projects, allowing easy compilation and installation using Maven. Assuming you have obtained the NDB Cluster source and already compiled and installed NDB Cluster and ClusterJ following the instructions given above, these are the steps to take:

1. Add the file path for the folder that contains the NDB client library (libndbclient.so) as a property named ndbclient.lib to your local Maven settings.xml file (found in the local Maven repository,

which is usually /home/username/.m2 for Linux platforms). The client library is to be found under the lib folder in the NDB Cluster's installation folder. If settings.xml does not exist in your local Maven repository, create one. This is how a simple settings.xml file containing the ndbclient.lib property looks like:

```
<settings xmlns="http://maven.apache.org/SETTINGS/1.0.0"</pre>
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
 xsi:schemaLocation="http://maven.apache.org/SETTINGS/1.0.0
                     http://maven.apache.org/xsd/settings-1.0.0.xsd">
  cprofiles>
    cprofile>
      <id>jni-library</id>
      <activation>
       <activeByDefault>true</activeByDefault>
      </activation>
      properties>
        <ndbclient.lib>/NDB_Cluster_installation_directory/lib/</ndbclient.lib>
      </properties>
    </profile>
  </profiles>
</settings>
```

2. Go to the build directory you created when compiling NDB Cluster (which is bld in the sample steps in Build the Distribution), and then to the storage/ndb/clusterj folder under it. Run the mvn install ndbjtie.sh script in the folder:

```
./mvn_install_ndbjtie.sh
```

It installs ndbjtie.jar, which provides the JNI layer for ClusterJ and is required for building CluterJ.

3. Install ClusterJ with Maven by running mvn install in the storage/ndb/clusterj directory:

```
mvn install
```

This causes ClusterJ to be built, with the resulting . jar files installed in the local Maven repository.



Note

You can skip the tests that takes place towards the end of the installation process by adding the option skipTests to the command:

```
mvn install -DskipTests
```

This prevents your installation from failing because you have not yet set up the testing environment.

Building ClusterJ with Maven in IDEs

Because the source files for ClusterJ are configured as Maven projects, you can easily import them into your favorite Maven-enabled IDEs, customize them, and rebuild them as needed by following these steps:

- Make sure that your IDE's support for Maven is enabled. You might need to install a Maven plugin for the purpose.
- 2. Follow step 1 and 2 in Building ClusterJ with Maven, which make the ClusterJ source ready to be used with Maven.
- 3. Import ClusterJ as a Maven project. This is how to do it in some popular IDEs:

In NetBeans:

- In the main menu, choose File > Open Project. The Open Project dialogue box appears
- In the **Open Project** dialogue box, browse to the storage/ndb folder under the build directory (see step 2 in Building ClusterJ with Maven); select the clusterj folder, which has the Maven icon

() beside it, and click Open Project. The ClusterJ Aggregate project is imported, with ClusterJ API, ClusterJ Core, ClusterJ Test Suite, ClusterJ Tie, and ClusterJ Unit Test Framework imported as subprojects under Modules.

Work with the ClusterJ projects like you would with any other Maven projects in NetBeans. Any
changes to the source code go into the source tree from which you compiled NDB Cluster to create
the build directory.

In Eclipse:

- In the main menu, choose File > Import. The Import dialogue box appears
- In the **Import** dialogue box, select **Maven > Existing Maven Projects** for import wizard and click **Next**. The **Import Maven Projects** dialogue box appears.
- In the Import Maven Projects dialogue box, browse to the storage/ndb folder under the build directory (see step 2 in Building ClusterJ with Maven); select the clusterj folder and click Select Folder. The clusterj-aggregate project, as well as its subprojects clusterj-api, clusterj-core, clusterj-test, clusterj-tie and clusterj-unit, appear in the Maven Projects dialogue box. Click Select All and then Finish. All the ClusterJ projects are imported.
- Work with the ClusterJ projects like you would with any other Maven projects in Eclipse.

4.2.2 Using ClusterJ

This section provides basic information for writing, compiling, and executing applications that use ClusterJ. For the API documentation for ClusterJ, see Section 4.3, "ClusterJ API Reference".

Requirements. ClusterJ requires Java 1.7 or 1.8. *NDB Cluster must be compiled with ClusterJ support*, NDB Cluster binaries supplied by Oracle include ClusterJ support. If you are building NDB Cluster from source, see Building and installing MySQL NDB Cluster Connector for Java from source, for information on configuring the build to enable ClusterJ support.

To compile applications that use ClusterJ, you either need to have the clusterj-api jar file in your classpath, or use a Maven dependency manager to install and configure the ClusterJ library in your project.

To run applications that use ClusterJ, you need the clusterj runtime jar file; in addition, libndbclient must be in the directory specified by java.library.path. Section 4.2.2.1, "Executing ClusterJ Applications and Sessions", provides more information about these requirements.

4.2.2.1 Executing ClusterJ Applications and Sessions

In this section, we discuss how to start ClusterJ applications and the ClusterJ application environment.

Executing a ClusterJ application. All of the ClusterJ jar files are normally found in <code>share/mysql/java/</code> in the MySQL installation directory. When executing a ClusterJ application, you must set the classpath to point to these files. In addition, you must set <code>java.library.path</code> variable to point to the directory containing the Cluster <code>ndbclient</code> library, normally found in <code>lib/mysql</code> (also in the MySQL)

installation directory). Thus you might execute a ClusterJ program MyClusterJApp in a manner similar to what is shown here:



Note

The precise locations of the ClusterJ jar files and of libndbclient depend on how the NDB Cluster software was installed. See Installation Layouts, for more information.

ClusterJ encourages you to use different jar files at compile time and runtime. This is to remove the ability of applications to access implementation artifacts accidentally. ClusterJ is intended to be independent of the NDB Cluster software version, whereas the ndbclient layer is version-specific. This makes it possible to maintain a stable API, so that applications written against it using a given NDB Cluster version continue to run following an upgrade of the cluster to a new version.

Getting the SessionFactory and getting a Session. SessionFactory is the source of all ClusterJ sessions that use a given NDB Cluster. Usually, there is only a single SessionFactory per NDB Cluster, per Java Virtual Machine.

SessionFactory can be configured by setting one or more properties. The preferred way to do this is by putting these in a properties file, like this:

```
com.mysql.clusterj.connectstring=localhost:1186
com.mysql.clusterj.database=mydb
```

The name of the properties file is arbitrary; however, by convention, such files are named with a .properties extension. For ClusterJ applications, it is customary to name the file clusterj.properties.

After editing and saving the file, you can load its contents into an instance of Properties, as shown here:

```
File propsFile = new File("clusterj.properties");
InputStream inStream = new FileInputStream(propsFile);
Properties props = new Properties();
props.load(inStream);
```

It is also possible to set these properties directly, without the use of a properties file:

```
Properties props = new Properties();
props.put("com.mysql.clusterj.connectstring", "localhost:1186");
props.put("com.mysql.clusterj.database", "mydb");
```

Once the properties have been set and loaded (using either of the techniques just shown), you can obtain a SessionFactory, and then from that a Session instance. For this, you use the SessionFactory's getSession() method, as shown here:

```
SessionFactory factory = ClusterJHelper.getSessionFactory(props);
Session session = factory.getSession();
```

It is usually sufficient to set and load the <code>com.mysql.clusterj.connectstring</code> and <code>com.mysql.clusterj.database</code> properties (and these properties, along with <code>com.mysql.clusterj.max.transactions</code>, cannot be changed after starting the <code>SessionFactory</code>). For a complete list of available <code>SessionFactory</code> properties and usual values, see <code>com.mysql.clusterj.Constants</code>.



Note

Session instances must not be shared among threads. Each thread in your application should use its own instance of Session.

For com.mysql.clusterj.connectstring, we use the default NDB Cluster connection string localhost:1186 (see NDB Cluster Connection Strings, for more information). For the value of com.mysql.clusterj.database, we use mydb in this example, but this value can be the name of any database containing NDB tables. For a listing of all SessionFactory properties that can be set in this manner, see com.mysql.clusterj.Constants.

Error Handling and Reconnection. Errors that occur while using ClusterJ should be handled by the application with a common error handler. The handler needs to be able to detect and distinguish among three types of errors, and handle them accordingly:

- Normal errors: These are errors at the application level (for example, those to deal with duplicate key, foreign key constraint, or timeout). They should be handled in application-specific ways, and, if resolved, the application can continue with the transaction.
- *Unexpected errors*: These are failures to work with the cluster that cannot be accounted for by the conditions of the application, but are nonfatal. The application should close the ClusterJ session and reopen a new one.
- Connectivity errors: These are errors like error 4009 and 4010, which indicate a network outage. There are two possible scenarios, depending on whether the automatic reconnection feature (available for NDB Cluster 7.5.7, 7.6.3, and for later releases in the 7.5 and 7.6 series) has been enabled:
 - Automatic reconnection is enabled: The feature is enabled when the connection property com.mysql.clusterj.connection.reconnect.timeout has been set to a positive number, which specifies a reconnection timeout in seconds.

When ClusterJ detects a disconnect with the NDB Cluster, it changes the State of the SessionFactory from OPEN to RECONNECTING; the SessionFactory then waits for the application to close all the sessions, and then attempts to reconnect the application to the NDB Cluster by closing all connections in the connection pool and recreating the pool using the original pool properties. After reestablishing all the connections, the State of the SessionFactory becomes OPEN again, and the application can now obtain sessions.

The SessionFactory.getState() method returns the State of the SessionFactory, which is one of OPEN, RECONNECTING, or CLOSED. Trying to obtain a session when the State is not OPEN results in a ClusterJUserException, with the message Session factory is not open.

If the application does not close all sessions by the end of the timeout period specified with com.mysql.clusterj.connection.reconnect.timeout, the SessionFactory closes any open sessions forcibly (which might result in loss of resources), and then attempts reconnection.

• Automatic reconnection is not enabled: This is when the connection property com.mysql.clusterj.connection.reconnect.timeout has not been set, or it has been set to zero (this is also the case for older NDB Cluster releases that do not support the automatic reconnection feature).

ClusterJ does not attempt to reconnect to the NDB Cluster once the connection is lost. The application should close all sessions and then restart the SessionFactory. The restarting of the SessionFactory can be an automatic application function or a manual intervention. In either case, the code should wait until all sessions have been closed (that is, the public method getConnectionPoolSessionCounts() in the SessionFactory interface returns zeros for all pooled

connections). Then the SessionFactory can be closed and reopened, and the application can obtain sessions again.

Instead of enabling the feature and waiting for ClusterJ to detect a disconnection and attempt a reconnection, you can also have the application itself initiate the reconnection process upon the detection of a connection error by calling the SessionFactory.reconnect(int timeout) method: that triggers the reconnection process described above, but uses the timeout argument of the reconnect() method as the time limit for having all open sessions closed.

Logging. ClusterJ uses Java logging. Here are some default settings for the ClusterJ logging, which are specified in the logging.properties file and can be modified there:

- Logging level is set at INFO for all classes.
- Using java.util.logging.FileHandler as the handler.
- Default level for java.util.logging.FileHandler is set at FINEST
- Using java.util.logging.SimpleFormatter as the formatter for the handler.
- Log files are put inside the target directory under the current working directory, and file names are, generally, in the pattern of logNum, where Num is a unique number for resolving file name conflicts (see the Java documentation for java.util.logging.FileHandler for details).

The logging.properties file is located by default in the current working directory, but the location can be changed by specifying the system property java.util.logging.config.file when you start Java.

4.2.2.2 Creating tables

ClusterJ's main purpose is to read, write, and update row data in an existing database, rather than to perform DDL. You can create the employee table that matches this interface, using the following CREATE TABLE statement, in a MySQL client application such as mysql.

```
CREATE TABLE employee (
   id INT NOT NULL PRIMARY KEY,
   first VARCHAR(64) DEFAULT NULL,
   last VARCHAR(64) DEFAULT NULL,
   municipality VARCHAR(64) DEFAULT NULL,
   started DATE DEFAULT NULL,
   ended DATE DEFAULT NULL,
   department INT NOT NULL DEFAULT 1,
   UNIQUE KEY idx_u_hash (last,first USING HASH),
   KEY idx_municipality (municipality)
) ENGINE=NDBCLUSTER;
```

Now that the table has been created in NDB Cluster, you can map a ClusterJ interface to it using annotations. We show you how to do this in the next section.

4.2.2.3 Annotations

In ClusterJ (as in JPA), annotations are used to describe how the interface is mapped to tables in a database. An annotated interface looks like this:

```
@PersistenceCapable(table="employee")
@Index(name="idx_uhash")
public interface Employee {
    @PrimaryKey
```

```
int getId();
void setId(int id);
String getFirst();
void setFirst(String first);
String getLast();
void setLast(String last);
@Column(name="municipality")
@Index(name="idx_municipality")
String getCity();
void setCity(String city);
Date getStarted();
void setStarted(Date date);
Date getEnded();
void setEnded(Date date);
Integer getDepartment();
void setDepartment(Integer department);
```

This interface maps seven columns: id, first, last, municipality started, ended, and department. The annotation @PersistenceCapable(table="employee") is used to let ClusterJ know which database table to map the Employee to (in this case, the employee table). The @Column annotation is used because the city property name implied by the getCity() and setCity() methods is different from the mapped column name municipality. The annotations @PrimaryKey and @Index inform ClusterJ about indexes in the database table.

The implementation of this interface is created dynamically by ClusterJ at runtime. When the newInstance() method is called, ClusterJ creates an implementation class for the Employee interface; this class stores the values in an internal object array.

ClusterJ does not require an annotation for every attribute. ClusterJ automatically detects the primary keys of tables; while there is an annotation in ClusterJ to permit the user to describe the primary keys of a table (see previous example), when specified, it is currently ignored. (The intended use of this annotation is for the generation of schemas from the domain object model interfaces, but this is not yet supported.)

The annotations themselves must be imported from the ClusterJ API. They can be found in package com.mysql.clusterj.annotation, and can be imported like this:

```
import com.mysql.clusterj.annotation.Column;
import com.mysql.clusterj.annotation.Index;
import com.mysql.clusterj.annotation.PersistenceCapable;
import com.mysql.clusterj.annotation.PrimaryKey;
```

4.2.2.4 ClusterJ Basic Operations

In this section, we describe how to perform operations basic to ClusterJ applications, including the following:

- Creating new instances, setting their properties, and saving them to the database
- Performing primary key lookups (reads)
- · Updating existing rows and saving the changes to the database
- · Deleting rows from the database
- Constructing and executing queries to fetch a set of rows meeting certain criteria from the database

Creating new rows. To insert a new row into the table, first create a new instance of Employee. This can be accomplished by calling the Session method newInstance(), as shown here:

```
Employee newEmployee = session.newInstance(Employee.class);
```

Set the Employee instance properties corresponding with the desired employee table columns. For example, the following sets the id, firstName, lastName, and started properties.

```
emp.setId(988);
newEmployee.setFirstName("John");
newEmployee.setLastName("Jones");
newEmployee.setStarted(new Date());
```

Once you are satisfied with the changes, you can persist the Employee instance, causing a new row containing the desired values to be inserted into the employee table, like this:

```
session.persist(newEmployee);
```

If autocommit is on, and a row with the same id as this instance of Employee already exists in the database, the persist() method fails. If autocommit is off and a row with the same id as this Employee instance already exists in the database, the persist() method succeeds but a subsequent commit() fails.

If you want the data to be saved even though the row already exists, use the $\mathtt{savePersistent}()$ method instead of the $\mathtt{persist}()$ method. The $\mathtt{savePersistent}()$ method updates an existing instance or creates a new instance as needed, without throwing an exception.

Values that you have not specified are stored with their Java default values (0 for integral types, 0.0 for numeric types, and null for reference types).

Primary key lookups. You can find an existing row in an NDB table using the Session's find() method, like this:

```
Employee theEmployee = session.find(Employee.class, 988);
```

This is equivalent to the primary key lookup query SELECT * FROM employee WHERE id = 988.

ClusterJ also supports compound primary keys. The find() method can take an object array as a key, where the components of the object array are used to represent the primary key columns in the order they were declared. In addition, queries are optimized to detect whether columns of the primary key are specified as part of the query criteria, and if so, a primary key lookup or scan is executed as a strategy to implement the query.



Note

ClusterJ also supports multiple column ordered btree and unique hash indexes. As with primary keys, if a query specifies values for ordered or unique index fields, ClusterJ optimizes the query to use the index for scanning the table.

NDB Cluster automatically spreads table data across multiple data nodes. For some operations—find, insert, delete, and update—it is more efficient to tell the cluster on which data node the data is physically located, and to have the transaction execute on that data node. ClusterJ automatically detects the partition key; if the operation can be optimized for a specific data node, ClusterJ automatically starts the transaction on that node.

Update and save a row. To update the value of a given column in the row that we just obtained as the Employee, use the set*() method whose name corresponds to the name of that column. For example, to update the started date for this Employee, use the Employee's setStarted() method, as shown here:

the Employee.setStarted(new Date(getMillisFor(2010, 01, 04)));



Note

For convenience, we use in this example a method <code>getMillisFor()</code>, which is defined as shown here, in the file <code>AbstractClusterJModelTest.java</code> (found in the <code>storage/ndb/clusterj/clusterj-test/src/main/java/testsuite/clusterj directory</code> of the NDB Cluster source tree):

```
** Convert year, month, day into milliseconds after the Epoch, UTC.
 Set hours, minutes, seconds, and milliseconds to zero.
  @param year the year
 @param month the month (0 for January)
 @param day the day of the month
 @return
protected static long getMillisFor(int year, int month, int day) {
  Calendar calendar = Calendar.getInstance();
  calendar.clear();
  calendar.set(Calendar.YEAR, year);
  calendar.set(Calendar.MONTH, month);
  calendar.set(Calendar.DATE, day);
  calendar.set(Calendar.HOUR, 0);
  calendar.set(Calendar.MINUTE, 0);
  calendar.set(Calendar.SECOND, 0);
  calendar.set(Calendar.MILLISECOND, 0);
  long result = calendar.getTimeInMillis();
  return result;
```

See the indicated file for further information.

You can update additional columns by invoking other Employee setter methods, like this:

```
theEmployee.setDepartment(3);
```

To save the changed row back to the NDB Cluster database, use the Session's updatePersistent() method, like this:

```
session.updatePersistent(theEmployee);
```

Deleting rows. You can delete a single row easily using the deletePersistent() method of Session. In this example, we find the employee whose ID is 13, then delete this row from the employee table:

There also exists a method for deleting multiple rows, which provides two options:

1. Delete all rows from a table.

2. Delete an arbitrary collection of rows.

Both kinds of multi-row delete can be performed using the deletePersistentAll() method. The first variant of this method acts on a Class. For example, the following statement deletes all rows from the employee table and returns the number of rows deleted, as shown here:

```
int numberDeleted = session.deletePersistentAll(Employee);
System.out.println("There used to be " + numberDeleted + " employees, but now there are none.");
```

The call to deletePersistentAll() just shown is equivalent to issuing the SQL statement DELETE FROM employee in the mysql client.

deletePersistentAll() can also be used to delete a collection of rows, as shown in this example:

```
// Assemble the collection of rows to be deleted...
List<Employee> redundancies = new ArrayList<Employee>();

for (int i = 1000; i < 2000; i += 100) {
    Employee redundant = session.newInstance(Employee.class);
    redundant.setId(i);
    redundancies.add(redundant);
}

numberDeleted = session.deletePersistentAll(redundancies);
System.out.println("Deleted " + numberDeleted + " rows.");</pre>
```

It is not necessary to find the instances in the database before deleting them.

Writing queries. The ClusterJ <code>QueryBuilder</code> interface is used to instantiate queries. The process begins with obtaining an instance of <code>QueryBuilder</code>, which is supplied by the current <code>Session</code>; we can then obtain a <code>QueryDefinition</code>, as shown here:

```
QueryBuilder builder = session.getQueryBuilder();
QueryDomainType<Employee> domain = builder.createQueryDefinition(Employee.class);
```

This is then used to set a column for comparison by the query. Here, we show how to prepare a query that compares the value of the employee table's department column with the constant value 8.

```
domain.where( domain.get("department").equal(domain.param("department") );
Query<Employee> query = session.createQuery(domain);
query.setParameter("department", 8);
```

To obtain the results from the query, invoke the Query's getResultList() method, as shown here;

```
List<Employee> results = query.getResultList();
```

The return value is a List that you can iterate over to retrieve and process the rows in the usual manner.

Transactions. The Transaction interface can optionally be used to bound transactions, via the following methods:

- begin(): Begin a transaction.
- commit(): Commit a transaction.
- rollback(): Roll back a transaction.

It is also possible using Transaction to check whether the transaction is active (via the isActive() method, and to get and set a rollback-only flag (using getRollbackOnly() and setRollbackOnly(), respectively).

If you do not use the Transaction interface, methods in Session that affect the database—such as persist(), deletePersistent(), updatePersistent(), and so on—are automatically enclosed in a database transaction.

4.2.2.5 ClusterJ Mappings Between MySQL and Java Data Types

ClusterJ provides mappings for all of the common MySQL database types to Java types. Java object wrappers of primitive types should be mapped to nullable database columns.



Note

Since Java does not have native unsigned data types, UNSIGNED columns should be avoided in table schemas if possible.

Compatibility with JDBC mappings. ClusterJ is implemented so as to be bug-compatible with the JDBC driver in terms of mapping from Java types to the database. That is, if you use ClusterJ to store or retrieve data, you obtain the same value as if you used the JDBC driver directly or through JPA.

The following tables show the mappings used by ClusterJ between common Java data types and MySQL column types. Separate tables are provided for numeric, floating-point, and variable-width types.

Numeric types. This table shows the ClusterJ mappings between Java numeric data types and MySQL column types:

Table 4.1 ClusterJ mappings between Java numeric data types and MySQL column types

Java Data Type	MySQL Column Type
boolean, Boolean	BIT(1)
byte, Byte	BIT(1) to BIT(8), TINYINT
short, Short	BIT(1) to BIT(16), SMALLINT, YEAR
int, Integer	BIT(1) to BIT(32), INT
long, Long	BIT(1) to BIT(64), BIGINT, BIGINT UNSIGNED
float, Float	FLOAT
double, Double	DOUBLE
java.math.BigDecimal	NUMERIC, DECIMAL
java.math.BigInteger	NUMERIC (precision = 0), DECIMAL (precision = 0)

Date and time types. The following table shows the ClusterJ mappings between Java date and time data types and MySQL column types:

Table 4.2 ClusterJ mappings between Java date and time data types and MySQL column types

Java Data Type	MySQL Column Type
Java.util.Date	DATETIME, TIMESTAMP, TIME, DATE
Java.sql.Date	DATE
Java.sql.Time	TIME

Java Data Type	MySQL Column Type
Java.sql.Timestamp	DATETIME, TIMESTAMP



Note

ClusterJ maps the MySQL YEAR type to a Java short (or java.lang.Short), as shown in the first table in this section.

java.util.Date represents date and time similar to the way in which Unix does so, but with more precision and a larger range. Where Unix represents a point in time as a 32-bit signed number of seconds since the Unix Epoch (01 January 1970), Java uses a 64-bit signed number of milliseconds since the Epoch.

Variable-width types. The following table shows the ClusterJ mappings between Java data types and MySQL variable-width column types:

Table 4.3 This table shows the ClusterJ mappings between Java data types and MySQL variable-width column types.

Java Data Type	MySQL Column Type
String	CHAR, VARCHAR, TEXT
byte[]	BINARY, VARBINARY, BLOB



Note

No translation binary data is performed when mapping from MySQL BINARY, VARBINARY, or BLOB column values to Java byte arrays. Data is presented to the application exactly as it is stored.

4.2.3 Using Connector/J with NDB Cluster

JDBC clients of an NDB Cluster data source, and using Connector/J 5.0.6 (or later), accept jdbc:mysq1:loadbalance:// URLs (see Configuration Properties for Connector/J), with which you can take advantage of the ability to connect with multiple MySQL servers to achieve load balancing and failover.

However, while Connector/J does not depend on the MySQL client libraries, it does require a connection to a MySQL Server, which ClusterJ does not. JDBC also does not provide any object mappings for database objects, properties, or operations, or any way to persist objects.

See MySQL Connector/J 5.1 Developer Guide, for general information about using Connector/J.

4.3 ClusterJ API Reference

The following sections contain specifications for ClusterJ packages, interfaces, classes, and methods.

4.3.1 com.mysql.clusterj

Provides classes and interfaces for using NDB Cluster directly from Java.

- A class for bootstrapping
- Interfaces for use in application programs
- Classes to define exceptions

This package contains three main groups of classes and interfaces:

4.3.1.1 Major Interfaces

ClusterJ provides these major interfaces for use by application programs:

```
com.mysql.clusterj.SessionFactory, com.mysql.clusterj.Session, com.mysql.clusterj.Transaction, com.mysql.clusterj.query.QueryBuilder, and com.mysql.clusterj.Query. Bootstrapping The helper class com.mysql.clusterj.ClusterJHelper contains methods for creating the com.mysql.clusterj.SessionFactory. Bootstrapping is the process of identifying an NDB Cluster and obtaining the SessionFactory for use with the cluster. There is one SessionFactory per cluster per Java VM.
```

SessionFactory

The com.mysql.clusterj.SessionFactory is configured via properties, which identify the NDB Cluster that the application connects to:

- · com.mysql.clusterj.connectstring identifies the ndb mgmd host name and port
- · com.mysql.clusterj.connect.retries is the number of retries when connecting
- com.mysql.clusterj.connect.delay is the delay in seconds between connection retries
- com.mysgl.clusterj.connect.verbose tells whether to display a message to System.out while connecting
- com.mysql.clusterj.connect.timeout.before is the number of seconds to wait until the first node responds to a connect request
- com.mysql.clusterj.connect.timeout.after is the number of seconds to wait until the last node responds to a connect request
- com.mysql.clusterj.connect.database is the name of the database to use

```
File propsFile = new File("clusterj.properties");
InputStream inStream = new FileInputStream(propsFile);
Properties props = new Properties();
props.load(inStream);
SessionFactory sessionFactory = ClusterJHelper.getSessionFactory(props);
```

Session The com.mysql.clusterj.Session represents the user's individual connection to the cluster. It contains methods for:

- finding persistent instances by primary key
- persistent instance factory (newInstance)
- persistent instance life cycle management (persist, remove)
- getting the QueryBuilder
- getting the Transaction (currentTransaction)

```
Session session = sessionFactory.getSession();
Employee existing = session.find(Employee.class, 1);
if (existing != null) {
    session.remove(existing);
}
Employee newemp = session.newInstance(Employee.class);
```

```
newemp.initialize(2, "Craig", 15, 146000.00);
session.persist(newemp);
```

Transaction The com.mysql.clusterj.Transaction allows users to combine multiple operations into a single database transaction. It contains methods to:

- · begin a unit of work
- · commit changes from a unit of work
- roll back all changes made since the unit of work was begun
- · mark a unit of work for rollback only
- · get the rollback status of the current unit of work

```
Transaction tx = session.currentTransaction();
tx.begin();
Employee existing = session.find(Employee.class, 1);
Employee newemp = session.newInstance(Employee.class);
newemp.initialize(2, "Craig", 146000.00);
session.persist(newemp);
tx.commit();
```

QueryBuilder The com.mysql.clusterj.query.QueryBuilder allows users to build queries. It contains methods to:

- define the Domain Object Model to query
- · compare properties with parameters using:
 - equal
 - lessThan
 - greaterThan
 - lessEqual
 - · greaterEqual
 - between
 - in
- combine comparisons using "and", "or", and "not" operators

```
QueryBuilder builder = session.getQueryBuilder();
QueryDomainType<Employee> qemp = builder.createQueryDefinition(Employee.class);
Predicate service = qemp.get("yearsOfService").greaterThan(qemp.param("service"));
Predicate salary = qemp.get("salary").lessEqual(qemp.param("salaryCap"));
qemp.where(service.and(salary));
Query<Employee> query = session.createQuery(qemp);
query.setParameter("service", 10);
query.setParameter("salaryCap", 180000.00);
List<Employee> results = query.getResultList();
```

4.3.1.2 ClusterJDatastoreException

ClusterJUserException represents a database error. The underlying cause of the exception is contained in the "cause".

Synopsis

```
public class ClusterJDatastoreException,
  extends ClusterJException {
// Public Constructors
  public ClusterJDatastoreException(
   String message);
  public ClusterJDatastoreException(
    String msg,
    int code,
    int mysqlCode,
   int status,
    int classification);
  public ClusterJDatastoreException(
    String message,
    Throwable t);
  public ClusterJDatastoreException(
    Throwable t);
// Public Methods
  public int getClassification();
  public int getCode();
  public int getMysqlCode();
  public int getStatus();
```

Methods inherited from com.mysql.clusterj.ClusterJException: printStackTrace

Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, setStackTrace, toString

 $\begin{tabular}{ll} \textbf{Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait} \\ \end{tabular}$

getClassification()

```
public int getClassification();
```

Get the classification

getCode()

```
public int getCode();
```

Get the code

Since 7.3.15, 7.4.13, 7.5.4

getMysqlCode()

```
public int getMysqlCode();
```

Get the mysql code

Since

7.3.15, 7.4.13, 7.5.4

getStatus()

```
public int getStatus();
```

Get the status

4.3.1.3 ClusterJDatastoreException.Classification

Helper class for getClassification(). import com.mysql.clusterj.ClusterJDatastoreException.Classification; Classification c = Classification.lookup(datastoreException.getClassification()); System.out.println("exceptionClassification" + c + " with value " + c.value);

Synopsis

```
public static final class ClusteryDatastoreException.Classification,
  extends Enum<Classification> {
// Public Static Fields
  public static final Classification
   ApplicationError;
 public static final Classification
    ConstraintViolation ;
 public static final Classification
    FunctionNotImplemented ;
  public static final Classification
    InsufficientSpace ;
 public static final Classification
   InternalError ;
 public static final Classification
   InternalTemporary ;
 public static final Classification
    NoDataFound ;
 public static final Classification
   NoError ;
 public static final Classification
    NodeRecoveryError ;
 public static final Classification
   NodeShutdown ;
 public static final Classification
    OverloadError ;
 public static final Classification
    SchemaError ;
  public static final Classification
    SchemaObjectExists ;
  public static final Classification
    TemporaryResourceError ;
  public static final Classification
    TimeoutExpired ;
```

```
public static final Classification
   UnknownErrorCode;

public static final Classification
   UnknownResultError;

public static final Classification
   UserDefinedError;

// Public Static Methods

public static Classification lookup(
   int value);

public static Classification valueOf(
   String name);

public static Classification[] values();
}
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

Since 7.3.15, 7.4.13, 7.5.4

lookup(int)

```
public static Classification lookup(
  int value);
```

Get the Classification enum for a value returned by ClusterJDatastoreException.getClassification().

Table 4.4 lookup(int)

Parameter	Description
value	the classification returned by getClassification()
return	the Classification for the error

4.3.1.4 ClusterJException

ClusterJException is the base for all ClusterJ exceptions. Applications can catch ClusterJException to be notified of all ClusterJ reported issues.

- User exceptions are caused by user error, for example providing a connect string that refers to an unavailable host or port.
 - If a user exception is detected during bootstrapping (acquiring a SessionFactory), it is thrown as a fatal exception. com.mysql.clusterj.ClusterJFatalUserException
 - If an exception is detected during initialization of a persistent interface, for example annotating a column that doesn't exist in the mapped table, it is reported as a user exception. com.mysql.clusterj.ClusterJUserException
- Datastore exceptions report conditions that result from datastore operations after bootstrapping. For example, duplicate keys on insert, or record does not exist on delete. com.mysql.clusterj.ClusterJDatastoreException

• Internal exceptions report conditions that are caused by errors in implementation. These exceptions should be reported as bugs. com.mysql.clusterj.ClusterJFatalInternalException

Exceptions are in three general categories: User exceptions, Datastore exceptions, and Internal exceptions.

Synopsis

```
public class ClusterJException,
    extends RuntimeException {
    // Public Constructors

public ClusterJException(
    String message);

public ClusterJException(
    String message,
    Throwable t);

public ClusterJException(
    Throwable t);

// Public Methods

public synchronized void printStackTrace(
    PrintStream s);
}
```

```
Direct known subclasses: com.mysql.clusterj.ClusterJDatastoreException, com.mysql.clusterj.ClusterJFatalException, com.mysql.clusterj.ClusterJUserException
```

Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, printStackTrace, setStackTrace, toString

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait

4.3.1.5 ClusterJFatalException

ClusterJFatalException represents an exception that is not recoverable.

Synopsis

```
public class ClusterJFatalException,
   extends ClusterJException {
   // Public Constructors

   public ClusterJFatalException(
        String string);

   public ClusterJFatalException(
        String string,
        Throwable t);

   public ClusterJFatalException(
        Throwable t);

}
```

Direct known subclasses: com.mysql.clusterj.ClusterJFatalInternalException, com.mysql.clusterj.ClusterJFatalUserException

Methods inherited from com.mysql.clusterj.ClusterJException: printStackTrace

Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, setStackTrace, toString

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait

4.3.1.6 ClusterJFatalInternalException

ClusterJFatalInternalException represents an implementation error that the user cannot recover from.

Synopsis

```
public class ClusterJFatalInternalException,
   extends ClusterJFatalException {
   // Public Constructors

   public ClusterJFatalInternalException(
        String string);

   public ClusterJFatalInternalException(
        String string,
        Throwable t);

   public ClusterJFatalInternalException(
        Throwable t);

}
```

Methods inherited from com.mysql.clusterj.ClusterJException: printStackTrace

Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, setStackTrace, toString

 $\label{lem:methods} \textbf{Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait}$

4.3.1.7 ClusterJFatalUserException

ClusterJFatalUserException represents a user error that is unrecoverable, such as programming errors in persistent classes or missing resources in the execution environment.

Synopsis

```
public class ClusterJFatalUserException,
  extends ClusterJFatalException {
  // Public Constructors

  public ClusterJFatalUserException(
    String string);

  public ClusterJFatalUserException(
    String string,
    Throwable t);
```

```
public ClusterJFatalUserException(
   Throwable t);
}
```

Methods inherited from com.mysql.clusterj.ClusterJException: printStackTrace

```
Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, setStackTrace, toString
```

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait

4.3.1.8 ClusterJHelper

ClusterJHelper provides helper methods to bridge between the API and the implementation.

Synopsis

```
public class ClusterJHelper {
// Public Constructors
 public ClusterJHelper();
// Public Static Methods
 public static boolean getBooleanProperty(
   String propertyName,
   String def);
 public static T getServiceInstance(
   Class<T> cls);
 public static T getServiceInstance(
   Class<T> cls,
   ClassLoader loader);
 public static T getServiceInstance(
   Class<T> cls,
   String implementationClassName);
 public static T getServiceInstance(
   Class<T> cls,
   String implementationClassName,
   ClassLoader loader);
 public static List<T> getServiceInstances(
   Class<T> cls,
   ClassLoader loader,
   StringBuffer errorMessages);
 public static SessionFactory getSessionFactory(
   Map props);
 public static SessionFactory getSessionFactory(
   Map props,
   ClassLoader loader);
 public static String getStringProperty(
   String propertyName,
   String def);
 public static Dbug newDbug();
```

}

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, toString, wait

getBooleanProperty(String, String)

```
public static boolean getBooleanProperty(
   String propertyName,
   String def);
```

Get the named boolean property from either the environment or system properties. If the property is not 'true' then return false.

Table 4.5 getBooleanProperty(String, String)

Parameter	Description
propertyName	the name of the property
def	the default if the property is not set
return	the system property if it is set via -D or the system environment

getServiceInstance(Class<T>)

```
public static T getServiceInstance(
  Class<T> cls);
```

Locate a service implementation by services lookup of the context class loader.

Table 4.6 getServiceInstance(Class<T>)

Parameter	Description
cls	the class of the factory
return	the service instance

getServiceInstance(Class<T>, ClassLoader)

```
public static T getServiceInstance(
  Class<T> cls,
  ClassLoader loader);
```

Locate a service implementation for a service by services lookup of a specific class loader. The first service instance found is returned.

Table 4.7 getServiceInstance(Class<T>, ClassLoader)

Parameter	Description
cls	the class of the factory
loader	the class loader for the factory implementation
return	the service instance

getServiceInstance(Class<T>, String)

```
public static T getServiceInstance(
  Class<T> cls,
```

```
String implementationClassName);
```

Locate a service implementation for a service. If the implementation name is not null, use it instead of looking up. If the implementation class is not loadable or does not implement the interface, throw an exception. Use the ClusterJHelper class loader to find the service.

Table 4.8 getServiceInstance(Class<T>, String)

Parameter	Description
cls	
implementationClassName	
return	the implementation instance for a service

getServiceInstance(Class<T>, String, ClassLoader)

```
public static T getServiceInstance(
  Class<T> cls,
  String implementationClassName,
  ClassLoader loader);
```

Locate a service implementation for a service. If the implementation name is not null, use it instead of looking up. If the implementation class is not loadable or does not implement the interface, throw an exception.

Table 4.9 getServiceInstance(Class<T>, String, ClassLoader)

Parameter	Description
cls	
implementationClassName	ename of implementation class to load
loader	the ClassLoader to use to find the service
return	the implementation instance for a service

getServiceInstances(Class<T>, ClassLoader, StringBuffer)

```
public static List<T> getServiceInstances(
  Class<T> cls,
  ClassLoader loader,
  StringBuffer errorMessages);
```

Locate all service implementations by services lookup of a specific class loader. Implementations in the services file are instantiated and returned. Failed instantiations are remembered in the errorMessages buffer.

Table 4.10 getServiceInstances(Class<T>, ClassLoader, StringBuffer)

Parameter	Description
cls	the class of the factory
loader	the class loader for the factory implementation
errorMessages	a buffer used to hold the error messages
return	the service instance

getSessionFactory(Map)

public static SessionFactory getSessionFactory(

```
Map props);
```

Locate a SessionFactory implementation by services lookup. The class loader used is the thread's context class loader.

Table 4.11 getSessionFactory(Map)

Parameter	Description
props	properties of the session factory
return	the session factory

Exceptions

ClusterFatalUserException if the connection to the cluster cannot be made

getSessionFactory(Map, ClassLoader)

```
public static SessionFactory getSessionFactory(
   Map props,
   ClassLoader loader);
```

Locate a SessionFactory implementation by services lookup of a specific class loader. The properties are a Map that might contain implementation-specific properties plus standard properties.

Table 4.12 getSessionFactory(Map, ClassLoader)

Parameter	Description
props	the properties for the factory
loader	the class loader for the factory implementation
return	the session factory

Exceptions

ClusterFatalUserException if the connection to the cluster cannot be made

getStringProperty(String, String)

```
public static String getStringProperty(
   String propertyName,
   String def);
```

Get the named String property from either the environment or system properties.

Table 4.13 getStringProperty(String, String)

Parameter	Description
propertyName	the name of the property
def	the default if the property is not set
return	the system property if it is set via -D or the system environment

newDbug()

```
public static Dbug newDbug();
```

Return a new Dbug instance.

Table 4.14 newDbug()

Parameter	Description
return	a new Dbug instance

4.3.1.9 ClusterJUserException

ClusterJUserException represents a user programming error.

Synopsis

```
public class ClusterJUserException,
  extends ClusterJException {
// Public Constructors

public ClusterJUserException(
  String message);

public ClusterJUserException(
  String message,
  Throwable t);

public ClusterJUserException(
  Throwable t);
}
```

Methods inherited from com.mysql.clusterj.ClusterJException: printStackTrace

Methods inherited from java.lang.Throwable: addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, setStackTrace, toString

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, wait

4.3.1.10 ColumnMetadata

```
public interface ColumnMetadata {
// Public Methods

public abstract String charsetName();

public abstract ColumnType columnType();

public abstract boolean isPartitionKey();

public abstract boolean isPrimaryKey();

public abstract Class<?> javaType();

public abstract int maximumLength();

public abstract String name();

public abstract boolean nullable();

public abstract int number();

public abstract int precision();

public abstract int precision();

public abstract int scale();
}
```

charsetName()

public abstract String charsetName();

Return the charset name.

Table 4.15 charsetName()

Parameter	Description
return	the charset name

columnType()

public abstract ColumnType columnType();

Return the type of the column.

Table 4.16 columnType()

Parameter	Description
return	the type of the column

isPartitionKey()

public abstract boolean isPartitionKey();

Return whether this column is a partition key column.

Table 4.17 isPartitionKey()

Parameter	Description
return	true if this column is a partition key column

isPrimaryKey()

public abstract boolean isPrimaryKey();

Return whether this column is a primary key column.

Table 4.18 isPrimaryKey()

Parameter	Description
return	true if this column is a primary key column

javaType()

public abstract Class<?> javaType();

Return the java type of the column.

Table 4.19 javaType()

Parameter	Description
return	the java type of the column

maximumLength()

public abstract int maximumLength();

Return the maximum number of bytes that can be stored in the column after translating the characters using the character set.

Table 4.20 maximumLength()

Parameter	Description
return	the maximum number of bytes that can be stored in the column

name()

public abstract String name();

Return the name of the column.

Table 4.21 name()

Parameter	Description
return	the name of the column

nullable()

public abstract boolean nullable();

Return whether this column is nullable.

Table 4.22 nullable()

Parameter	Description
return	whether this column is nullable

number()

public abstract int number();

Return the column number. This number is used as the first parameter in the get and set methods of DynamicColumn.

Table 4.23 number()

Parameter	Description
return	the column number.

precision()

public abstract int precision();

Return the precision of the column.

Table 4.24 precision()

Parameter	Description
return	the precision of the column

scale()

public abstract int scale();

Return the scale of the column.

Table 4.25 scale()

Parameter	Description
return	the scale of the column

4.3.1.11 ColumnType

This class enumerates the column types for columns in ndb.

Synopsis

```
public final class ColumnType,
  extends Enum<ColumnType> {
// Public Static Fields
  public static final ColumnType
   Bigint ;
 public static final ColumnType
   Bigunsigned ;
  public static final ColumnType
    Binary ;
  public static final ColumnType
   Bit ;
  public static final ColumnType
  public static final ColumnType
  public static final ColumnType
   Date ;
  public static final ColumnType
   Datetime ;
  public static final ColumnType
   Datetime2 ;
  public static final ColumnType
    Decimal ;
  public static final ColumnType
    Decimalunsigned ;
  public static final ColumnType
   Double ;
  public static final ColumnType
   Float ;
  public static final ColumnType
    Int ;
  public static final ColumnType
   Longvarbinary;
  public static final ColumnType
   Longvarchar ;
  public static final ColumnType
    Mediumint ;
```

```
public static final ColumnType
   Mediumunsigned ;
 public static final ColumnType
   Olddecimal ;
 public static final ColumnType
   Olddecimalunsigned ;
 public static final ColumnType
   Smallint ;
 public static final ColumnType
   Smallunsigned;
 public static final ColumnType
   Text ;
 public static final ColumnType
   Time ;
 public static final ColumnType
   Time2 ;
 public static final ColumnType
   Timestamp ;
 public static final ColumnType
   Timestamp2 ;
 public static final ColumnType
   Tinyint ;
 public static final ColumnType
   Tinyunsigned ;
 public static final ColumnType
   Undefined ;
 public static final ColumnType
   Unsigned ;
 public static final ColumnType
   Varbinary ;
 public static final ColumnType
   Varchar ;
 public static final ColumnType
   Year ;
// Public Static Methods
 public static ColumnType valueOf(
   String name);
 public static ColumnType[] values();
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

4.3.1.12 Constants

Constants used in the ClusterJ project.

Synopsis

```
public interface Constants {
// Public Static Fields
 public static final String
   DEFAULT_PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES
        = "256, 10240, 102400, 1048576";
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BATCH_SIZE
 public static final long
   DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_START
       = 1L;
 public static final long
   DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_STEP
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_DELAY
       = 5;
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_RETRIES
       = 4;
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER
       = 20;
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE
        = 30;
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM
        = 30000;
 public static final int
   DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE
       = 0;
 public static final String
   DEFAULT_PROPERTY_CLUSTER_DATABASE
       = "test";
 public static final int
   DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS
 public static final int
   DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD
       = 8;
 public static final int
   DEFAULT_PROPERTY_CONNECTION_POOL_SIZE
       = 1;
 public static final int
   DEFAULT_PROPERTY_CONNECTION_RECONNECT_TIMEOUT
       = 0;
```

```
public static final String
  ENV_CLUSTERJ_LOGGER_FACTORY_NAME
      = "CLUSTERJ_LOGGER_FACTORY";
public static final String
  PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES
      = "com.mysql.clusterj.byte.buffer.pool.sizes";
public static final String
  PROPERTY_CLUSTER_CONNECTION_SERVICE
      = "com.mysql.clusterj.connection.service";
public static final String
  PROPERTY_CLUSTER_CONNECTSTRING
      = "com.mysql.clusterj.connectstring";
public static final String
  PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BATCH_SIZE
      = "com.mysql.clusterj.connect.autoincrement.batchsize";
public static final String
  PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_START
      = "com.mysql.clusterj.connect.autoincrement.offset";
public static final String
  PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_STEP
      = "com.mysql.clusterj.connect.autoincrement.increment";
public static final String
  PROPERTY_CLUSTER_CONNECT_DELAY
      = "com.mysql.clusterj.connect.delay";
public static final String
  PROPERTY_CLUSTER_CONNECT_RETRIES
      = "com.mysql.clusterj.connect.retries";
public static final String
  PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER
      = "com.mysql.clusterj.connect.timeout.after";
public static final String
  PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE
      = "com.mysql.clusterj.connect.timeout.before";
public static final String
  PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM
      = "com.mysql.clusterj.connect.timeout.mgm";
public static final String
  PROPERTY_CLUSTER_CONNECT_VERBOSE
      = "com.mysql.clusterj.connect.verbose";
public static final String
  PROPERTY_CLUSTER_DATABASE
      = "com.mysql.clusterj.database";
public static final String
  PROPERTY_CLUSTER_MAX_TRANSACTIONS
      = "com.mysql.clusterj.max.transactions";
public static final String
  PROPERTY_CONNECTION_POOL_NODEIDS
        "com.mysql.clusterj.connection.pool.nodeids";
public static final String
  PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD
      = "com.mysql.clusterj.connection.pool.recv.thread.activation.threshold";
```

```
public static final String
  PROPERTY_CONNECTION_POOL_RECV_THREAD_CPUIDS
     = "com.mysql.clusterj.connection.pool.recv.thread.cpuids";
public static final String
  PROPERTY_CONNECTION_POOL_SIZE
      = "com.mysql.clusterj.connection.pool.size";
public static final String
  PROPERTY_CONNECTION_RECONNECT_TIMEOUT
      = "com.mysql.clusterj.connection.reconnect.timeout";
public static final String
  PROPERTY_DEFER_CHANGES
      = "com.mysql.clusterj.defer.changes";
public static final String
  PROPERTY_JDBC_DRIVER_NAME
      = "com.mysql.clusterj.jdbc.driver";
public static final String
  PROPERTY_JDBC_PASSWORD
      = "com.mysql.clusterj.jdbc.password";
public static final String
  PROPERTY_JDBC_URL
     = "com.mysql.clusterj.jdbc.url";
public static final String
  PROPERTY_JDBC_USERNAME
     = "com.mysql.clusterj.jdbc.username";
public static final String
  SESSION_FACTORY_SERVICE_CLASS_NAME
      = "com.mysql.clusterj.SessionFactoryService";
public static final String
  SESSION_FACTORY_SERVICE_FILE_NAME
     = "META-INF/services/com.mysql.clusterj.SessionFactoryService";
```

DEFAULT_PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES

The default value of the byte buffer pool sizes property: 256, 10K, 100K, 1M

DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BATCH_SIZE

The default value of the connection autoincrement batch size property

DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_START

The default value of the connection autoincrement start property

DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_STEP

The default value of the connection autoincrement step property

DEFAULT PROPERTY CLUSTER CONNECT DELAY

The default value of the connection delay property

DEFAULT_PROPERTY_CLUSTER_CONNECT_RETRIES

The default value of the connection retries property

DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER

The default value of the connection timeout after property

DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE

The default value of the connection timeout before property

DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM

The default value of the connection timeout mgm property

DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE

The default value of the connection verbose property

DEFAULT_PROPERTY_CLUSTER_DATABASE

The default value of the database property

DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS

The default value of the maximum number of transactions property

DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD

The default value of the receive thread activation threshold

DEFAULT_PROPERTY_CONNECTION_POOL_SIZE

The default value of the connection pool size property

DEFAULT PROPERTY CONNECTION RECONNECT TIMEOUT

Since 7.5.7

The default value of the connection reconnect timeout property. The default means that the automatic reconnection due to network failures is disabled.

ENV_CLUSTERJ_LOGGER_FACTORY_NAME

```
public static final String
ENV_CLUSTERJ_LOGGER_FACTORY_NAME
= "CLUSTERJ_LOGGER_FACTORY";
```

The name of the environment variable to set the logger factory

PROPERTY CLUSTER BYTE BUFFER POOL SIZES

The name of the byte buffer pool sizes property. To disable buffer pooling for blob objects, set the value of this property to "1". With this setting, buffers will be allocated and freed (and cleaned if possible) immediately after being used for blob data transfer.

PROPERTY CLUSTER CONNECT AUTO INCREMENT BATCH SIZE

The name of the connection autoincrement batch size property.

PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_START

The name of the connection autoincrement start property.

PROPERTY CLUSTER CONNECT AUTO INCREMENT STEP

The name of the connection autoincrement step property.

PROPERTY_CLUSTER_CONNECT_DELAY

```
public static final String
    PROPERTY_CLUSTER_CONNECT_DELAY
    = "com.mysql.clusterj.connect.delay";
```

The name of the connection delay property. For details, see Ndb_cluster_connection::connect()

PROPERTY_CLUSTER_CONNECT_RETRIES

```
public static final String
    PROPERTY_CLUSTER_CONNECT_RETRIES
    = "com.mysql.clusterj.connect.retries";
```

The name of the connection retries property. For details, see Ndb cluster connection::connect()

PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER

The name of the connection timeout after property. For details, see Ndb_cluster_connection::wait_until_ready()

PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE

The name of the connection timeout before property. For details, see Ndb_cluster_connection::wait_until_ready()

PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM

```
public static final String
    PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM
    = "com.mysql.clusterj.connect.timeout.mgm";
```

The name of the initial timeout for cluster connection to connect to MGM before connecting to data nodes Ndb_cluster_connection::set_timeout()

PROPERTY CLUSTER CONNECT VERBOSE

```
public static final String
```

```
PROPERTY_CLUSTER_CONNECT_VERBOSE = "com.mysql.clusterj.connect.verbose";
```

The name of the connection verbose property. For details, see Ndb_cluster_connection::connect()

PROPERTY_CLUSTER_CONNECTION_SERVICE

```
public static final String
    PROPERTY_CLUSTER_CONNECTION_SERVICE
    = "com.mysql.clusterj.connection.service";
```

The name of the connection service property

PROPERTY CLUSTER CONNECTSTRING

The name of the connection string property. For details, see Ndb_cluster_connection constructor

PROPERTY CLUSTER DATABASE

The name of the database property. For details, see the catalogName parameter in the Ndb constructor. Ndb constructor

PROPERTY_CLUSTER_MAX_TRANSACTIONS

The name of the maximum number of transactions property. For details, see Ndb::init()

PROPERTY CONNECTION POOL NODEIDS

```
public static final String
    PROPERTY_CONNECTION_POOL_NODEIDS
    = "com.mysql.clusterj.connection.pool.nodeids";
```

The name of the connection pool node ids property. There is no default. This is the list of node ids to force the connections to be assigned to specific node ids. If this property is specified and connection pool size is not the default, the number of node ids of the list must match the connection pool size, or the number of node ids must be 1 and node ids will be assigned to connections starting with the specified node id.

PROPERTY CONNECTION POOL RECV THREAD ACTIVATION THRESHOLD

The receive thread activation threshold for all connections in the connection pool. The default is no activation threshold.

PROPERTY CONNECTION POOL RECV THREAD CPUIDS

```
public static final String
```

```
PROPERTY_CONNECTION_POOL_RECV_THREAD_CPUIDS
= "com.mysql.clusterj.connection.pool.recv.thread.cpuids";
```

The cpu binding of the receive threads for the connections in the connection pool. The default is no cpu binding for receive threads. If this property is specified, the number of cpu ids in the list must be equal to:
a) the connection pool size if the connection pooling is not disabled (i.e. connection pool size > 0) (or) b) 1 if the connection pooling is disabled.

PROPERTY_CONNECTION_POOL_SIZE

The name of the connection pool size property. This is the number of connections to create in the connection pool. The default is 1 (all sessions share the same connection; all requests for a SessionFactory with the same connect string and database will share a single SessionFactory). A setting of 0 disables pooling; each request for a SessionFactory will receive its own unique SessionFactory.

PROPERTY_CONNECTION_RECONNECT_TIMEOUT

```
public static final String
    PROPERTY_CONNECTION_RECONNECT_TIMEOUT
    = "com.mysql.clusterj.connection.reconnect.timeout";
```

Since 7.5.7

The number of seconds to wait for all sessions to be closed when reconnecting a SessionFactory due to network failures. The default, 0, indicates that the automatic reconnection to the cluster due to network failures is disabled. Reconnection can be enabled by using the method SessionFactory.reconnect(int timeout) and specifying a new timeout value.

PROPERTY DEFER CHANGES

The flag for deferred inserts, deletes, and updates

PROPERTY JDBC DRIVER NAME

The name of the jdbc driver

PROPERTY JDBC PASSWORD

```
public static final String
   PROPERTY_JDBC_PASSWORD
   = "com.mysql.clusterj.jdbc.password";
```

The jdbc password

PROPERTY_JDBC_URL

The jdbc url

PROPERTY_JDBC_USERNAME

The jdbc username

SESSION_FACTORY_SERVICE_CLASS_NAME

The name of the session factory service interface

SESSION_FACTORY_SERVICE_FILE_NAME

The name of the files with names of implementation classes for session factory service

4.3.1.13 Dbug

Dbug allows clusterj applications to enable the DBUG functionality in cluster ndbapi library. The dbug state is a control string that consists of flags separated by colons. Flags are:

- · d set the debug flag
- a[,filename] append debug output to the file
- A[,filename] like a[,filename] but flush the output after each operation
- d[,keyword[,keyword...]] enable output from macros with specified keywords
- D[,tenths] delay for specified tenths of a second after each operation
- f[,function[,function...]] limit output to the specified list of functions
- · F mark each output with the file name of the source file
- i mark each output with the process id of the current process
- g[,function[,function...]] profile specified list of functions
- L mark each output with the line number of the source file
- n mark each output with the current function nesting depth
- N mark each output with a sequential number
- o[,filename] overwrite debug output to the file
- O[,filename] like o[,filename] but flush the output after each operation
- p[,pid[,pid...]] limit output to specified list of process ids

- · P mark each output with the process name
- · r reset the indentation level to zero
- t[,depth] limit function nesting to the specified depth
- T mark each output with the current timestamp

For example, the control string to trace calls and output debug information only for "jointx" and overwrite the contents of file "/tmp/dbug/jointx", use "t:d,jointx:o,/tmp/dbug/jointx". The above can be written as ClusterJHelper.newDbug().trace().debug("jointx").output("/tmp/dbug/jointx").set();

Synopsis

```
public interface Dbug {
// Public Methods
 public abstract Dbug append(
   String fileName);
 public abstract Dbug debug(
   String string);
 public abstract Dbug debug(
   String[] strings);
 public abstract Dbug flush();
 public abstract String get();
 public abstract Dbug output(
   String fileName);
 public abstract void pop();
 public abstract void print(
   String keyword,
   String message);
 public abstract void push();
 public abstract void push(
   String state);
 public abstract void set();
 public abstract void set(
   String state);
 public abstract Dbug trace();
```

append(String)

```
public abstract Dbug append(
   String fileName);
```

Specify the file name for debug output (append).

Table 4.26 append(String)

Parameter	Description
fileName	the name of the file

Parameter	Description
return	this

debug(String)

```
public abstract Dbug debug(
   String string);
```

Set the list of debug keywords.

Table 4.27 debug(String)

Parameter	Description
string	the comma separated debug keywords
return	this

debug(String[])

```
public abstract Dbug debug(
   String[] strings);
```

Set the list of debug keywords.

Table 4.28 debug(String[])

Parameter	Description
strings	the debug keywords
return	this

flush()

```
public abstract Dbug flush();
```

Force flush after each output operation.

Table 4.29 flush()

Parameter	Description
return	this

get()

```
public abstract String get();
```

Return the current state.

Table 4.30 get()

Parameter	Description
return	the current state

output(String)

```
public abstract Dbug output(
    String fileName);
```

Specify the file name for debug output (overwrite).

Table 4.31 output(String)

Parameter	Description
fileName	the name of the file
return	this

pop()

```
public abstract void pop();
```

Pop the current state. The new state will be the previously pushed state.

print(String, String)

```
public abstract void print(
   String keyword,
   String message);
```

Print debug message.

push()

```
public abstract void push();
```

Push the current state as defined by the methods.

push(String)

```
public abstract void push(
   String state);
```

Push the current state and set the parameter as the new state.

Table 4.32 push(String)

Parameter	Description
state	the new state

set()

```
public abstract void set();
```

Set the current state as defined by the methods.

set(String)

```
public abstract void set(
   String state);
```

Set the current state from the parameter.

Table 4.33 set(String)

Parameter	Description
state	the new state

trace()

```
public abstract Dbug trace();
```

Set the trace flag.

Table 4.34 trace()

Parameter	Description
return	this

4.3.1.14 DynamicObject

```
public abstract class DynamicObject {
// Public Constructors

public DynamicObject();

// Public Methods

public final ColumnMetadata[] columnMetadata();

public final DynamicObjectDelegate delegate();

public final void delegate(
    DynamicObjectDelegate delegate);

public Boolean found();

public final Object get(
    int columnNumber);

public final void set(
    int columnNumber,
    Object value);

public String table();
}
```

Methods inherited from java.lang.Object: equals, getClass, hashCode, notify, notifyAll, toString, wait

4.3.1.15 DynamicObjectDelegate

```
public interface DynamicObjectDelegate {
// Public Methods

public abstract ColumnMetadata[] columnMetadata();

public abstract Boolean found();

public abstract void found(
   Boolean found);

public abstract Object get(
   int columnNumber);

public abstract void release();

public abstract void set(
   int columnNumber,
   Object value);

public abstract boolean wasReleased();
}
```

4.3.1.16 LockMode

Lock modes for read operations.

- · SHARED: Set a shared lock on rows
- EXCLUSIVE: Set an exclusive lock on rows
- READ_COMMITTED: Set no locks but read the most recent committed values

Synopsis

```
public final class LockMode,
   extends Enum<LockMode> {
   // Public Static Fields

   public static final LockMode
       EXCLUSIVE;

   public static final LockMode
       READ_COMMITTED;

   public static final LockMode
       SHARED;

// Public Static Methods

   public static LockMode valueOf(
       String name);

   public static LockMode[] values();
}
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

4.3.1.17 Query

A Query instance represents a specific query with bound parameters. The instance is created by the method

com.mysql.clusterj.Session.<T>createQuery(com.mysql.clusterj.query.QueryDefinition<T>).

Synopsis

```
public static final String
   SCAN_TYPE_TABLE_SCAN
       = "TABLE_SCAN";
 public static final String
   SCAN_TYPE_UNIQUE_KEY
       = "UNIQUE_KEY";
// Public Methods
 public abstract int deletePersistentAll();
 public abstract Results<E> execute(
   Object parameter);
 public abstract Results<E> execute(
   Object[] parameters);
 public abstract Results<E> execute(
   Map<String, ?> parameters);
 public abstract Map<String, Object> explain();
 public abstract List<E> getResultList();
 public abstract void setLimits(
   long skip,
   long limit);
 public abstract void setOrdering(
   Ordering ordering,
   String[] orderingFields);
 public abstract void setParameter(
   String parameterName,
   Object value);
```

INDEX USED

The query explain index used key

SCAN_TYPE

```
public static final String
    SCAN_TYPE
    = "ScanType";
```

The query explain scan type key

SCAN TYPE INDEX SCAN

The query explain scan type value for index scan

SCAN_TYPE_PRIMARY_KEY

The query explain scan type value for primary key

SCAN_TYPE_TABLE_SCAN

```
public static final String
SCAN_TYPE_TABLE_SCAN
= "TABLE_SCAN";
```

The query explain scan type value for table scan

SCAN_TYPE_UNIQUE_KEY

```
public static final String
SCAN_TYPE_UNIQUE_KEY
= "UNIQUE_KEY";
```

The query explain scan type value for unique key

deletePersistentAll()

```
public abstract int deletePersistentAll();
```

Delete the instances that satisfy the query criteria.

Table 4.35 deletePersistentAll()

Parameter	Description
return	the number of instances deleted

execute(Map<String, ?>)

```
public abstract Results<E> execute(
   Map<String, ?> parameters);
```

Execute the query with one or more named parameters. Parameters are resolved by name.

Table 4.36 execute(Map<String, ?>)

Parameter	Description
parameters	the parameters
return	the result

execute(Object...)

```
public abstract Results<E> execute(
   Object[] parameters);
```

Execute the query with one or more parameters. Parameters are resolved in the order they were declared in the query.

Table 4.37 execute(Object...)

Parameter	Description
parameters	the parameters

Parameter	Description
return	the result

execute(Object)

```
public abstract Results<E> execute(
   Object parameter);
```

Execute the query with exactly one parameter.

Table 4.38 execute(Object)

Parameter	Description
parameter	the parameter
return	the result

explain()

```
public abstract Map<String, Object> explain();
```

Explain how this query will be or was executed. If called before binding all parameters, throws ClusterJUserException. Return a map of key:value pairs that explain how the query will be or was executed. Details can be obtained by calling toString on the value. The following keys are returned:

- ScanType: the type of scan, with values:
 - PRIMARY_KEY: the query used key lookup with the primary key
 - UNIQUE_KEY: the query used key lookup with a unique key
 - INDEX_SCAN: the query used a range scan with a non-unique key
 - TABLE_SCAN: the query used a table scan
- IndexUsed: the name of the index used, if any

Table 4.39 explain()

Parameter	Description
return	the data about the execution of this query

Exceptions

ClusterJUserException if not all parameters are bound

getResultList()

```
public abstract List<E> getResultList();
```

Get the results as a list.

Table 4.40 getResultList()

Parameter	Description
return	the result

Exceptions

ClusterJUserException if not all parameters are bound

ClusterJDatastoreExceptionif an exception is reported by the datastore

setLimits(long, long)

```
public abstract void setLimits(
  long skip,
  long limit);
```

Set limits on results to return. The execution of the query is modified to return only a subset of results. If the filter would normally return 100 instances, skip is set to 50, and limit is set to 40, then the first 50 results that would have been returned are skipped, the next 40 results are returned and the remaining 10 results are ignored.

Skip must be greater than or equal to 0. Limit must be greater than or equal to 0. Limits may not be used with deletePersistentAll.

Table 4.41 setLimits(long, long)

Parameter	Description
skip	the number of results to skip
limit	the number of results to return after skipping; use Long.MAX_VALUE for no limit.

setOrdering(Query.Ordering, String...)

```
public abstract void setOrdering(
   Ordering ordering,
   String[] orderingFields);
```

Set ordering for the results of this query. The execution of the query is modified to use an index previously defined.

- There must be an index defined on the columns mapped to the ordering fields, in the order of the ordering fields.
- There must be no gaps in the ordering fields relative to the index.
- · All ordering fields must be in the index, but not all fields in the index need be in the ordering fields.
- If an "in" predicate is used in the filter on a field in the ordering, it can only be used with the first field.
- If any of these conditions is violated, ClusterJUserException is thrown when the query is executed.

If an "in" predicate is used, each element in the parameter defines a separate range, and ordering is performed within that range. There may be a better (more efficient) index based on the filter, but specifying the ordering will force the query to use an index that contains the ordering fields.

Table 4.42 setOrdering(Query.Ordering, String...)

Parameter	Description
ordering	either Ordering.ASCENDING or Ordering.DESCENDING
orderingFields	the fields to order by

setParameter(String, Object)

```
public abstract void setParameter(
   String parameterName,
   Object value);
```

Set the value of a parameter. If called multiple times for the same parameter, silently replace the value.

Table 4.43 setParameter(String, Object)

Parameter	Description
parameterName	the name of the parameter
value	the value for the parameter

4.3.1.18 Query.Ordering

Ordering

Synopsis

```
public static final class Query.Ordering,
   extends Enum<Ordering> {
   // Public Static Fields

   public static final Ordering
      ASCENDING;

   public static final Ordering
      DESCENDING;

// Public Static Methods

   public static Ordering valueOf(
      String name);

   public static Ordering[] values();
}
```

 $\label{lem:methods} \textbf{Methods inherited from java.lang.} \textbf{Enum:} \ \texttt{compareTo} \ , \ \texttt{equals} \ , \ \texttt{getDeclaringClass} \ , \ \texttt{hashCode} \ , \\ \texttt{name} \ , \ \texttt{ordinal} \ , \ \texttt{toString} \ , \ \texttt{valueOf} \\$

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

4.3.1.19 Results

Results of a query.

Synopsis

```
public interface Results<E>,
   extends Iterable<E> {
   // Public Methods
   public abstract Iterator<E> iterator();
}
```

iterator()

```
public abstract Iterator<E> iterator();
```

Specified by: Method iterator in interface Iterable

Get an iterator over the results of a query.

Table 4.44 iterator()

Parameter	Description
return	the iterator

4.3.1.20 Session

Session is the primary user interface to the cluster. Session extends AutoCloseable so it can be used in the try-with-resources pattern. This pattern allows the application to create a session in the try declaration and regardless of the outcome of the try/catch/finally block, clusterj will clean up and close the session. If the try block exits with an open transaction, the transaction will be rolled back before the session is closed.

Synopsis

```
public interface Session,
  extends AutoCloseable {
// Public Methods
 public abstract void close();
 public abstract Query<T> createQuery(
   QueryDefinition<T> qd);
 public abstract Transaction currentTransaction();
 public abstract void deletePersistent(
   Class<T> cls,
   Object key);
 public abstract void deletePersistent(
   Object instance);
 public abstract int deletePersistentAll(
   Class<T> cls);
 public abstract void deletePersistentAll(
   Iterable<?> instances);
 public abstract T find(
   Class<T> cls,
   Object key);
 public abstract void flush();
 public abstract Boolean found(
   Object instance);
 public abstract QueryBuilder getQueryBuilder();
 public abstract boolean isClosed();
 public abstract T load(
   T instance);
 public abstract T makePersistent(
   T instance);
  public abstract Iterable<?> makePersistentAll(
    Iterable<?> instances);
```

```
public abstract void markModified(
  Object instance,
  String fieldName);
public abstract T newInstance(
 Class<T> cls);
public abstract T newInstance(
  Class<T> cls,
  Object key);
public abstract void persist(
  Object instance);
public abstract T release(
  T obj);
public abstract void remove(
 Object instance);
public abstract T savePersistent(
 T instance);
public abstract Iterable<?> savePersistentAll(
  Iterable<?> instances);
public abstract void setLockMode(
 LockMode lockmode);
public abstract void setPartitionKey(
  Class<?> cls,
  Object key);
public abstract String unloadSchema(
  Class<?> cls);
public abstract void updatePersistent(
  Object instance);
public abstract void updatePersistentAll(
  Iterable<?> instances);
```

close()

```
public abstract void close();
```

Specified by: Method close in interface AutoCloseable

Close this session.

createQuery(QueryDefinition<T>)

```
public abstract Query<T> createQuery(
   QueryDefinition<T> qd);
```

Create a Query from a QueryDefinition.

Table 4.45 createQuery(QueryDefinition<T>)

Parameter	Description
qd	the query definition
return	the query instance

currentTransaction()

```
public abstract Transaction currentTransaction();
```

Get the current com.mysql.clusterj.Transaction.

Table 4.46 currentTransaction()

Parameter	Description
return	the transaction

deletePersistent(Class<T>, Object)

```
public abstract void deletePersistent(
  Class<T> cls,
  Object key);
```

Delete an instance of a class from the database given its primary key. For single-column keys, the key parameter is a wrapper (e.g. Integer). For multi-column keys, the key parameter is an Object[] in which elements correspond to the primary keys in order as defined in the schema.

Table 4.47 deletePersistent(Class<T>, Object)

Parameter	Description
cls	the interface or dynamic class
key	the primary key

deletePersistent(Object)

```
public abstract void deletePersistent(
   Object instance);
```

Delete the instance from the database. Only the id field is used to determine which instance is to be deleted. If the instance does not exist in the database, an exception is thrown.

Table 4.48 deletePersistent(Object)

Parameter	Description
instance	the instance to delete

deletePersistentAll(Class<T>)

```
public abstract int deletePersistentAll(
   Class<T> cls);
```

Delete all instances of this class from the database. No exception is thrown even if there are no instances in the database.

Table 4.49 deletePersistentAll(Class<T>)

Parameter	Description
cls	the interface or dynamic class
return	the number of instances deleted

deletePersistentAll(Iterable<?>)

public abstract void deletePersistentAll(

```
Iterable<?> instances);
```

Delete all parameter instances from the database.

Table 4.50 deletePersistentAll(Iterable<?>)

Parameter	Description
instances	the instances to delete

find(Class<T>, Object)

```
public abstract T find(
  Class<T> cls,
  Object key);
```

Find a specific instance by its primary key. The key must be of the same type as the primary key defined by the table corresponding to the cls parameter. The key parameter is the wrapped version of the primitive type of the key, e.g. Integer for INT key types, Long for BIGINT key types, or String for char and varchar types. For multi-column primary keys, the key parameter is an Object[], each element of which is a component of the primary key. The elements must be in the order of declaration of the columns (not necessarily the order defined in the CONSTRAINT ... PRIMARY KEY clause) of the CREATE TABLE statement.

Table 4.51 find(Class<T>, Object)

Parameter	Description
cls	the interface or dynamic class to find an instance of
key	the key of the instance to find
return	the instance of the interface or dynamic class with the specified key

flush()

```
public abstract void flush();
```

Flush deferred changes to the back end. Inserts, deletes, loads, and updates are sent to the back end.

found(Object)

```
public abstract Boolean found(
   Object instance);
```

Was the row corresponding to this instance found in the database?

Table 4.52 found(Object)

Parameter	Description
instance	the instance corresponding to the row in the database
return	 null if the instance is null or was created via newInstance and never loaded; true if the instance was returned from a find or query or created via newInstance and successfully loaded;
	false if the instance was created via newInstance and not found.

See Also

load(T) , newInstance(java.lang.Class<T>, java.lang.Object)

getQueryBuilder()

```
public abstract QueryBuilder getQueryBuilder();
```

Get a QueryBuilder.

Table 4.53 getQueryBuilder()

Parameter	Description
return	the query builder

isClosed()

```
public abstract boolean isClosed();
```

Is this session closed?

Table 4.54 isClosed()

Parameter	Description
return	true if the session is closed

load(T)

```
public abstract T load(
   T instance);
```

Load the instance from the database into memory. Loading is asynchronous and will be executed when an operation requiring database access is executed: find, flush, or query. The instance must have been returned from find or query; or created via session.newlnstance and its primary key initialized.

Table 4.55 load(T)

Parameter	Description
instance	the instance to load
return	the instance

See Also found(java.lang.Object)

makePersistent(T)

```
public abstract T makePersistent(
   T instance);
```

Insert the instance into the database. If the instance already exists in the database, an exception is thrown.

Table 4.56 makePersistent(T)

Parameter	Description
instance	the instance to insert
return	the instance

See Also savePersistent(T)

makePersistentAll(Iterable<?>)

```
public abstract Iterable<?> makePersistentAll(
```

```
Iterable<?> instances);
```

Insert the instances into the database.

Table 4.57 makePersistentAll(Iterable<?>)

Parameter	Description
instances	the instances to insert.
return	the instances

markModified(Object, String)

```
public abstract void markModified(
   Object instance,
   String fieldName);
```

Mark the field in the object as modified so it is flushed.

Table 4.58 markModified(Object, String)

Parameter	Description
instance	the persistent instance
fieldName	the field to mark as modified

newInstance(Class<T>)

```
public abstract T newInstance(
   Class<T> cls);
```

Create an instance of an interface or dynamic class that maps to a table.

Table 4.59 newInstance(Class<T>)

Parameter	Description
cls	the interface for which to create an instance
return	an instance that implements the interface

newInstance(Class<T>, Object)

```
public abstract T newInstance(
  Class<T> cls,
  Object key);
```

Create an instance of an interface or dynamic class that maps to a table and set the primary key of the new instance. The new instance can be used to create, delete, or update a record in the database.

Table 4.60 newInstance(Class<T>, Object)

Parameter	Description
cls	the interface for which to create an instance
return	an instance that implements the interface

persist(Object)

```
public abstract void persist(
   Object instance);
```

Insert the instance into the database. This method has identical semantics to makePersistent.

Table 4.61 persist(Object)

Parameter	Description
instance	the instance to insert

release(T)

```
public abstract T release(
   T obj);
```

Release resources associated with an instance. The instance must be a domain object obtained via session.newInstance(T.class), find(T.class), or query; or Iterable, or array T[]. Resources released can include direct buffers used to hold instance data. Released resources may be returned to a pool.

Table 4.62 release(T)

Parameter	Description
obj	a domain object of type T, an Iterable, or array T[]
return	the input parameter

Exceptions

ClusterJUserException

if the instance is not a domain object T, Iterable, or array T[], or if the object is used after calling this method.

remove(Object)

```
public abstract void remove(
   Object instance);
```

Delete the instance from the database. This method has identical semantics to deletePersistent.

Table 4.63 remove(Object)

Parameter	Description
instance	the instance to delete

savePersistent(T)

```
public abstract T savePersistent(
    T instance);
```

Save the instance in the database without checking for existence. The id field is used to determine which instance is to be saved. If the instance exists in the database it will be updated. If the instance does not exist, it will be created.

Table 4.64 savePersistent(T)

Parameter	Description
instance	the instance to update

savePersistentAll(Iterable<?>)

```
public abstract Iterable<?> savePersistentAll(
```

```
Iterable<?> instances);
```

Update all parameter instances in the database.

Table 4.65 savePersistentAll(Iterable<?>)

Parameter	Description
instances	the instances to update

setLockMode(LockMode)

```
public abstract void setLockMode(
  LockMode lockmode);
```

Set the lock mode for read operations. This will take effect immediately and will remain in effect until this session is closed or this method is called again.

Table 4.66 setLockMode(LockMode)

Parameter	Description
lockmode	the LockMode

setPartitionKey(Class<?>, Object)

```
public abstract void setPartitionKey(
  Class<?> cls,
  Object key);
```

Set the partition key for the next transaction. The key must be of the same type as the primary key defined by the table corresponding to the cls parameter. The key parameter is the wrapped version of the primitive type of the key, e.g. Integer for INT key types, Long for BIGINT key types, or String for char and varchar types. For multi-column primary keys, the key parameter is an Object[], each element of which is a component of the primary key. The elements must be in the order of declaration of the columns (not necessarily the order defined in the CONSTRAINT ... PRIMARY KEY clause) of the CREATE TABLE statement.

Table 4.67 setPartitionKey(Class<?>, Object)

Parameter	Description
key	the primary key of the mapped table

Exceptions

ClusterJUserException if a transaction is enlisted

ClusterJUserException if a partition key is null

ClusterJUserException if called twice in the same transaction

ClusterJUserException if a partition key is the wrong type

unloadSchema(Class<?>)

```
public abstract String unloadSchema(
  Class<?> cls);
```

Unload the schema definition for a class. This must be done after the schema definition has changed in the database due to an alter table command. The next time the class is used the schema will be reloaded.

Table 4.68 unloadSchema(Class<?>)

Parameter	Description
cls	the class for which the schema is unloaded
return	the name of the schema that was unloaded

updatePersistent(Object)

```
public abstract void updatePersistent(
   Object instance);
```

Update the instance in the database without necessarily retrieving it. The id field is used to determine which instance is to be updated. If the instance does not exist in the database, an exception is thrown. This method cannot be used to change the primary key.

Table 4.69 updatePersistent(Object)

Parameter	Description
instance	the instance to update

updatePersistentAll(Iterable<?>)

```
public abstract void updatePersistentAll(
   Iterable<?> instances);
```

Update all parameter instances in the database.

Table 4.70 updatePersistentAll(Iterable<?>)

Parameter	Description
instances	the instances to update

4.3.1.21 SessionFactory

SessionFactory represents a cluster.

```
public interface SessionFactory {
// Public Methods

public abstract void close();

public abstract State currentState();

public abstract List<Integer> getConnectionPoolSessionCounts();

public abstract int getRecvThreadActivationThreshold();

public abstract short[] getRecvThreadCPUids();

public abstract Session getSession();

public abstract Session getSession(
    Map properties);

public abstract void reconnect();

public abstract void reconnect(
    int timeout);
```

```
public abstract void setRecvThreadActivationThreshold(
   int threshold);

public abstract void setRecvThreadCPUids(
   short[] cpuids);
}
```

close()

```
public abstract void close();
```

Close this session factory. Release all resources. Set the current state to Closed. When closed, calls to getSession will throw ClusterJUserException.

currentState()

```
public abstract State currentState();
```

Get the current state of this session factory.

Since 7.5.7

See Also com.mysql.clusterj.SessionFactory.State

getConnectionPoolSessionCounts()

```
public abstract List<Integer> getConnectionPoolSessionCounts();
```

Get a list containing the number of open sessions for each connection in the connection pool.

Since 7.3.14, 7.4.12, 7.5.2

getRecvThreadActivationThreshold()

```
public abstract int getRecvThreadActivationThreshold();
```

Get the receive thread activation threshold for all connections in the connection pool. 16 or higher means that receive threads are never used as receivers. 0 means that the receive thread is always active, and that retains poll rights for its own exclusive use, effectively blocking all user threads from becoming receivers. In such cases care should be taken to ensure that the receive thread does not compete with the user thread for CPU resources; it is preferable for it to be locked to a CPU for its own exclusive use. The default is 8.

Since 7.5.7

getRecvThreadCPUids()

```
public abstract short[] getRecvThreadCPUids();
```

Get receive thread bindings to cpus for all connections in the connection pool. If a receive thread is not bound to a cpu, the corresponding value will be -1.

Since 7.5.7

getSession()

```
public abstract Session getSession();
```

Create a Session to use with the cluster, using all the properties of the SessionFactory.

Table 4.71 getSession()

Parameter	Description
return	the session

getSession(Map)

```
public abstract Session getSession(
   Map properties);
```

Create a session to use with the cluster, overriding some properties. Properties PROPERTY_CLUSTER_CONNECTSTRING, PROPERTY_CLUSTER_DATABASE, and PROPERTY_CLUSTER_MAX_TRANSACTIONS may not be overridden.

Table 4.72 getSession(Map)

Parameter	Description
properties	overriding some properties for this session
return	the session

reconnect()

```
public abstract void reconnect();
```

Reconnect this session factory using the most recent timeout value specified. The timeout may have been specified in the original session factory properties or may have been changed by an application call to reconnect(int timeout).

See Also reconnect(int)

Since 7.5.7

reconnect(int)

```
public abstract void reconnect(
  int timeout);
```

Disconnect and reconnect this session factory using the specified timeout value and change the saved timeout value. This is a heavyweight method and should be used rarely. It is intended for cases where the process in which clusterj is running has lost connectivity to the cluster and is not able to function normally. Reconnection is done in several phases. First, the session factory is set to state Reconnecting and a reconnect thread is started to manage the reconnection procedure. In the Reconnecting state, the getSession methods throw ClusterJUserException and the connection pool is quiesced until all sessions have closed. If sessions fail to close normally after timeout seconds, the sessions are forced to close. Next, all connections in the connection pool are closed, which frees their connection slots in the cluster. Finally, the connection pool is recreated using the original connection pool properties and the state is set to Open. The reconnection procedure is asynchronous. To observe the progress of the procedure, use the methods currentState and getConnectionPoolSessionCounts. If the timeout value is non-zero, automatic reconnection will be done by the clusterj implementation upon recognizing that a network failure has occurred. If the timeout value is 0, automatic reconnection is disabled. If the current state of this session factory is Reconnecting, this method silently does nothing.

Table 4.73 reconnect(int)

Parameter	Description
timeout	the timeout value in seconds; 0 to disable automatic reconnection

Since 7.5.7

setRecvThreadActivationThreshold(int)

```
public abstract void setRecvThreadActivationThreshold(
  int threshold);
```

Set the receive thread activation threshold for all connections in the connection pool. 16 or higher means that receive threads are never used as receivers. 0 means that the receive thread is always active, and that retains poll rights for its own exclusive use, effectively blocking all user threads from becoming receivers. In such cases care should be taken to ensure that the receive thread does not compete with the user thread for CPU resources; it is preferable for it to be locked to a CPU for its own exclusive use. The default is 8.

Exceptions

ClusterJUserException if the value is negative

ClusterJFatalInternalExcepttheomethod fails due to some internal reason.

Since 7.5.7

setRecvThreadCPUids(short[])

```
public abstract void setRecvThreadCPUids(
   short[] cpuids);
```

Bind receive threads to cpuids for all connections in the connection pool. Specify -1 to unset receive thread cpu binding for a connection. The cpuid must be between 0 and the number of cpus in the machine.

Exceptions

ClusterJUserException

if the cpuid is illegal or if the number of elements in cpuids is not equal to the number of connections in the connection pool.

ClusterJFatalInternalExcept the binding fails due to some internal reason.

Since 7.5.7

4.3.1.22 SessionFactory.State

State of this session factory

```
public static final class SessionFactory.State,
  extends Enum<State> {
  // Public Static Fields

  public static final State
    Closed;

  public static final State
    Open;

  public static final State
    Reconnecting;

// Public Static Methods

  public static State valueOf(
    String name);
```

```
public static State[] values();
}
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

Since 7.5.7

4.3.1.23 SessionFactoryService

This interface defines the service to create a SessionFactory from a Map<String, String> of properties.

Synopsis

```
public interface SessionFactoryService {
// Public Methods

public abstract SessionFactory getSessionFactory(
    Map<String, String> props);
}
```

getSessionFactory(Map<String, String>)

```
public abstract SessionFactory getSessionFactory(
   Map<String, String> props);
```

Create or get a session factory. If a session factory with the same value for PROPERTY_CLUSTER_CONNECTSTRING has already been created in the VM, the existing factory is returned, regardless of whether other properties of the factory are the same as specified in the Map.

Table 4.74 getSessionFactory(Map<String, String>)

Parameter	Description
props	the properties for the session factory, in which the keys are defined in Constants and the values describe the environment
return	the session factory

See Also com.mysql.clusterj.Constants

4.3.1.24 Transaction

Transaction represents a user transaction active in the cluster.

```
public interface Transaction {
// Public Methods

public abstract void begin();

public abstract void commit();

public abstract boolean getRollbackOnly();

public abstract boolean isActive();
```

```
public abstract void rollback();
public abstract void setRollbackOnly();
}
```

begin()

```
public abstract void begin();
```

Begin a transaction.

commit()

```
public abstract void commit();
```

Commit a transaction.

getRollbackOnly()

```
public abstract boolean getRollbackOnly();
```

Has this transaction been marked for rollback only?

Table 4.75 getRollbackOnly()

Parameter	Description
return	true if the transaction has been marked for rollback only

isActive()

```
public abstract boolean isActive();
```

Is there a transaction currently active?

Table 4.76 isActive()

Parameter	Description
return	true if a transaction is active

rollback()

```
public abstract void rollback();
```

Roll back a transaction.

setRollbackOnly()

```
public abstract void setRollbackOnly();
```

Mark this transaction as rollback only. After this method is called, commit() will roll back the transaction and throw an exception; rollback() will roll back the transaction and not throw an exception.

4.3.2 com.mysql.clusterj.annotation

This package provides annotations for domain object model interfaces mapped to database tables.

4.3.2.1 Column

Annotation for a column in the database.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.FIELD, java.lang.annotation.ElementType.METHOD}) @Retention(value)
public String
   name;

public String
   allowsNull;

public String
   defaultValue;
}
```

allowsNull

Whether the column allows null values to be inserted. This overrides the database definition and requires that the application provide non-null values for the database column.

Table 4.77 allowsNull

Parameter	Description
return	whether the column allows null values to be inserted

defaultValue

Default value for this column.

Table 4.78 defaultValue

Parameter	Description
return	the default value for this column

name

Name of the column.

Table 4.79 name

Parameter	Description
return	the name of the column

4.3.2.2 Columns

Annotation for a group of columns. This annotation is used for multi-column structures such as indexes and keys.

```
@Target(value={java.lang.annotation.ElementType.FIELD, java.lang.annotation.ElementType.METHOD, java.lang.anno
public Column[]
  value;
}
```

value

The columns annotation information.

Table 4.80 value

Parameter	Description
return	the columns

4.3.2.3 Extension

Annotation for a non-standard extension.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.TYPE, java.lang.annotation.ElementType.FIELD, java.lang.an
public String
  vendorName;

public String
  key;

public String
  value;
}
```

key

The key for the extension (required).

Table 4.81 key

Parameter	Description
return	the key

value

The value for the extension (required).

Table 4.82 value

Parameter	Description
return	the value

vendorName

Vendor that the extension applies to (required to make the key unique).

Table 4.83 vendorName

Parameter	Description
return	the vendor

4.3.2.4 Extensions

Annotation for a group of extensions.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.TYPE, java.lang.annotation.ElementType.FIELD, java.lang.annota
public Extension[]
  value;
}
```

value

The extensions.

Table 4.84 value

Parameter	Description
return	the extensions

4.3.2.5 Index

Annotation for a database index.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.TYPE, java.lang.annotation.ElementType.FIELD, java.lang.annota
public String
   name ;

public String
   unique ;

public Column[]
   columns ;
}
```

columns

Columns that compose this index.

Table 4.85 columns

Parameter	Description
return	columns that compose this index

name

Name of the index

Table 4.86 name

Parameter	Description
return	the name of the index

unique

Whether this index is unique

Table 4.87 unique

Parameter	Description
return	whether this index is unique

4.3.2.6 Indices

Annotation for a group of indices. This is used on a class where there are multiple indices defined.

Synopsis

```
@Target(value=java.lang.annotation.ElementType.TYPE) @Retention(value=java.lang.annotation.RetentionPolicy
   public Index[]
   value;
}
```

value

The indices.

Table 4.88 value

Parameter	Description
return	The indices

4.3.2.7 Lob

Annotation for a Large Object (lob). This annotation can be used with byte[] and InputStream types for binary columns; and with String and InputStream types for character columns.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.FIELD, java.lang.annotation.ElementType.METHOD}) @Retention.
```

4.3.2.8 NotPersistent

Annotation to specify that the member is not persistent. If used, this is the only annotation allowed on a member.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.FIELD, java.lang.annotation.ElementType.METHOD}) @Retention}
```

4.3.2.9 NullValue

Enumeration of the "null-value" behavior values. This behavior is specified in the @Persistent annotation.

```
public final class NullValue,
  extends Enum<NullValue> {
  // Public Static Fields
  public static final NullValue
```

```
public static final NullValue
    EXCEPTION;

public static final NullValue
    NONE;

// Public Static Methods

public static NullValue valueOf(
    String name);

public static NullValue[] values();
}
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

4.3.2.10 PartitionKey

Annotation on a class or member to define the partition key. If annotating a class or interface, either a single column or multiple columns can be specified. If annotating a member, neither column nor columns should be specified.

Synopsis

```
@Target(value={java.lang.annotation.ElementType.TYPE, java.lang.annotation.ElementType.FIELD, java.lang.annotation.Elemen
```

column

Name of the column to use for the partition key

Table 4.89 column

Parameter	Description
return	the name of the column to use for the partition key

columns

The column(s) for the partition key

Table 4.90 columns

Parameter	Description
return	the column(s) for the partition key

4.3.2.11 PersistenceCapable

Annotation for whether the class or interface is persistence-capable.

Synopsis

```
@Target(value=java.lang.annotation.ElementType.TYPE) @Retention(value=java.lang.annotation.RetentionPolicy
public String
  table ;

public String
  database ;

public String
  schema ;
}
```

4.3.2.12 PersistenceModifier

Enumeration of the persistence-modifier values for a member.

Synopsis

```
public final class PersistenceModifier,
    extends Enum<PersistenceModifier> {
// Public Static Fields

public static final PersistenceModifier
    NONE;

public static final PersistenceModifier
    PERSISTENT;

public static final PersistenceModifier
    UNSPECIFIED;

// Public Static Methods

public static PersistenceModifier valueOf(
    String name);

public static PersistenceModifier[] values();
}
```

Methods inherited from java.lang.Enum: compareTo, equals, getDeclaringClass, hashCode, name, ordinal, toString, valueOf

Methods inherited from java.lang.Object: getClass, notify, notifyAll, wait

4.3.2.13 Persistent

Annotation for defining the persistence of a member.

```
@Target(value={java.lang.annotation.ElementType.FIELD, java.lang.annotation.ElementType.METHOD}) @Retention
public NullValue
   nullValue;
public String
```

```
primaryKey ;

public String
  column ;

public Extension[]
  extensions ;
}
```

column

Column name where the values are stored for this member.

Table 4.91 column

Parameter	Description
return	the name of the column

extensions

Non-standard extensions for this member.

Table 4.92 extensions

Parameter	Description
return	the non-standard extensions

nullValue

Behavior when this member contains a null value.

Table 4.93 nullValue

Parameter	Description
return	the behavior when this member contains a null value

primaryKey

Whether this member is part of the primary key for the table. This is equivalent to specifying @PrimaryKey as a separate annotation on the member.

Table 4.94 primaryKey

Parameter	Description
return	whether this member is part of the primary key

4.3.2.14 PrimaryKey

Annotation on a member to define it as a primary key member of a class or persistent interface.

```
@Target(value={java.lang.annotation.ElementType.TYPE, java.lang.annotation.ElementType.FIELD, java.lang.annotation
public String
   name;
```

```
public String
  column;

public Column[]
  columns;
}
```

column

Name of the column to use for the primary key

Table 4.95 column

Parameter	Description
return	the name of the column to use for the primary key

columns

The column(s) for the primary key

Table 4.96 columns

Parameter	Description
return	the column(s) for the primary key

name

Name of the primary key constraint

Table 4.97 name

Parameter	Description
return	the name of the primary key constraint

4.3.2.15 Projection

Annotation on a type to define it as a projection of a table. Only the columns mapped to persistent fields/methods will be used when performing operations on the table.

Synopsis

@Target(value=java.lang.annotation.ElementType.TYPE) @Retention(value=java.lang.annotation.RetentionPolicy
}

4.3.3 com.mysql.clusterj.query

Provides interfaces for building queries for ClusterJ.

4.3.3.1 Predicate

Used to combine multiple predicates with boolean operations.

```
public interface Predicate {
```

```
// Public Methods

public abstract Predicate and(
   Predicate predicate);

public abstract Predicate not();

public abstract Predicate or(
   Predicate predicate);
}
```

and(Predicate)

```
public abstract Predicate and(
    Predicate predicate);
```

Combine this Predicate with another, using the "and" semantic.

Table 4.98 and(Predicate)

Parameter	Description
predicate	the other predicate
return	a new Predicate combining both Predicates

not()

```
public abstract Predicate not();
```

Negate this Predicate.

Table 4.99 not()

Parameter	Description
return	this predicate

or(Predicate)

```
public abstract Predicate or(
   Predicate predicate);
```

Combine this Predicate with another, using the "or" semantic.

Table 4.100 or(Predicate)

Parameter	Description
predicate	the other predicate
return	a new Predicate combining both Predicates

4.3.3.2 PredicateOperand

PredicateOperand represents a column or parameter that can be compared to another

```
public interface PredicateOperand {
```

```
// Public Methods
 public abstract Predicate between(
   PredicateOperand lower,
   PredicateOperand upper);
 public abstract Predicate equal(
   PredicateOperand other);
 public abstract Predicate greaterEqual(
   PredicateOperand other);
 public abstract Predicate greaterThan(
   PredicateOperand other);
 public abstract Predicate in(
   PredicateOperand other);
 public abstract Predicate isNotNull();
 public abstract Predicate isNull();
 public abstract Predicate lessEqual(
   PredicateOperand other);
 public abstract Predicate lessThan(
   PredicateOperand other);
 public abstract Predicate like(
   PredicateOperand other);
```

between(PredicateOperand, PredicateOperand)

```
public abstract Predicate between(
  PredicateOperand lower,
  PredicateOperand upper);
```

Return a Predicate representing comparing this to another using "between" semantics.

Table 4.101 between(PredicateOperand, PredicateOperand)

Parameter	Description
lower	another PredicateOperand
upper	another PredicateOperand
return	a new Predicate

equal(PredicateOperand)

```
public abstract Predicate equal(
   PredicateOperand other);
```

Return a Predicate representing comparing this to another using "equal to" semantics.

Table 4.102 equal(PredicateOperand)

Parameter	Description
other	the other PredicateOperand
return	a new Predicate

greaterEqual(PredicateOperand)

```
public abstract Predicate greaterEqual(
   PredicateOperand other);
```

Return a Predicate representing comparing this to another using "greater than or equal to" semantics.

Table 4.103 greaterEqual(PredicateOperand)

Parameter	Description
other	the other PredicateOperand
return	a new Predicate

greaterThan(PredicateOperand)

```
public abstract Predicate greaterThan(
    PredicateOperand other);
```

Return a Predicate representing comparing this to another using "greater than" semantics.

Table 4.104 greaterThan(PredicateOperand)

Parameter	Description
other	the other PredicateOperand
return	a new Predicate

in(PredicateOperand)

```
public abstract Predicate in(
   PredicateOperand other);
```

Return a Predicate representing comparing this to a collection of values using "in" semantics.

Table 4.105 in(PredicateOperand)

Parameter	Description
other	another PredicateOperand
return	a new Predicate

isNotNull()

```
public abstract Predicate isNotNull();
```

Return a Predicate representing comparing this to not null.

Table 4.106 isNotNull()

Parameter	Description
return	a new Predicate

isNull()

```
public abstract Predicate isNull();
```

Return a Predicate representing comparing this to null.

Table 4.107 isNull()

Parameter	Description
return	a new Predicate

lessEqual(PredicateOperand)

```
public abstract Predicate lessEqual(
   PredicateOperand other);
```

Return a Predicate representing comparing this to another using "less than or equal to" semantics.

Table 4.108 lessEqual(PredicateOperand)

Parameter	Description
other	the other PredicateOperand
return	a new Predicate

lessThan(PredicateOperand)

```
public abstract Predicate lessThan(
    PredicateOperand other);
```

Return a Predicate representing comparing this to another using "less than" semantics.

Table 4.109 lessThan(PredicateOperand)

Parameter	Description
other	the other PredicateOperand
return	a new Predicate

like(PredicateOperand)

```
public abstract Predicate like(
   PredicateOperand other);
```

Return a Predicate representing comparing this to another using "like" semantics.

Table 4.110 like(PredicateOperand)

Parameter	Description
other	another PredicateOperand
return	a new Predicate

4.3.3.3 QueryBuilder

QueryBuilder represents a factory for queries.

```
public interface QueryBuilder {
// Public Methods

public abstract QueryDomainType<T> createQueryDefinition(
    Class<T> cls);
}
```

See Also

getQueryBuilder()

createQueryDefinition(Class<T>)

```
public abstract QueryDomainType<T> createQueryDefinition(
   Class<T> cls);
```

Create a QueryDefinition to define queries.

Table 4.111 createQueryDefinition(Class<T>)

Parameter	Description
cls	the class of the type to be queried
return	the QueryDomainType to define the query

4.3.3.4 QueryDefinition

QueryDefinition allows users to define queries.

Synopsis

```
public interface QueryDefinition<E> {
// Public Methods

public abstract Predicate not(
   Predicate predicate);

public abstract PredicateOperand param(
   String parameterName);

public abstract QueryDefinition<E> where(
   Predicate predicate);
}
```

not(Predicate)

```
public abstract Predicate not(
   Predicate predicate);
```

Convenience method to negate a predicate.

Table 4.112 not(Predicate)

Parameter	Description
predicate	the predicate to negate
return	the inverted predicate

param(String)

```
public abstract PredicateOperand param(
   String parameterName);
```

Specify a parameter for the query.

Table 4.113 param(String)

Parameter	Description
parameterName	the name of the parameter

Parameter	Description
return	the PredicateOperand representing the parameter

where(Predicate)

```
public abstract QueryDefinition<E> where(
    Predicate predicate);
```

Specify the predicate to satisfy the query.

Table 4.114 where(Predicate)

Parameter	Description
predicate	the Predicate
return	this query definition

4.3.3.5 QueryDomainType

QueryDomainType represents the domain type of a query. The domain type validates property names that are used to filter results.

Synopsis

```
public interface QueryDomainType<E>,
   extends QueryDefinition<E> {
   // Public Methods

   public abstract PredicateOperand get(
       String propertyName);

   public abstract Class<E> getType();
}
```

get(String)

```
public abstract PredicateOperand get(
   String propertyName);
```

Get a PredicateOperand representing a property of the domain type.

Table 4.115 get(String)

Parameter	Description	
propertyName	the name of the property	
return	a representation the value of the property	

getType()

```
public abstract Class<E> getType();
```

Get the domain type of the query.

Table 4.116 getType()

Parameter	Description
return	the domain type of the query

4.3.4 Constant field values

4.3.4.1 com.mysql.clusterj.*

Table 4.117 com.mysql.clusterj.*

PROPERTY_CLUSTER_CONNECT_AUTO_INCRE_MEDITRB_ATCHILS_BET_CONNECT_AUTO_INCRE_AUTO_INCRE_MEDITRB_ATCHILS_BET_CONNECT_AUTO_INCRE_AUTO_	Name	Description	
DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_START DEFAULT_PROPERTY_CLUSTER_CONNECT_DE_AY DEFAULT_PROPERTY_CLUSTER_CONNECT_DE_AY DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CONNECTION_POOL_REC_ATTIMEOUT_BEFORE DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_SECONNEC_TIMEOUT ENV_CLUSTER_LOGGER_FACTORY_NAME "CLUSTER_LOGGER_FACTORY" PROPERTY_CLUSTER_CONNECT_SERVICE "com.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECT_SERVICE "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMONT_GASGAULSERS_Connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Edom.mysql.clusters_c	DEFAULT_PROPERTY_CLUSTER_BYTE_BUFFEF	₹ <u>"₽\$\$</u> \$\$\t <u>0</u> \$420E\$\$02400, 1048576"	
DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_STEP DEFAULT_PROPERTY_CLUSTER_CONNECT_DELSAY DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_B DEFAULT_PROPERTY_CLUSTER_CONNECT_NAME "CLUSTER_LOGGER_FACTORY" PROPERTY_CLUSTER_CONNECT_STRING "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_BASERICUSTERj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_BASERICUSTERj.connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_BASERICUSTERj.connect.autoincrement.increment" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER MEMIT_BASERICUSTERj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER MEMIT_MASKERICUSTERJ.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGVtcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGVtcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGVtcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGVtcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CUSTER_DATABAS	DEFAULT_PROPERTY_CLUSTER_CONNECT_AU	TOO_INCREMENT_BATCH_SIZE	
DEFAULT_PROPERTY_CLUSTER_CONNECT_DELSAY DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE 'test' DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECSY_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_B DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_B DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_B DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_B DEFAULT_PROPERTY_CONNECTION_SERVICE 'com.mysql.clusterj.byte.buffer.pool.sizes' PROPERTY_CLUSTER_CONNECTSRING 'com.mysql.clusterj.connection.service' PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVICE 'com.mysql.clusterj.connect.autoincrement.offset' PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVISE 'connect.autoincrement.offset' PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVISE (connect.autoincrement.offset') PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVISE (connect.autoincrement.offset') PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVISE (connect.autoincrement.offset') PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RESIGNED SERVISE (connect.autoincrement.offset') PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER SERVISE (connect.timeout.after') PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER SERVISE (connect.timeout.after') PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE mysql.clusterj.connect.timeout.mgm' PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE mysql.clusterj.connect.timeout.mgm' PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE mysql.clusterj.connect.timeout.mgm' PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE mysql.clusterj.connect.timeout.mgm' PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE mysql.clusterj.connect.verbose 'com.mysql.clusterj.connect.verbose 'com.mysql.clusterj.connect.verbose 'com.mysql.clusterj.connect.verbose 'com.mysql.clusterj.connect.verbose 'com.mysql.clusterj.co	DEFAULT_PROPERTY_CLUSTER_CONNECT_AU	TO_INCREMENT_START	
DEFAULT_PROPERTY_CLUSTER_CONNECT_RETRIES DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECW_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_RECONNECT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME "CLUSTERJ_LOGGER_FACTORY" PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZESm.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECTSTRING "com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.increment "PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.increment "PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.increment "PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEONT_BASICUSTERJ_connect.autoincrement.increment "PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EARM.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EARM.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFTOASE.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFTOASE.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNtcon.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "co	DEFAULT_PROPERTY_CLUSTER_CONNECT_AU	TO_INCREMENT_STEP	
DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MEMOUT_MEMOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZED DEFAULT_PROPERTY_CONNECTION_POOL_SIZED DEFAULT_PROPERTY_CONNECTION_POOL_SIZED DEFAULT_PROPERTY_CONNECTION_RECONNEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME "CLUSTERJ_LOGGER_FACTORY" PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZESM.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_MS_TCUSTECT_CONNECT.auto_Increment_Increment. PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_MS_TCUSTER_CONNECT.auto_Increment.orgent.increment.increment. PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_MS_TCUSTER_CONNECT.entert.increment. PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.autoincrement.increment." PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.trites" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_MS_M.mysql.clusterj.connect.trites" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFOREM.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFOREM.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG_Mom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.torlose" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connect.torlose.nool.nodeids" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_COMRUTIONSITIONSITIONSITIONSITI	DEFAULT_PROPERTY_CLUSTER_CONNECT_DE		
DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMBOUT_BEFORE DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMBOUTO_MGM DEFAULT_PROPERTY_CLUSTER_CATABASE "test" DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_PRODLEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME "CLUSTERJ_LOGGER_FACTORY" PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BASTCHUSSET_connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BASTCHUSSET_connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BASTCHUST_connect.autoincrement.increment" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BASTCHUST_connect.autoincrement.increment." PROPERTY_CLUSTER_CONNECT_BELAY "com.mysql.clusterj.connect.autoincrement.increment." PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.trites" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EAM.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EAM.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.torlose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.torlose" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_CANTIVATIONS_TIPME_TIMEOUT.THREAD_CANTIVATIONS_TIPME_TIMEOUT.Thread	DEFAULT_PROPERTY_CLUSTER_CONNECT_RE	TARIES	
DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMBODION_MGM DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE "test" DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZE! DEFAULT_PROPERTY_CONNECTION_RECONNEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME "CLUSTERJ_LOGGER_FACTORY" PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES.m.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connectstring" PROPERTY_CLUSTER_CONNECTSTRING "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_SYSTEMSUsterj.connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_SYSTEMSUsterj.connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_SYSTEMSUsterj.connect.delay" PROPERTY_CLUSTER_CONNECT_BLAY "com.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERS.m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERS.m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERS.m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERS.m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERS.m.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGWtom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGWtom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.ton.pool.nodeids" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.connect.on.pool.nodeids" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connect.on.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_CONT.Mysql.clusterj.connect.on.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_CONT.Mysql.clusterj.connect.on.pool.nodeids"	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIME	POUT_AFTER	
DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE DEFAULT_PROPERTY_CLUSTER_DATABASE DEFAULT_PROPERTY_CLUSTER_MAX_TRANSA¢TIONS DEFAULT_PROPERTY_CONNECTION_POOL_RE¢_0_Y_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_1 DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_21 DEFAULT_PROPERTY_CONNECTION_RECONNE_OT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZ_6_6	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIME	/BOUT_BEFORE	
DEFAULT_PROPERTY_CLUSTER_DATABASE DEFAULT_PROPERTY_CONNECTION_POOL_RECX/_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_BI DEFAULT_PROPERTY_CONNECTION_POOL_SIZ_BI DEFAULT_PROPERTY_CONNECTION_RECONNE_OT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZ_BOM_mysql.clusterj.byte.buffer.pool.sizes* PROPERTY_CLUSTER_CONNECTION_SERVICE PROPERTY_CLUSTER_CONNECTSTRING PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_ISA_TICHUSMET_CONNECT.autoincrement.batchsize* PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_ISA_TICHUSMET_CONNECT.autoincrement.offset* PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_ISA_TICHUSMET_CONNECT.autoincrement.increment* PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEMIT_ISA_TICHUSMET_CONNECT.autoincrement.increment* PROPERTY_CLUSTER_CONNECT_DELAY PROPERTY_CLUSTER_CONNECT_TETRIES PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EMB.m.mysql.clusterj.connect.timeout.after* PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT_EMB.m.mysql.clusterj.connect.timeout.mgm* PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG_Woom.mysql.clusterj.connect.timeout.mgm* PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG_Woom.mysql.clusterj.connect.timeout.mgm* PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG_Woom.mysql.clusterj.connect.timeout.mgm* PROPERTY_CLUSTER_CONNECT_VERBOSE PROPERTY_CLUSTER_DATABASE PROPERTY_CLUSTER_DATABASE PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_CAME.TIMEAD	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIME	/BONDO_MGM	
DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS DEFAULT_PROPERTY_CONNECTION_POOL_RECX_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_RECONNECT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME	DEFAULT_PROPERTY_CLUSTER_CONNECT_VE	ROBOSE	
DEFAULT_PROPERTY_CONNECTION_POOL_REC2/_THREAD_ACTIVATION_THRESHOLD DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_RECONNEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME ENV_CLUSTERJ_LOGGER_FACTORY_NAME PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZE6m.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE Com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECT_STRING Com.mysql.clusterj.connectstring PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTOCHI_SET_connect.autoincrement.batchsize PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTOCHI_SET_connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTOCHI_SET_connect.delay PROPERTY_CLUSTER_CONNECT_DELAY Com.mysql.clusterj.connect.delay PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERm.mysql.clusterj.connect.timeout.after PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERm.mysql.clusterj.connect.timeout.after PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERm.mysql.clusterj.connect.timeout.before PROPERTY_CLUSTER_CONNECT_TIMEOUT_BETORE.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGNVcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE Com.mysql.clusterj.connect.verbose PROPERTY_CLUSTER_DATABASE Com.mysql.clusterj.database PROPERTY_CLUSTER_MAX_TRANSACTIONS PROPERTY_CONNECTION_POOL_NODEIDS Com.mysql.clusterj.connection.pool.nodeids' PROPERTY_CONNECTION_POOL_RECV_THREADCOMP.idelatification.pool.recv.thread.activation.thr	DEFAULT_PROPERTY_CLUSTER_DATABASE	"test"	
DEFAULT_PROPERTY_CONNECTION_POOL_SIZE DEFAULT_PROPERTY_CONNECTION_RECONNEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME "CLUSTERJ_LOGGER_FACTORY" PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZE6m.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECTSTRING "com.mysql.clusterj.connectstring" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTCHILSSET_CONNECT.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTCHILSSET_CONNECT.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_BASTCHILSSET_CONNECT.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.delay" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERm.mysql.clusterj.connect.trires" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERm.mysql.clusterj.connect.trimeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BETORE.mysql.clusterj.connect.trimeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MENVorm.mysql.clusterj.connect.trimeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MENVorm.mysql.clusterj.connect.trimeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_ORNERIMSRl.clusterj.connection.pool.recv.thread.activation.thr PROPERTY_CONNECTION_POOL_RECV_THREAD_ORNERIMSRl.clusterj.connection.pool.recv.thread.cpuids"	DEFAULT_PROPERTY_CLUSTER_MAX_TRANSAC	CATIONS	
DEFAULT_PROPERTY_CONNECTION_RECONNEOT_TIMEOUT ENV_CLUSTERJ_LOGGER_FACTORY_NAME	DEFAULT_PROPERTY_CONNECTION_POOL_REG	08/_THREAD_ACTIVATION_THRESHOLD	
ENV_CLUSTERJ_LOGGER_FACTORY_NAME PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZESm.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECTSTRING "com.mysql.clusterj.connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INSEQRATIONSECT_AUTO_INCREMEDIT_INSEQRATIONSECT_AUTO_INCREMEDIT_INSEQRATIONSECT_AUTO_INCREMEDIT_INSEQRATIONSECT_AUTO_INCREMEDIT	DEFAULT_PROPERTY_CONNECTION_POOL_SIZ	<u> </u>	
PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZESm.mysql.clusterj.byte.buffer.pool.sizes" PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECTSTRING "com.mysql.clusterj.connectstring" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RDJEGROINECT.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RDJEGRICUSTErj.connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_RDJEGRICUSTErj.connect.autoincrement.increment" PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.delay" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER "com.mysql.clusterj.connect.retries" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER "m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MEDIT_MSDJ.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MSDJ.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.max.transactions" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD.com.mysql.clusterj.connection.pool.recv.thread.activ.ation.thr	DEFAULT_PROPERTY_CONNECTION_RECONNE	<u>COT_TIMEOUT</u>	
PROPERTY_CLUSTER_CONNECTION_SERVICE "com.mysql.clusterj.connection.service" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INS_SERVICES "com.mysql.clusterj.connectstring" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INS_SERVICES "connect.autoincrement.batchsize" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INS_SERVICES "connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INS_SERVICES "connect.autoincrement.increment" PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.delay" PROPERTY_CLUSTER_CONNECT_RETRIES "com.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTERM.mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE "com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_cont.timeout.pool.recv.thread.activation.thr PROPERTY_CONNECTION_POOL_RECV_THREAD_cont.timeout.pool.recv.thread.cpuids"	ENV_CLUSTERJ_LOGGER_FACTORY_NAME	"CLUSTERJ_LOGGER_FACTORY"	
PROPERTY_CLUSTER_CONNECT_AUTO_INCRE_MEDITRB_ATCHILS_BET_CONNECT_AUTO_INCRE_M	PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SI	ZE6m.mysql.clusterj.byte.buffer.pool.sizes"	
PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INS_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INS_INS_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INS_INS_INS_INS_INSTANCTIONS CONNECT.AUTO_INCREMEDIT_INS_INS_INS_INS_INS_INS_INS_INS_INS_INS	PROPERTY_CLUSTER_CONNECTION_SERVICE	"com.mysql.clusterj.connection.service"	
PROPERTY_CLUSTER_CONNECT_AUTO_INCRE_MEMIT_INSTERNEDIES_connect.autoincrement.offset" PROPERTY_CLUSTER_CONNECT_AUTO_INCRE_MEMIT_INSTERNEDIES_connect.autoincrement.increment" PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.delay" PROPERTY_CLUSTER_CONNECT_RETRIES "com.mysql.clusterj.connect.retries" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BE_TORMS.mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG wom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREAD_cont.timeout.startiplexiconnection.pool.recv.thread.activation.thread.ectivation.thread.com.ectivation.pool.recv.thread.activation.thread.com.ectivation.pool.recv.thread.com.ectivation.ectivation.pool.recv.thread.com.ectivation.ectivation.pool.recv.thread.com.ectivation.ectivation.ectivation.pool.recv.thread.com.ectivation.ectiv	PROPERTY_CLUSTER_CONNECTSTRING	"com.mysql.clusterj.connectstring"	
PROPERTY_CLUSTER_CONNECT_AUTO_INCREMEDIT_INSTERP:clusterj.connect.autoincrement.increment PROPERTY_CLUSTER_CONNECT_DELAY "com.mysql.clusterj.connect.delay" PROPERTY_CLUSTER_CONNECT_RETRIES "com.mysql.clusterj.connect.retries" PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFT Exam.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFTORM.mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGN/com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADcont.timeout.mgm" PROPERTY_CONNECTION_POOL_RECV_THREADcont.timeout.mgm" PROPERTY_CONNECTION_POOL_RECV_THREADcont.timeout.mgm "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.connect.timeout.ngm" "com.mysql.clusterj.connect.timeout.ngm" "com.mysql.clusterj.connect.timeout.ngm" PROPERTY_CONNECTION_POOL_RECV_THREADcont.timeout.mgm" "com.mysql.clusterj.connect.timeout.ngm" "com.mysql.clusterj.connect.timeout.ngm			
### PROPERTY_CLUSTER_CONNECT_DELAY ### com.mysql.clusterj.connect.delay #### property_cluster_connect.retries ### com.mysql.clusterj.connect.retries ### property_cluster_connect.timeout.after ### property_cluster_connect.timeout.after ### property_cluster_connect.timeout.after ### property_cluster_connect.timeout.mg ### property_cluster_connect.timeout.mg ### property_cluster_connect.timeout.mg ### property_cluster_connect.verbose ### com.mysql.clusterj.connect.verbose ### property_cluster_database ### ### com.mysql.clusterj.database ### property_cluster_max_transactions ### property_connection_pool_nodeids ### property_connection_pool_nodeids ### property_connection_pool_recv.thread.activation.thr ### property_connection_pool_recv.thread.activation.thr ### property_connection_pool_recv.thread.cpuids #### property_connection_pool_recv.thread.cpuids ####################################	PROPERTY_CLUSTER_CONNECT_AUTO_INCRE	MEDNT.nS/TS4RdTusterj.connect.autoincrement.offset"	
PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER m.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORD mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORD mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGWcom.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADcont.timlyscil.clusterj.connection.pool.recv.thread.activ.ation.thr PROPERTY_CONNECTION_POOL_RECV_THREADcont.timlyscil.clusterj.connection.pool.recv.thread.activ.ation.thr	PROPERTY_CLUSTER_CONNECT_AUTO_INCRE	MEDNT.nS/SQP:clusterj.connect.autoincrement.increment	
PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTENsm.mysql.clusterj.connect.timeout.after" PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFONDS.mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG\(\frac{1}{2}\)com.mysql.clusterj.connect.timeout.mgm\(\frac{1}{2}\) PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose\(\frac{1}{2}\) PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database\(\frac{1}{2}\) PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions\(\frac{1}{2}\) PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids\(\frac{1}{2}\) PROPERTY_CONNECTION_POOL_RECV_THREA\(\frac{1}{2}\)CONTINESTICNSE	PROPERTY_CLUSTER_CONNECT_DELAY	"com.mysql.clusterj.connect.delay"	
PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORME.mysql.clusterj.connect.timeout.before" PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG\"com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconomic Timeout.before" "com.mysql.clusterj.connect.timeout.before" "com.mysql.clusterj.connect.timeout.before" "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.connect.timeout.mgm" "com.mysql.clusterj.database" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconomic Timeout.before" "com.mysql.clusterj.connection.pool.nodeids" "com.mysql.clusterj.connection.pool.nodeids" "com.mysql.clusterj.connection.pool.nodeids" "com.mysql.clusterj.connection.pool.nodeids" "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconomic Timeout.mgm"	PROPERTY_CLUSTER_CONNECT_RETRIES	"com.mysql.clusterj.connect.retries"	
PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG\(\form\) com.mysql.clusterj.connect.timeout.mgm" PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADcontribysql.clusterj.connection.pool.recv.thread.activation.thr PROPERTY_CONNECTION_POOL_RECV_THREADcontribysql.clusterj.connection.pool.recv.thread.cpuids"	PROPERTY_CLUSTER_CONNECT_TIMEOUT_AF	TERm.mysql.clusterj.connect.timeout.after"	
PROPERTY_CLUSTER_CONNECT_VERBOSE "com.mysql.clusterj.connect.verbose" PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconc.tinlysql.clusterj.connection.pool.recv.thread.activation.thr PROPERTY_CONNECTION_POOL_RECV_THREADconc.tinlysql.clusterj.connection.pool.recv.thread.activation.thr	PROPERTY_CLUSTER_CONNECT_TIMEOUT_BE	"Oate.mysql.clusterj.connect.timeout.before"	
### PROPERTY_CLUSTER_DATABASE "com.mysql.clusterj.database" PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconomic and the property of the prop	PROPERTY_CLUSTER_CONNECT_TIMEOUT_MG	Wcom.mysql.clusterj.connect.timeout.mgm"	
PROPERTY_CLUSTER_MAX_TRANSACTIONS "com.mysql.clusterj.max.transactions" PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADconc.Thly会可以处理时间处理的地位的。pool.recv.thread.activation.thr PROPERTY_CONNECTION_POOL_RECV_THREADconc.Thly会可以处理时间是最近的。pool.recv.thread.activation.thr	PROPERTY_CLUSTER_CONNECT_VERBOSE	"com.mysql.clusterj.connect.verbose"	
PROPERTY_CONNECTION_POOL_NODEIDS "com.mysql.clusterj.connection.pool.nodeids" PROPERTY_CONNECTION_POOL_RECV_THREADomnormal Control of the Co	PROPERTY_CLUSTER_DATABASE	"com.mysql.clusterj.database"	
PROPERTY_CONNECTION_POOL_RECV_THREAD CONTINUE AT LOUISIE HIS BOOK CONNECTION_POOL_RECV_THREAD CONTINUE AT LOUISIE LOUISIE LOUIS CONNECTION_POOL_RECV_THREAD CONTINUE AT LOUISIE LOUISI	PROPERTY_CLUSTER_MAX_TRANSACTIONS	"com.mysql.clusterj.max.transactions"	
PROPERTY_CONNECTION_POOL_RECV_THREADon Plus Connection.pool.recv.thread.cpuids"	PROPERTY_CONNECTION_POOL_NODEIDS	"com.mysql.clusterj.connection.pool.nodeids"	
	PROPERTY_CONNECTION_POOL_RECV_THREA	៶ <u>Dcaro.Trilysa[IQuistatiji]BarសielQuidD</u> .pool.recv.thread.activa	tion.thresh
PROPERTY_CONNECTION_POOL_SIZE	PROPERTY_CONNECTION_POOL_RECV_THREA	വുട്ടു പ്രവാദ്യം വാധിച്ച് I.clusterj.connection.pool.recv.thread.cpuids	s"
	PROPERTY_CONNECTION_POOL_SIZE	"com.mysql.clusterj.connection.pool.size"	

Name	Description
PROPERTY_CONNECTION_RECONNECT_TIMEO	Uāom.mysql.clusterj.connection.reconnect.timeout"
PROPERTY_DEFER_CHANGES	"com.mysql.clusterj.defer.changes"
PROPERTY_JDBC_DRIVER_NAME	"com.mysql.clusterj.jdbc.driver"
PROPERTY_JDBC_PASSWORD	"com.mysql.clusterj.jdbc.password"
PROPERTY_JDBC_URL	"com.mysql.clusterj.jdbc.url"
PROPERTY_JDBC_USERNAME	"com.mysql.clusterj.jdbc.username"
SESSION_FACTORY_SERVICE_CLASS_NAME	"com.mysql.clusterj.SessionFactoryService"
SESSION_FACTORY_SERVICE_FILE_NAME	"META-INF/services/ com.mysql.clusterj.SessionFactoryService"

Table 4.118 com.mysql.clusterj.*

Name	Description	
INDEX_USED	"IndexUsed"	
SCAN_TYPE	"ScanType"	
SCAN_TYPE_INDEX_SCAN	"INDEX_SCAN"	
SCAN_TYPE_PRIMARY_KEY	"PRIMARY_KEY"	
SCAN_TYPE_TABLE_SCAN	"TABLE_SCAN"	
SCAN_TYPE_UNIQUE_KEY	"UNIQUE_KEY"	

4.4 MySQL NDB Cluster Connector for Java: Limitations and Known Issues

This section discusses the limitations and known issues in the MySQL NDB Cluster Connector for Java APIs.

Known issues in ClusterJ:

- *Joins:* With ClusterJ, queries are limited to single tables. This is not a problem with JPA or JDBC, both of which support joins.
- Database views: Because MySQL database views do not use the NDB storage engine, ClusterJ
 applications cannot "see" views, and thus cannot access them. To work with views using Java, you
 should use JPA or JDBC.
- Relations and inheritance: ClusterJ does not support relations or inheritance. Tables are mapped one-to-one onto domain classes, and only single-table operations are supported. NDB tables for NDB Cluster 7.3 and later support foreign keys, and foreign key constraints are enforced when using ClusterJ for inserts, updates, and deletes.
- TIMESTAMP: Currently, ClusterJ does not support the TIMESTAMP data type for a primary key field.

Known issues in JDBC and Connector/J: For information about limitations and known issues with JDBC and Connector/J, see JDBC API Implementation Notes, and Troubleshooting Connector/J Applications.

Known issues in NDB Cluster: For information about limitations and other known issues with NDB Cluster, see Known Limitations of NDB Cluster.

Chapter 5 MySQL NoSQL Connector for JavaScript

Table of Contents

5.1 MySQL NoSQL Connector for JavaScript Overview	735
5.2 Installing the JavaScript Connector	736
5.3 Connector for JavaScript API Documentation	737
5.3.1 Batch	737
5.3.2 Context	737
5.3.3 Converter	740
5.3.4 Errors	
5.3.5 Mynode	
5.3.6 Session	743
5.3.7 SessionFactory	744
5.3.8 TableMapping and FieldMapping	
5.3.9 TableMetadata	746
5.3.10 Transaction	747
5.4 Using the MySQL JavaScript Connector: Examples	748
5.4.1 Requirements for the Examples	
5.4.2 Example: Finding Rows	752
5.4.3 Inserting Rows	
5.4.4 Deleting Rows	756

This section provides information about the MySQL NoSQL Connector for JavaScript, a set of Node.js adapters for NDB Cluster and MySQL Server available beginning with NDB 7.3.1, which make it possible to write JavaScript applications for Node.js using MySQL data.



Important

Beginning with NDB 8.0.22, Node.js support is included only in NDB 8.0.

Node.js support was removed from previous versions of NDB Cluster as of the following releases:

NDB 7.3 series: NDB 7.3.31

• NDB 7.4 series: NDB 7.4.30

NDB 7.5 series: NDB 7.5.20

• NDB 7.6 series: NDB 7.6.16

5.1 MySQL NoSQL Connector for JavaScript Overview

This connector differs in a number of key respects from most other MySQL Connectors and APIs. The interface is asynchronous, following the built-in Node.js event model. In addition, it employs a domain object model for data storage. Applications retrieve data in the form of fully-instantiated objects, rather than as rows and columns.

The MySQL Node.js adapter includes 2 drivers. The ndb driver accesses the NDB storage engine directly, using the NDB API (see Chapter 2, *The NDB API*). No MySQL Server is required for the ndb driver. The mysql driver uses a MySQL Server for its data source, and depends on the node-mysql Node.js

module from https://github.com/felixge/node-mysql/. Regardless of the driver in use, no SQL statements are required; when using the Connector for JavaScript, Node.js applications employ data objects for all requests made to the database.

5.2 Installing the JavaScript Connector

This section covers basic installation and setup of the MySQL JavaScript Connector and its prerequites. The Connector requires both Node.js and NDB Cluster to be installed first; you can install these in either order. In addition, the mysql-js adapter requires the node-mysql driver. Building the Connector also requires that your system have a working C++ compiler such as gcc or Microsoft Visual Studio.

To install all of the prerequisites for the JavaScript Connector, including node-mysql, you should perform the following steps:

 Node.js. If you do not already have Node.js installed on your system, you can obtain it from http:// nodejs.org/download/. In addition to source code, prebuilt binaries and installers are available for a number of platforms. Many Linux distributions also have Node.js in their repositories (you may need to add an alternative repository in your package manager).

NDB uses node-gyp for compiling add-on Node.js modules; for more information about this tool, see https://npmjs.org/package/node-gyp.

Beginning with NDB 8.0.22, NDBCLUSTER requires Node.js version 12.18.3 or later.

Regardless of the method by which you obtain Node.js, keep in mind that the architecture of the version you install must match that of the NDB Cluster binaries you intend to use; you cannot, for example, install the JavaScript Connector using 64-bit Node.js and 32-bit NDB Cluster. If you do not know the architecture of your existing Node.js installation, you can determine this by checking the value of global.process.arch.

2. **NDB Cluster.** If NDB Cluster, including all header and library files, is not already installed on the system, install it (see NDB Cluster Installation).

As mentioned previously, you must make sure that the architecture (32-bit or 64-bit) is the same for both NDB Cluster and Node.js. You can check the architecture of an existing NDB Cluster installation in the output of ndb_mgm -V.

3. **node-mysql driver.** The mysql-js adapter also requires a working installation of the node-mysql driver from https://github.com/felixge/node-mysql/. You can install the driver using the Node.js npm install command; see the project website for the recommended version and package identifier.

Once the requirements just listed are met, you can find the files needed to install the MySQL Connector for JavaScript in share/nodejs in the NDB Cluster installation directory. (If you installed NDB Cluster as an RPM, this is /usr/share/mysql/nodejs.) To use the Node.js npm tool to perform a "best-guess" installation without any user intervention, change to the share/nodejs directory, then use npm as shown here:

```
shell> npm install .
```

The final period (.) character is required. Note that you must run this command in share/node.js in the NDB Cluster installation directory.

You can test your installation using the supplied test program. This requires a running NDB Cluster, including a MySQL Server with a database named test. The mysql client executable must be in the path.

To run the test suite, change to the test directory, then execute command shown here:

```
shell> node driver
```

By default, all servers are run on the local machine using default ports; this can be changed by editing the file test/test_connection.js, which is generated by running the test suite. If this file is not already present (see Bug #16967624), you can copy share/nodejs/test/lib/test_connection_js to the test directory for this purpose.

If you istalled NDB Cluster to a nondefault location, you may need to export the LD_LIBRARY_PATH to enable the test suite. The test suite also requires that the test database be available on the MySQL server.

NDB 7.3.1 also provided an alternative build script in share/node.js/setup; this was removed in NDB 7.3.2 and later NDB Cluster 7.3 releases.

5.3 Connector for JavaScript API Documentation

This section contains prototype descriptions and other information for the MySQL Connector for JavaScript.

5.3.1 Batch

This class represents a batch of operations.

Batch extends Context

```
execute(Function(Object error) callback);
```

Execute this batch. When a batch is executed, all operations are executed; the callback for each operation is called when that operation is executed (operations are not performed in any particular order). The execute() function's callback is also called.

A batch is executed in the context of the session's current state: this is autocommit if a transaction has not been started; this also includes the default lock mode and the partition key.

```
clear();
```

Clear this batch without affecting the transaction state. After being cleared, the batch is still valid, but all operations previously defined are removed; this restores the batch to a clean state.

The callbacks for any operations that are defined for this batch are called with an error indicating that the batch has been cleared.

This function requires no arguments.

```
getSession();
```

Get the session from which this batch was created.

This function requires no arguments.

5.3.2 Context

Context is the supertype of Session and Batch. It contains functions that are executed immediately if called from a session, or when the batch is executed.

The Mynode implementation does have any concept of a user and does not define any such property.

```
find(Function constructor, Object keys, Function(Object error, Object instance[, ...]) callback[, ...]);
find(String tableName, Object keys, Function(Object error, Object instance[, ...]) callback[, ...]);
```

Find a specific instance based on a primary key or unique key value.

You can use either of two versions of this function. In the first version, the *constructor* parameter is the constructor function of a mapped domain object. Alternatively, you can use the *tableName* instead, in the second variant of the function.

For both versions of find(), the *keys* may be of any type. A key must uniquely identify a single row in the database. If *keys* is a simple type (number or string), then the parameter type must be the same type as or compatible with the primary key type of the mapped object. Otherwise, properties are taken from the parameter and matched against property names in the mapping. Primary key properties are used if all are present, and other properties ignored. If *keys* cannot be used identify the primary key, property names corresponding to unique key columns are used instead. If no complete primary or unique key properties are found, an error is reported. The returned object is loaded based on the mapping and the current values in the database.

For multi-column primary or unique keys, all key fields must be set.

```
load(Object instance, Function(Object error) callback);
```

Load a specific instance by matching its primary or unique key with a database row, without creating a new domain object. (This is unlike find(), which creates a new, mapped domain object.)

The *instance* must have its primary or unique key value or values set. The mapped values in the object are loaded based on the current values in the database. Unmapped properties in the object are not changed.

Primary key properties are used if all are present, and all other properties are ignored; otherwise, property names corresponding to unique key columns are used. If no complete primary or unique key properties can be found, an error is reported.

The *callback* function is called with the parameters provided when the operation has completed. The *error* is the Node.js *Error* object; see Section 5.3.4, "Errors", for more information.

```
persist(Object instance, Function(Object error) callback);
persist(Function constructor, Object values, Function(Object error) callback);
persist(String tableName, Object values, Function(Object error) callback);
```

Insert an instance into the database, unless the instance already exists in the database, in which case an exception is reported to a *callback* function. Autogenerated values are present in the instance when the *callback* is executed.

The role of an instance to be persisted can be fulfilled in any of three ways: by an instance object; by a constructor, with parameters, for a mapped domain object; or by table name and values to be inserted.

In all three cases, the *callback* function is called with the parameters provided, if any, when the operation has completed. The *error* is the Node.js *Error* object; see Section 5.3.4, "Errors", for more information.

```
remove(Object instance, Function(Object error) callback);
```

```
remove(Function constructor, Object keys, Function(Object error) callback);
remove(String tableName, Object keys, Function(Object error) callback);
```

Delete an instance of a class from the database by a primary or unique key.

There are three versions of <code>remove()</code>; these allow you to delete an instance by referring to the <code>instance</code> object, to a <code>constructor</code> function, or by name of the table. The <code>instance</code> object must contain key values that uniquely identify a single row in the database. Otherwise, if the <code>keys</code> supplied with the function constructor or table name is a simple type (<code>Number</code> or <code>String</code>), then the parameter type must be of either the same type as or a type compatible with the primary key type of the mapped object. If <code>keys</code> is not a simple type, properties are taken from the parameter and matched against property names in the mapping. Primary key properties are used if all are present, and other properties ignored. If <code>keys</code> does not identify the primary key, property names corresponding to unique key columnsare used instead. If no complete primary or unique key properties are found, an error is reported to the <code>callback</code>.

All three versions of remove() call the *callback* function with the parameters provided, if any, when the operation is complete. The *error* object is a Node.js *Error*; see Section 5.3.4, "Errors", for error codes.

```
update(Object instance, Function(Object error) callback);
update(Function constructor, keys, values, Function(Object error) callback);
update(String tableName, keys, values, Function(Object error) callback);
```

Update an instance in the database with the supplied *values* without retrieving it. The primary key is used to determine which instance is updated. If the instance does not exist in the database, an exception is reported in the *callback*.

As with the methods previously shown for persisting instances in and removing them from the database, update() exists in three variations, which allow you to use the *instance* as an object, an object constructor with keys, or by tableName and keys.

Unique key fields of the *keys* object determine which *instance* is to be updated. The *values* object provides values to be updated. If the *keys* object contains all fields corresponding to the primary key, the primary key identifies the instance. If not, unique keys are chosen is a nondeterministic manner.



Note

update() cannot be used to change the primary key.

```
save(Object instance, Function(Object error) callback);
save(Function constructor, Object values, Function(Object error) callback);
save(String tableName, Object values, Function(Object error) callback);
```

Save an instance in the database without checking for its existence. If the instance already exists, it is updated (as if you had used update()); otherwise, it is created (as if persist() had been used). The instance id property is used to determine which instance should be saved. As with update(), persist(), and remove(), this method allows you to specify the instance using an object, object constructor, or table name.

All three versions of the save() method call the *callback* function with any parameters provided when the operation has been completed. The *error* is a Node.js *Error* object; see Section 5.3.4, "Errors", for error codes and messages.

```
Boolean isBatch()
```

Context also exposes an isBatch() instance method, which returns true if this Context is a Batch, and false if it is a Session. isBatch() takes no arguments.

5.3.3 Converter

Converter classes convert between JavaScript types and MySQL types. If the user supplies a JavaScript converter, it used to read and write to the database.

Converters have several purposes, including the following:

- To convert between MySQL DECIMAL types and a user's preferred JavaScript fixed-precision utility library
- To convert between MySQL BIGINT types and a user's preferred JavaScript big number utility library
- To serialize arbitrary application objects into character or binary columns

The ndb back end also uses converters to support SET and ENUM columns. (The mysql back end does not use these.)

A Converter class has the interface defined here:

```
function Converter() {}:

Converter.prototype = {
  "toDB" : function(obj) { },
  "fromDB" : function(val) { }
};
```

The Converter *must* implement the following two functions:

- 1. toDB(obj): Convert an application object obj into a form that can be stored in the database.
- 2. fromDB(val): Convert a value val read from the database into application object format.

Each function returns the result of the conversion.

Converter invocations are chained in the following ways:

- When writing to the database, first the registered FieldConverter, if any, is invoked. Later, any registered TypeConverter is invoked.
- When reading from the database, first the registered TypeConverter, if any, is invoked. Later, any registered FieldConverter is invoked.

5.3.4 Errors

The Errors object contains the error codes and message exposed by the MySQL Node.js adapters.

```
var Errors;
Errors = {
   /* Standard-defined classes, SQL-99 */
   "02000" : "No Data",
```

```
// connection errors
"08000" : "Connection error",
"08001" : "Unable to connect to server",
"08004" : "Connection refused",
// data errors
"22000" : "Data error",
"22001" : "String too long",
"22003" : "Numeric value out of range",
"22008" : "Invalid datetime",
// Constraint violations
// 23000 includes both duplicate primary key and duplicate unique key
"23000" : "Integrity Constraint Violation",
// misc. errors
"25000" : "Invalid Transaction State",
"2C000": "Invalid character set name",
"42S02" : "Table not found",
"IM001" : "Driver does not support this function",
/* Implementation-defined classes (NDB) */
"NDB00" : "Refer to ndb_error for details"
```

5.3.5 Mynode

This class is used to generate and obtain information about sessions (Session objects). To create an instance, use the Node.js require() function with the driver name, like this:

```
var nosql = require("mysql-js");
```

ConnectionProperties can be used to retrieve or set the connection properties for a given session. You can obtain a complete set of of default connection properties for a given adapter using the ConnectionProperties constructor, shown here, with the name of the adapter (a string) used as the value of nameOrProperties:

```
ConnectionProperties(nameOrProperties);
```

You can also create your own ConnectionProperties object by supplying a list of property names and values to a new ConnectionProperties object in place of the adapter name. Then you can use this object to set the connection properties for a new session, as shown here:

```
var NdbConnectionProperties = {
  "implementation" : "ndb",
  "ndb_connectstring" : "localhost:1186",
  "database" : "test",
  "mysql_user"
                     : "root",
  "ndb_connect_retries" : 4,
  "ndb_connect_delay" : 5,
  "ndb_connect_verbose" : 0,
  "linger_on_close_msec": 500,
  "use_ndb_async_api" : false,
 "ndb_session_pool_min" : 4,
  "ndb_session_pool_max" : 100,
var sharePath = '/usr/local/mysql/share/nodejs';
                                                     // path to share/nodejs
var nosql = require(sharePath);
```

```
var dbProperties = nosql.ConnectionProperties(NdbConnectionProperties);
```

It is also possible to obtain an object with the adapter's default connection properties, after which you can update a selected number of these properties, then use the modified object to set connection properties for the session, as shown here:

The ConnectionProperties object includes the following properties:

- implementation: For Node.js applications using NDB Cluster, this is always "ndb".
- ndb_connectstring: NDB Cluster connection string used to connect to the management server.
- database: Name of the MySQL database to use.
- mysql_user: MySQL user name.
- ndb_connect_retries: Number of times to retry a failed connection before timing out; use a number less than 0 for this to keep trying the connection without ever stopping.
- ndb connect delay: Interval in seconds between connection retries.
- ndb_connect_verbose: 1 or 0; 1 enables extra console output during connection.
- linger_on_close_msec: When a client closes a DBConnectionPool, the underlying connection is kept open for this many milliseconds in case another client tries to reuse it.
- use_ndb_async_api: If true, some operations are executed using asynchronous calls for improved concurrency. If false, the number of operations in transit is limited to one per worker thread.
- ndb_session_pool_min: Minimum number of DBSession objects per NdbConnectionPool.
- ndb_session_pool_max: Maximum number of DBSession objects per NdbConnectionPool.

Each NdbConnectionPool maintains a pool of DBSession objects, along with their underlying Ndb objects. This parameter, together with ndb_session_pool_min, sets guidelines for the size of that pool.

The TableMapping constructor is also visible as a top-level function. You can get the mapping either by name, or by using an existing mapping:

```
TableMapping(tableName);
TableMapping(tableMapping);
```

```
openSession(properties, mappings, Function(err, Session) callback);
```

Connect to the data source and get a Session in the *callback* function. This is equivalent to calling connect() (see later in this section), and then calling getSession() on the SessionFactory that is returned in the callback function.



Note

Executing this method could result in connections being made to many other nodes on the network, waiting for them to become ready, and making multiple requests to them. You should avoid opening new sessions unnecessarily for this reason.

The implementation member of the *properties* object determines the implementation of the Session.

If *mappings* is undefined, null, or an empty array, no mappings are loaded or validated. In this case, any required mappings are loaded and validated when needed during execution. If *mappings* contains a string or a constructor function, the metadata for the table (or mapped table) is loaded from the database and validated against the requirements of the mapping.

Multiple tables and constructors may be passed to openSession() as elements in an array.

```
connect(properties, mappings, Function(err, SessionFactory) callback);
```

Connect to the data source to obtain a SessionFactory in the *callback* function. In order to obtain a Session, you must then call <code>getSession()</code> on this SessionFactory, whose implementation is determined by the implementation member of the *properties* object.

If *mappings* is undefined, null, or an empty array, no mappings are loaded or validated. In this case, any required mappings are loaded and validated when needed. If *mappings* contains a string or a constructor function, the metadata for the table (or mapped table) is loaded from the database and validated against the requirements of the mapping.

Multiple tables and constructors may be passed as elements in an array.

```
Array getOpenSessionFactories()
```

Get an array of all the SessionFactory objects that have been created by this module.



Note

The following functions are part of the public API but are not intended for application use. They form part of the contract between Mynode and SessionFactory.

- Connection()
- getConnectionKey()
- getConnection()
- newConnection()
- deleteFactory()

5.3.6 Session

A session is the main user access path to the database. The Session class models such a session.

```
Session extends Context

getMapping(Object parameter, Function(Object err, Object mapping) callback);
```

Get the mappings for a table or class.

The *parameter* may be a table name, a mapped constructor function, or a domain object. This function returns a fully resolved TableMapping object.

```
Batch createBatch()
```

Creates a new, empty batch for collecting multiple operations to be executed together. In an application, you can invoke this function similarly to what is shown here:

```
var nosql = require("mysql-js");
var myBatch = nosql.createBatch();
```

```
Array listBatches():
```

Return an array whose elements consist of all current batches belonging to this session.

```
Transaction currentTransaction();
```

Get the current Transaction.

```
void close(Function(Object error) callback);
```

Close this session. Must be called when the session is no longer needed.

```
boolean isClosed();
```

Returns true if this session is closed.

```
void setLockMode(String lockMode);
```

Set the lock mode for read operations. This takes effect immediately and remains in effect until the session is closed or this method is called again. <code>lockMode</code> must be one of <code>'EXCLUSIVE'</code>, <code>'SHARED'</code>, OR <code>'NONE'</code>.

```
Array listTables(databaseName, callback);
```

List all tables in database databaseName.

```
TableMetadata getTableMetadata(String databaseName, String tableName, callback);
```

Fetch metadata for table tableName in database databaseName.

5.3.7 SessionFactory

This class is used to generate and manage sessions. A Session provides a context for database transactions and operations. Each independent user should have its own session.

```
openSession(Object mappings, Function(Object error, Session session) callback);
```

Open a database session object. Table *mappings* are validated at the beginning of the session. Resources required for sessions are allocated in advance; if those resources are not available, the method returns an error in the callback.

```
Array getOpenSessions();
```

Get all open sessions that have been created by this SessionFactory.

```
close(Function(Error err));
```

Close the connection to the database. This ensures proper disconnection. The function passed in is called when the close operation is complete.

5.3.8 TableMapping and FieldMapping

A TableMapping describes the mapping of a domain object in the application to a table stored in the database. A *default* table mapping is one which maps each column in a table to a field of the same name.

```
TableMapping = {
String table : "" ,
String database : "" ,
boolean mapAllColumns : true,
Array fields : null
};
```

The table and data members are the names of the table and database, respectively. mapAllColumns, if true, creates a default FieldMapping for all columns not listed in fields, such that that all columns not explicitly mapped are given a default mapping to a field of the same name. fields holds an array of FieldMapping objects; this can also be a single FieldMapping.

A FieldMapping describes a single field in a domain object. There is no public constructor for this object; you can create a FieldMapping using TableMapping.mapField(), or you can use FieldMapping literals can be used directly in the TableMapping constructor.

```
FieldMapping = {
   String fieldName : "" ,
   String columnName : "" ,
   Boolean persistent : true,
   Converter converter : null
};
```

fieldName and columnName are the names of the field and the column where this field are stored, respectively, in the domain object. If persistent is true (the default), the field is stored in the database. converter specifies a Converter class, if any, to use with this field (defaults to null). };

The TableMapping constructor can take either the name of a table (possibly qualified with the database name) or a TableMapping literal.

```
TableMapping mapField(String fieldName, [String columnName], [Converter converter], [Boolean persistent])
```

Create a field mapping for a named field of a mapped object. The only mandatory parmeter is *fieldName*, which provides the name a field in a JavaScript application object. The remaining parameters are optional, and may appear in any order. The cyrrent TableMapping object is returned.

columnName specifies the name of the database column that maps to this object field. If omitted, columnName defaults to the same value as fieldName. A converter can be used to supply a Converter class that performs custom conversion between JavaScript and database data types. The default is null. persistent specifies whether the field is persisted to the database, and defaults to true.



Important

If persistent is false, then the columnName and converter parameters may not be used.

```
TableMapping applyToClass(Function constuctor)
```

Attach a TableMapping to a *constructor* for mapped objects. After this is done, any object created from the constructor will qualify as a mapped instance, which several forms of the relevant Session and Batch methods can be used.

For example, an application can construct an instance that is only partly complete, then use Session.load() to populate it with all mapped fields from the database. After the application modifies the instance, Session.save() saves it back. Similarly, Session.find() can take the mapped constructor, retrieve an object based on keys, and then use the constructor to create a fully-fledged domain object.

5.3.9 TableMetadata

A TableMetadata object represents a table. This is the object returned in the getTable() callback. indexes[0] represents the table's intrinsic primary key.

```
TableMetadata = {
  database    : ""    , // Database name
  name    : ""    , // Table Name
  columns    : {}    , // ordered array of ColumnMetadata objects
  indexes    : {}    , // array of IndexMetadata objects
  partitionKey    : {}    , // ordered array of column numbers in the partition key
};
```

ColumnMetadata object represents a table column.

```
ColumnMetadata = {
  /* Required Properties */
  name : "" , columnNumber : -1 ,
                                        // column name
                       : -1 , // position of column in table, and in columns array : "" , // a ColumnTypes value
  columnType : "" , // a ColumnTypes value isIntegral : false , // true if column is some variety of INTEGER type isNullable : false , // true if NULLABLE
  isInPrimaryKey : false , // true if column is part of PK isInPartitionKey : false , // true if column is part of partition key
  columnSpace : 0 , // buffer space required for encoded stored value defaultValue : null , // default value for column: null for default value
                       : null , // default value for column: null for default NULL;
                                        // undefined for no default; or a type-appropriate
                                        // value for column
  /* Optional Properties, depending on columnType */
   /* Group A: Numeric */
  isUnsigned : false , // true for UNSIGNED
  intSize : null , // 1,2,3,4, or 8 scale : 0 , // DECIMAL scale precision : 0 , // DECIMAL precis
                         : null , // 1,2,3,4, or 8 if column type is INT
                                        // DECIMAL precision
  isAutoincrement : false , // true for AUTO_INCREMENT columns
  /* Group B: Non-numeric */
  length : 0 , // CHAR or VARCHAR length in characters isBinary : false . // true for BLOB/BINARY/VARRINARY
  isBinary : false , // true for BLOB/BINARY/VARBINARY
charsetNumber : 0 , // internal number of charset
charsetName : "" , // name of charset
                                    , // name of charset
```

An IndexMetadata object represents a table index. The indexes array of TableMetadata contains one IndexMetadata object per table index.

NDB implements a primary key as both an ordered index and a unique index, and might be viewed through the NDB API adapter as two indexes, but through a MySQL adapter as a single index that is both unique

and ordered. We tolerate this discrepancy and note that the implementation in Adapter/api must treat the two descriptions as equivalent.

The ColumnMetaData object's columnType must be a valid ColumnTypes value, as shown in this object's definition here:

```
ColumnTypes = [
  "TINYINT",
  "SMALLINT",
  "MEDIUMINT",
 "INT",
 "BIGINT",
 "FLOAT",
  "DOUBLE",
  "DECIMAL",
  "CHAR",
 "VARCHAR",
 "BLOB",
  "TEXT",
  "DATE",
  "TIME",
 "DATETIME",
 "YEAR",
 "TIMESTAMP",
  "BIT",
  "BINARY"
  "VARBINARY"
```

5.3.10 Transaction

A transaction is always either automatic or explicit. If it is automatic, (autocommit), every operation is performed as part of a new transaction that is automatically committed.

Beginning, committing, and rolling back a transaction

```
begin();
```

Begin a transaction. No arguments are required. If a transaction is already active, an exception is thrown.

```
commit(Function(Object error) callback);
```

Commit a transaction.

This method takes as its sole argument a callback function that returns an error object.

```
rollback(Function(Object error) callback);
```

Roll back a transaction. Errors are reported in the *callback* function.

Transaction information methods

```
Boolean isActive();
```

Determine whether or not a given transaction is currently active. Returns true if a transaction is active, and false otherwise.

isActive() requires no arguments.

```
setRollbackOnly();
```

Mark the transaction as rollback-only. Once this is done, <code>commit()</code> rolls back the transaction and throws an exception; <code>rollback()</code> rolls the transaction back, but does not throw an exception. To mark a transaction as rollback-only, call the <code>setRollbackOnly()</code> method, as shown here.

This method is one-way; a transaction marked as rollback-only cannot be unmarked. Invoking setRollbackOnly() while in autocommit mode throws an exception. This method requires no arguments.

```
boolean getRollbackOnly();
```

Determine whether a transaction has been marked as rollback-only. Returns true if the transaction has been so marked. setRollbackOnly() takes no arguments.

5.4 Using the MySQL JavaScript Connector: Examples

This section contains a number of examples performing basic database operations such as retrieving, inserting, or deleting rows from a table. The source for these files ca also be found in share/nodejs/samples, under the NDB Cluster installation directory.

5.4.1 Requirements for the Examples

The software requirements for running the examples found in the next few sections are as follows:

- A working Node.js installation
- Working installations of the ndb and mysql-js adapters
- The mysql-js adapter also requires a working installation of the node-mysql driver from https://github.com/felixge/node-mysql/.

Section 5.2, "Installing the JavaScript Connector", describes the installation process for all three of these requirements.

Sample database, table, and data. All of the examples use a sample table named tweet, in the test database. This table is defined as in the following CREATE TABLE statement:

```
CREATE TABLE IF NOT EXISTS tweet (
   id CHAR(36) NOT NULL PRIMARY KEY,
   author VARCHAR(20),
   message VARCHAR(140),
   date_created TIMESTAMP,

   KEY idx_btree_date_created (date_created),
   KEY idx_btree_author(author)
)
ENGINE=NDB;
```

The tweet table can be created by running the included SQL script create.sql in the mysql client. You can do this by invoking mysql in your system shell, as shown here:

```
shell> mysql < create.sql
```

All of the examples also make use of two modules defined in the file lib.js, whose contents are reproduced here:

```
# FILE: lib.js
"use strict";
var udebug = unified_debug.getLogger("samples/lib.js");
var exec = require("child_process").exec;
var SQL = {};
/* Pseudo random UUID generator */
var randomUUID = function() {
  \texttt{return 'xxxxxxx-xxxx-4xxx-yxxx-xxxxxxxxxx'.replace(/[xy]/g, function(c))} \ \{ \texttt{function}(x) : \texttt{function}(x) \in \mathbb{R}^{n} \} \}
    var r = Math.random()*16|0, v = c == 'x' ? r : (r&0x3|0x8);
    return v.toString(16);
};
/* Tweet domain object model */
var Tweet = function(author, message) {
  this.id = randomUUID();
  this.date_created = new Date();
  this.author = author;
  this.message = message;
};
/* SQL DDL Utilities */
var runSQL = function(sqlPath, source, callback) {
  function childProcess(error, stdout, stderr) {
    udebug.log('harness runSQL process completed.');
    udebug.log(source + ' stdout: ' + stdout);
    udebug.log(source + ' stderr: ' + stderr);
    if (error !== null) {
      console.log(source + 'exec error: ' + error);
    } else {
      udebug.log(source + ' exec OK');
    if(callback) {
      callback(error);
  }
  var p = mysql_conn_properties;
  var cmd = 'mysql';
  if(p) {
    if(p.mysql_socket)
                             { cmd += " --socket=" + p.mysql_socket; }
    else if(p.mysql_port) { cmd += " --port=" + p.mysql_port; }
    if(p.mysql_host)
                        { cmd += " -h " + p.mysql_host;
                           cmd += " -u " + p.mysql_user;
    if(p.mysql_user)
    if(p.mysql_password) { cmd += " --password=" + p.mysql_password; }
  cmd += ' <' + sqlPath;
  udebug.log('harness runSQL forking process...');
  var child = exec(cmd, childProcess);
SQL.create = function(suite, callback) {
 var sqlPath = path.join(suite.path, 'create.sql');
  udebug.log_detail("createSQL path: " + sqlPath);
 runSQL(sqlPath, 'createSQL', callback);
```

```
SQL.drop = function(suite, callback) {
  var sqlPath = path.join(suite.path, 'drop.sql');
  udebug.log_detail("dropSQL path: " + sqlPath);
  runSQL(sqlPath, 'dropSQL', callback);
};

/* Exports from this module */
exports.SQL = SQL;
exports.Tweet = Tweet;
```

Finally, a module used for random data generation is included in the file ndb_loader/lib/RandomData.js, shown here:

```
# FILE: RandomData.js
var assert = require("assert");
function RandomIntGenerator(min, max) {
 assert(max > min);
 var range = max - min;
 this.next = function() {
   var x = Math.floor(Math.random() * range);
   return min + x;
function SequentialIntGenerator(startSeq) {
 var seq = startSeq - 1;
 this.next = function() {
   seq += 1;
   return seq;
  };
function RandomFloatGenerator(min, max, prec, scale) {
 assert(max > min);
 this.next = function() {
   var x = Math.random();
    /* fixme! */
   return 100 * x;
  };
function RandomCharacterGenerator() {
 var intGenerator = new RandomIntGenerator(32, 126);
 this.next = function() {
   return String.fromCharCode(intGenerator.next());
function RandomVarcharGenerator(length) {
 var lengthGenerator = new RandomIntGenerator(0, length),
      characterGenerator = new RandomCharacterGenerator();
  this.next = function() {
   var i = 0,
       str = "",
        len = lengthGenerator.next();
    for(; i < len ; i++) str += characterGenerator.next();</pre>
    return str;
```

```
function RandomCharGenerator(length) {
  var characterGenerator = new RandomCharacterGenerator();
  this.next = function() {
   var i = 0,
       str = "";
    for(; i < length ; i++) str += characterGenerator.next();</pre>
}
function RandomDateGenerator() {
  var generator = new RandomIntGenerator(0, Date.now());
  this.next = function() {
   return new Date(generator.next());
  };
function RandomGeneratorForColumn(column) {
  var g = \{\},
     min, max, bits;
  switch(column.columnType.toLocaleUpperCase()) {
    case "TINYINT":
    case "SMALLINT":
    case "MEDIUMINT":
    case "INT":
    case "BIGINT":
     if(column.isInPrimaryKey) {
       g = new SequentialIntGenerator(0);
      else {
       bits = column.intSize * 8;
        max = column.isUnsigned ? Math.pow(2,bits)-1 : Math.pow(2, bits-1);
                                                  0 : 1 - \max;
       min = column.isUnsigned ?
       g = new RandomIntGenerator(min, max);
     break;
    case "FLOAT":
    case "DOUBLE":
    case "DECIMAL":
     g = new RandomFloatGenerator(0, 100000); // fixme
     break;
    case "CHAR":
     g = new RandomCharGenerator(column.length);
     break;
    case "VARCHAR":
     g = new RandomVarcharGenerator(column.length);
     break;
    case "TIMESTAMP":
      g = new RandomIntGenerator(0, Math.pow(2,32)-1);
     break;
    case "YEAR":
     g = new RandomIntGenerator(1900, 2155);
     break;
    case "DATE":
    case "TIME":
    case "DATETIME":
     g = new RandomDateGenerator();
     break;
    case "BLOB":
    case "TEXT":
    case "BIT":
    case "BINARY":
```

```
case "VARBINARY":
    default:
      throw("UNSUPPORTED COLUMN TYPE " + column.columnType);
 return g;
function RandomRowGenerator(table) {
 var i = 0,
      generators = [];
 for(; i < table.columns.length ; i++) {</pre>
   generators[i] = RandomGeneratorForColumn(table.columns[i]);
  this.newRow = function() {
   var n, col, row = {};
    for(n = 0; n < table.columns.length ; n++) {</pre>
      col = table.columns[n];
     row[col.name] = generators[n].next();
   return row;
exports.RandomRowGenerator = RandomRowGenerator;
exports.RandomGeneratorForColumn = RandomGeneratorForColumn;
```

5.4.2 Example: Finding Rows

```
# FILE: find.js
var nosql = require('..');
var lib = require('./lib.js');
var adapter = 'ndb';
global.mysql_conn_properties = {};
var user_args = [];
// *** program starts here ***
// analyze command line
var usageMessage =
  "Usage: node find key\n" +
            -h or --help: print this message\n" +
            -d or --debug: set the debug flagn +
    --mysql_socket=value: set the mysql socket\n" +
      --mysql_port=value: set the mysql portn" +
       --mysql_host=value: set the mysql hostn" +
      --mysql_user=value: set the mysql user\n" +
  "--mysql_password=value: set the mysql password\n" + \,
                 --detail: set the detail debug flagn" +
      --adapter=<adapter>: run on the named adapter (e.g. ndb or mysql)\n"
// handle command line arguments
var i, exit, val, values;
for(i = 2; i < process.argv.length ; i++) {</pre>
 val = process.argv[i];
  switch (val) {
 case '--debug':
 case '-d':
   unified_debug.on();
```

```
unified_debug.level_debug();
   break;
 case '--detail':
   unified_debug.on();
   unified_debug.level_detail();
   break;
 case '--help':
 case '-h':
   exit = true;
   break;
 default:
   values = val.split('=');
   if (values.length === 2) {
      switch (values[0]) {
      case '--adapter':
       adapter = values[1];
       break;
      case '--mysql_socket':
       mysql_conn_properties.mysql_socket = values[1];
      case '--mysql_port':
       mysql_conn_properties.mysql_port = values[1];
      case '--mysql_host':
       mysql_conn_properties.mysql_host = values[1];
      case '--mysql_user':
       mysql_conn_properties.mysql_user = values[1];
      case '--mysql_password':
       mysql_conn_properties.mysql_password = values[1];
       break;
      default:
       console.log('Invalid option ' + val);
       exit = true;
    } else {
      user_args.push(val);
 }
if (user_args.length !== 1) {
 console.log(usageMessage);
 process.exit(0);
};
if (exit) {
 console.log(usageMessage);
 process.exit(0);
console.log('Running find with adapter', adapter, user_args);
//create a database properties object
var dbProperties = nosql.ConnectionProperties(adapter);
// create a basic mapping
var annotations = new nosql.TableMapping('tweet').applyToClass(lib.Tweet);
//check results of find
var onFind = function(err, object) {
 console.log('onFind.');
 if (err) {
   console.log(err);
  } else {
   console.log('Found: ' + JSON.stringify(object));
```

```
}
process.exit(0);
};

// find an object
var onSession = function(err, session) {
   if (err) {
      console.log('Error onSession.');
      console.log(err);
      process.exit(0);
   } else {
      session.find(lib.Tweet, user_args[0], onFind);
   }
};

// connect to the database
nosql.openSession(dbProperties, annotations, onSession);
```

5.4.3 Inserting Rows

```
# FILE: insert.js
var nosql = require('..');
var lib = require('./lib.js');
var adapter = 'ndb';
global.mysql_conn_properties = {};
var user_args = [];
// *** program starts here ***
// analyze command line
var usageMessage =
  "Usage: node insert author message\n" +
             -h or --help: print this message\n" +
            -d or --debug: set the debug flagn" +
    --mysql_socket=value: set the mysql socket\n" +
       --mysql_port=value: set the mysql portn" +
      --mysql_host=value: set the mysql hostn" +
       --mysql_user=value: set the mysql usern" +
  "--mysql_password=value: set the mysql password\n" +
                 --detail: set the detail debug flagn" +
      --adapter=<adapter>: run on the named adapter (e.g. ndb or mysql)\n"
// handle command line arguments
var i, exit, val, values;
for(i = 2; i < process.argv.length ; i++) {</pre>
 val = process.argv[i];
 switch (val) {
 case '--debug':
 case '-d':
   unified_debug.on();
   unified_debug.level_debug();
   break;
 case '--detail':
   unified_debug.on();
   unified_debug.level_detail();
   break;
  case '--help':
  case '-h':
   exit = true;
   break;
  default:
   values = val.split('=');
```

```
if (values.length === 2) {
      switch (values[0]) {
      case '--adapter':
       adapter = values[1];
       break;
      case '--mysql_socket':
       mysql_conn_properties.mysql_socket = values[1];
       break;
      case '--mysql_port':
       mysql_conn_properties.mysql_port = values[1];
       break;
      case '--mysql_host':
       mysql_conn_properties.mysql_host = values[1];
       break;
      case '--mysql_user':
       mysql_conn_properties.mysql_user = values[1];
       break;
      case '--mysql_password':
       mysql_conn_properties.mysql_password = values[1];
      default:
       console.log('Invalid option ' + val);
       exit = true;
    } else {
      user_args.push(val);
 }
if (user_args.length !== 2) {
 console.log(usageMessage);
 process.exit(0);
};
if (exit) {
 console.log(usageMessage);
 process.exit(0);
console.log('Running insert with adapter', adapter, user_args);
//create a database properties object
var dbProperties = nosql.ConnectionProperties(adapter);
// create a basic mapping
var annotations = new nosql.TableMapping('tweet').applyToClass(lib.Tweet);
//check results of insert
var onInsert = function(err, object) {
 console.log('onInsert.');
 if (err) {
   console.log(err);
  } else {
   console.log('Inserted: ' + JSON.stringify(object));
 process.exit(0);
};
// insert an object
var onSession = function(err, session) {
 if (err) {
   console.log('Error onSession.');
   console.log(err);
   process.exit(0);
  } else {
   var data = new lib.Tweet(user_args[0], user_args[1]);
```

```
session.persist(data, onInsert, data);
};

// connect to the database
nosql.openSession(dbProperties, annotations, onSession);
```

5.4.4 Deleting Rows

```
FILE: delete.js
var nosql = require('..');
var lib = require('./lib.js');
var adapter = 'ndb';
global.mysql_conn_properties = {};
var user_args = [];
// *** program starts here ***
// analyze command line
var usageMessage =
  "Usage: node delete message-idn" +
             -h or --help: print this message\n" +
            -d or --debug: set the debug flagn" +
    --mysql_socket=value: set the mysql socket\n" +
      --mysql_port=value: set the mysql port\n" +
      --mysql_host=value: set the mysql hostn" +
       --mysql_user=value: set the mysql usern" +
  "--mysql_password=value: set the mysql passwordn" +
                 --detail: set the detail debug flagn" +
      --adapter=<adapter>: run on the named adapter (e.g. ndb or mysql)\n"
// handle command line arguments
var i, exit, val, values;
for(i = 2; i < process.argv.length ; i++) {</pre>
 val = process.argv[i];
 switch (val) {
  case '--debug':
 case '-d':
   unified_debug.on();
   unified_debug.level_debug();
   break;
 case '--detail':
   unified_debug.on();
   unified_debug.level_detail();
  case '--help':
 case '-h':
   exit = true;
   break;
  default:
   values = val.split('=');
   if (values.length === 2) {
      switch (values[0]) {
      case '--adapter':
       adapter = values[1];
       break;
      case '--mysql_socket':
       mysql_conn_properties.mysql_socket = values[1];
      case '--mysql_port':
       mysql_conn_properties.mysql_port = values[1];
        break;
```

```
case '--mysql_host':
       mysql_conn_properties.mysql_host = values[1];
       break;
      case '--mysql_user':
       mysql_conn_properties.mysql_user = values[1];
       break;
      case '--mysql_password':
       mysql_conn_properties.mysql_password = values[1];
       break;
      default:
       console.log('Invalid option ' + val);
       exit = true;
    } else {
      user_args.push(val);
if (user_args.length !== 1) {
 console.log(usageMessage);
 process.exit(0);
};
if (exit) {
 console.log(usageMessage);
 process.exit(0);
console.log('Running delete with adapter', adapter, user_args);
//create a database properties object
var dbProperties = nosql.ConnectionProperties(adapter);
// create a basic mapping
var annotations = new nosql.TableMapping('tweet').applyToClass(lib.Tweet);
// check results of delete
var onDelete = function(err, object) {
 console.log('onDelete.');
 if (err) {
   console.log(err);
  } else {
   console.log('Deleted: ' + JSON.stringify(object));
 process.exit(0);
};
// delete an object
var onSession = function(err, session) {
 if (err) {
   console.log('Error onSession.');
   console.log(err);
   process.exit(0);
 } else {
   var tweet = new lib.Tweet();
   tweet.id = user_args[0];
   session.remove(tweet, onDelete, user_args[0]);
};
// connect to the database
nosql.openSession(dbProperties, annotations, onSession);
```

Chapter 6 ndbmemcache—Memcache API for NDB Cluster (NO LONGER SUPPORTED)

Table of Contents

6.1	Overview	759
6.2	Compiling NDB Cluster with Memcache Support	759
	memcached command line options	
	NDB Engine Configuration	
	Memcache protocol commands	
6.6	The memcached log file	769
6.7	Known Issues and Limitations of ndbmemcache	770



Note

This feature has been removed from NDB Cluster, and is no longer supported. See What is New in NDB Cluster, for more information.

This section provides information about the Memcache API for NDB Cluster, which makes it possible to access NDB Cluster data using the memcache protocol.

6.1 Overview

Memcached is a distributed in-memory caching server using a simple text-based protocol, commonly used for key-value data stores, with clients available for many platforms and programming languages. The most recent release of the memcached server is available from memcached.org.

The Memcache API for NDB Cluster is implemented as a loadable storage engine for memcached version 1.6 and later, which employs a storage engine architecture. This API can be used to provide a persistent NDB Cluster data store which is accessible employing the memcache protocol. It is also possible for the memcached server to provide a strictly defined interface to existing NDB Cluster tables such that an administrator can control exactly which tables and columns are referenced by particular memcache keys and values, and which operations are allowed on these keys and values.

The standard memcached caching engine is included in the NDB Cluster distribution. Each memcache server, in addition to providing direct access to data stored in NDB Cluster, is able to cache data locally and serve (some) requests from this local cache. As with table and column mappings, cache policies are configurable based on a prefix of a memcache key.

6.2 Compiling NDB Cluster with Memcache Support

Support for the Memcache API is built automatically using the memcached and libevent sources included in the NDB Cluster sources when compiling NDB from source. By default, make install places the memcached binary in the NDB Cluster installation bin directory, and the ndbmemcache engine shared object file ndb_engine.so in the installation lib directory.

You can disable use of the bundled memcached when building ndbmemcache, by using – DWITH_BUNDLED_MEMCACHED=OFF; you can instead use your own system's memcached server and

sources, installed in *path*, with -DWITH_BUNDLED_MEMCACHED=OFF -DMEMCACHED_HOME=*path*. You can also cause your system's version of libevent to be used, rather than the version bundled with NDB Cluster, by using the -DWITH_BUNDLED_LIBEVENT=OFF option.

For additional information about CMake options relating to ndbmemcache support, see Options for Compiling NDB Cluster.

For general information about building NDB Cluster, see Building NDB Cluster from Source on Linux, and Compiling and Installing NDB Cluster from Source on Windows. For information about building MySQL Server from source, see Installing MySQL from Source, as well as MySQL Source-Configuration Options.

6.3 memcached command line options

The following list contains memcached command line options that are of particular interest or usefulness when working with ndbmemcache.

• -E so_file

Specifies an engine (module) to be dynamically loaded on startup by memcached (version 1.6 or later).

If this option is not specified, memcached tries to load the default engine, which provides the same caching engine as used in memcached 1.4 and previous versions

To load the NDB engine, use this option as shown here:

-E /path/to/ndb_engine.so

• -e "configuration string"

Specifies options for use by the loaded engine. Options are given as <code>option=value</code> pairs separated by semicolons. The complete string should be quoted to prevent the possibility that the shell might interpret the semicolon as a command separator. All options to be passed to the NDB memcached engine must be specified in this fashion, as shown in the following example:

```
shell> memcached -E lib/ndb_engine.so -e "connectstring=maddy:1186;role=dev"
```

See Section 6.4, "NDB Engine Configuration" for a list of NDB memcached engine configuration options.

• -t number of worker threads

Sets the number of worker threads to be used by memcached. Because memcached uses an eventdriven model in which each worker thread should be able to saturate a CPU core, the number of worker threads should be approximately the same as the number of CPU cores that memcached is to use.

In some cases, adding worker threads does not improve performance unless you also provide additional connections to NDB Cluster. The default (4 memcached threads and 2 cluster connections) should work in most cases.

• -p tcp_port

The default TCP port is port 11211.

• -U udb port

The default UDP port is port 11211. Setting this option to 0 disables UDP support.

• -h

Causes memcached to print help information.

For general information memcached command line options, see the documentation at http://code.google.com/p/memcached/wiki/NewStart.

6.4 NDB Engine Configuration

NDB memcache engine configuration options. The NDB engine supports the following configuration options for use with memcache -e (see Section 6.3, "memcached command line options"):

• debug={true|false}

Enables writing of debug tracing output to stderr or the memcached log file, as shown in this example:

```
shell> memcached -E lib/ndb_engine.so -e "debug=true"
```

Because the debug output can be quite large, you should enable this option as a diagnostic tool only, and not in production.

By default, this option is false.

• connectstring=connect_string

This option takes as its value an NDB Cluster connection string (see NDB Cluster Connection Strings) pointing to the primary NDB Cluster—that is, the NDB Cluster in which the ndbmemcache configuration database is stored, as shown here:

```
shell > memcached -E lib/ndb_engine.so -e "connectstring=sam:1186;debug=true"
```

The default value is localhost:1186.

reconf={true|false}

Enables online reconfiguration (reloading of the configuration stored in the ndbmemcache information database).

This option is enabled (true) by default.

• role=role name

Sets the role assumed by this memcached server. A role corresponds to a set of key-prefix mappings described in the ndbmemcache configuration database, identified by a *role_name* found in the ndbmemcache.memcache_server_roles table.

The default role is default_role.

An example is shown here:

```
shell> memcached -E lib/ndb_engine.so -e "role=db-only"
```

• scheduler=scheduler_name:scheduler_options

This option controls some advanced aspects of how the NDB engine sends requests to NDB Cluster. The <code>scheduler_name</code> of the default scheduler or <code>S-scheduler</code> is <code>S</code>. An S-scheduler option takes the form of a single letter followed by a number; multiple S-scheduler options are separated by commas. In most cases, the default value <code>S:c0,f0,t1</code> is sufficient.

These S-scheduler options are described in the following list:

- c: Number of connections to NDB. Possible values are in the range 0-4 inclusive, with 0 (the default) causing this number to be calculated automatically. Using 1, 2, 3, or 4 causes that number of connections to be created.
- f: Can be either 0 or 1; setting to 1 enables force-send. The default is 0 (force-send disabled).
- t: Sets the send-thread timer to 1-10 milliseconds (inclusive). The default is 1.

Initial Configuration.

When a the NDB engine starts up, its most important command-line arguments are the cluster connection string and server role. The connection string is used to connect to a particular cluster, called the primary cluster, which contains a configuration schema. The tables in the configuration schema are read to retrieve a set of key-prefix mappings for the given server role (see the ndbmemcache configuration schema). Those mappings instruct the server how to respond to memcache operations on particular keys, based on the leftmost part of the key. For instance, they may specify that data is stored in particular columns of a certain table. This table may be stored in the same cluster as the configuration schema, or in a different cluster. A memcache server may have connections to several different clusters, and many memcache servers may connect to a single cluster but with a variety of roles.

The ndbmemcache configuration schema. When the memcache NDB engine starts up, it connects to a cluster, and looks for the ndbmemcache configuration schema there. If the schema is not found, it shuts down.

The schema is described (with full comments) in the file ndb_memcache_metadata.sql

The main concept of the schema is a key-prefix mapping. This takes a prefix of a memcache key and maps it to a specific container table, on a particular cluster, with a particular cache policy.

A server role is defined as a set of key-prefix mappings that a memcached server will implement.

Whenever a memcached server is started with a particular server role (from the command-line arguments), that server role must exist in the ndbmemcache.server_roles table.

The following table lists table names and descriptions for tables that belong to the ndbmemcache configuration schema.

Table 6.1 ndbmemcache configuration schema, table names and descriptions

Table Name	Description
meta	The meta table describes the version number of the ndbmemcache tables. It should be considered as a read-only table.
ndb_clusters	For each cluster, this table holds a numeric cluster-id and a connection string. The microsec_rtt column is used for performance tuning. It is recommended to use the default value of this column. See Autotuning.
cache_policies	This table maps a policy name to a set of get, set, delete, and flush policies. The policy_name column is used as the key (there is no numeric policy id). Additional information about cache policies can found in the text following the table.
containers	The containers table describes how the memcached server can use a database table to store data. Additional information about containers can found in the text following the table.
memcache_server	The msmcache_server_roles table maps a role name to a numeric ID and a max_tps specifier, which is used for performance tuning. See Autotuning. It is recommended to use the default value.

Table Name	Description
	This table also has an update_timestamp column. This column can be updated to enable online reconfiguration. See Online reconfiguration.
	Additional information about server roles can found in the text following the table.
key_prefixes	In this table, the leftmost part of a memcache key is paired with a cluster ID, container, and cache policy to make a <i>key prefix mapping</i> .
	Additional information about key prefix mappings can found in the text following the table.

Cache policies. There are four policy types: <code>get_policy</code>, <code>set_policy</code>, <code>delete_policy</code>, and <code>flush_from_db</code>. These are described in the following paragraphs.

get_policy determines how the memcached server interprets GET commands. Possible values and their meanings are shown in the following list:

- cache_only: The server searches in its local cache only.
- ndb_only: The server searches in the NDB Cluster database only.
- caching: The server searches the local cache first, then the NDB Cluster database.
- disabled: GET commands are not permitted.

The set_policy determines how the memcached server interprets SET, INSERT, and REPLACE commands. Possible set_policy values and their meanings are listed here:

- cache_only: The server updates the value in its local cache only.
- ndb_only: The server updates the value stored in NDB Cluster only.
- caching: The server updates the value stored in NDB Cluster, and then stores a copy of that value in its local cache.
- disabled: SET, INSERT, and REPLACE commands are not allowed.

delete_policy describes how the memcached server interprets DELETE commands. It can take on the values shown and described in the following list:

- cache only: The server deletes the value from its local cache only.
- ndb only: The server deletes the value from the NDB Cluster database only.
- caching: The server deletes the value from both the database and its local cache.
- disabled: DELETE operations are not allowe.

flush_from_db determines how the memcached server interprets a FLUSH_ALL command with regard to data stored in the NDB Cluster database, as shown here:

- true: FLUSH_ALL commands cause data to be deleted from the NDB Cluster database.
- false: FLUSH ALL commands do not affect the NDB Cluster database.

containers table columns. The columns in the containers table are described in the following list:

- name: Name of container; primary key of table.
- db_schema: Name of database (schema) holding container table.
- db_table: table name of container table.
- key_columns: List of columns that map to the memcache key. Most keys are one-part keys, but a key can have up to four parts, in which case multiple columns are listed and separated by commas.
- value_columns: List of columns that map to the memcache value. It can also contain a commaseparated list of up to 16 value columns.
- flags: Currently unimplemented; it is intended hold either a numeric value which is used as the memcache FLAGS value for the entire container, or the name of that column of the container table used to store this value.
- increment_column: Name of the column in the container table which stores the numeric value used in memcached INCR and DECR operations. If set, this must be a BIGINT UNSIGNED column.
- cas_column Name of the column in the container table storing the memcache CAS value. If set, it must be a BIGINT UNSIGNED column.
- expire_time_column: Currently unimplemented.

Key mappings.

- server_role_id is a numeric server role identifier which references the memcache_server_roles table
- key_prefix is a string that corresponds to the leftmost part of the memcache key. If this string is empty, then the defined prefix will be the "default prefix". The default prefix matches any memcache key that does not match some more specific prefix.
- cluster_id is an int that references the ndb_clusters table
- policy is a string that references a policy name in the cache_policies table
- container is a container name that references the containers table

The following table lists table names and descriptions for non-configuration ndbmemcache logging and container tables.

Table 6.2 ndbmemcache logging and container tables not for configuration, with descriptions

Table Name	Description
last_memcached_	This table is not part of the configuration schema, but is an informative logging table. It records the most recent login time of each memcached server using the configuration.
	ndb_node_id is an int recording the API node id of the server
	hostname is the hostname of the memcached server
	• server_role is the role assigned to the server at signon time
	signon_time is a timestamp recording the memcached startup time

Table Name	Description
	In the case of online reconfiguration, signon_time records the time of the latest reconfiguration, not the time of startup. This is an unintended consequence and might be considered a bug.
demo_table	demo_table is the container table used with default key prefix in the default server role. It is used to demonstrate SET and GET operations as well as INCR, DECR, and CAS, with one key column and one value column.
demo_table_tabs	demo_table_tabs is the container table for the "demo_tabs" container, which is used with the key prefix "t:" in the default server role. It is used to demonstrate one key column with multiple value columns. In memcache operations, the value columns are represented as a tab-separated list of values.

Predefined configuration objects

Predefined clusters. A single ndb_cluster record is predefined, referring to the primary cluster (the one where configuration data is stored) as cluster id 0. Id 0 should always be reserved for the primary cluster.

Predefined cache policies

- "memcache-only": a policy in which all memcache operations are to use local cache only
- "ndb-only": a policy in which all memcache operations use the NDB Cluster database, except for FLUSH ALL, which is disabled
- "caching": a policy with get_policy, set_policy, and delete_policy all set to "caching". FLUSH_ALL is disabled.
- "caching-with-local-deletes": a policy in which get_policy and set_policy are set to caching, but delete_policy is set to "cache-only", and FLUSH_ALL is disabled.
- "ndb-read-only": a policy in which get_policy is set to ndb_only, so that memcache GET operations use the database, but all other memcache operations are disabled
- "ndb-test": a policy like "ndb-only" with the difference that FLUSH_ALL is allowed (flush_from_db) is true. This is the only predefined policy with flush_from_db enabled. This policy is enabled by default for the default server role, so taht the entire memcache command set can be demonstrated.

Predefined containers

- "demo table": a container using the table ndbmemcache.demo table as a container table
- "demo_tabs": a container using the table ndbmemcache.demo_table_tabs as a container table

Predefined memcache server roles and their key prefixes

- "default role" (role id 0)
 - "": The empty (default) prefix uses the ndb-test policy and the demo_table container
 - "mc:" Memcache keys beginning with "mc:" are treated according to the memcache-only cache policy
 - "t:" Memcache keys beginning with "t:" use the ndb-test cache policy and the demo_tabs container
- The "db-only" role (role id 1)

"": the empty (default) prefix uses the ndb-only role and demo_table container

The "t:" prefix uses the ndb-only role and demo_tabs container

- The "mc-only" role (role id 2)
 - "": The empty (default) prefix uses local caching only for all keys
- The "ndb-caching" role (role id 3)
 - "": The empty (default) prefix uses the "caching" cache policy and "demo_table" container for all keys

Configuration versioning and upgrade.

The configuration schema is versioned, and the version number is stored in the ndbmemcache.meta table. The NDB Engine begins the configuration process by reading the schema version number from this table. As a rule, newer versions of the NDB engine will remain compatible with older versions of the configuration schema.

STABILITY NOTE: consider this section "unstable" & subject to change

Performance Tuning.

Two parameters are used to tune performance of the NDB memcache engine. The parameters are stored in the configuration schema: the "usec_rtt" value of a particular cluster, and the "max_tps" value of a memcache server role. These values are currently used in two ways: to configure the number of connections to each cluster, and to configure a particular fixed number of concurrent operations supported from each connection.

Autotuning. Autotuning uses an estimated round trip time between cluster data nodes and a target rate of throughput to determine the ideal number of cluster connections and transactions per connection for a given workload. Autotuning parameters are described in the next few paragraphs.

- usec_rtt: The round trip time, in microseconds, between cluster nodes. The default value is 250, which is typical for an NDB Cluster on a local switched ethernet. To represent a cluster with higher inter-node latency (wider area), a higher value should be used.
- max_tps: The desired throughput from a server. This value is a heuristic, and does not in any way
 express either a floor or a ceiling on the actual throughput obtained. The default value (100000) is
 reasonable in most cases.

These values are used, as described in the next few paragraphs, to calculate an optimum number of cluster connections with a given transactions-per-second capacity..

Number of cluster connections. The NDB Engine scheduler attempts to open 1 cluster connection per 50000 transactions per second (TPS). This behavior can be overridden by using a scheduler configuration string (see Section 6.4, "NDB Engine Configuration".) If the scheduler fails to open a second or subsequent connection to a cluster—for example, because a node id is not available—this is not a fatal error; it will run with only the connections actually opened.

Number of transactions per connection. We assume that a transaction takes 5 times the cluster round trip time to complete. We can obtain the total number of in-flight transactions by dividing the server's max_tps by 5 * rtt (in seconds). These in-flight transaction objects are evenly distributed among the cluster connections.

Tuning example. The following example starts with the default values usec_rtt = 250 and max_tps = 100000, and assumes a memcached server with 4 worker threads.

• 100000 TPS divided by 50000 is 2, and the server opens two NDB cluster connections.

- Transaction time in microseconds = 250 µs round trip time * 5 round trips = 1250 µs.
- Transactions per connection per second = 1000000 / tx time in µsec = 1000000 / 1250 = 800.
- Total Ndb objects = max_tps / tx_per_ndb_per_sec = 100000 / 800 = 125.
- 125 Ndb objects / 2 connections = 63 Ndb objects per connection (rounding upward).
- (Rounding upward once more) each of 4 worker threads gets 32 Ndb objects

Online reconfiguration.

It is possible to reconfigure the key-prefix mappings of a running NDB engine without restarting it. This is done by committing a change to the configuration schema, and then updating the update_timestamp column of a particular server role in the memcache server roles table. The updating of the timestamp causes an event trigger to fire, so that the memcache server receives notification of the event.

Online reconfiguration can be disabled by using the -e reconf=false option on the command line.

Online reconfiguration can be used to connect to new clusters and to create new key-prefix mappings. However, it cannot be used to reset autotuning values on existing connections.

Online reconfiguration is a risky operation that could result in memcache server crashes or data corruption, and is used extensively in the mysql test suite. However, it is not recommended for reconfiguring a production server under load.

The stats reconf command can be run before and after online reconfiguration to verify that the version number of the running configuration has increased. Verification of reconfiguration is also written into the memcached log file.

6.5 Memcache protocol commands

The NDB engine supports the complete set of memcache protocol commands. When a newly installed server is started with the default server role and configuration schema, you should be able to run memcapable, a memcache-server verification tool, and see all tests pass. After a configuration has been customized, however—for instance, by disabling the FLUSH_ALL command—some memcapable tests are expected to fail.

GET, SET, ADD, REPLACE, and DELETE operations. Each of these operations is always performed according to a cache policy associated with the memcache key prefix. It may operate on a locally cached item, an item stored in the database, or both. If an operation has been disabled for the prefix, the developer should be sure to test the disabled operation, since it may fail silently, or with a misleading response code.

CAS. CAS, in the memcache protocol, refers to a "compare and set" value, which is used as a sort of version number on a cached value, and enables some optimistic application behavior

If a container includes a CAS column, the ndb engine will generate a unique CAS ID every time it writes a data value, and store it in the CAS column.

Some memcache operations include CAS checks, such as the ASCII CAS update which has the semantics "update this value, but only if its CAS id matches the CAS id in the request". These operations are supported by the NDB engine. The check of the stored CAS ID against the application's CAS ID is performed in an atomic operation on the NDB data node. This allows CAS checks to work correctly even when multiple memcached servers access the same key-value pair.

If CAS ID checks are in use, and additional NDB Cluster APIs other than memcached are being used to manipulate the data, then the applications using those APIs are responsible for invalidating the stored CAS IDs whenever they update data. They can do this by setting the stored CAS ID value to 0 or NULL.

The CAS ID is generated using a scheme that attempts to prevent different servers from generating overlapping IDs. This scheme can be considered a best effort, but not a guarantee, of uniqueness. The scheme constructs an initial CAS as follows:

Part of the 32-bit Cluster GCI from the primary cluster at memcached startup time is used for the highorder bits of the 64-bit CAS ID

Part of the unique cluster node id in the primary cluster used when fetching configuration is used for middle-order bits of the CAS ID

An incrementing counter in the low-order bits of the CAS ID is at least 28-bits wide.

While the NDB engine generates one sequence of CAS IDs, the default engine—used for caching values in local memcached servers—generates a different sequence. Not all combinations of CAS behavior and cache policies have been tested, so any application developer wishing to use CAS should thoroughly test whether a particular configuration behaves as desired.

FLUSH_ALL. FLUSH_ALL is implemented as follows: First, the NDB engine iterates over all configured key-prefixes. For any prefix whose cache policy enables a database flush (flush_from_db is true), it performs a scanning delete of every row in that prefix's container table. Other prefixes are ignored. This can be a slow operation if the table is large, and some memcache clients may time out before the DELETE operation is complete. After all database deletes are complete, the FLUSH_ALL command is forwarded to the standard caching engine, which sets a flag invalidating all cached data.

INCR and DECR. All INCR and DECR operations are pushed down to the NDB data nodes and performed atomically there. This allows multiple memcached servers to increment or decrement the same key and be guaranteed a unique value each time.

The INCR and DECR operations have clearer and more useful semantics in the binary memcache protocol than in the ASCII protocol. The binary protocol is recommended.

The memcached ASCII protocol introduces some ambiguities in the handling of INCR and DECR, and forces the NDB engine to work in dup_numbers mode, in which the value_column and the math_column must mirror each other.

dup_numbers mode is enabled for key prefixes that meet all of the following conditions:

- · The container includes a math column, AND
- The container includes a single value column, AND
- The data type of the value column is non-numeric

In dup_numbers mode, the following special behavior applies:

- Whenever an ASCII SET, ADD, or REPLACE command sets a value that could be interpreted as numeric, and the container defines a math_column, then the text value is stored in the value column and the numeric value is also stored in the math column.
- Whenever an ASCII INCR or DECR command is performed, the text value in that container's value column is set to NULL.
- Whenever a memcached GET command is issued, and the container's value column is NULL, but the container's math column is not NULL, then the math value is returned to the client.

APPEND and **PREPEND**. The memcache APPEND and PREPEND operations are implemented as a single transaction which involves a read of the existing value with an exclusive lock, followed by a write of

the new value. The read and write are grouped atomically into a transaction, but unlike INCR and DECR, which can run natively on the data nodes, APPEND and PREPEND are executed inside the memcached server. This means that multiple memcached servers can contend to APPEND and PREPEND the same value, and that no updates will be lost, but this contention relies on locking behavior that could cause noticably increased latency.

STATS. A memcached server can provide many sets of statistics; use STATS KEYWORD from a login shell.

All statistics usually available from the memcached 1.6 core and the default engine are available. For instance, STATS, STATS SLABS, and STATS SETTINGS are all currently supported as described in the memcached documentation. Some special sets of statistics are available from the NDB engine, using the STATS commands described in the following list:

- STATS NDB: Returns NDB API statistics for each NDB cluster connection. These are the same internal statistics which are available as system status variables from the MySQL Server. See NDB API Statistics Counters and Variables, for more information.
- STATS SCHEDULER: Returns statistics for the S scheduler. All of these statistics are reported on the cluster connection level.
 - cl%d.conn%d.sent_operations: Records the number of operations sent from the connection's send thread to the cluster data nodes.
 - c1%d.conn%d.batches: Records the number of operation batches sent from the send thread to the data nodes. Each batch contains one or more operations. sent_operations / batches can be used to compute the average batch size.
 - cl%d.conn%d.timeout_races: This records a rare race condition that may occur in the send thread. It is expected to be 0, or to be a very low number compared to sent_operations.
- stats reconf: If the NDB engine is currently loading a new configuration, command returns the single-line message Loading revno, where revno is the version number of the configuration being loaded.

Otherwise, this command returns the statistical message Running revno.

revno starts at 1 when the memcached server begins running, and is incremented by 1 for each online reconfiguration.

6.6 The memcached log file

Whenever the NDB memcache engine is initialized, it writes a message including a timestamp and version number to its log file, as shown here:

```
12-Oct-2011 13:40:00 PDT NDB Memcache 8.0.24-ndb-8.0.24 started [NDB 8.0.24; MySQL 8.0.24-ndb-8.0.24]
```

It also logs its attempt to connect to a primary cluster:

```
Contacting primary management server (localhost:1186) ...
•Connected to "localhost:1186" as node id 4.
```

Upon successfully fetching initial configuration data, the memcache engine logs a summary message describing the configuration similar to what is shown here:

```
Retrieved 3 key prefixes for server role "default_role"
The default behavior is that:
```

```
GET uses NDB only
SET uses NDB only
DELETE uses NDB only
The 2 explicitly defined key prefixes are "mc:" () and "t:" (demo_table_tabs)
Server started with 4 threads.
```

The memcache engine also logs the establishment of each additional cluster connection, as shown here:

```
Connected to "" as node id 5.
```

A priming the pump... message indicates that the engine is about to prefetch a pool of transaction objects (API Connect Records). It is followed by a done ... message indicating how much time was used by prefetching. The server is not ready to respond to clients until after the prefetching is completed.

```
Priming the pump ...
Scheduler: using 2 connections to cluster 0
Scheduler: starting for 1 cluster; c0,f0,t1
done [0.579 sec].
```

Once the NDB engine has finished initializing, memcached prints a message verifying that the engine was loaded, and enumerating some of its features:

```
Loaded engine: NDB Memcache 8.0.24-ndb-8.0.24
Supplying the following features: compare and swap, persistent storage, LRU
```

If online reconfiguration is enabled, the NDB engine logs each reconfiguration, along with a summary of the new configuration, similar to what is shown here:

```
Received update to server role default_role
Retrieved 3 key prefixes for server role "default_role".
The default behavior is that:
GET uses NDB only
SET uses NDB only
DELETE uses NDB only.
The 2 explicitly defined key prefixes are "mc:" () and "t:" (demo_table_tabs)
ONLINE RECONFIGURATION COMPLETE
```

On shutdown, memcached logs the shutdown sequence'a initialization and completion, and the NDB engine's scheduler logs its own shutdown as well:

```
Initiating shutdown
Shutting down scheduler.
Shutdown completed.
```

6.7 Known Issues and Limitations of ndbmemcache

This section provides information about known issues with and design limitations of the Memcache API for NDB Cluster.

Problems with AUTO_INCREMENT. ndbmemcache bypasses the NDB storage engine's mechanism for handling AUTO_INCREMENT columns. This means that, when you insert rows using ndbmemcache into a table having an AUTO_INCREMENT column, this column is not automatically updated. This can lead to duplicate key errors when inserts are performed later using SQL in a MySQL client application such as mysql.

To work around this issue, you can employ a sequence generator as described here.

Online schema changes not supported. The memcached daemon does not detect online schema changes; after making such changes, you must restart the memcached daemon before the updated schema can be used by your application.

 $\begin{tabular}{ll} \textbf{Fractional seconds.} & \textbf{ndbmemcache supports the use of fractional seconds with the TIME, DATE, and DATETIME data types as implemented in MySQL 5.6.4 and later.} \\ \end{tabular}$

Index В backup defined. 3 Batch class (Connector for JavaScript), 737 AbortOption (NdbOperation data type), 209 Batch.clear(), 737 Batch.execute(), 737 and NDB Kernel, 13 Batch.getSession(), 737 defined. 4 begin (ClusterJ), 717 Access Manager begin() (method of NdbScanFilter), 235 defined. 4 begin() (method of Transaction), 747 ActiveHook (NdbBlob data type), 147 beginSchemaTrans() (method of Dictionary), 60 addColumn() (method of Index), 99 between (ClusterJ), 727 addColumn() (method of Table), 285 BinaryCondition (NdbScanFilter data type), 236 addColumnName() (method of Index), 99 **BLOB** handling addColumnNames() (method of Index), 100 example, 559 addEventColumn() (method of Event), 78 example (using NdbRecord), 566 addEventColumns() (method of Event), 79 blobsFirstBlob() (method of NdbBlob), 147 addTableEvent() (method of Event), 80 blobsNextBlob() (method of NdbBlob), 147 add reg() (method of NdbInterpretedCode), 188 BoundType (NdbIndexScanOperation data type), 178 add val() (method of NdbInterpretedCode), 188 branch_col_and_mask_eq_mask() (method of aggregate() (method of Table), 285 NdbInterpretedCode), 189 allowsNull (ClusterJ), 718 branch_col_and_mask_eq_zero() (method of and (ClusterJ), 726 NdbInterpretedCode), 190 Annotations (ClusterJ) branch_col_and_mask_ne_mask() (method of Column, 718 NdbInterpretedCode), 190 Columns, 718 branch col and mask ne zero() (method of Extension, 719 NdbInterpretedCode), 190 Extensions, 719 branch_col_eq() (method of NdbInterpretedCode), 191 Index, 720 branch_col_eq_null() (method of NdbInterpretedCode), Indices, 721 192 Lob, 721 branch_col_ge() (method of NdbInterpretedCode), 192 NotPersistent, 721 branch_col_gt() (method of NdbInterpretedCode), 193 PartitionKey, 722 branch_col_le() (method of NdbInterpretedCode), 194 PersistenceCapable, 723 branch_col_like() (method of NdbInterpretedCode), 195 Persistent, 723 branch_col_lt() (method of NdbInterpretedCode), 195 PrimaryKey, 724 branch_col_ne() (method of NdbInterpretedCode), 196 Projection, 725 branch col ne null() (method of NdbInterpretedCode), API documentation JavaScript, 737 branch col notlike() (method of NdbInterpretedCode), API node 197 defined. 3 branch eq() (method of NdbInterpretedCode), 198 append (ClusterJ), 694 branch_eq_null() (method of NdbInterpretedCode), 198 application-level partitioning, 15 branch_ge() (method of NdbInterpretedCode), 199 applications branch_gt() (method of NdbInterpretedCode), 199 structure. 5 branch_label() (method of NdbInterpretedCode), 199 applyToClass() (method of TableMapping), 746 branch_le() (method of NdbInterpretedCode), 199 aRef() (method of NdbRecAttr), 228 branch It() (method of NdbInterpretedCode), 200 ArrayType (Column data type), 38 branch ne() (method of NdbInterpretedCode), 200 **AutoGrowSpecification** branch_ne_null() (method of NdbInterpretedCode), 200 NDB API structure, 156 **AUTO INCREMENT** C

ndbmemcache, 770

call sub() (method of NdbInterpretedCode), 201

charsetName (ClusterJ), 681

char_value() (method of NdbRecAttr), 228	Column::getPartitionKey(), 42
checkpoint	Column::getPartSize(), 42
defined, 3	Column::getPrecision(), 42
Classes (ClusterJ)	Column::getPrimaryKey(), 43
Cluster J Datastore Exception. Classification, 672	Column::getSizeInBytesForRecord(), 43
ClusterJHelper, 676	Column::getStorageType(), 44
ColumnType, 683	Column::getStripeSize(), 44
DynamicObject, 697	Column::getType(), 44
LockMode, 697	Column::setArrayType(), 44
NullValue, 721	Column::setCharset(), 45
PersistenceModifier, 723	Column::setDefaultValue(), 45
Query.Ordering, 703	Column::setLength(), 46
SessionFactory.State, 715	Column::setName(), 46
Classification (NdbError data type), 163	Column::setNullable(), 46
clear() (method of Batch), 737	Column::setPartitionKey(), 46
clearError() (method of NdbEventOperation)	Column::setPartSize(), 47
(DEPRECATED), 167	Column::setPrecision(), 47
clone() (method of NdbRecAttr), 228	Column::setPrimaryKey(), 47
close (ClusterJ), 705, 713	Column::setScale(), 48
close() (method of NdbBlob), 148	Column::setStorageType(), 48
close() (method of NdbScanOperation), 244	Column::setStripeSize(), 48
close() (method of NdbTransaction), 258	Column::setType(), 49
close() (method of Session), 744	Column::StorageType, 49
close() (method of SessionFactory), 745	Column::Type, 49
closeTransaction() (method of Ndb), 113	ColumnMetadata (ClusterJ), 680
ClusterJ	ColumnMetadata class (Connector for JavaScript), 746
defined, 653	Columns (ClusterJ), 718
ClusterJDatastoreException (ClusterJ), 670	columns (ClusterJ), 720, 722, 725
ClusterJDatastoreException.Classification (ClusterJ), 672	columnType (ClusterJ), 681
ClusterJException (ClusterJ), 673	ColumnType (ClusterJ), 683
ClusterJFatalException (ClusterJ), 674	Commit
ClusterJFatalInternalException (ClusterJ), 675	defined, 6
ClusterJFatalUserException (ClusterJ), 675	commit (ClusterJ), 717
ClusterJHelper (ClusterJ), 676	commit() (method of Transaction), 747
ClusterJUserException (ClusterJ), 680	commitStatus() (method of NdbTransaction), 259
cmp() (method of NdbScanFilter), 237	CommitStatusType (NdbTransaction data type), 259
coding examples	computeHash() (method of Ndb), 113
MGM API, 645	concurrency control, 14
NDB API, 467	connect() (method of Mynode), 743
Column	connect() (method of Ndb_cluster_connection), 135
and NDB Cluster replication, 38	connecting to multiple clusters
NDB API class, 34	example, 472, 648
Column (ClusterJ), 717	ConnectionProperties() object (Node.js), 741
column (ClusterJ), 722, 724, 725	Connector for JavaScript, 735
Column::ArrayType, 38	Batch class, 737
Column::equal(), 39	ColumnMetadata class, 746
Column::getArrayType(), 39	concepts, 735
Column::getCharset(), 39	Context class, 737
Column::getColumnNo(), 40	Converter class, 740
Column::getDefaultValue(), 40	CPU architecture, 736
Column::getInlineSize(), 40	Errors, 740
Column::getLength(), 41	examples, 748
Column::getName(), 41	FieldMapping class, 745
Column::getNullable(), 41	installing, 736
Outumm.genvanable(), 41	mataning, 700

Mynode, 741	Datafile::getSize(), 54
prerequisites, 736	Datafile::getTablespace(), 55
Session class, 743	Datafile::getTablespaceId(), 55
SessionFactory class, 744	Datafile::setNode(), 55
TableMapping class, 745	Datafile::setPath(), 55
TableMetadata class, 746	Datafile::setSize(), 56
test program, 736	Datafile::setTablespace(), 56
Transaction class, 747	Dbug (ClusterJ), 693
Connector/J	debug (ClusterJ), 695, 695
known issues, 733	defaultValue (ClusterJ), 718
Constants (ClusterJ), 684	DEFAULT_PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZ
containers table (ndbmemcache), 764	(ClusterJ), 687
Context class (Connector for JavaScript), 737	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREM
Context.find(), 738	(ClusterJ), 687
Context.isBatch(), 740	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREM
Context.load(), 738	(ClusterJ), 687
Context.persist(), 738	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCREM
Context.remove(), 738	(ClusterJ), 688
Context.save(), 739	DEFAULT_PROPERTY_CLUSTER_CONNECT_DELAY
Context.update(), 739	(ClusterJ), 688
Converter class (Connector for JavaScript), 740	DEFAULT_PROPERTY_CLUSTER_CONNECT_RETRIES
copy() (method of NdbInterpretedCode), 201	(ClusterJ), 688
CPU architecture	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTI
Connector for JavaScript, 736	(ClusterJ), 688
createBatch() (method of Session), 744	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEF
createDatafile() (method of Dictionary), 61	(ClusterJ), 688
createEvent() (method of Dictionary), 61	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGN
createForeignKey() (method of Dictionary), 61	(ClusterJ), 688
createHashMap() (method of Dictionary), 62	DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE
createIndex() (method of Dictionary), 62	(ClusterJ), 688
createLogfileGroup() (method of Dictionary), 62	DEFAULT_PROPERTY_CLUSTER_DATABASE
createQuery (ClusterJ), 705	(ClusterJ), 688
createQueryDefinition (ClusterJ), 730	DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS
createRecord() (method of Dictionary), 62	(ClusterJ), 689
createTable() (method of Dictionary), 63	DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THREAD
createTablespace() (method of Dictionary), 64	(ClusterJ), 689
createUndofile() (method of Dictionary), 64	DEFAULT_PROPERTY_CONNECTION_POOL_SIZE
currentState (ClusterJ), 713	(ClusterJ), 689
currentTransaction (ClusterJ), 706	DEFAULT_PROPERTY_CONNECTION_RECONNECT_TIMEOU
currentTransaction() (method of Session), 744	(ClusterJ), 689
_	def_label() (method of NdbInterpretedCode), 201
D	def_sub() (method of NdbInterpretedCode), 201
data node	deleteCurrentTuple() (method of NdbScanOperation),
defined, 3	245
Datafile	deletePersistent (ClusterJ), 706, 706
NDB API class, 51	deletePersistentAll (ClusterJ), 700, 706, 706
Datafile::getFileNo(), 53	deleteTuple() (method of NdbIndexOperation), 176
Datafile::getFree(), 53	deleteTuple() (method of NdbOperation), 210
Datafile::getNode(), 53	deleteTuple() (method of NdbTransaction), 259
Datafile::getObjectId(), 54	Dictionary
Datafile::getObjectStatus(), 54	NDB API class, 56
Datafile::getObjectVersion(), 54	Dictionary::beginSchemaTrans(), 60
Datafile::getPath(), 54	Dictionary::create*() methods and NDB Cluster replication, 59
	and NDD Oldstor repribation, 00

Dictionary::createDatafile(), 61	dropTablespace() (method of Dictionary), 66
Dictionary::createEvent(), 61	dropUndofile() (method of Dictionary), 66
Dictionary::createForeignKey(), 61	DynamicObject (ClusterJ), 697
Dictionary::createHashMap(), 62	DynamicObjectDelegate (ClusterJ), 697
Dictionary::createIndex(), 62	
Dictionary::createLogfileGroup(), 62	E
Dictionary::createRecord(), 62	Element
Dictionary::createTable(), 63	NDB API structure, 74
Dictionary::createTablespace(), 64	Elements (ClusterJ)
Dictionary::createUndofile(), 64	allowsNull, 718
Dictionary::dropDatafile(), 64	column, 722, 724, 725
Dictionary::dropEvent(), 64	columns, 720, 724, 725
Dictionary::dropForeignKey(), 65	defaultValue, 718
Dictionary::dropIndex(), 65	extensions, 724
Dictionary::dropLogfileGroup(), 65	·
Dictionary::dropTable(), 66	key, 719
Dictionary::dropTablespace(), 66	name, 718, 720, 725
Dictionary::dropUndofile(), 66	nullValue, 724
Dictionary::endSchemaTrans(), 66	primaryKey, 724
Dictionary::getDatafile(), 67	unique, 720
Dictionary::getDefaultHashMap(), 67	value, 719, 719, 720, 721
Dictionary::getEvent(), 68	vendorName, 719
Dictionary::getForeignKey(), 68	end() (method of NdbScanFilter), 238
Dictionary::getHashMap(), 68	endSchemaTrans() (method of Dictionary), 66
Dictionary::getIndex(), 69	end_of_bound() (method of NdbIndexScanOperation)
Dictionary::getLogfileGroup(), 69	178
Dictionary::getNdbError(), 69	ENV_CLUSTERJ_LOGGER_FACTORY_NAME
Dictionary::getTable(), 70	(ClusterJ), 689
Dictionary::getTablespace(), 70	eq() (method of NdbScanFilter), 239
Dictionary::getUndofile(), 70	equal (ClusterJ), 727
Dictionary::hasSchemaTrans(), 71	equal() (method of Column), 39
Dictionary::initDefaultHashMap(), 71	equal() (method of HashMap), 96
Dictionary::invalidateIndex(), 71	equal() (method of NdbOperation), 210
Dictionary::invalidateTable(), 72	equal() (method of Table), 286
Dictionary::List	error classification (defined), 161
NDB API class, 108	error classifications, 466
Dictionary::List::Element	error code (defined), 162
NDB API structure, 74	Error code types, 318
Dictionary::listIndexes(), 72	Error codes, 318
Dictionary::listObjects(), 72	error detail message (defined), 162
Dictionary::prepareHashMap(), 73	error handling
Dictionary::releaseRecord(), 74	example, 477
Dictionary::removeCachedIndex(), 74	overview, 12
Dictionary::removeCachedTable(), 74	error message (defined), 162
Dictionary::SchemaTransFlag, 67	Error status, 161
distribution awareness, 131	error types
double_value() (method of NdbRecAttr), 228	in applications, 478
	errors
dropDatafile() (method of Dictionary), 64 dropEvent() (method of Dictionary), 64	classifying, 466
dropEventOperation() (method of Ndb), 114	MGM API, 643
. , , , , , , , , , , , , , , , , , , ,	NDB API, 314
dropForeignKey() (method of Dictionary), 65	Errors (Connector for JavaScript), 740
dropIndex() (method of Dictionary), 65	ER_DDL, 85
dropLogfileGroup() (method of Dictionary), 65 dropTable() (method of Dictionary), 66	Event
IOD FADICO UNCUOU DI DIGUOTATVI. 1010	

NDB API class, 75	extensions (ClusterJ), 724
event reporting	_
DDL, 85	F
event subscriptions	FieldMapping class (Connector for JavaScript), 745
lifetime, 114	Fields (ClusterJ)
Event::addEventColumn(), 78	DEFAULT_PROPERTY_CLUSTER_BYTE_BUFFER_POOL_S
Event::addEventColumns(), 79	687
Event::addTableEvent(), 80	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCR
Event: EventDurability, 80	687
Event::EventReport, 81 Event::getDurability(), 82	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCR
Event::getEventColumn(), 82	687
Event::getName(), 82	DEFAULT_PROPERTY_CLUSTER_CONNECT_AUTO_INCRI
Event::getNoOfEventColumns(), 82	688
Event::getObjectId(), 83	DEFAULT_PROPERTY_CLUSTER_CONNECT_DELAY,
Event::getObjectNatus(), 83	688
Event::getObjectVersion(), 83	DEFAULT_PROPERTY_CLUSTER_CONNECT_RETRIES,
Event::getReport(), 83	688
Event::getTable(), 83	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_AI
Event::getTable(), 63 Event::getTableEvent(), 84	688
Event::getTableName(), 84	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_BI
Event::mergeEvents(), 84	688
Event::setDurability(), 85	DEFAULT_PROPERTY_CLUSTER_CONNECT_TIMEOUT_M
Event::setName(), 85	688
Event::setReport(), 85	DEFAULT_PROPERTY_CLUSTER_CONNECT_VERBOSE,
Event::setTable(), 86	688
Event::TableEvent, 86	DEFAULT_PROPERTY_CLUSTER_DATABASE, 688
EventBufferMemoryUsage	DEFAULT_PROPERTY_CLUSTER_MAX_TRANSACTIONS,
NDB API structure, 115	689
EventDurability (Event data type), 80	DEFAULT_PROPERTY_CONNECTION_POOL_RECV_THRE
EventReport (Event data type), 81	689
events	DEFAULT_PROPERTY_CONNECTION_POOL_SIZE,
example, 648	689 DEFAULT PROPERTY CONNECTION RECONNECT TIME
handling	689
example, 554	ENV_CLUSTERJ_LOGGER_FACTORY_NAME, 689
examples	INDEX_USED, 699
Connector for JavaScript, 748	PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES,
Exceptions (ClusterJ)	689
ClusterJDatastoreException, 670	PROPERTY_CLUSTER_CONNECTION_SERVICE,
ClusterJException, 673	691
ClusterJFatalException, 674	PROPERTY_CLUSTER_CONNECTSTRING, 691
ClusterJFataIInternalException, 675	PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_BA
ClusterJFatalUserException, 675	689
ClusterJUserException, 680	PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_ST
ExecType (NdbTransaction data type), 260	690
execute (ClusterJ), 700, 700, 701	PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_ST
execute() (method of Batch), 737	690
execute() (method of NdbEventOperation), 168	PROPERTY CLUSTER CONNECT DELAY, 690
execute() (method of NdbTransaction), 261	PROPERTY_CLUSTER_CONNECT_RETRIES, 690
executePendingBlobOps() (method of NdbTransaction),	PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER,
262	690
explain (ClusterJ), 701	PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE,
Extension (ClusterJ), 719	690
Extensions (ClusterJ), 719	

		fractional seconds
	690	ndbmemcache, 771
	PROPERTY_CLUSTER_CONNECT_VERBOSE, 690	fragment
	PROPERTY_CLUSTER_DATABASE, 691	defined, 4
	PROPERTY_CLUSTER_MAX_TRANSACTIONS, 691	fragment replica
	PROPERTY_CONNECTION_POOL_NODEIDS, 691	defined, 4
	PROPERTY_CONNECTION_POOL_RECV_THREAD_A	.Œīālgināēhūīī yp ēH(®lēj&ldi@lata , type), 275
	691	
	PROPERTY_CONNECTION_POOL_RECV_THREAD_C	COUIDS,
	691	GCP (Global Checkpoint)
	PROPERTY_CONNECTION_POOL_SIZE, 692	defined, 3
	${\tt PROPERTY_CONNECTION_RECONNECT_TIMEOUT},$	ge() (method of NdbScanFilter), 240
	692	get (ClusterJ), 695, 731
	PROPERTY_DEFER_CHANGES, 692	getArrayType() (method of Column), 39
	PROPERTY_JDBC_DRIVER_NAME, 692	getAutoGrowSpecification() (method of LogfileGroup),
	PROPERTY_JDBC_PASSWORD, 692	105
	PROPERTY_JDBC_URL, 692	getAutoGrowSpecification() (method of Tablespace), 306
	PROPERTY_JDBC_USERNAME, 693	getBlobEventName() (method of NdbBlob), 148
	SCAN_TYPE, 699	getBlobHandle() (method of NdbEventOperation), 168
	SCAN_TYPE_INDEX_SCAN, 699	getBlobHandle() (method of NdbOperation), 212
	SCAN_TYPE_PRIMARY_KEY, 699	getBlobTableName() (method of NdbBlob), 149
	SCAN_TYPE_TABLE_SCAN, 700	getBooleanProperty (ClusterJ), 677
	SCAN_TYPE_UNIQUE_KEY, 700	getCharset() (method of Column), 39
	SESSION_FACTORY_SERVICE_CLASS_NAME, 693	getChildColumnCount() (method of ForeignKey), 90
	SESSION_FACTORY_SERVICE_FILE_NAME, 693	getChildColumnNo() (method of ForeignKey), 90
fir	alise() (method of NdbInterpretedCode), 202	getChildIndex() (method of ForeignKey), 91
fir	nd (ClusterJ), 707	getChildTable() (method of ForeignKey), 90
fir	nd() (method of Context), 738	getClassification (ClusterJ), 671
flo	pat_value() (method of NdbRecAttr), 229	getCode (ClusterJ), 671
flι	ish (ClusterJ), 695, 707	• ,
F	preignKey	getColumn() (method of Index), 100
	NDB API class, 87	getColumn() (method of NdbBlob), 149
F	preignKey(), 89	getColumn() (method of NdbRecAttr), 229
	preignKey() (ForeignKey constructor), 89	getColumn() (method of Table), 286
	preignKey::getChildColumnCount(), 90	getColumnNo() (method of Column), 40
	preignKey::getChildColumnNo(), 91	getConnectionPoolSessionCounts (ClusterJ), 713
	preignKey::getChildIndex(), 91	getDatabaseName() (method of Ndb), 116
	preignKey::getChildTable(), 90	getDatabaseSchemaName() (method of Ndb), 116
	preignKey::getName(), 89	getDatafile() (method of Dictionary), 67
	preignKey::getObjectId(), 93	getDefaultHashMap() (method of Dictionary), 67
	preignKey::getObjectStatus(), 93	getDefaultLogfileGroup() (method of Tablespace), 306
	preignKey::getObjectVersion(), 94	getDefaultLogfileGroupId() (method of Tablespace), 306
	preignKey::getOnDeleteAction(), 92	getDefaultNoPartitionsFlag() (method of Table), 286
	oreignKey::getOnUpdateAction(), 92	getDefaultValue() (method of Column), 40
	preignKey::getParentColumnCount(), 90	getDescending() (method of NdbIndexScanOperation),
	preignKey::getParentColumnNo(), 91	179
	preignKey::getParentIndex(), 91	getDictionary() (method of Ndb), 115
	preignKey::getParentTable(), 90	getDurability() (method of Event), 82
	preignKey::setChild(), 92	getEmptyBitmask() (method of NdbDictionary), 157
	preignKey::setName(), 92	getEpoch() (method of NdbEventOperation), 168
	preignKey::setOnDeleteAction(), 93	getEvent() (method of Dictionary), 68
	preignKey::setOnUpdateAction(), 93	getEventColumn() (method of Event), 82
	preignKey::setParent(), 92	getEventType() (method of NdbEventOperation)
	und (ClusterJ), 707	(DEPRECATED), 169
11.		

getEventType2() (method of NdbEventOperation), 169 getName() (method of HashMap), 96 getExtentSize() (method of Tablespace), 307 getName() (method of Index), 101 getExtraMetadata() (method of Table), 287 getName() (method of LogfileGroup), 106 getFileNo() (method of Datafile), 53 getName() (method of Tablespace), 307 getFileNo() (method of Undofile) (OBSOLETE), 311 getNdbError() (method of Dictionary), 69 getFirstAttrId() (method of NdbDictionary), 157 getNdbError() (method of Ndb), 118 getForeignKey() (method of Dictionary), 68 getNdbError() (method of NdbBlob), 150 getFragmentCount() (method of Table), 287 getNdbError() (method of NdbEventOperation), 170 getFragmentData() (method of Table), 287 getNdbError() (method of NdbInterpretedCode), 202 getFragmentDataLen() (method of Table), 288 getNdbError() (method of NdbOperation), 213 getNdbError() (method of NdbScanFilter), 240 getFragmentNodes() (method of Table), 288 getFragmentType() (method of Table), 288 getNdbError() (method of NdbTransaction), 263 getFree() (method of Datafile), 53 getNdbErrorDetail() (method of Ndb), 119 getFrmData() (method of Table), 288 getNdbErrorLine() (method of NdbOperation), 214 getFrmLength() (method of Table), 289 getNdbErrorLine() (method of NdbTransaction), 263 getGCI() (method of NdbEventOperation) getNdbErrorOperation() (method of NdbTransaction), 264 getNdbIndexOperation() (method of NdbTransaction), (DEPRECATED), 169 getGCI() (method of NdbTransaction), 262 264 getGCIEventOperations() (method of Ndb) getNdbIndexScanOperation() (method of (DEPRECATED), 116 NdbTransaction), 264 getHashMap() (method of Dictionary), 68 getNdbObjectName() (method of Ndb), 119 getHashMap() (method of Table), 289 getNdbOperation() (method of NdbBlob), 150 getHighestQueuedEpoch() (method of Ndb), 117 getNdbOperation() (method of NdbScanFilter), 241 getNdbOperation() (method of NdbTransaction), 264 getIndex() (method of Dictionary), 69 getIndex() (method of NdbIndexOperation), 176 getNdbScanOperation() (method of NdbTransaction), getInlineSize() (method of Column), 40 getKValue() (method of Table), 289 getNdbTransaction() (method of NdbOperation), 214 getLatestGCI() (method of Ndb), 118 getNdbTransaction() (method of NdbScanOperation), getLatestGCI() (method of NdbEventOperation) (DEPRECATED), 169 getNextAttrId() (method of NdbDictionary), 157 getLength() (method of Column), 41 getNextCompletedOperation() (method of getLength() (method of NdbBlob), 149 NdbTransaction), 265 getLinearFlag() (method of Table), 289 getNode() (method of Datafile), 53 getLockHandle() (method of NdbOperation), 212 getNode() (method of Undofile) (OBSOLETE), 312 getLockMode() (method of NdbOperation), 213 getNoOfColumns() (method of Index), 101 getLogfileGroup() (method of Dictionary), 69 getNoOfColumns() (method of Table), 291 getLogfileGroup() (method of Undofile), 311 getNoOfEventColumns() (method of Event), 82 getLogfileGroupId() (method of Undofile), 311 getNoOfPrimaryKeys() (method of Table), 291 getLogging() (method of Index), 100 getNull() (method of NdbBlob), 149 getLogging() (method of Table), 290 getNullable() (method of Column), 41 getNullBitOffset() (method of NdbDictionary), 157 getMapLen() (method of HashMap), 96 getObjectId() (method of Datafile), 54 getMapping() (method of Session), 743 getMapValues() (method of HashMap), 96 getObjectId() (method of Event), 83 getMaxLoadFactor() (method of Table), 290 getObjectId() (method of ForeignKey), 93 getObjectId() (method of HashMap), 97 getMaxPendingBlobReadBytes() (method of getObjectId() (method of Index), 102 NdbTransaction), 263 getMaxPendingBlobWriteBytes() (method of getObjectId() (method of LogfileGroup), 106 NdbTransaction), 263 getObjectId() (method of Object), 276 getMaxRows() (method of Table), 290 getObjectId() (method of Table), 291 getMinLoadFactor() (method of Table), 290 getObjectId() (method of Tablespace), 307 getMysqlCode (ClusterJ), 671 getObjectId() (method of Undofile), 312 getName() (method of Column), 41 getObjectStatus() (method of Datafile), 54 getName() (method of Event), 82 getObjectStatus() (method of Event), 83 getName() (method of ForeignKey), 89 getObjectStatus() (method of ForeignKey), 93

getRowChecksumIndicator() (method of Table), 294 getObjectStatus() (method of HashMap), 97 getObjectStatus() (method of Index), 101 getRowGCIIndicator() (method of Table), 294 getObjectStatus() (method of LogfileGroup), 106 getServiceInstance (ClusterJ), 677, 677, 677, 678 getObjectStatus() (method of Object), 276 getServiceInstances (ClusterJ), 678 getObjectStatus() (method of Table), 291 getSession (ClusterJ), 713, 714 getObjectStatus() (method of Tablespace), 307 getSession() (method of Batch), 737 getObjectStatus() (method of Undofile), 312 getSessionFactory (ClusterJ), 678, 679, 716 getObjectType() (method of Table) (OBSOLETE), 292 getSingleUserMode() (method of Table), 294 getObjectVersion() (method of Datafile), 54 getSize() (method of Datafile), 54 getObjectVersion() (method of Event), 83 getSize() (method of Undofile), 313 getObjectVersion() (method of ForeignKey), 94 getSizeInBytesForRecord() (method of Column), 43 getObjectVersion() (method of HashMap), 97 getSorted() (method of NdbIndexScanOperation), 179 getObjectVersion() (method of Index), 101 getState() (method of NdbBlob), 151 getObjectVersion() (method of LogfileGroup), 106 getState() (method of NdbEventOperation), 171 getObjectVersion() (method of Object), 276 getStatus (ClusterJ), 672 getObjectVersion() (method of Table), 292 getStorageType() (method of Column), 44 getObjectVersion() (method of Tablespace), 308 getStringProperty (ClusterJ), 679 getObjectVersion() (method of Undofile), 312 getStripeSize() (method of Column), 44 getOffset() (method of NdbDictionary), 158 getTable() (method of Dictionary), 70 getOnDeleteAction() (method of ForeignKey), 92 getTable() (method of Event), 83 getOnUpdateAction() (method of ForeignKey), 92 getTable() (method of Index), 102 getOpenSessionFactories() (method of Mynode), 743 getTable() (method of NdbInterpretedCode), 202 getOpenSessions() (method of SessionFactory), 744 getTable() (method of NdbOperation), 214 getParentColumnCount() (method of ForeignKey), 90 getTableEvent() (method of Event), 84 getParentColumnNo() (method of ForeignKey), 91 getTableId() (method of Table), 294 getParentIndex() (method of ForeignKey), 91 getTableMetadata() (method of Session), 744 getParentTable() (method of ForeignKey), 90 getTableName() (method of Event), 84 getPartitionBalance() (method of Table), 292 getTableName() (method of NdbOperation), 214 getPartitionBalanceString() (method of Table), 292 getTablespace() (method of Datafile), 55 getPartitionId() (method of Table), 293 getTablespace() (method of Dictionary), 70 getTablespace() (method of Table), 294 getPartitionKey() (method of Column), 42 getPartSize() (method of Column), 42 getTablespaceData() (method of Table), 295 getPath() (method of Datafile), 54 getTablespaceDataLen() (method of Table), 295 getPath() (method of Undofile), 312 getTablespaceId() (method of Datafile), 55 getPos() (method of NdbBlob), 150 getTablespaceNames() (method of Table), 296 getPreBlobHandle() (method of NdbEventOperation), 170 getTablespaceNamesLen() (method of Table), 296 getPrecision() (method of Column), 42 getTransactionId() (method of NdbTransaction), 265 getPreValue() (method of NdbEventOperation), 170 getType (ClusterJ), 731 getType() (method of Column), 44 getPrimaryKey() (method of Column), 43 getPrimaryKey() (method of Table), 293 getType() (method of Index), 102 getPruned() (method of NdbScanOperation), 246 getType() (method of NdbOperation), 214 getQueryBuilder (ClusterJ), 708 getType() (method of NdbRecAttr), 229 getRangeListData() (method of Table), 293 getUndoBufferSize() (method of LogfileGroup), 107 getRangeListDataLen() (method of Table), 293 getUndofile() (method of Dictionary), 70 getUndoFreeWords() (method of LogfileGroup), 107 getRecordIndexName() (method of NdbDictionary), 158 getRecordRowLength() (method of NdbDictionary), 158 getValue() (method of NdbBlob), 151 getRecordTableName() (method of NdbDictionary), 158 getValue() (method of NdbEventOperation), 171 getRecordType() (method of NdbDictionary), 159 getValue() (method of NdbOperation), 215 getRecvThreadActivationThreshold (ClusterJ), 713 getValuePtr() (method of NdbDictionary), 159 getRecvThreadCPUids (ClusterJ), 713 GetValueSpec getReport() (method of Event), 83 NDB API structure, 216 getResultList (ClusterJ), 701 getVersion() (method of NdbBlob), 151 getRollbackOnly (ClusterJ), 717 getWordsUsed() (method of NdbInterpretedCode), 202 getRollbackOnly() (method of Transaction), 748

get_auto_reconnect() (method of	Index::getColumn(), 100
Ndb_cluster_connection), 136	Index::getLogging(), 100
get_eventbuffer_free_percent() (method of Ndb), 117	Index::getName(), 101
get_eventbuf_max_alloc()() (method of Ndb), 116	Index::getNoOfColumns(), 101
get_event_buffer_memory_usage() (method of Ndb), 117	Index::getObjectId(), 102
get_latest_error() (method of Ndb_cluster_connection),	Index::getObjectStatus(), 101
136	Index::getObjectVersion(), 101
get_latest_error_msg() (method of	Index::getTable(), 102
Ndb_cluster_connection), 136	Index::getType(), 102
get_max_adaptive_send_time() (method of	Index::setName(), 102
Ndb_cluster_connection), 137	Index::setTable(), 103
get_next_ndb_object() (method of	Index::setType(), 103
Ndb_cluster_connection), 137	Index::Type, 103
get_num_recv_threads() (method of	IndexBound
Ndb_cluster_connection), 137	NDB API structure, 179
get_range_no() (method of NdbIndexScanOperation),	
	INDEX_USED (ClusterJ), 699
179	Indices (ClusterJ), 721
get_size_in_bytes() (method of NdbRecAttr), 229	init() (method of Ndb), 121
get_system_name() (method of	initDefaultHashMap() (method of Dictionary), 71
Ndb_cluster_connection), 138	initial node restart
grant tables	defined, 4
and NDB API applications, 2	insertTuple() (method of NdbOperation), 218
greaterEqual (ClusterJ), 728	insertTuple() (method of NdbTransaction), 266
greaterThan (ClusterJ), 728	int32_value() (method of NdbRecAttr), 230
Group (NdbScanFilter data type), 241	int64_value() (method of NdbRecAttr), 230
gt() (method of NdbScanFilter), 241	int8_value() (method of NdbRecAttr), 229
	integer comparison methods (of NdbScanFilter class),
H	235
hasDefaultValues() (method of Table), 296	Interfaces (ClusterJ)
hasError() (method of NdbEventOperation)	ColumnMetadata, 680
(DEPRECATED), 172	Constants, 684
HashMap	Dbug, 693
NDB API class, 94	DynamicObjectDelegate, 697
HashMap constructor, 95	Predicate, 725
•	PredicateOperand, 726
HashMap::getMapl.op() 06	Query, 698
HashMap::getMapLen(), 96	QueryBuilder, 729
HashMap::getMapValues(), 96	QueryDefinition, 730
HashMap::getName(), 96	QueryDomainType, 731
HashMap::getObjectId(), 97	Results, 703
HashMap::getObjectStatus(), 97	Session, 704
HashMap::getObjectVersion(), 97	SessionFactory, 712
HashMap::setMap(), 96	SessionFactoryService, 716
HashMap::setName(), 95	Transaction, 716
hasSchemaTrans() (method of Dictionary), 71	interpret_exit_last_row() (method of
	NdbInterpretedCode), 203
	interpret_exit_nok() (method of NdbInterpretedCode),
in (ClusterJ), 728	203
Index	interpret_exit_ok() (method of NdbInterpretedCode), 203
NDB API class, 97	invalidateIndex() (method of Dictionary), 71
Index (ClusterJ), 720	, · · · · · · · · · · · · · · · · · · ·
Index (Glusters), 720 Index::addColumn(), 99	invalidateTable() (method of Dictionary), 72
Index::addColumnName(), 99	isActive (ClusterJ), 717
Index::addColumnNames(), 100	isActive() (method of Transaction), 747
machaddColumniames(), 100	isBatch() (method of Context), 740

isClosed (ClusterJ), 708	load_const_u16() (method of NdbInterpretedCode), 204
sClosed() (method of Session), 744	load_const_u32() (method of NdbInterpretedCode), 204
sConsistent() (method of Ndb) (DEPRECATED), 121	load_const_u64() (method of NdbInterpretedCode), 204
sConsistent() (method of NdbEventOperation)	Lob (ClusterJ), 721
(DEPRECATED), 172	lock handles
isConsistentGCI() (method of Ndb) (DEPRECATED), 122	NDB API, 212, 272
sEmptyEpoch() (method of NdbEventOperation), 173	lock handling
isErrorEpoch() (method of NdbEventOperation), 173	and scan operations, 11
isExpectingHigherQueuedEpochs() (method of Ndb), 122	lockCurrentTuple() (method of NdbScanOperation), 247
isfalse() (method of NdbScanFilter), 239	locking and transactions
isNotNull (ClusterJ), 728	NDB API, 212
isnotnull() (method of NdbScanFilter), 239	LockMode (ClusterJ), 697
isNull (ClusterJ), 728	LockMode (NdbOperation data type), 218
isNull() (method of NdbDictionary), 159	lock_ndb_objects() (method of ndb_cluster_connection)
isNULL() (method of NdbRecAttr), 230	138
isnull() (method of NdbScanFilter), 240	LogfileGroup
isOverrun() (method of NdbEventOperation), 173	NDB API class, 104
isPartitionKey (ClusterJ), 681	LogfileGroup::getAutoGrowSpecification(), 105
isPrimaryKey (ClusterJ), 681	LogfileGroup::getName(), 106
istrue() (method of NdbScanFilter), 240	LogfileGroup::getObjectId(), 106
iteration	
Ndb objects, 137	LogfileGroup::getObjectStatus(), 106
	LogfileGroup::getObjectVersion(), 106
iterator (ClusterJ), 703	LogfileGroup::getUndoBufferSize(), 107
1	LogfileGroup::getUndoFreeWords(), 107
J	LogfileGroup::setAutoGrowSpecification(), 107
Java, 653	LogfileGroup::setName(), 107
JavaScript, 735	LogfileGroup::setUndoBufferSize(), 107
API documentation, 737	lookup (ClusterJ), 673
avaType (ClusterJ), 681	It() (method of NdbScanFilter), 242
JDBC	
known issues, 733	M
	makePersistent (ClusterJ), 708
K	makePersistentAll (ClusterJ), 708
key (ClusterJ), 719	management (MGM) node
Key_part_ptr	defined, 3
NDB API structure, 122	mapField() (method of TableMapping), 745
11007111011401410, 122	markModified (ClusterJ), 709
	maximumLength (ClusterJ), 681
LOD (harad Obardaria)	medium_value() (method of NdbRecAttr), 230
LCP (Local Checkpoint)	memcache commands
defined, 3	ndbmemcache, 767
le() (method of NdbScanFilter), 242	mergeEvents() (method of Event), 84
lessEqual (ClusterJ), 729	mergeEvents() (method of NdbEventOperation), 173
lessThan (ClusterJ), 729	Methods (ClusterJ)
like (ClusterJ), 729	and, 726
List	append, 694
NDB API class, 108	begin, 717
listBatches() (method of Session), 744	between, 727
listIndexes() (method of Dictionary), 72	charsetName, 681
listObjects() (method of Dictionary), 72	close, 705, 713
listTables() (method of Session), 744	columnType, 681
oad (ClusterJ), 708	commit, 717
load() (method of Context), 738	createQuery, 705
load_const_null() (method of NdbInterpretedCode), 204	, ,

createQueryDefinition, 730	nullable, 682
currentState, 713	number, 682
currentTransaction, 706	or, 726
debug, 695, 695	output, 695
deletePersistent, 706, 706	param, 730
deletePersistentAll, 700, 706, 706	persist, 709
equal, 727	pop, 696
execute, 700, 700, 701	precision, 682
explain, 701	print, 696
find, 707	push, 696, 696
flush, 695, 707	reconnect, 714, 714
found, 707	release, 710
get, 695, 731	remove, 710
getBooleanProperty, 677	rollback, 717
getClassification, 671	savePersistent, 710
getCode, 671	saver ersistent, 710
- -	
getConnectionPoolSessionCounts, 713	scale, 682
getMysqlCode, 671	set, 696, 696
getQueryBuilder, 708	setLimits, 702
getRecvThreadActivationThreshold, 713	setLockMode, 711
getRecvThreadCPUids, 713	setOrdering, 702
getResultList, 701	setParameter, 703
getRollbackOnly, 717	setPartitionKey, 711
getServiceInstance, 677, 677, 677, 678	setRecvThreadActivationThreshold, 715
getServiceInstances, 678	setRecvThreadCPUids, 715
getSession, 713, 714	setRollbackOnly, 717
getSessionFactory, 678, 679, 716	trace, 696
getStatus, 672	unloadSchema, 711
getStringProperty, 679	updatePersistent, 712
getType, 731	updatePersistentAll, 712
greaterEqual, 728	where, 731
greaterThan, 728	MGM API
in, 728	coding examples, 645
isActive, 717	errors, 643
isClosed, 708	multiple clusters, 15
isNotNull, 728	multiple clusters, connecting to
isNull, 728	example, 472, 648
isPartitionKey, 681	Mynode (Connector for JavaScript), 741
isPrimaryKey, 681	Mynode.connect(), 743
iterator, 703	Mynode.ConnectionProperties(), 741
javaType, 681	Mynode.getOpenSessionFactories(), 743
lessEqual, 729	Mynode.openSession(), 742
lessThan, 729	MySQL NDB Cluster Connector for Java, 653
like, 729	and foreign keys, 733
load, 708	and joins, 733
lookup, 673	and TIMESTAMP, 733
makePersistent, 708	and views, 733
makePersistentAll, 708	known issues, 733, 733
markModified, 709	MySQL privileges
maximumLength, 681	and NDB API applications, 2
name, 682	and 1100 / 11 1 applications, 2
newDbug, 679	NI .
newInstance, 709, 709	N
not, 726, 730	name (ClusterJ), 682, 718, 720, 725
1101, 120, 100	

NDB	Ndb::setNdbObjectName(), 130
defined, 4	Ndb::set_eventbuffer_free_percent(), 129
record structure, 14	Ndb::set_eventbuf_max_alloc(), 129
Ndb	Ndb::startTransaction(), 130
NDB API class, 108	NdbBlob
NDB API	close(), 148
and MySQL privileges, 2	NDB API class, 143
coding examples, 467	NdbBlob::ActiveHook type, 147
defined, 5	NdbBlob::blobsFirstBlob(), 147
errors, 314	NdbBlob::blobsNextBlob(), 147
lock handles, 212, 272	NdbBlob::getBlobEventName(), 148
NDB API classes	NdbBlob::getBlobTableName(), 149
overview, 5	NdbBlob::getColumn(), 149
NDB Cluster	NdbBlob::getLength(), 149
benchmarks, 7	NdbBlob::getNdbError(), 150
configuration (ndbmemcache), 761	NdbBlob::getNdbOperation(), 150
memcache, 759	NdbBlob::getNull(), 149
ndbmemcache, 759	NdbBlob::getPos(), 150
Node.js, 735	NdbBlob::getState(), 151
performance, 6	NdbBlob::getValue(), 151
NDB Cluster replication	NdbBlob::getVersion(), 151
and Column, 38	NdbBlob::readData(), 152
and Dictionary::create*() methods, 59	NdbBlob::setActiveHook(), 152
Ndb::closeTransaction(), 113	NdbBlob::setNull(), 152
Ndb::computeHash(), 113	NdbBlob::setPos(), 152
Ndb::dropEventOperation(), 114	NdbBlob::setValue(), 153
Ndb::EventBufferMemoryUsage	NdbBlob::State type, 153
NDB API structure, 115	NdbBlob::truncate(), 154
Ndb::getDatabaseName(), 116	NdbBlob::writeData(), 154
Ndb::getDatabaseSchemaName(), 116	NdbDictionary
Ndb::getDictionary(), 115	NDB API class, 154
Ndb::getGClEventOperations() (DEPRECATED), 116	NdbDictionary::AutoGrowSpecification
Ndb::getHighestQueuedEpoch(), 117	NDB API structure, 156
Ndb::getLatestGCI() (DEPRECATED), 118	NdbDictionary::Column
Ndb::getNdbError(), 118	NDB API class, 34
Ndb::getNdbErrorDetail(), 119	NdbDictionary::Dictionary
Ndb::getNdbObjectName(), 119	NDB API class, 56
Ndb::get_eventbuffer_free_percent(), 117	NdbDictionary::Event
Ndb::get_eventbuf=nax_alloc(), 116	NDB API class, 75
Ndb::get_event_buffer_memory_usage(), 117	NdbDictionary::getEmptyBitmask(), 157
	NdbDictionary::getFirstAttrId(), 157
Ndb::init(), 121 Ndb::isConsistent() (DEPRECATED), 121	NdbDictionary::getNextAttrld(), 157
, ,	NdbDictionary::getNullBitOffset(), 157
Ndb::isConsistentGCI() (DEPRECATED), 122 Ndb::isExpectingHigherQueuedEpochs(), 122	, ,
	NdbDictionary::getOffset(), 158
Ndb::Key_part_ptr	NdbDictionary::getRecordIndexName(), 158
NDB API structure, 122	NdbDictionary::getRecordRowLength(), 158
Ndb::nextEvent() (DEPRECATED), 123	NdbDictionary::getRecordTableName(), 158
Ndb::nextEvent2(), 123	NdbDictionary::getRecordType(), 159
Ndb::PartitionSpec	NdbDictionary::getValuePtr(), 159
NDB API structure, 124	NdbDictionary::Index
Ndb::pollEvents() (DEORECATED), 126	NDB API class, 97
Ndb::pollEvents2(), 127	NdbDictionary::isNull(), 159
Ndb::setDatabaseName(), 128	NdbDictionary::LogfileGroup
Ndb::setDatabaseSchemaName(), 128	NDB API class, 104

NdbDictionary::Object NdbIndexScanOperation::getDescending(), 179 NdbIndexScanOperation::getSorted(), 179 NDB API class, 274 NdbDictionary::RecordSpecification NdbIndexScanOperation::get_range_no(), 179 NDB API structure, 160 NdbIndexScanOperation::IndexBound NdbDictionary::setNull(), 161 NDB API structure, 179 NdbDictionary::Table NdbIndexScanOperation::readTuples(), 180 NDB API class, 279 NdbIndexScanOperation::reset_bounds(), 181 NdbDictionary::Tablespace NdbInterpretedCode NDB API class, 304 NDB API class, 183 NdbDictionary::Undofile NdbInterpretedCode register-loading methods, 17 NDB API class, 309 NdbInterpretedCode() (constructor), 187 NdbInterpretedCode::add_reg(), 188 NdbError NDB API structure, 161 NdbInterpretedCode::add val(), 188 NdbInterpretedCode::branch_col_and_mask_eq_mask(), NdbError::Classification type, 163 NdbError::Status type, 164 NdbEventOperation NdbInterpretedCode::branch_col_and_mask_eq_zero(), NDB API class, 164 190 NdbEventOperation::clearError() (DEPRECATED), 167 NdbInterpretedCode::branch_col_and_mask_ne_mask(), NdbEventOperation::execute(), 168 NdbEventOperation::getBlobHandle(), 168 NdbInterpretedCode::branch_col_and_mask_ne_zero(), NdbEventOperation::getEpoch(), 168 190 NdbEventOperation::getEventType() (DEPRECATED), NdbInterpretedCode::branch_col_eq(), 191 169 NdbInterpretedCode::branch_col_eq_null(), 192 NdbEventOperation::getEventType2(), 169 NdbInterpretedCode::branch col ge(), 192 NdbEventOperation::getGCI() (DEPRECATED), 169 NdbInterpretedCode::branch_col_gt(), 193 NdbEventOperation::getLatestGCI() (DEPRECATED), NdbInterpretedCode::branch col le(), 194 169 NdbInterpretedCode::branch_col_like(), 195 NdbEventOperation::getNdbError(), 170 NdbInterpretedCode::branch_col_lt(), 195 NdbEventOperation::getPreBlobHandle(), 170 NdbInterpretedCode::branch_col_ne(), 196 NdbEventOperation::getPreValue(), 170 NdbInterpretedCode::branch col ne null(), 197 NdbEventOperation::getState(), 171 NdbInterpretedCode::branch_col_notlike(), 197 NdbEventOperation::getValue(), 171 NdbInterpretedCode::branch_eq(), 198 NdbEventOperation::hasError() (DEPRECATED), 172 NdbInterpretedCode::branch_eq_null(), 198 NdbEventOperation::isConsistent() (DEPRECATED), 172 NdbInterpretedCode::branch_ge(), 199 NdbEventOperation::isEmptyEpoch(), 172 NdbInterpretedCode::branch gt(), 199 NdbEventOperation::isErrorEpoch(), 173 NdbInterpretedCode::branch_label(), 199 NdbEventOperation::isOverrun(), 173 NdbInterpretedCode::branch le(), 199 NdbEventOperation::mergeEvents(), 173 NdbInterpretedCode::branch_lt(), 200 NdbEventOperation::State, 174 NdbInterpretedCode::branch_ne(), 200 NdbEventOperation::tableFragmentationChanged(), 174 NdbInterpretedCode::branch_ne_null(), 200 NdbEventOperation::tableFrmChanged(), 174 NdbInterpretedCode::call sub(), 201 NdbEventOperation::tableNameChanged(), 175 NdbInterpretedCode::copy(), 201 NdbInterpretedCode::def_label(), 201 NdbIndexOperation NDB API class, 175 NdbInterpretedCode::def_sub(), 201 NdbIndexOperation class NdbInterpretedCode::finalise(), 202 NdbInterpretedCode::getNdbError(), 202 example, 8 NdbInterpretedCode::getTable(), 202 NdbIndexOperation::deleteTuple(), 176 NdbIndexOperation::getIndex(), 176 NdbInterpretedCode::getWordsUsed(), 202 NdbIndexOperation::readTuple(), 176 NdbInterpretedCode::interpret_exit_last_row(), 203 NdbIndexOperation::updateTuple(), 177 NdbInterpretedCode::interpret_exit_nok(), 203 NdbIndexScanOperation NdbInterpretedCode::interpret_exit_ok(), 203 NDB API class, 177 NdbInterpretedCode::load const null(), 204 NdbIndexScanOperation::BoundType, 178 NdbInterpretedCode::load_const_u16(), 204 NdbIndexScanOperation::end_of_bound(), 178 NdbInterpretedCode::load_const_u32(), 204

NdbInterpretedCode::load_const_u64(), 204	NdbOperation::NdbIndexOperation
NdbInterpretedCode::read_attr(), 205	NDB API class, 175
NdbInterpretedCode::ret_sub(), 205	NdbOperation::NdbScanOperation
NdbInterpretedCode::sub_reg(), 205	NDB API class, 243
NdbInterpretedCode::sub_val(), 206	NdbOperation::OperationOptions
NdbInterpretedCode::write_attr(), 207	NDB API structure, 218
NdbLockHandle	NdbOperation::readTuple(), 221
defined, 213	NdbOperation::setValue(), 221
using, 212	NdbOperation::SetValueSpec
ndbmemcache, 759	NDB API structure, 223
AUTO_INCREMENT columns, 770	NdbOperation::Type, 224
availability, 759	NdbOperation::updateTuple(), 224
cache policies, 763	NdbOperation::writeTuple(), 225
compiling, 760	NdbRecAttr
configuration, 761, 762, 765, 766, 767	NDB API class, 225
configuration tables, 762, 763	NdbRecAttr class, 225
configuration versioning, 766	NdbRecAttr::aRef(), 228
enabling support for, 759	NdbRecAttr::char_value(), 228
fractional seconds, 771	NdbRecAttr::clone(), 228
known issues, 770	NdbRecAttr::double_value(), 228
limitations, 770	NdbRecAttr::float_value(), 229
log file, 769	NdbRecAttr::getColumn(), 229
memcache commands, 767	NdbRecAttr::getType(), 229
memcache protocol, 767	NdbRecAttr::get_size_in_bytes(), 229
memcached options, 760	NdbRecAttr::int32_value(), 230
metadata, 762	NdbRecAttr::int64_value(), 230
online configuration, 767	NdbRecAttr::int8_value(), 229
performance, 766, 766	NdbRecAttr::isNULL(), 230
schema changes, 770	NdbRecAttr::medium_value(), 230
server_roles table, 762	NdbRecAttr::short_value(), 231
starting, 762	NdbRecAttr::u_32_value(), 231
upgrades, 766	NdbRecAttr::u_64_value(), 231
NdbMgmHandle, 599, 606, 606, 607	NdbRecAttr::u_8_value(), 231
NdbOperation	NdbRecAttr::u_char_value(), 232
NDB API class, 207	NdbRecAttr::u_medium_value(), 232
NdbOperation class	NdbRecAttr::u_short_value(), 232
example, 7	NdbRecord
NdbOperation::AbortOption, 209	example, 500, 566
NdbOperation::deleteTuple(), 210	NDB API interface, 232
NdbOperation::equal(), 210	obtaining column size for, 43
NdbOperation::getBlobHandle(), 212	NdbScanFilter
NdbOperation::getLockHandle(), 212	NDB API class, 233
NdbOperation::getLockMode(), 213	NdbScanFilter class
NdbOperation::getNdbError(), 213	integer comparison methods, 235
NdbOperation::getNdbErrorLine(), 214	NdbScanFilter::begin(), 235
NdbOperation::getNdbTransaction(), 214	NdbScanFilter::BinaryCondition, 236
NdbOperation::getTable(), 214	NdbScanFilter::cmp(), 237
NdbOperation::getTableName(), 214	NdbScanFilter::end(), 238
NdbOperation::getType(), 214	NdbScanFilter::eq(), 239
NdbOperation::getValue(), 215	NdbScanFilter::ge(), 240
NdbOperation::GetValueSpec	NdbScanFilter::getNdbError(), 240
NDB API structure, 216	NdbScanFilter::getNdbOperation(), 241
NdbOperation::insertTuple(), 218	NdbScanFilter::Group, 241
NdbOperation::LockMode, 218	NdbScanFilter::gt(), 241

NdbScanFilter::isfalse(), 239	NdbTransaction::setMaxPendingBlobWriteBytes(), 271
NdbScanFilter::isnotnull(), 239	NdbTransaction::unlock(), 272
NdbScanFilter::isnull(), 240	NdbTransaction::updateTuple(), 272
NdbScanFilter::istrue(), 240	NdbTransaction::writeTuple(), 273
NdbScanFilter::le(), 242	Ndb_cluster_connection
NdbScanFilter::lt(), 242	get_max_adaptive_send_time() method, 137
NdbScanFilter::ne(), 243	get_next_ndb_object() method, 137
NdbScanOperation	get_num_recv_threads(), 137
NDB API class, 243	get_recv_thread_activation_threshold(), 138
NdbScanOperation::close(), 244	get_system_name(), 138
NdbScanOperation::deleteCurrentTuple(), 245	NDB API class, 132
NdbScanOperation::getNdbTransaction(), 246	set_max_adaptive_send_time(), 139
NdbScanOperation::getPruned(), 246	set_num_recv_threads(), 140
NdbScanOperation::lockCurrentTuple(), 247	set_recv_thread_activation_threshold(), 140
NdbScanOperation::NdbIndexScanOperation	set_recv_thread_cpu(), 142
NDB API class, 177	set_service_uri(), 141
NdbScanOperation::nextResult(), 248	unset_recv_thread_cpu(), 143
NdbScanOperation::readTuples(), 250	ndb_cluster_connection
NdbScanOperation::restart(), 250	lock_ndb_objects() method, 138
NdbScanOperation::ScanFlag, 250	unlock_ndb_objects() method, 142
NdbScanOperation::ScanOptions	Ndb_cluster_connection::connect(), 135
NDB API structure, 252	Ndb_cluster_connection::get_auto_reconnect(), 136
NdbScanOperation::updateCurrentTuple(), 254	Ndb_cluster_connection::get_latest_error(), 136
NdbTransaction	Ndb_cluster_connection::get_latest_error_msg(), 136
NDB API class, 255	Ndb_cluster_connection::set_auto_reconnect(), 139
NdbTransaction class methods	Ndb_cluster_connection::set_data_node_neighbour(),
using, 6	139
NdbTransaction::AbortOption, 209	Ndb_cluster_connection::set_name(), 140
NdbTransaction::close(), 258	Ndb_cluster_connection::set_optimized_node_selection(),
NdbTransaction::commitStatus(), 259	140
NdbTransaction::CommitStatusType, 259	Ndb_cluster_connection::set_timeout(), 142
NdbTransaction::deleteTuple(), 259	Ndb_cluster_connection::wait_until_ready(), 143
NdbTransaction::ExecType, 260	ndb_end()
NdbTransaction::execute(), 261	NDB API function, 27
NdbTransaction::executePendingBlobOps(), 262	ndb_init()
NdbTransaction::getGCI(), 262	NDB API function, 27
NdbTransaction::getMaxPendingBlobReadBytes(), 263	ndb_logevent structure (MGM API), 637
NdbTransaction::getMaxPendingBlobWriteBytes(), 263	ndb_logevent_get_fd() function (MGM API), 602
NdbTransaction::getNdbError(), 263	ndb_logevent_get_latest_error() function (MGM API),
NdbTransaction::getNdbErrorLine(), 263	604
NdbTransaction::getNdbErrorOperation(), 264	ndb_logevent_get_latest_error_msg() function (MGM
NdbTransaction::getNdbIndexOperation(), 264	API), 604
NdbTransaction::getNdbIndexScanOperation(), 264	ndb_logevent_get_next() function (MGM API), 603
NdbTransaction::getNdbOperation(), 264	ndb_logevent_get_next2() function (MGM API), 603
NdbTransaction::getNdbScanOperation(), 265	ndb_logevent_handle_error type (MGM API), 635
NdbTransaction::getNextCompletedOperation(), 265	Ndb_logevent_type type (MGM API), 629
NdbTransaction::getTransactionId(), 265	ndb_memcache_metadata.sql, 762
NdbTransaction::insertTuple(), 266	ndb_mgm_abort_backup() function (MGM API), 626
NdbTransaction::readTuple(), 267	ndb_mgm_check_connection() function (MGM API), 610
NdbTransaction::refresh(), 268	ndb_mgm_cluster_state structure (MGM API), 643
NdbTransaction::releaseLockHandle(), 268	ndb_mgm_connect() function (MGM API), 612
NdbTransaction::scanIndex(), 269	ndb_mgm_create_handle() function (MGM API), 606
NdbTransaction::scanTable(), 270	ndb_mgm_create_logevent_handle() function (MGM
NdbTransaction::setMaxPendingBlobReadBytes(), 271	API), 602, 602

ndb_mgm_destroy_handle() function (MGM API), 607 ndb_mgm_set_timeout() function (MGM API), 612 ndb mgm destroy logevent handle() function (MGM ndb mgm start() function (MGM API), 616 API), 602 ndb_mgm_start_backup() function (MGM API), 623 ndb mgm disconnect() function (MGM API), 613 ndb mgm start backup2() function (MGM API), 624 ndb_mgm_dump_state() function (MGM API), 614 ndb_mgm_start_backup3() function (MGM API), 625 ndb mgm start backup4() function (MGM API), 625 ndb mgm enter single user() function (MGM API), 627 ndb_mgm_error type (MGM API), 629 ndb_mgm_stop() function (MGM API), 616 ndb mgm event category type (MGM API), 636 ndb mgm stop2() function (MGM API), 616 ndb_mgm_event_severity type (MGM API), 634 ndb_mgm_stop3() function (MGM API), 617 ndb_mgm_exit_single_user() function (MGM API), 627 ndb_mgm_stop4() function (MGM API), 618 ndb_mgm_get_clusterlog_loglevel() function (MGM API), ne() (method of NdbScanFilter), 243 newDbug (ClusterJ), 679 ndb mgm get clusterlog severity filter() function (MGM newInstance (ClusterJ), 709, 709 API), 621 nextEvent() (method of Ndb) (DEPRECATED), 123 nextEvent2() (method of Ndb), 123 ndb mgm get configuration nodeid() function (MGM API), 608 nextResult() (method of NdbScanOperation), 248 ndb_mgm_get_connected_host() function (MGM API), **NoCommit** 609 defined, 6 ndb mgm get connected port() function (MGM API), node 609 defined, 3 ndb_mgm_get_connectstring() function (MGM API), 608 node failure ndb_mgm_get_latest_error() function (MGM API), 605 defined, 4 ndb_mgm_get_latest_error_desc() function (MGM API), node restart 605 defined, 4 ndb_mgm_get_latest_error_msg() function (MGM API), Node.is, 735 605 not (ClusterJ), 726, 730 ndb_mgm_get_loglevel_clusterlog() function (MGM API) NotPersistent (ClusterJ), 721 - DEPRECATED, 622 nullable (ClusterJ), 682 NullValue (ClusterJ), 721 ndb_mgm_get_status() function (MGM API), 613 ndb mgm get status2() function (MGM API), 613 nullValue (ClusterJ), 724 ndb_mgm_get_version() function (MGM API), 609 number (ClusterJ), 682 ndb_mgm_is_connected() function (MGM API), 609 ndb_mgm_listen_event() function (MGM API), 601 0 ndb_mgm_node_state structure (MGM API), 642 Object ndb mgm node status type (MGM API), 628 NDB API class, 274 ndb_mgm_node_type type (MGM API), 628 Object::Datafile ndb mgm number of mgmd in connect string() NDB API class, 51 function (MGM API), 610 Object::ForeignKey ndb_mgm_reply structure (MGM API), 643 NDB API class, 87 ndb_mgm_restart() function (MGM API), 618 Object::FragmentType, 275 ndb mgm restart2() function (MGM API), 619 Object::getObjectId(), 276 ndb_mgm_restart3() function (MGM API), 619 Object::getObjectStatus(), 276 ndb_mgm_restart4() function (MGM API), 620 Object::getObjectVersion(), 276 ndb_mgm_set_bindaddress() function (MGM API), 610 Object::HashMap ndb_mgm_set_clusterlog_loglevel() function (MGM API), NDB API class, 94 623 Object::PartitionBalance, 277 ndb_mgm_set_clusterlog_severity_filter() function (MGM Object::State, 277 API), 622 Object::Status, 277 ndb_mgm_set_configuration_nodeid() function (MGM Object::Store, 278 API), 612 Object::Type, 278 ndb_mgm_set_connectstring() function (MGM API), 611 obtaining ndbmemcache, 759 ndb mgm set error stream() function (MGM API), 606 openSession() (method of Mynode), 742 ndb_mgm_set_ignore_sigpipe() function (MGM API), 607 openSession() (method of SessionFactory), 744 ndb_mgm_set_name() function (MGM API), 606

OperationOptions	PROPERTY_CLUSTER_CONNECT_TIMEOUT_MGM
NDB API structure, 218	(ClusterJ), 690
operations	PROPERTY_CLUSTER_CONNECT_VERBOSE
defined, 6	(ClusterJ), 690
scanning, 9	PROPERTY_CLUSTER_DATABASE (ClusterJ), 691
single-row, 7	PROPERTY_CLUSTER_MAX_TRANSACTIONS
transactions and, 6	(ClusterJ), 691
	PROPERTY_CONNECTION_POOL_NODEIDS
or (ClusterJ), 726	
output (ClusterJ), 695	(ClusterJ), 691
_	PROPERTY_CONNECTION_POOL_RECV_THREAD_ACTIVAT
P	(ClusterJ), 691
param (ClusterJ), 730	PROPERTY_CONNECTION_POOL_RECV_THREAD_CPUIDS
PartitionBalance (Object data type), 277	(ClusterJ), 691
PartitionKey (ClusterJ), 722	PROPERTY_CONNECTION_POOL_SIZE (ClusterJ),
PartitionSpec	692
NDB API structure, 124	PROPERTY_CONNECTION_RECONNECT_TIMEOUT
persist (ClusterJ), 709	(ClusterJ), 692
persist() (method of Context), 738	PROPERTY_DEFER_CHANGES (ClusterJ), 692
PersistenceCapable (ClusterJ), 722	PROPERTY_JDBC_DRIVER_NAME (ClusterJ), 692
PersistenceModifier (ClusterJ), 723	PROPERTY_JDBC_PASSWORD (ClusterJ), 692
Persistent (ClusterJ), 723	PROPERTY_JDBC_URL (ClusterJ), 692
pollEvents() (method of Ndb) (DEORECATED), 126	PROPERTY_JDBC_USERNAME (ClusterJ), 693
	push (ClusterJ), 696, 696
pollEvents2() (method of Ndb), 127	
pop (ClusterJ), 696	Q
precision (ClusterJ), 682	·
Predicate (ClusterJ), 725	Query (ClusterJ), 698
PredicateOperand (ClusterJ), 726	Query.Ordering (ClusterJ), 703
prepareHashMap() (method of Dictionary), 73	QueryBuilder (ClusterJ), 729
primaryKey (ClusterJ), 724	QueryDefinition (ClusterJ), 730
PrimaryKey (ClusterJ), 724	QueryDomainType (ClusterJ), 731
print (ClusterJ), 696	
Projection (ClusterJ), 725	R
PROPERTY_CLUSTER_BYTE_BUFFER_POOL_SIZES	readData() (method of NdbBlob), 152
(ClusterJ), 689	readTuple() (method of NdbIndexOperation), 176
PROPERTY_CLUSTER_CONNECTION_SERVICE	readTuple() (method of NdbOperation), 221
(ClusterJ), 691	readTuple() (method of NdbOperation), 227
PROPERTY_CLUSTER_CONNECTSTRING (ClusterJ),	readTuples() (method of NdbIndexScanOperation), 180
691	
PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_	readTuples() (method of NdbScanOperation), 250 -read_attr() (method of NdbInterpretedCode), 205
(ClusterJ), 689	reconnect (Cluster I) 714 714
PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT	reconnect (ClusterJ), 714, 714 Fig. 1. Fig. 1.
(ClusterJ), 690	
PROPERTY_CLUSTER_CONNECT_AUTO_INCREMENT_	NDB, 14 STEP RecordSpecification
(ClusterJ), 690	- Record Specification
PROPERTY_CLUSTER_CONNECT_DELAY (ClusterJ),	NDB API structure, 160
690	refresh() (method of NdbTransaction), 268
PROPERTY_CLUSTER_CONNECT_RETRIES	Register-loading methods (NdbInterpretedCode), 17
(ClusterJ), 690	release (ClusterJ), 710
PROPERTY_CLUSTER_CONNECT_TIMEOUT_AFTER	releaseLockHandle() (method of NdbTransaction), 268
(ClusterJ), 690	releaseRecord() (method of Dictionary), 74
PROPERTY_CLUSTER_CONNECT_TIMEOUT_BEFORE	remove (ClusterJ), 710
(ClusterJ), 690	remove() (method of Context), 738
(Ciusieio), Uau	removeCachedIndex() (method of Dictionary), 74
	removeCachedTable() (method of Dictionary), 74

reset_bounds() (method of NdbIndexScanOperation), 181	Session.setLockMode(), 744 SessionFactory (ClusterJ), 712
restart() (method of NdbScanOperation), 250	SessionFactory class (Connector for JavaScript), 744
restore	SessionFactory.close(), 745
defined, 3	SessionFactory.getOpenSessions(), 744
Results (ClusterJ), 703	SessionFactory.openSession(), 744
ret_sub() (method of NdbInterpretedCode), 205	SessionFactory.State (ClusterJ), 715
rollback (ClusterJ), 717	SessionFactoryService (ClusterJ), 716
rollback() (method of Transaction), 747	SESSION_FACTORY_SERVICE_CLASS_NAME
	(ClusterJ), 693
S	SESSION_FACTORY_SERVICE_FILE_NAME
save() (method of Context), 739	(ClusterJ), 693
savePersistent (ClusterJ), 710	set (ClusterJ), 696, 696
savePersistentAll (ClusterJ), 710	setActiveHook() (method of NdbBlob), 152
scale (ClusterJ), 682	setArrayType() (method of Column), 44
scan operations, 9	setAutoGrowSpecification() (method of LogfileGroup),
characteristics, 9	107
used for updates or deletes, 10	setAutoGrowSpecification() (method of Tablespace), 308
with lock handling, 11	setCharset() (method of Column), 45
ScanFlag (NdbScanOperation data type), 250	setChild() (method of ForeignKey), 92
scanIndex() (method of NdbTransaction), 269	setDatabaseName() (method of Ndb), 128
ScanOptions	setDatabaseSchemaName() (method of Ndb), 128
NDB API structure, 252	setDefaultLogfileGroup() (method of Tablespace), 308
scans	setDefaultNoPartitionsFlag() (method of Table), 296
performing with NdbScanFilter and	setDefaultValue() (method of Column), 45
NdbScanOperation, 482	setDurability() (method of Event), 85
types supported, 1	setEventBufferQueueEmptyEpoch() (method of Ndb),
using secondary indexes	129
example, 496	setExtentSize() (method of Tablespace), 309
example (using NdbRecord), 500	setExtraMetadata() (method of Table), 297
scanTable() (method of NdbTransaction), 270	setFragmentCount() (method of Table), 297
SCAN_TYPE (ClusterJ), 699	setFragmentData() (method of Table), 297
SCAN_TYPE_INDEX_SCAN (ClusterJ), 699	setFragmentType() (method of Table), 298
SCAN_TYPE_PRIMARY_KEY (ClusterJ), 699	setFrm() (method of Table), 298
SCAN_TYPE_TABLE_SCAN (ClusterJ), 700	setHashMap() (method of Table), 298
SCAN_TYPE_UNIQUE_KEY (ClusterJ), 700	setKValue() (method of Table), 299
schema changes	setLength() (method of Column), 46
ndbmemcache, 770	setLimits (ClusterJ), 702
Schema transactions, 60	setLinearFlag() (method of Table), 299
schema transactions	setLockMode (ClusterJ), 711
and Dictionary::prepareHashMap() method, 73	setLockMode() (method of Session), 744
SchemaTransFlag, 67	setLogfileGroup() (method of Undofile), 313
server_roles table (ndbmemcache), 762	setLogging() (method of Table), 299 setMap() (method of HashMap), 96
Session (ClusterJ), 704	setMaxLoadFactor() (method of Table), 299
Session class (Connector for JavaScript), 743	setMaxPendingBlobReadBytes() (method of
Session.close(), 744	NdbTransaction), 271
Session.createBatch(), 744	setMaxPendingBlobWriteBytes() (method of
Session.currentTransaction(), 744	NdbTransaction), 271
Session.getMapping(), 743	setMaxRows() (method of Table), 299
Session.getTableMetadata(), 744	setMinLoadFactor() (method of Table), 300
Session.isClosed(), 744	setName() (method of Column), 46
Session.listBatches(), 744	setName() (method of Event), 85
Session.listTables(), 744	setName() (method of Eventy, 65 setName() (method of ForeignKey), 92
	55

setName() (method of HashMap), 95	setValue() (method of NdbOperation), 221
setName() (method of Index), 102	SetValueSpec
setName() (method of LogfileGroup), 107	NDB API structure, 223
setName() (method of Table), 300	set_auto_reconnect() (method of
setName() (method of Tablespace), 309	Ndb_cluster_connection), 139
setNdbObjectName() (method of Ndb), 130	set_data_node_neighbour() (method of
setNode() (method of Datafile), 55	Ndb_cluster_connection), 139
setNode() (method of Undofile) (OBSOLETE), 313	set_eventbuffer_free_percent() (method of Ndb), 130
setNull() (method of NdbBlob), 152	set_eventbuf_max_alloc() (method of Ndb), 129
setNull() (method of NdbDictionary), 161	set_max_adaptive_send_time() (method of
setNullable() (method of Column), 46	Ndb_cluster_connection), 139
setObjectType() (method of Table) (OBSOLETE), 300	set_name() (method of Ndb_cluster_connection), 140
setOnDeleteAction() (method of ForeignKey), 93	set_num_recv_threads() (method of
setOnUpdateAction() (method of ForeignKey), 93	Ndb_cluster_connection), 140
setOrdering (ClusterJ), 702	set_optimized_node_selection() (method of
setParameter (ClusterJ), 703	Ndb_cluster_connection), 140
setParent() (method of ForeignKey), 92	set_recv_thread_activation_threshold() (method of
setPartitionBalance() (method of Table), 301	Ndb_cluster_connection), 138, 140
setPartitionKey (ClusterJ), 711	set_recv_thread_cpu() (method of
setPartitionKey() (method of Column), 46	Ndb_cluster_connection), 142
setPartSize() (method of Column), 47	set_service_uri() (method of Ndb_cluster_connection),
setPath() (method of Datafile), 55	141
setPath() (method of Undofile), 314	set_timeout() (method of Ndb_cluster_connection), 142
setPos() (method of NdbBlob), 152	short_value() (method of NdbRecAttr), 231
setPrecision() (method of Column), 47	SingleUserMode (Table data type), 303
setPrimaryKey() (method of Column), 47	SQL node
setRangeListData() (method of Table), 301	defined, 3
setRecvThreadActivationThreshold (ClusterJ), 715	startTransaction() (method of Ndb), 130
setRecvThreadCPUids (ClusterJ), 715	State (NdbBlob data type), 153
setReport() (method of Event), 85	State (NdbEventOperation data type), 174
setRollbackOnly (ClusterJ), 717	State (Object data type), 277
setRollbackOnly() (method of Transaction), 748	Status (NdbError data type), 164
setRowChecksumIndicator() (method of Table), 301	Status (Object data type), 277
setRowGCIIndicator() (method of Table), 301	StorageType (Column data type), 49
setScale() (method of Column), 48	Store (Object data type), 278
setSchemaObjectOwnerChecks(), 271	sub_reg() (method of NdbInterpretedCode), 206
setSchemaObjectOwnerChecks() (method of	sub_val() (method of NdbInterpretedCode), 206
NdbTransaction), 271	system crash
setSingleUserMode() (method of Table), 302	defined, 4
setSize() (method of Datafile), 56	system restart
setSize() (method of Undofile), 314	defined, 4
setStatusInvalid() (method of Table), 302	3063,
setStorageType() (method of Column), 48	T
setStripeSize() (method of Column), 48	_
setTable() (method of Event), 86	Table
setTable() (method of Index), 103	getExtraMetadata(), 287
setTablespace() (method of Datafile), 56	getSingleUserMode(), 294
setTablespace() (method of Table), 302	NDB API class, 279
setTablespaceData() (method of Table), 303	setExtraMetadata(), 297
setTablespaceNames() (method of Table), 303	setSingleUserMode(), 302
setType() (method of Column), 49	Table::addColumn(), 285
setType() (method of Index), 103	Table::aggregate(), 285
setUndoBufferSize() (method of LogfileGroup), 107	Table::equal(), 286
setValue() (method of NdbBlob), 153	Table::getColumn(), 286

Table::getDefaultNoPartitionsFlag(), 286	Table::setStatusInvalid(), 302
Table::getFragmentCount(), 287	Table::setTablespace(), 302
Table::getFragmentData(), 287	Table::setTablespaceData(), 303
Table::getFragmentDataLen(), 288	Table::setTablespaceNames(), 303
Table::getFragmentNodes(), 288	Table::SingleUserMode, 303
Table::getFragmentType(), 288	Table::validate(), 303
Table::getFrmData(), 288	TableEvent (Event data type), 86
Table::getFrmLength(), 289	tableFragmentationChanged() (method of
Table::getHashMap(), 289	NdbEventOperation), 174
Table::getKValue(), 289	tableFrmChanged() (method of NdbEventOperation), 17
Table::getLinearFlag(), 289	TableMapping class (Connector for JavaScript), 745
Table::getLogging(), 290	TableMapping.applyToClass(), 745
Table::getMaxLoadFactor(), 290	TableMapping.mapField(), 745
Table::getMaxRows(), 290	TableMetadata class (Connector for JavaScript), 746
Table::getMinLoadFactor(), 290	tableNameChanged() (method of NdbEventOperation),
Table::getNoOfColumns(), 291	175
Table::getNoOfPrimaryKeys(), 291	Tablespace
Table::getObjectId(), 291	NDB API class, 304
Table::getObjectStatus(), 291	Tablespace::getAutoGrowSpecification(), 306
Table::getObjectType() (OBSOLETE), 292	Tablespace::getDefaultLogfileGroup(), 306
Table::getObjectVersion(), 292	Tablespace::getDefaultLogfileGroupId(), 306
Table::getPartitionBalance(), 292	Tablespace::getExtentSize(), 307
Table::getPartitionBalanceString(), 292	Tablespace::getName(), 307
Table::getPartitionId(), 293	Tablespace::getObjectId(), 307
Table::getPrimaryKey(), 293	Tablespace::getObjectStatus(), 307
Table::getRangeListData(), 293	Tablespace::getObjectVersion(), 308
Table::getRangeListDataLen(), 293	Tablespace::setAutoGrowSpecification(), 308
Table::getRowChecksumIndicator(), 294	Tablespace::setDefaultLogfileGroup(), 308
Table::getRowGCIIndicator(), 294	Tablespace::setExtentSize(), 309
Fable::getTableId(), 294	Tablespace::setName(), 309
Fable::getTablespace(), 294	TC
Fable::getTablespaceData(), 295	and NDB Kernel, 13
Fable::getTablespaceDataLen(), 295	defined, 4
Fable::getTablespaceNames(), 296	selecting, 13
Table::getTablespaceNamesLen(), 296	threading, 15
Table::hasDefaultValues(), 296	trace (ClusterJ), 696
Table::setDefaultNoPartitionsFlag(), 296	Transaction (ClusterJ), 716
Table::setFragmentCount(), 297	Transaction class (Connector for JavaScript), 747
Table::setFragmentData(), 297	Transaction Coordinator
Table::setFragmentType(), 298	defined, 4
Table::setFrm(), 298	transaction coordinator, 131
Table::setHashMap(), 298	Transaction.begin(), 747
Table::setKValue(), 299	Transaction.commit(), 747
Table::setLinearFlag(), 299	Transaction.getRollbackOnly(), 748
Fable::setLogging(), 299	Transaction.isActive(), 747
Fable::setMaxLoadFactor(), 299	Transaction.rollback(), 747
Γable::setMaxRows(), 299	Transaction.setRollbackOnly(), 748
Table::setMinLoadFactor(), 300	transactions
Table::setName(), 300	concurrency, 14
Table::setObjectType() (OBSOLETE), 300	example, 472
Table::setPartitionBalance(), 301	handling and transmission, 14
Table::setRangeListData(), 301	performance, 14
Table::setRowChecksumIndicator(), 301	synchronous, 6
Table::setRowGCIIndicator(), 301	example of use, 468

using, 5 transactions and locking
NDB API, 212
transporter
defined, 4
truncate() (method of NdbBlob), 154 TUP
and NDB Kernel, 13
defined, 4 Tuple Manager
defined, 4
Type (Column data type), 49
Type (Index data type), 103
Type (NdbOperation data type), 224
Type (Object data type), 278
U
Undofile
NDB API class, 309
Undofile::getFileNo() (OBSOLETE), 311 Undofile::getLogfileGroup(), 311
Undofile::getLogfileGroupId(), 311
Undofile::getNode() (OBSOLETE), 312
Undofile::getObjectId(), 312
Undofile::getObjectStatus(), 312
Undofile::getObjectVersion(), 312
Undofile::getPath(), 312
Undofile::getSize(), 313
Undofile::setLogfileGroup(), 313
Undofile::setNode() (OBSOLETE), 313 Undofile::setPath(), 314
Undofile::setSize(), 314
unique (ClusterJ), 720
unloadSchema (ClusterJ), 711
unlock() (method of NdbTransaction), 272
unlock_ndb_objects() (method of
ndb_cluster_connection), 142
unset_recv_thread_cpu() (method of
Ndb_cluster_connection), 143
update() (method of Context), 739 updateCurrentTuple() (method of NdbScanOperation)
254
updatePersistent (ClusterJ), 712
updatePersistentAll (ClusterJ), 712
updateTuple() (method of NdbIndexOperation), 177
updateTuple() (method of NdbOperation), 224
updateTuple() (method of NdbTransaction), 272
u_32_value() (method of NdbRecAttr), 231
u_64_value() (method of NdbRecAttr), 231 u_8_value() (method of NdbRecAttr), 231
u_o_value() (method of NdbRecAttr), 231 u_char_value() (method of NdbRecAttr), 232
u_medium_value() (method of NdbRecAttr), 232
u short value() (method of NdbRecAttr), 232

٧

validate() (method of Table), 303 value (ClusterJ), 719, 719, 720, 721 vendorName (ClusterJ), 719 version information in MGM API, 609 visibility of database objects and MySQL Server, 38, 59

W

wait_until_ready() (method of Ndb_cluster_connection), 143
where (ClusterJ), 731
writeData() (method of NdbBlob), 154
writeTuple() (method of NdbOperation), 225
writeTuple() (method of NdbTransaction), 273
write_attr() (method of NdbInterpretedCode), 207