AVFoundation Programming Guide



Contents

About AVFoundation 7 At a Glance 8 Representing and Using Media with AVFoundation 9 Concurrent Programming with AVFoundation 11 Prerequisites 12 See Also 12 **Using Assets** 13 Creating an Asset Object 13 Options for Initializing an Asset 13 Accessing the User's Assets 14 Preparing an Asset for Use 15 Getting Still Images From a Video 16 Generating a Single Image 17 Generating a Sequence of Images 18 Trimming and Transcoding a Movie 19 Playback 22 Playing Assets 22 Handling Different Types of Asset 24 Playing an Item 26 Changing the Playback Rate 26 Seeking—Repositioning the Playhead 27 Playing Multiple Items 28 Monitoring Playback 28 Responding to a Change in Status 29 Tracking Readiness for Visual Display 30 Tracking Time 30 Reaching the End of an Item 31 Putting It All Together: Playing a Video File Using AVPlayerLayer 31 The Player View 32 A Simple View Controller 32 Creating the Asset 33 Responding to the Player Item's Status Change 35

Playing the Item 36

Editing 37

Creating a Composition 40

Options for Initializing a Composition Track 41

Adding Audiovisual Data to a Composition 41

Retrieving Compatible Composition Tracks 42

Generating a Volume Ramp 42

Performing Custom Video Processing 43

Changing the Composition's Background Color 43

Applying Opacity Ramps 43

Incorporating Core Animation Effects 44

Putting It All Together: Combining Multiple Assets and Saving the Result to the Camera Roll 45

Creating the Composition 46

Adding the Assets 46

Checking the Video Orientations 47

Applying the Video Composition Layer Instructions 48

Setting the Render Size and Frame Duration 49

Exporting the Composition and Saving it to the Camera Roll 50

Still and Video Media Capture 52

Use a Capture Session to Coordinate Data Flow 54

Configuring a Session 54

Monitoring Capture Session State 55

An AVCaptureDevice Object Represents an Input Device 56

Device Characteristics 56

Device Capture Settings 58

Configuring a Device 62

Switching Between Devices 63

Use Capture Inputs to Add a Capture Device to a Session 63

Use Capture Outputs to Get Output from a Session 64

Saving to a Movie File 65

Processing Frames of Video 67

Capturing Still Images 69

Showing the User What's Being Recorded 70

Video Preview 71

Showing Audio Levels 72

Putting It All Together: Capturing Video Frames as Ullmage Objects 72

Create and Configure a Capture Session 73

Create and Configure the Device and Device Input 73

```
Create and Configure the Video Data Output 74
    Implement the Sample Buffer Delegate Method 74
    Starting and Stopping Recording 75
High Frame Rate Video Capture 76
    Playback 77
    Editing 77
    Export 78
    Recording 78
Export 79
Reading an Asset 79
    Creating the Asset Reader 79
    Setting Up the Asset Reader Outputs 80
    Reading the Asset's Media Data 82
Writing an Asset 83
    Creating the Asset Writer 84
    Setting Up the Asset Writer Inputs 84
    Writing Media Data 86
Reencoding Assets 88
Putting It All Together: Using an Asset Reader and Writer in Tandem to Reencode an Asset 89
    Handling the Initial Setup 90
    Initializing the Asset Reader and Writer 92
    Reencoding the Asset 96
    Handling Completion 101
    Handling Cancellation 102
Asset Output Settings Assistant 104
Time and Media Representations 106
Representation of Assets 106
Representations of Time 107
    CMTime Represents a Length of Time 107
    CMTimeRange Represents a Time Range 109
Representations of Media 110
Converting CMSampleBuffer to a Ullmage Object 111
Document Revision History 113
```

Swift 6

Figures and Listings

| About Avroundation / | |
|------------------------------------|--|
| Figure I-1 | AVFoundation stack on iOS 7 |
| Figure I-2 | AVFoundation stack on OS X 8 |
| Using Assets 13 | |
| Figure 1-1 | The export session workflow 19 |
| Playback 22 | 2 |
| Figure 2-1 | Playing an asset 23 |
| Figure 2-2 | Playing the same asset in different ways 24 |
| Editing 37 | |
| Figure 3-1 | AVMutableComposition assembles assets together 37 |
| Figure 3-2 | AVMutableAudioMix performs audio mixing 38 |
| Figure 3-3 | AVMutableVideoComposition 39 |
| Figure 3-4 | Use AVAssetExportSession to combine media elements into an output file 40 |
| Still and Video Media Capture 52 | |
| Figure 4-1 | A single session can configure multiple inputs and outputs 52 |
| Figure 4-2 | AVCaptureConnection represents a connection between an input and output 53 |
| Figure 4-3 | iOS device front and back facing camera positions 57 |
| Listing 4-1 | Setting the orientation of a capture connection 62 |
| Export 79 | |
| Listing 5-1 | AVOutputSettingsAssistant sample 104 |
| Time and Media Representations 106 | |
| Figure 6-1 | AVAsset provides an abstraction of time-based audiovisual data 106 |
| Figure 6-2 | AVAssetTrack 107 |



About AVFoundation

AVFoundation is one of several frameworks that you can use to play and create time-based audiovisual media. It provides an Objective-C interface you use to work on a detailed level with time-based audiovisual data. For example, you can use it to examine, create, edit, or reencode media files. You can also get input streams from devices and manipulate video during realtime capture and playback. Figure I-1 shows the architecture on iOS.

Figure I-1 AVFoundation stack on iOS





Figure I-2 (page 8) shows the corresponding media architecture on OS X.

Figure I-2 AVFoundation stack on OS X



You should typically use the highest-level abstraction available that allows you to perform the tasks you want.

- If you simply want to play movies, use the AVKit framework.
- On iOS, to record video when you need only minimal control over format, use the UIKit framework (UIImagePickerController).

Note, however, that some of the primitive data structures that you use in AV Foundation—including time-related data structures and opaque objects to carry and describe media data—are declared in the Core Media framework.

At a Glance

There are two facets to the AVFoundation framework—APIs related to video and APIs related just to audio. The older audio-related classes provide easy ways to deal with audio. They are described in the *Multimedia Programming Guide*, not in this document.

- To play sound files, you can use AVAudioPlayer.
- To record audio, you can use AVAudioRecorder.

You can also configure the audio behavior of your application using AVAudioSession; this is described in *Audio Session Programming Guide*.

Representing and Using Media with AVFoundation

The primary class that the AV Foundation framework uses to represent media is AVAsset. The design of the framework is largely guided by this representation. Understanding its structure will help you to understand how the framework works. An AVAsset instance is an aggregated representation of a collection of one or more pieces of media data (audio and video tracks). It provides information about the collection as a whole, such as its title, duration, natural presentation size, and so on. AVAsset is not tied to particular data format. AVAsset is the superclass of other classes used to create asset instances from media at a URL (see Using Assets (page 13)) and to create new compositions (see Editing (page 10)).

Each of the individual pieces of media data in the asset is of a uniform type and called a *track*. In a typical simple case, one track represents the audio component, and another represents the video component; in a complex composition, however, there may be multiple overlapping tracks of audio and video. Assets may also have metadata.

A vital concept in AV Foundation is that initializing an asset or a track does not necessarily mean that it is ready for use. It may require some time to calculate even the duration of an item (an MP3 file, for example, may not contain summary information). Rather than blocking the current thread while a value is being calculated, you ask for values and get an answer back asynchronously through a callback that you define using a block.

Relevant Chapters: Using Assets (page 13), Time and Media Representations (page 106)

Playback

AVFoundation allows you to manage the playback of asset in sophisticated ways. To support this, it separates the presentation state of an asset from the asset itself. This allows you to, for example, play two different segments of the same asset at the same time rendered at different resolutions. The presentation state for an asset is managed by a *player item* object; the presentation state for each track within an asset is managed by a *player item track* object. Using the player item and player item tracks you can, for example, set the size at which the visual portion of the item is presented by the player, set the audio mix parameters and video composition settings to be applied during playback, or disable components of the asset during playback.

You play player items using a *player* object, and direct the output of a player to the Core Animation layer. You can use a *player queue* to schedule playback of a collection of player items in sequence.

Relevant Chapter: Playback (page 22)

Reading, Writing, and Reencoding Assets

AVFoundation allows you to create new representations of an asset in several ways. You can simply reencode an existing asset, or—in iOS 4.1 and later—you can perform operations on the contents of an asset and save the result as a new asset.

You use an *export session* to reencode an existing asset into a format defined by one of a small number of commonly-used presets. If you need more control over the transformation, in iOS 4.1 and later you can use an *asset reader* and *asset writer* object in tandem to convert an asset from one representation to another. Using these objects you can, for example, choose which of the tracks you want to be represented in the output file, specify your own output format, or modify the asset during the conversion process.

To produce a visual representation of the waveform, you use an asset reader to read the audio track of an asset.

Relevant Chapter: Using Assets (page 13)

Thumbnails

To create thumbnail images of video presentations, you initialize an instance of AVAssetImageGenerator using the asset from which you want to generate thumbnails. AVAssetImageGenerator uses the default enabled video tracks to generate images.

Relevant Chapter: Using Assets (page 13)

Editing

AVFoundation uses *compositions* to create new assets from existing pieces of media (typically, one or more video and audio tracks). You use a mutable composition to add and remove tracks, and adjust their temporal orderings. You can also set the relative volumes and ramping of audio tracks; and set the opacity, and opacity ramps, of video tracks. A composition is an assemblage of pieces of media held in memory. When you export a composition using an *export session*, it's collapsed to a file.

You can also create an asset from media such as sample buffers or still images using an asset writer.

Relevant Chapter: Editing (page 37)

Still and Video Media Capture

Recording input from cameras and microphones is managed by a *capture session*. A capture session coordinates the flow of data from input devices to outputs such as a movie file. You can configure multiple inputs and outputs for a single session, even when the session is running. You send messages to the session to start and stop data flow.

In addition, you can use an instance of a preview layer to show the user what a camera is recording.

Relevant Chapter: Still and Video Media Capture (page 52)

Concurrent Programming with AVFoundation

Callbacks from AVFoundation—invocations of blocks, key-value observers, and notification handlers—are not generally not guaranteed to be made on any particular thread or queue. Instead, AVFoundation invokes these handlers on threads or queues on which it performs its internal tasks.

There are two general guidelines as far as notifications and threading:

- UI related notifications occur on the main thread.
- Classes or methods that require you create and/or specify a queue will return notifications on that queue.

Beyond those two guidelines (and there are exceptions, which are noted in the reference documentation) you should not assume that a notification will be returned on any specific thread.

If you're writing a multithreaded application, you can use the NSTh read method isMainTh read or [[NSTh read currentTh read] isEqual:<#A stored thread reference#>] to test whether the invocation thread is a thread you expect to perform your work on. You can redirect messages to appropriate threads using methods such as performSelectorOnMainThread:withObject:waitUntilDone: and performSelector:onThread:withObject:waitUntilDone:modes:.You could also use dispatch_async to "bounce" to your blocks on an appropriate queue, either the main queue for UI tasks or a queue you have up for concurrent operations. For more about concurrent operations, see Concurrency Programming Guide; for more about blocks, see Blocks Programming Topics. The AVCam for iOS sample code is considered the primary example for all AVFoundation functionality and can be consulted for examples of thread and queue usage with AVFoundation.

Prerequisites

AVFoundation is an advanced Cocoa framework. To use it effectively, you must have:

- A solid understanding of fundamental Cocoa development tools and techniques
- A basic grasp of blocks
- A basic understanding of key-value coding and key-value observing
- For playback, a basic understanding of Core Animation (see *Core Animation Programming Guide* or, for basic playback, the *AVKit Framework Reference*.

See Also

There are several AVFoundation examples including two that are key to understanding and implementation Camera capture functionality:

AVCam for iOS is the canonical sample code for implementing any program that uses the camera functionality. It is a complete sample, well documented, and covers the majority of the functionality showing the best practices.

AVCamManual: Using the Manual Capture API is the companion application to AVCam. It implements Camera functionality using the manual camera controls. It is also a complete example, well documented, and should be considered the canonical example for creating camera applications that take advantage of manual controls.

RosyWriter is an example that demonstrates real time frame processing and in particular how to apply filters to video content. This is a very common developer requirement and this example covers that functionality.

AVLocationPlayer: Using AVFoundation Metadata Reading APIs demonstrates using the metadata APIs.

Using Assets

Objective-CSwift

Assets can come from a file or from media in the user's iPod library or Photo library. When you create an asset object all the information that you might want to retrieve for that item is not immediately available. Once you have a movie asset, you can extract still images from it, transcode it to another format, or trim the contents.

Creating an Asset Object

To create an asset to represent any resource that you can identify using a URL, you use AVURLAsset. The simplest case is creating an asset from a file:

```
NSURL *url = <#A URL that identifies an audiovisual asset such as a movie file#>;
AVURLAsset *anAsset = [[AVURLAsset alloc] initWithURL:url options:nil];
```

Options for Initializing an Asset

The AVURLAsset initialization methods take as their second argument an options dictionary. The only key used in the dictionary is AVURLAssetPreferPreciseDurationAndTimingKey. The corresponding value is a Boolean (contained in an NSValue object) that indicates whether the asset should be prepared to indicate a precise duration and provide precise random access by time.

Getting the exact duration of an asset may require significant processing overhead. Using an approximate duration is typically a cheaper operation and sufficient for playback. Thus:

- If you only intend to play the asset, either pass nil instead of a dictionary, or pass a dictionary that contains
 the AVURLAssetPreferPreciseDurationAndTimingKey key and a corresponding value of NO
 (contained in an NSValue object).
- If you want to add the asset to a composition (AVMutableComposition), you typically need precise
 random access. Pass a dictionary that contains the AVURLAssetPreferPreciseDurationAndTimingKey
 key and a corresponding value of YES (contained in an NSValue object—recall that NSNumber inherits
 from NSValue):

```
NSURL *url = <#A URL that identifies an audiovisual asset such as a movie
file#>;
```

```
NSDictionary *options = @{ AVURLAssetPreferPreciseDurationAndTimingKey :
  @YES };
AVURLAsset *anAssetToUseInAComposition = [[AVURLAsset alloc]
  initWithURL:url options:options];
```

Accessing the User's Assets

To access the assets managed by the iPod library or by the Photos application, you need to get a URL of the asset you want.

- To access the iPod Library, you create an MPMediaQuery instance to find the item you want, then get its URL using MPMediaItemPropertyAssetURL.
 - For more about the Media Library, see Multimedia Programming Guide.
- To access the assets managed by the Photos application, you use ALAssetsLibrary.

The following example shows how you can get an asset to represent the first video in the Saved Photos Album.

```
ALAssetsLibrary *library = [[ALAssetsLibrary alloc] init];
// Enumerate just the photos and videos group by using ALAssetsGroupSavedPhotos.
[library enumerateGroupsWithTypes:ALAssetsGroupSavedPhotos usingBlock:^(ALAssetsGroup
*group, BOOL *stop) {
// Within the group enumeration block, filter to enumerate just videos.
[group setAssetsFilter:[ALAssetsFilter allVideos]];
// For this example, we're only interested in the first item.
[group enumerateAssetsAtIndexes: [NSIndexSet indexSetWithIndex:0]
                        options:0
                     usingBlock:^(ALAsset *alAsset, NSUInteger index, BOOL
*innerStop) {
                         // The end of the enumeration is signaled by asset ==
nil.
                         if (alAsset) {
                             ALAssetRepresentation *representation = [alAsset
defaultRepresentation];
```

Preparing an Asset for Use

Initializing an asset (or track) does not necessarily mean that all the information that you might want to retrieve for that item is immediately available. It may require some time to calculate even the duration of an item (an MP3 file, for example, may not contain summary information). Rather than blocking the current thread while a value is being calculated, you should use the AVAsynchronousKeyValueLoading protocol to ask for values and get an answer back later through a completion handler you define using a block. (AVAsset and AVAssetTrack conform to the AVAsynchronousKeyValueLoading protocol.)

You test whether a value is loaded for a property using statusOfValueForKey:error:. When an asset is first loaded, the value of most or all of its properties is AVKeyValueStatusUnknown. To load a value for one or more properties, you invoke loadValuesAsynchronouslyForKeys:completionHandler:. In the completion handler, you take whatever action is appropriate depending on the property's status. You should always be prepared for loading to not complete successfully, either because it failed for some reason such as a network-based URL being inaccessible, or because the load was canceled.

```
NSURL *url = <#A URL that identifies an audiovisual asset such as a movie file#>;
AVURLAsset *anAsset = [[AVURLAsset alloc] initWithURL:url options:nil];
NSArray *keys = @[@"duration"];
[asset loadValuesAsynchronouslyForKeys:keys completionHandler:^() {
    NSError *error = nil;
```

```
AVKeyValueStatus tracksStatus = [asset statusOfValueForKey:@"duration"
error:&error];
switch (tracksStatus) {
    case AVKeyValueStatusLoaded:
        [self updateUserInterfaceForDuration];
        break;
    case AVKeyValueStatusFailed:
        [self reportError:error forAsset:asset];
        break;
    case AVKeyValueStatusCancelled:
        // Do whatever is appropriate for cancelation.
        break;
}
}];
```

If you want to prepare an asset for playback, you should load its tracks property. For more about playing assets, see Playback (page 22).

Getting Still Images From a Video

To get still images such as thumbnails from an asset for playback, you use an AVAssetImageGenerator object. You initialize an image generator with your asset. Initialization may succeed, though, even if the asset possesses no visual tracks at the time of initialization, so if necessary you should test whether the asset has any tracks with the visual characteristic using tracksWithMediaCharacteristic:

```
AVAsset anAsset = <#Get an asset#>;
if ([[anAsset tracksWithMediaType:AVMediaTypeVideo] count] > 0) {
    AVAssetImageGenerator *imageGenerator =
        [AVAssetImageGenerator assetImageGeneratorWithAsset:anAsset];
    // Implementation continues...
}
```

You can configure several aspects of the image generator, for example, you can specify the maximum dimensions for the images it generates and the aperture mode using maximumSize and apertureMode respectively. You can then generate a single image at a given time, or a series of images. You must ensure that you keep a strong reference to the image generator until it has generated all the images.

Generating a Single Image

You use copyCGImageAtTime:actualTime:error: to generate a single image at a specific time. AVFoundation may not be able to produce an image at exactly the time you request, so you can pass as the second argument a pointer to a CMTime that upon return contains the time at which the image was actually generated.

```
AVAsset *myAsset = <#An asset#>];
AVAssetImageGenerator *imageGenerator = [[AVAssetImageGenerator alloc]
initWithAsset:myAsset];
Float64 durationSeconds = CMTimeGetSeconds([myAsset duration]);
CMTime midpoint = CMTimeMakeWithSeconds(durationSeconds/2.0, 600);
NSError *error;
CMTime actualTime;
CGImageRef halfWayImage = [imageGenerator copyCGImageAtTime:midpoint
actualTime:&actualTime error:&error];
if (halfWayImage != NULL) {
   NSString *actualTimeString = (NSString *)CMTimeCopyDescription(NULL, actualTime);
    NSString *requestedTimeString = (NSString *)CMTimeCopyDescription(NULL,
midpoint);
    NSLog(@"Got halfWayImage: Asked for %@, got %@", requestedTimeString,
actualTimeString);
    // Do something interesting with the image.
    CGImageRelease(halfWayImage);
}
```

Generating a Sequence of Images

To generate a series of images, you send the image generator a

generateCGImagesAsynchronouslyForTimes:completionHandler: message. The first argument is an array of NSValue objects, each containing a CMTime structure, specifying the asset times for which you want images to be generated. The second argument is a block that serves as a callback invoked for each image that is generated. The block arguments provide a result constant that tells you whether the image was created successfully or if the operation was canceled, and, as appropriate:

- The image
- The time for which you requested the image and the actual time for which the image was generated
- An error object that describes the reason generation failed

In your implementation of the block, check the result constant to determine whether the image was created. In addition, ensure that you keep a strong reference to the image generator until it has finished creating the images.

```
AVAsset *myAsset = <#An asset#>];
// Assume: @property (strong) AVAssetImageGenerator *imageGenerator;
self.imageGenerator = [AVAssetImageGenerator assetImageGeneratorWithAsset:myAsset];
Float64 durationSeconds = CMTimeGetSeconds([myAsset duration]);
CMTime firstThird = CMTimeMakeWithSeconds(durationSeconds/3.0, 600);
CMTime secondThird = CMTimeMakeWithSeconds(durationSeconds*2.0/3.0, 600);
CMTime end = CMTimeMakeWithSeconds(durationSeconds, 600);
NSArray *times = @[NSValue valueWithCMTime:kCMTimeZero],
                  [NSValue valueWithCMTime:firstThird], [NSValue
valueWithCMTime:secondThird],
                  [NSValue valueWithCMTime:end]];
[image Generator\ generate CGI mages A synchronous ly For Times: times
               completionHandler:^(CMTime requestedTime, CGImageRef image, CMTime
 actualTime,
                                     AVAssetImageGeneratorResult result, NSError
*error) {
                NSString *requestedTimeString = (NSString *)
                   CFBridgingRelease(CMTimeCopyDescription(NULL, requestedTime));
```

You can cancel the generation of the image sequence by sending the image generator a cancelAllCGImageGeneration message.

Trimming and Transcoding a Movie

You can transcode a movie from one format to another, and trim a movie, using an AVAssetExportSession object. The workflow is shown in Figure 1-1. An export session is a controller object that manages asynchronous export of an asset. You initialize the session using the asset you want to export and the name of a export preset that indicates the export options you want to apply (see allExportPresets). You then configure the export session to specify the output URL and file type, and optionally other settings such as the metadata and whether the output should be optimized for network use.

Figure 1-1 The export session workflow



You can check whether you can export a given asset using a given preset using exportPresetsCompatibleWithAsset: as illustrated in this example:

```
AVAsset *anAsset = <#Get an asset#>;
NSArray *compatiblePresets = [AVAssetExportSession
exportPresetsCompatibleWithAsset:anAsset];
if ([compatiblePresets containsObject:AVAssetExportPresetLowQuality]) {
    AVAssetExportSession *exportSession = [[AVAssetExportSession alloc]
        initWithAsset:anAsset presetName:AVAssetExportPresetLowQuality];
    // Implementation continues.
}
```

You complete the configuration of the session by providing the output URL (The URL must be a file URL.) AVAssetExportSession can infer the output file type from the URL's path extension; typically, however, you set it directly using outputFileType. You can also specify additional properties such as the time range, a limit for the output file length, whether the exported file should be optimized for network use, and a video composition. The following example illustrates how to use the timeRange property to trim the movie:

```
exportSession.outputURL = <#A file URL#>;
exportSession.outputFileType = AVFileTypeQuickTimeMovie;

CMTime start = CMTimeMakeWithSeconds(1.0, 600);

CMTime duration = CMTimeMakeWithSeconds(3.0, 600);

CMTimeRange range = CMTimeRangeMake(start, duration);
exportSession.timeRange = range;
```

To create the new file, you invoke exportAsynchronouslyWithCompletionHandler:. The completion handler block is called when the export operation finishes; in your implementation of the handler, you should check the session's status value to determine whether the export was successful, failed, or was canceled:

```
break;

default:
    break;
}
}
```

You can cancel the export by sending the session a cancelExport message.

The export will fail if you try to overwrite an existing file, or write a file outside of the application's sandbox. It may also fail if:

- There is an incoming phone call
- Your application is in the background and another application starts playback

In these situations, you should typically inform the user that the export failed, then allow the user to restart the export.

Playback

To control the playback of assets, you use an AVPlayer object. During playback, you can use an AVPlayerItem instance to manage the presentation state of an asset as a whole, and an AVPlayerItemTrack object to manage the presentation state of an individual track. To display video, you use an AVPlayerLayer object.

Playing Assets


A player is a controller object that you use to manage playback of an asset, for example starting and stopping playback, and seeking to a particular time. You use an instance of AVPlayer to play a single asset. You can use an AVQueuePlayer object to play a number of items in sequence (AVQueuePlayer is a subclass of AVPlayer). On OS X you have the option of the using the AVKit framework's AVPlayerView class to play the content back within a view.

A player provides you with information about the state of the playback so, if you need to, you can synchronize your user interface with the player's state. You typically direct the output of a player to a specialized Core Animation layer (an instance of AVPlayerLayer or AVSynchronizedLayer). To learn more about layers, see *Core Animation Programming Guide*.

Multiple player layers: You can create many AVPlayerLayer objects from a single AVPlayer instance, but only the most recently created such layer will display any video content onscreen.


Although ultimately you want to play an asset, you don't provide assets directly to an AVPlayer object. Instead, you provide an instance of AVPlayerItem. A player item manages the presentation state of an asset with which it is associated. A player item contains player item tracks—instances of AVPlayerItemTrack—that correspond to the tracks in the asset. The relationship between the various objects is shown in Figure 2-1.

Figure 2-1 Playing an asset



This abstraction means that you can play a given asset using different players simultaneously, but rendered in different ways by each player. Figure 2-2 shows one possibility, with two different players playing the same asset, with different settings. Using the item tracks, you can, for example, disable a particular track during playback (for example, you might not want to play the sound component).

Figure 2-2 Playing the same asset in different ways



You can initialize a player item with an existing asset, or you can initialize a player item directly from a URL so that you can play a resource at a particular location (AVPlayerItem will then create and configure an asset for the resource). As with AVAsset, though, simply initializing a player item doesn't necessarily mean it's ready for immediate playback. You can observe (using key-value observing) an item's status property to determine if and when it's ready to play.

Handling Different Types of Asset

The way you configure an asset for playback may depend on the sort of asset you want to play. Broadly speaking, there are two main types: file-based assets, to which you have random access (such as from a local file, the camera roll, or the Media Library), and stream-based assets (HTTP Live Streaming format).

To load and play a file-based asset. There are several steps to playing a file-based asset:

- Create an asset using AVURLAsset.
- Create an instance of AVPlayerItem using the asset.

- Associate the item with an instance of AVPlayer.
- Wait until the item's status property indicates that it's ready to play (typically you use key-value observing to receive a notification when the status changes).

This approach is illustrated in Putting It All Together: Playing a Video File Using AVPlayerLayer (page 31).

To create and prepare an HTTP live stream for playback. Initialize an instance of AVPlayerItem using the URL. (You cannot directly create an AVAsset instance to represent the media in an HTTP Live Stream.)

```
NSURL *url = [NSURL URLWithString:@"<#Live stream URL#>];
// You may find a test stream at
<http://devimages.apple.com/iphone/samples/bipbop/bipbopall.m3u8>.
self.playerItem = [AVPlayerItem playerItemWithURL:url];
[playerItem addObserver:self forKeyPath:@"status" options:0
context:&ItemStatusContext];
self.player = [AVPlayer playerWithPlayerItem:playerItem];
```

When you associate the player item with a player, it starts to become ready to play. When it is ready to play, the player item creates the AVAsset and AVAssetTrack instances, which you can use to inspect the contents of the live stream.

To get the duration of a streaming item, you can observe the duration property on the player item. When the item becomes ready to play, this property updates to the correct value for the stream.

Note: Using the duration property on the player item requires iOS 4.3 or later. An approach that is compatible with all versions of iOS involves observing the status property of the player item. When the status becomes AVPlayerItemStatusReadyToPlay, the duration can be fetched with the following line of code:

```
[[[[[playerItem tracks] objectAtIndex:0] assetTrack] asset] duration];
```

If you simply want to play a live stream, you can take a shortcut and create a player directly using the URL use the following code:

```
self.player = [AVPlayer playerWithURL:<#Live stream URL#>];
[player addObserver:self forKeyPath:@"status" options:0
context:&PlayerStatusContext];
```

As with assets and items, initializing the player does not mean it's ready for playback. You should observe the player's status property, which changes to AVPlayerStatusReadyToPlay when it is ready to play. You can also observe the currentItem property to access the player item created for the stream.

If you don't know what kind of URL you have, follow these steps:

- 1. Try to initialize an AVURLASSET using the URL, then load its tracks key.

 If the tracks load successfully, then you create a player item for the asset.
- If 1 fails, create an AVPlayerItem directly from the URL.
 Observe the player's status property to determine whether it becomes playable.

If either route succeeds, you end up with a player item that you can then associate with a player.

Playing an Item

To start playback, you send a play message to the player.

```
- (IBAction)play:sender {
    [player play];
}
```

In addition to simply playing, you can manage various aspects of the playback, such as the rate and the location of the playhead. You can also monitor the play state of the player; this is useful if you want to, for example, synchronize the user interface to the presentation state of the asset—see Monitoring Playback (page 28).

Changing the Playback Rate

You change the rate of playback by setting the player's rate property.

```
aPlayer.rate = 0.5;
aPlayer.rate = 2.0;
```

A value of 1.0 means "play at the natural rate of the current item". Setting the rate to 0.0 is the same as pausing playback—you can also use pause.

Items that support reverse playback can use the rate property with a negative number to set the reverse playback rate. You determine the type of reverse play that is supported by using the playerItem properties canPlayReverse (supports a rate value of -1.0), canPlaySlowReverse (supports rates between 0.0 and 1.0) and canPlayFastReverse (supports rate values less than -1.0).

Seeking—Repositioning the Playhead

To move the playhead to a particular time, you generally use seekToTime: as follows:

```
CMTime fiveSecondsIn = CMTimeMake(5, 1);
[player seekToTime:fiveSecondsIn];
```

The seekToTime: method, however, is tuned for performance rather than precision. If you need to move the playhead precisely, instead you use seekToTime:toleranceBefore:toleranceAfter: as in the following code fragment:

```
CMTime fiveSecondsIn = CMTimeMake(5, 1);
[player seekToTime:fiveSecondsIn toleranceBefore:kCMTimeZero
toleranceAfter:kCMTimeZero];
```

Using a tolerance of zero may require the framework to decode a large amount of data. You should use zero only if you are, for example, writing a sophisticated media editing application that requires precise control.

After playback, the player's head is set to the end of the item and further invocations of play have no effect. To position the playhead back at the beginning of the item, you can register to receive an AVPlayerItemDidPlayToEndTimeNotification notification from the item. In the notification's callback method, you invoke seekToTime: with the argument kCMTimeZero.

```
// Register with the notification center after creating the player item.
   [[NSNotificationCenter defaultCenter]
      addObserver:self
      selector:@selector(playerItemDidReachEnd:)
      name:AVPlayerItemDidPlayToEndTimeNotification
      object:<#The player item#>];

- (void)playerItemDidReachEnd:(NSNotification *)notification {
      [player seekToTime:kCMTimeZero];
}
```

Playing Multiple Items

You can use an AVQueuePlayer object to play a number of items in sequence. The AVQueuePlayer class is a subclass of AVPlayer. You initialize a queue player with an array of player items.

```
NSArray *items = <#An array of player items#>;
AVQueuePlayer *queuePlayer = [[AVQueuePlayer alloc] initWithItems:items];
```

You can then play the queue using play, just as you would an AVPlayer object. The queue player plays each item in turn. If you want to skip to the next item, you send the queue player an advanceToNextItem message.

You can modify the queue using insertItem:afterItem:, removeItem:, and removeAllItems. When adding a new item, you should typically check whether it can be inserted into the queue, using canInsertItem:afterItem:. You pass nil as the second argument to test whether the new item can be appended to the queue.

```
AVPlayerItem *anItem = <#Get a player item#>;
if ([queuePlayer canInsertItem:anItem afterItem:nil]) {
    [queuePlayer insertItem:anItem afterItem:nil];
}
```

Monitoring Playback

You can monitor a number of aspects of both the presentation state of a player and the player item being played. This is particularly useful for state changes that are not under your direct control. For example:

- If the user uses multitasking to switch to a different application, a player's rate property will drop to 0.0.
- If you are playing remote media, a player item's loadedTimeRanges and seekableTimeRanges properties will change as more data becomes available.

These properties tell you what portions of the player item's timeline are available.

- A player's currentItem property changes as a player item is created for an HTTP live stream.
- A player item's tracks property may change while playing an HTTP live stream.
 - This may happen if the stream offers different encodings for the content; the tracks change if the player switches to a different encoding.
- A player or player item's status property may change if playback fails for some reason.

You can use key-value observing to monitor changes to values of these properties.

Important: You should register for KVO change notifications and unregister from KVO change notifications on the main thread. This avoids the possibility of receiving a partial notification if a change is being made on another thread. AV Foundation invokes observeValueForKeyPath:ofObject:change:context: on the main thread, even if the change operation is made on another thread.

Responding to a Change in Status

When a player or player item's status changes, it emits a key-value observing change notification. If an object is unable to play for some reason (for example, if the media services are reset), the status changes to AVPlayerStatusFailed or AVPlayerItemStatusFailed as appropriate. In this situation, the value of the object's error property is changed to an error object that describes why the object is no longer be able to play.

AV Foundation does not specify what thread that the notification is sent on. If you want to update the user interface, you must make sure that any relevant code is invoked on the main thread. This example uses dispatch_async to execute code on the main thread.

```
- (void)observeValueForKeyPath:(NSString *)keyPath ofObject:(id)object
                        change:(NSDictionary *)change context:(void *)context {
   if (context == <#Player status context#>) {
        AVPlayer *thePlayer = (AVPlayer *)object;
        if ([thePlayer status] == AVPlayerStatusFailed) {
            NSError *error = [<#The AVPlayer object#> error];
            // Respond to error: for example, display an alert sheet.
            return;
        }
        // Deal with other status change if appropriate.
   }
   // Deal with other change notifications if appropriate.
    [super observeValueForKeyPath:keyPath ofObject:object
           change:change context:context];
    return;
}
```

Tracking Readiness for Visual Display

You can observe an AVPlayerLayer object's readyForDisplay property to be notified when the layer has user-visible content. In particular, you might insert the player layer into the layer tree only when there is something for the user to look at and then perform a transition from.

Tracking Time

To track changes in the position of the playhead in an AVPlayer object, you can use addPeriodicTimeObserverForInterval:queue:usingBlock: or addBoundaryTimeObserverForTimes:queue:usingBlock:. You might do this to, for example, update your user interface with information about time elapsed or time remaining, or perform some other user interface synchronization.

- With addPeriodicTimeObserverForInterval:queue:usingBlock:, the block you provide is invoked at the interval you specify, if time jumps, and when playback starts or stops.
- With addBoundaryTimeObserverForTimes:queue:usingBlock:, you pass an array of CMTime structures contained in NSValue objects. The block you provide is invoked whenever any of those times is traversed.

Both of the methods return an opaque object that serves as an observer. You must keep a strong reference to the returned object as long as you want the time observation block to be invoked by the player. You must also balance each invocation of these methods with a corresponding call to removeTimeObserver:.

With both of these methods, AV Foundation does not guarantee to invoke your block for every interval or boundary passed. AV Foundation does not invoke a block if execution of a previously invoked block has not completed. You must make sure, therefore, that the work you perform in the block does not overly tax the system.

```
// Assume a property: @property (strong) id playerObserver;

Float64 durationSeconds = CMTimeGetSeconds([<#An asset#> duration]);

CMTime firstThird = CMTimeMakeWithSeconds(durationSeconds/3.0, 1);

CMTime secondThird = CMTimeMakeWithSeconds(durationSeconds*2.0/3.0, 1);

NSArray *times = @[[NSValue valueWithCMTime:firstThird], [NSValue valueWithCMTime:secondThird]];

self.playerObserver = [<#A player#> addBoundaryTimeObserverForTimes:times queue:NULL usingBlock:^{
```

```
NSString *timeDescription = (NSString *)
    CFBridgingRelease(CMTimeCopyDescription(NULL, [self.player currentTime]));
NSLog(@"Passed a boundary at %@", timeDescription);
}];
```

Reaching the End of an Item

You can register to receive an AVPlayerItemDidPlayToEndTimeNotification notification when a player item has completed playback.

Putting It All Together: Playing a Video File Using AVPlayerLayer

This brief code example illustrates how you can use an AVPlayer object to play a video file. It shows how to:

- Configure a view to use an AVPlayerLayer layer
- Create an AVPlayer object
- Create an AVPlayerItem object for a file-based asset and use key-value observing to observe its status
- Respond to the item becoming ready to play by enabling a button
- Play the item and then restore the player's head to the beginning

Note: To focus on the most relevant code, this example omits several aspects of a complete application, such as memory management and unregistering as an observer (for key-value observing or for the notification center). To use AV Foundation, you are expected to have enough experience with Cocoa to be able to infer the missing pieces.

For a conceptual introduction to playback, skip to Playing Assets (page 22).

The Player View

To play the visual component of an asset, you need a view containing an AVPlayerLayer layer to which the output of an AVPlayer object can be directed. You can create a simple subclass of UIView to accommodate this:

```
#import <UIKit/UIKit.h>
#import <AVFoundation/AVFoundation.h>
@interface PlayerView: UIView
@property (nonatomic) AVPlayer *player;
@end
@implementation PlayerView
+ (Class)layerClass {
    return [AVPlayerLayer class];
}
- (AVPlayer*)player {
    return [(AVPlayerLayer *)[self layer] player];
}
- (void)setPlayer:(AVPlayer *)player {
    [(AVPlayerLayer *)[self layer] setPlayer:player];
}
@end
```

A Simple View Controller

Assume you have a simple view controller, declared as follows:

```
@class PlayerView;
@interface PlayerViewController : UIViewController

@property (nonatomic) AVPlayer *player;
@property (nonatomic) AVPlayerItem *playerItem;
@property (nonatomic, weak) IBOutlet PlayerView *playerView;
@property (nonatomic, weak) IBOutlet UIButton *playButton;
- (IBAction)loadAssetFromFile:sender;
```

```
- (IBAction)play:sender;
- (void)syncUI;
@end
```

The syncUI method synchronizes the button's state with the player's state:

```
- (void)syncUI {
   if ((self.player.currentItem != nil) &&
        ([self.player.currentItem status] == AVPlayerItemStatusReadyToPlay)) {
        self.playButton.enabled = YES;
   }
   else {
        self.playButton.enabled = NO;
   }
}
```

You can invoke syncUI in the view controller's viewDidLoad method to ensure a consistent user interface when the view is first displayed.

```
- (void)viewDidLoad {
    [super viewDidLoad];
    [self syncUI];
}
```

The other properties and methods are described in the remaining sections.

Creating the Asset

You create an asset from a URL using AVURLASSET. (The following example assumes your project contains a suitable video resource.)

In the completion block, you create an instance of AVPlayerItem for the asset and set it as the player for the player view. As with creating the asset, simply creating the player item does not mean it's ready to use. To determine when it's ready to play, you can observe the item's status property. You should configure this observing before associating the player item instance with the player itself.

You trigger the player item's preparation to play when you associate it with the player.

```
// Define this constant for the key-value observation context.
static const NSString *ItemStatusContext;
// Completion handler block.
         dispatch_async(dispatch_get_main_queue(),
                NSError *error;
                AVKeyValueStatus status = [asset statusOfValueForKey:tracksKey
error:&error];
                if (status == AVKeyValueStatusLoaded) {
                    self.playerItem = [AVPlayerItem playerItemWithAsset:asset];
                   // ensure that this is done before the playerItem is associated
with the player
                    [self.playerItem addObserver:self forKeyPath:@"status"
                                options:NSKeyValueObservingOptionInitial
context:&ItemStatusContext];
                    [[NSNotificationCenter defaultCenter] addObserver:self
selector:@selector(playerItemDidReachEnd:)
```

Responding to the Player Item's Status Change

When the player item's status changes, the view controller receives a key-value observing change notification. AV Foundation does not specify what thread that the notification is sent on. If you want to update the user interface, you must make sure that any relevant code is invoked on the main thread. This example uses dispatch_async to queue a message on the main thread to synchronize the user interface.

Playing the Item

Playing the item involves sending a play message to the player.

```
- (IBAction)play:sender {
    [player play];
}
```

The item is played only once. After playback, the player's head is set to the end of the item, and further invocations of the play method will have no effect. To position the playhead back at the beginning of the item, you can register to receive an AVPlayerItemDidPlayToEndTimeNotification from the item. In the notification's callback method, invoke seekToTime: with the argument kCMTimeZero.


```
// Register with the notification center after creating the player item.
   [[NSNotificationCenter defaultCenter]
      addObserver:self
      selector:@selector(playerItemDidReachEnd:)
      name:AVPlayerItemDidPlayToEndTimeNotification
      object:[self.player currentItem]];

- (void)playerItemDidReachEnd:(NSNotification *)notification {
      [self.player seekToTime:kCMTimeZero];
}
```

Editing


The AVFoundation framework provides a feature-rich set of classes to facilitate the editing of audio visual assets. At the heart of AVFoundation's editing API are compositions. A composition is simply a collection of tracks from one or more different media assets. The AVMutableComposition class provides an interface for inserting and removing tracks, as well as managing their temporal orderings. Figure 3-1 shows how a new composition is pieced together from a combination of existing assets to form a new asset. If all you want to do is merge multiple assets together sequentially into a single file, that is as much detail as you need. If you want to perform any custom audio or video processing on the tracks in your composition, you need to incorporate an audio mix or a video composition, respectively.

Figure 3-1 AVMutableComposition assembles assets together



Using the AVMutableAudioMix class, you can perform custom audio processing on the audio tracks in your composition, as shown in Figure 3-2. Currently, you can specify a maximum volume or set a volume ramp for an audio track.


Figure 3-2 AVMutableAudioMix performs audio mixing



You can use the AVMutableVideoComposition class to work directly with the video tracks in your composition for the purposes of editing, shown in Figure 3-3. With a single video composition, you can specify the desired render size and scale, as well as the frame duration, for the output video. Through a video composition's instructions (represented by the AVMutableVideoCompositionInstruction class), you can modify the background color of your video and apply layer instructions. These layer instructions (represented by the AVMutableVideoCompositionLayerInstruction class) can be used to apply transforms, transform ramps,

opacity and opacity ramps to the video tracks within your composition. The video composition class also gives you the ability to introduce effects from the Core Animation framework into your video using the animationTool property.

Figure 3-3 AVMutableVideoComposition



To combine your composition with an audio mix and a video composition, you use an AVAssetExportSession object, as shown in Figure 3-4. You initialize the export session with your composition and then simply assign your audio mix and video composition to the audioMix and videoComposition properties respectively.

AVMutableComposition

AVMutableCompositionTrack (video)

AVMutableCompositionTrack (video)

AVMutableVideoComposition

AVMutableVideoCompositionInstruction

AVMutableVideoCompositionInstruction

AVMutableVideoCompositionInstruction

AVMutableAudioMix

AVMutableAudioMixInputParameters

AVMutableAudioMixInputParameters

Figure 3-4 Use AVAssetExportSession to combine media elements into an output file

Creating a Composition

To create your own composition, you use the AVMutableComposition class. To add media data to your composition, you must add one or more composition tracks, represented by the AVMutableCompositionTrack class. The simplest case is creating a mutable composition with one video track and one audio track:

```
AVMutableComposition *mutableComposition = [AVMutableComposition composition];

// Create the video composition track.

AVMutableCompositionTrack *mutableCompositionVideoTrack = [mutableComposition addMutableTrackWithMediaType:AVMediaTypeVideo preferredTrackID:kCMPersistentTrackID_Invalid];

// Create the audio composition track.

AVMutableCompositionTrack *mutableCompositionAudioTrack = [mutableComposition addMutableTrackWithMediaType:AVMediaTypeAudio preferredTrackID:kCMPersistentTrackID_Invalid];
```

Options for Initializing a Composition Track

When adding new tracks to a composition, you must provide both a media type and a track ID. Although audio and video are the most commonly used media types, you can specify other media types as well, such as AVMediaTypeSubtitle or AVMediaTypeText.

Every track associated with some audiovisual data has a unique identifier referred to as a track ID. If you specify kCMPersistentTrackID_Invalid as the preferred track ID, a unique identifier is automatically generated for you and associated with the track.

Adding Audiovisual Data to a Composition

Once you have a composition with one or more tracks, you can begin adding your media data to the appropriate tracks. To add media data to a composition track, you need access to the AVAsset object where the media data is located. You can use the mutable composition track interface to place multiple tracks with the same underlying media type together on the same track. The following example illustrates how to add two different video asset tracks in sequence to the same composition track:

```
// You can retrieve AVAssets from a number of places, like the camera roll for
example.
AVAsset *videoAsset = <#AVAsset with at least one video track#>;
AVAsset *anotherVideoAsset = <#another AVAsset with at least one video track#>;
// Get the first video track from each asset.
AVAssetTrack *videoAssetTrack = [[videoAsset tracksWithMediaType:AVMediaTypeVideo]
objectAtIndex:0];
AVAssetTrack *anotherVideoAssetTrack = [[anotherVideoAsset
tracksWithMediaType:AVMediaTypeVideo] objectAtIndex:0];
// Add them both to the composition.
[mutableCompositionVideoTrack
insertTimeRange:CMTimeRangeMake(kCMTimeZero, videoAssetTrack.timeRange.duration)
ofTrack:videoAssetTrack atTime:kCMTimeZero error:nil];
[mutableCompositionVideoTrack
insertTimeRange:CMTimeRangeMake(kCMTimeZero,anotherVideoAssetTrack.timeRange.duration)
ofTrack:anotherVideoAssetTrack atTime:videoAssetTrack.timeRange.duration error:nil];
```

Retrieving Compatible Composition Tracks

Where possible, you should have only one composition track for each media type. This unification of compatible asset tracks leads to a minimal amount of resource usage. When presenting media data serially, you should place any media data of the same type on the same composition track. You can query a mutable composition to find out if there are any composition tracks compatible with your desired asset track:

```
AVMutableCompositionTrack *compatibleCompositionTrack = [mutableComposition
mutableTrackCompatibleWithTrack:<#the AVAssetTrack you want to insert#>];
if (compatibleCompositionTrack) {
    // Implementation continues.
}
```

Note: Placing multiple video segments on the same composition track can potentially lead to dropping frames at the transitions between video segments, especially on embedded devices. Choosing the number of composition tracks for your video segments depends entirely on the design of your app and its intended platform.

Generating a Volume Ramp

A single AVMutableAudioMix object can perform custom audio processing on all of the audio tracks in your composition individually. You create an audio mix using the audioMix class method, and you use instances of the AVMutableAudioMixInputParameters class to associate the audio mix with specific tracks within your composition. An audio mix can be used to vary the volume of an audio track. The following example displays how to set a volume ramp on a specific audio track to slowly fade the audio out over the duration of the composition:

```
AVMutableAudioMix *mutableAudioMix = [AVMutableAudioMix audioMix];

// Create the audio mix input parameters object.

AVMutableAudioMixInputParameters *mixParameters = [AVMutableAudioMixInputParameters audioMixInputParametersWithTrack:mutableCompositionAudioTrack];

// Set the volume ramp to slowly fade the audio out over the duration of the composition.

[mixParameters setVolumeRampFromStartVolume:1.f toEndVolume:0.f timeRange:CMTimeRangeMake(kCMTimeZero, mutableComposition.duration)];

// Attach the input parameters to the audio mix.

mutableAudioMix.inputParameters = @[mixParameters];
```

Performing Custom Video Processing

As with an audio mix, you only need one AVMutableVideoComposition object to perform all of your custom video processing on your composition's video tracks. Using a video composition, you can directly set the appropriate render size, scale, and frame rate for your composition's video tracks. For a detailed example of setting appropriate values for these properties, see Setting the Render Size and Frame Duration (page 49).

Changing the Composition's Background Color

All video compositions must also have an array of AVVideoCompositionInstruction objects containing at least one video composition instruction. You use the AVMutableVideoCompositionInstruction class to create your own video composition instructions. Using video composition instructions, you can modify the composition's background color, specify whether post processing is needed or apply layer instructions.

The following example illustrates how to create a video composition instruction that changes the background color to red for the entire composition.

```
AVMutableVideoCompositionInstruction *mutableVideoCompositionInstruction = [AVMutableVideoCompositionInstruction videoCompositionInstruction];

mutableVideoCompositionInstruction.timeRange = CMTimeRangeMake(kCMTimeZero, mutableComposition.duration);

mutableVideoCompositionInstruction.backgroundColor = [[UIColor redColor] CGColor];
```

Applying Opacity Ramps

Video composition instructions can also be used to apply video composition layer instructions. An AVMutableVideoCompositionLayerInstruction object can apply transforms, transform ramps, opacity and opacity ramps to a certain video track within a composition. The order of the layer instructions in a video composition instruction's layerInstructions array determines how video frames from source tracks should be layered and composed for the duration of that composition instruction. The following code fragment shows how to set an opacity ramp to slowly fade out the first video in a composition before transitioning to the second video:

```
AVAsset *firstVideoAssetTrack = <#AVAssetTrack representing the first video segment played in the composition#>;

AVAsset *secondVideoAssetTrack = <#AVAssetTrack representing the second video segment played in the composition#>;

// Create the first video composition instruction.

AVMutableVideoCompositionInstruction *firstVideoCompositionInstruction = [AVMutableVideoCompositionInstruction videoCompositionInstruction];

// Set its time range to span the duration of the first video track.
```

```
firstVideoCompositionInstruction.timeRange = CMTimeRangeMake(kCMTimeZero,
firstVideoAssetTrack.timeRange.duration);
// Create the layer instruction and associate it with the composition video track.
AVMutableVideoCompositionLayerInstruction *firstVideoLayerInstruction =
[AVMutableVideoCompositionLayerInstruction
videoCompositionLayerInstructionWithAssetTrack:mutableCompositionVideoTrack];
// Create the opacity ramp to fade out the first video track over its entire
duration.
[firstVideoLayerInstruction setOpacityRampFromStartOpacity:1.f toEndOpacity:0.f
timeRange:CMTimeRangeMake(kCMTimeZero, firstVideoAssetTrack.timeRange.duration)];
// Create the second video composition instruction so that the second video track
isn't transparent.
AVMutableVideoCompositionInstruction *secondVideoCompositionInstruction =
[AVMutableVideoCompositionInstruction videoCompositionInstruction];
// Set its time range to span the duration of the second video track.
secondVideoCompositionInstruction.timeRange =
CMTimeRangeMake(firstVideoAssetTrack.timeRange.duration,
CMTimeAdd(firstVideoAssetTrack.timeRange.duration,
secondVideoAssetTrack.timeRange.duration));
// Create the second layer instruction and associate it with the composition video
track.
AVMutableVideoCompositionLayerInstruction *secondVideoLayerInstruction =
[AVMutableVideoCompositionLayerInstruction
videoCompositionLayerInstructionWithAssetTrack:mutableCompositionVideoTrack];
// Attach the first layer instruction to the first video composition instruction.
firstVideoCompositionInstruction.layerInstructions = @[firstVideoLayerInstruction];
// Attach the second layer instruction to the second video composition instruction.
secondVideoCompositionInstruction.layerInstructions = @[secondVideoLayerInstruction];
// Attach both of the video composition instructions to the video composition.
mutableVideoComposition.instructions = @[firstVideoCompositionInstruction,
secondVideoCompositionInstruction];
```

Incorporating Core Animation Effects

A video composition can add the power of Core Animation to your composition through the animationTool property. Through this animation tool, you can accomplish tasks such as watermarking video and adding titles or animating overlays. Core Animation can be used in two different ways with video compositions: You can add a Core Animation layer in as its own individual composition track, or you can render Core Animation effects (using a Core Animation layer) into the video frames in your composition directly. The following code displays the latter option by adding a watermark to the center of the video:

```
CALayer *watermarkLayer = <#CALayer representing your desired watermark image#>;
CALayer *parentLayer = [CALayer layer];
CALayer *videoLayer = [CALayer layer];
parentLayer.frame = CGRectMake(0, 0, mutableVideoComposition.renderSize.width, mutableVideoComposition.renderSize.height);
videoLayer.frame = CGRectMake(0, 0, mutableVideoComposition.renderSize.width, mutableVideoComposition.renderSize.height);
[parentLayer addSublayer:videoLayer];
watermarkLayer.position = CGPointMake(mutableVideoComposition.renderSize.width/2, mutableVideoComposition.renderSize.height/4);
[parentLayer addSublayer:watermarkLayer];
mutableVideoComposition.animationTool = [AVVideoCompositionCoreAnimationTool videoCompositionCoreAnimationToolWithPostProcessingAsVideoLayer:videoLayerinLayer:parentLayer];
```

Putting It All Together: Combining Multiple Assets and Saving the Result to the Camera Roll

This brief code example illustrates how you can combine two video asset tracks and an audio asset track to create a single video file. It shows how to:

- Create an AVMutableComposition object and add multiple AVMutableCompositionTrack objects
- Add time ranges of AVAssetTrack objects to compatible composition tracks
- Check the preferredTransform property of a video asset track to determine the video's orientation
- Use AVMutableVideoCompositionLayerInstruction objects to apply transforms to the video tracks within a composition
- Set appropriate values for the renderSize and frameDuration properties of a video composition
- Use a composition in conjunction with a video composition when exporting to a video file
- Save a video file to the Camera Roll

Note: To focus on the most relevant code, this example omits several aspects of a complete app, such as memory management and error handling. To use AVFoundation, you are expected to have enough experience with Cocoa to infer the missing pieces.

Creating the Composition

To piece together tracks from separate assets, you use an AVMutableComposition object. Create the composition and add one audio and one video track.

```
AVMutableComposition *mutableComposition = [AVMutableComposition composition];

AVMutableCompositionTrack *videoCompositionTrack = [mutableComposition addMutableTrackWithMediaType:AVMediaTypeVideo preferredTrackID:kCMPersistentTrackID_Invalid];

AVMutableCompositionTrack *audioCompositionTrack = [mutableComposition addMutableTrackWithMediaType:AVMediaTypeAudio preferredTrackID:kCMPersistentTrackID_Invalid];
```

Adding the Assets

An empty composition does you no good. Add the two video asset tracks and the audio asset track to the composition.

```
AVAssetTrack *firstVideoAssetTrack = [[firstVideoAsset tracksWithMediaType:AVMediaTypeVideo] objectAtIndex:0];

AVAssetTrack *secondVideoAssetTrack = [[secondVideoAsset tracksWithMediaType:AVMediaTypeVideo] objectAtIndex:0];

[videoCompositionTrack insertTimeRange:CMTimeRangeMake(kCMTimeZero, firstVideoAssetTrack.timeRange.duration) ofTrack:firstVideoAssetTrack atTime:kCMTimeZero error:nil];

[videoCompositionTrack insertTimeRange:CMTimeRangeMake(kCMTimeZero, secondVideoAssetTrack.timeRange.duration) ofTrack:secondVideoAssetTrack atTime:firstVideoAssetTrack.timeRange.duration error:nil];

[audioCompositionTrack insertTimeRange:CMTimeRangeMake(kCMTimeZero, CMTimeAdd(firstVideoAssetTrack.timeRange.duration, secondVideoAssetTrack.timeRange.duration)) ofTrack:[[audioAsset tracksWithMediaType:AVMediaTypeAudio] objectAtIndex:0] atTime:kCMTimeZero error:nil];
```

Note: This assumes that you have two assets that contain at least one video track each and a third asset that contains at least one audio track. The videos can be retrieved from the Camera Roll, and the audio track can be retrieved from the music library or the videos themselves.

Checking the Video Orientations

Once you add your video and audio tracks to the composition, you need to ensure that the orientations of both video tracks are correct. By default, all video tracks are assumed to be in landscape mode. If your video track was taken in portrait mode, the video will not be oriented properly when it is exported. Likewise, if you try to combine a video shot in portrait mode with a video shot in landscape mode, the export session will fail to complete.

```
BOOL isFirstVideoPortrait = NO;
CGAffineTransform firstTransform = firstVideoAssetTrack.preferredTransform;
// Check the first video track's preferred transform to determine if it was recorded
in portrait mode.
if (firstTransform.a == 0 && firstTransform.d == 0 && (firstTransform.b == 1.0 ||
firstTransform.b == -1.0) && (firstTransform.c == 1.0 || firstTransform.c ==
-1.0)) {
    isFirstVideoPortrait = YES;
}
BOOL isSecondVideoPortrait = NO;
CGAffineTransform secondTransform = secondVideoAssetTrack.preferredTransform;
// Check the second video track's preferred transform to determine if it was
recorded in portrait mode.
if (secondTransform.a == 0 && secondTransform.d == 0 && (secondTransform.b == 1.0
 || secondTransform.b == -1.0) && (secondTransform.c == 1.0 || secondTransform.c
== -1.0)) {
    isSecondVideoPortrait = YES;
}
if ((isFirstVideoAssetPortrait && !isSecondVideoAssetPortrait) ||
(!isFirstVideoAssetPortrait && isSecondVideoAssetPortrait)) {
    UIAlertView *incompatibleVideoOrientationAlert = [[UIAlertView alloc]]
initWithTitle:@"Error!" message:@"Cannot combine a video shot in portrait mode
with a video shot in landscape mode." delegate:self cancelButtonTitle:@"Dismiss"
otherButtonTitles:nil];
    [incompatibleVideoOrientationAlert show];
    return;
}
```

Applying the Video Composition Layer Instructions

Once you know the video segments have compatible orientations, you can apply the necessary layer instructions to each one and add these layer instructions to the video composition.

```
AVMutableVideoCompositionInstruction *firstVideoCompositionInstruction =
[AVMutableVideoCompositionInstruction videoCompositionInstruction];
// Set the time range of the first instruction to span the duration of the first
video track.
firstVideoCompositionInstruction.timeRange = CMTimeRangeMake(kCMTimeZero,
firstVideoAssetTrack.timeRange.duration);
AVMutable Video Composition Instruction * second Video Composition Instruction = \\
[AVMutableVideoCompositionInstruction videoCompositionInstruction];
// Set the time range of the second instruction to span the duration of the second
video track.
secondVideoCompositionInstruction.timeRange =
CMTimeRangeMake(firstVideoAssetTrack.timeRange.duration,
CMTimeAdd(firstVideoAssetTrack.timeRange.duration,
secondVideoAssetTrack.timeRange.duration));
AVMutableVideoCompositionLayerInstruction *firstVideoLayerInstruction =
[AVMutableVideoCompositionLayerInstruction
videoCompositionLayerInstructionWithAssetTrack:videoCompositionTrack];
// Set the transform of the first layer instruction to the preferred transform of
the first video track.
[firstVideoLayerInstruction setTransform:firstTransform atTime:kCMTimeZero];
AVMutableVideoCompositionLayerInstruction *secondVideoLayerInstruction =
[AVMutableVideoCompositionLayerInstruction
videoCompositionLayerInstructionWithAssetTrack:videoCompositionTrack];
// Set the transform of the second layer instruction to the preferred transform
of the second video track.
[secondVideoLayerInstruction setTransform:secondTransform
atTime:firstVideoAssetTrack.timeRange.duration];
firstVideoCompositionInstruction.layerInstructions = @[firstVideoLayerInstruction];
secondVideoCompositionInstruction.layerInstructions = @[secondVideoLayerInstruction];
AVMutableVideoComposition *mutableVideoComposition = [AVMutableVideoComposition
videoComposition];
mutableVideoComposition.instructions = @[firstVideoCompositionInstruction,
secondVideoCompositionInstruction];
```

All AVAssetTrack objects have a preferredTransform property that contains the orientation information for that asset track. This transform is applied whenever the asset track is displayed onscreen. In the previous code, the layer instruction's transform is set to the asset track's transform so that the video in the new composition displays properly once you adjust its render size.

Setting the Render Size and Frame Duration

To complete the video orientation fix, you must adjust the renderSize property accordingly. You should also pick a suitable value for the frameDuration property, such as 1/30th of a second (or 30 frames per second). By default, the renderScale property is set to 1.0, which is appropriate for this composition.

```
CGSize naturalSizeFirst, naturalSizeSecond;
// If the first video asset was shot in portrait mode, then so was the second one
if we made it here.
if (isFirstVideoAssetPortrait) {
// Invert the width and height for the video tracks to ensure that they display
properly.
    naturalSizeFirst = CGSizeMake(firstVideoAssetTrack.naturalSize.height,
firstVideoAssetTrack.naturalSize.width);
    naturalSizeSecond = CGSizeMake(secondVideoAssetTrack.naturalSize.height,
secondVideoAssetTrack.naturalSize.width);
}
else {
// If the videos weren't shot in portrait mode, we can just use their natural
sizes.
    naturalSizeFirst = firstVideoAssetTrack.naturalSize;
    naturalSizeSecond = secondVideoAssetTrack.naturalSize;
}
float renderWidth, renderHeight;
// Set the renderWidth and renderHeight to the max of the two videos widths and
heights.
if (naturalSizeFirst.width > naturalSizeSecond.width) {
    renderWidth = naturalSizeFirst.width;
}
else {
    renderWidth = naturalSizeSecond.width;
}
if (naturalSizeFirst.height > naturalSizeSecond.height) {
    renderHeight = naturalSizeFirst.height;
```

```
else {
    renderHeight = naturalSizeSecond.height;
}
mutableVideoComposition.renderSize = CGSizeMake(renderWidth, renderHeight);
// Set the frame duration to an appropriate value (i.e. 30 frames per second for video).
mutableVideoComposition.frameDuration = CMTimeMake(1,30);
```

Exporting the Composition and Saving it to the Camera Roll

The final step in this process involves exporting the entire composition into a single video file and saving that video to the camera roll. You use an AVAssetExportSession object to create the new video file and you pass to it your desired URL for the output file. You can then use the ALAssetsLibrary class to save the resulting video file to the Camera Roll.

```
// Create a static date formatter so we only have to initialize it once.
static NSDateFormatter *kDateFormatter;
if (!kDateFormatter) {
    kDateFormatter = [[NSDateFormatter alloc] init];
    kDateFormatter.dateStyle = NSDateFormatterMediumStyle;
    kDateFormatter.timeStyle = NSDateFormatterShortStyle;
}
// Create the export session with the composition and set the preset to the highest
 quality.
AVAssetExportSession *exporter = [[AVAssetExportSession alloc]
initWithAsset:mutableComposition presetName:AVAssetExportPresetHighestQuality];
// Set the desired output URL for the file created by the export process.
exporter.outputURL = [[[[NSFileManager defaultManager]
URLForDirectory:NSDocumentDirectory inDomain:NSUserDomainMask appropriateForURL:nil
 create:@YES error:nil] URLByAppendingPathComponent:[kDateFormatter
stringFromDate:[NSDate date]]]
URLByAppendingPathExtension: CPBridgingPelease(UTTypeCopyPreferredTadWithClass((CPStringPef)AVFileTypeQuidkTimeMovie,
 kUTTagClassFilenameExtension))];
// Set the output file type to be a QuickTime movie.
exporter.outputFileType = AVFileTypeQuickTimeMovie;
exporter.shouldOptimizeForNetworkUse = YES;
exporter.videoComposition = mutableVideoComposition;
```

Still and Video Media Capture

Objective-CSwift

To manage the capture from a device such as a camera or microphone, you assemble objects to represent inputs and outputs, and use an instance of AVCaptureSession to coordinate the data flow between them. Minimally you need:

- An instance of AVCaptureDevice to represent the input device, such as a camera or microphone
- An instance of a concrete subclass of AVCaptureInput to configure the ports from the input device
- An instance of a concrete subclass of AVCaptureOutput to manage the output to a movie file or still image
- An instance of AVCaptureSession to coordinate the data flow from the input to the output

To show the user a preview of what the camera is recording, you can use an instance of AVCaptureVideoPreviewLayer (a subclass of CALayer).

You can configure multiple inputs and outputs, coordinated by a single session, as shown in Figure 4-1




Figure 4-1 A single session can configure multiple inputs and outputs

For many applications, this is as much detail as you need. For some operations, however, (if you want to monitor the power levels in an audio channel, for example) you need to consider how the various ports of an input device are represented and how those ports are connected to the output.

A connection between a capture input and a capture output in a capture session is represented by an AVCaptureConnection object. Capture inputs (instances of AVCaptureInput) have one or more input ports (instances of AVCaptureInputPort). Capture outputs (instances of AVCaptureOutput) can accept data from one or more sources (for example, an AVCaptureMovieFileOutput object accepts both video and audio data).

When you add an input or an output to a session, the session forms connections between all the compatible capture inputs' ports and capture outputs, as shown in Figure 4-2. A connection between a capture input and a capture output is represented by an AVCaptureConnection object.

Capture Device Input
Capture input port
(Video)
Capture input port
(Audio)
Capture Session
Connections
Capture connection
Capture connection
Capture connection

Figure 4-2 AVCaptureConnection represents a connection between an input and output

AVCaptureMovieFileOutput

You can use a capture connection to enable or disable the flow of data from a given input or to a given output. You can also use a connection to monitor the average and peak power levels in an audio channel.

AVCaptureStillImageOutput

Note: Media capture does not support simultaneous capture of both the front-facing and back-facing cameras on iOS devices.

Use a Capture Session to Coordinate Data Flow

An AVCaptureSession object is the central coordinating object you use to manage data capture. You use an instance to coordinate the flow of data from AV input devices to outputs. You add the capture devices and outputs you want to the session, then start data flow by sending the session a startRunning message, and stop the data flow by sending a stopRunning message.

```
AVCaptureSession *session = [[AVCaptureSession alloc] init];
// Add inputs and outputs.
[session startRunning];
```

Configuring a Session

You use a *preset* on the session to specify the image quality and resolution you want. A preset is a constant that identifies one of a number of possible configurations; in some cases the actual configuration is device-specific:

| Symbol | Resolution | Comments |
|--------------------------------|------------|--|
| AVCaptureSessionPresetHigh | High | Highest recording quality. This varies per device. |
| AVCaptureSessionPresetMedium | Medium | Suitable for Wi-Fi sharing. The actual values may change. |
| AVCaptureSessionPresetLow | Low | Suitable for 3G sharing. The actual values may change. |
| AVCaptureSessionPreset640x480 | 640x480 | VGA. |
| AVCaptureSessionPreset1280x720 | 1280x720 | 720p HD. |
| AVCaptureSessionPresetPhoto | Photo | Full photo resolution. This is not supported for video output. |

If you want to set a media frame size-specific configuration, you should check whether it is supported before setting it, as follows:

```
if ([session canSetSessionPreset:AVCaptureSessionPreset1280x720]) {
    session.sessionPreset = AVCaptureSessionPreset1280x720;
}
else {
    // Handle the failure.
}
```

If you need to adjust session parameters at a more granular level than is possible with a preset, or you'd like to make changes to a running session, you surround your changes with the beginConfiguration and commitConfiguration methods. The beginConfiguration and commitConfiguration methods ensure that devices changes occur as a group, minimizing visibility or inconsistency of state. After calling beginConfiguration, you can add or remove outputs, alter the sessionPreset property, or configure individual capture input or output properties. No changes are actually made until you invoke commitConfiguration, at which time they are applied together.

```
[session beginConfiguration];
// Remove an existing capture device.
// Add a new capture device.
// Reset the preset.
[session commitConfiguration];
```

Monitoring Capture Session State

A capture session posts notifications that you can observe to be notified, for example, when it starts or stops running, or when it is interrupted. You can register to receive an

AVCaptureSessionRuntimeErrorNotification if a runtime error occurs. You can also interrogate the session's running property to find out if it is running, and its interrupted property to find out if it is interrupted. Additionally, both the running and interrupted properties are key-value observing compliant and the notifications are posted on the main thread.

An AVCaptureDevice Object Represents an Input Device

An AVCaptureDevice object abstracts a physical capture device that provides input data (such as audio or video) to an AVCaptureSession object. There is one object for each input device, for example, two video inputs—one for the front-facing the camera, one for the back-facing camera—and one audio input for the microphone.

You can find out which capture devices are currently available using the AVCaptureDevice class methods devices and devicesWithMediaType:. And, if necessary, you can find out what features an iPhone, iPad, or iPod offers (see Device Capture Settings (page 58)). The list of available devices may change, though. Current input devices may become unavailable (if they're used by another application), and new input devices may become available, (if they're relinquished by another application). You should register to receive AVCaptureDeviceWasConnectedNotification and AVCaptureDeviceWasDisconnectedNotification notifications to be alerted when the list of available devices changes.


You add an input device to a capture session using a capture input (see Use Capture Inputs to Add a Capture Device to a Session (page 63)).


Device Characteristics

You can ask a device about its different characteristics. You can also test whether it provides a particular media type or supports a given capture session preset using hasMediaType: and supportsAVCaptureSessionPreset: respectively. To provide information to the user, you can find out the position of the capture device (whether it is on the front or the back of the unit being tested), and its localized name. This may be useful if you want to present a list of capture devices to allow the user to choose one.

Figure 4-3 shows the positions of the back-facing (AVCaptureDevicePositionBack) and front-facing (AVCaptureDevicePositionFront) cameras.

Note: Media capture does not support simultaneous capture of both the front-facing and back-facing cameras on iOS devices.





The following code example iterates over all the available devices and logs their name—and for video devices, their position—on the unit.

```
NSArray *devices = [AVCaptureDevice devices];

for (AVCaptureDevice *device in devices) {
    NSLog(@"Device name: %@", [device localizedName]);

    if ([device hasMediaType:AVMediaTypeVideo]) {

        if ([device position] == AVCaptureDevicePositionBack) {
            NSLog(@"Device position : back");
        }
        else {
```

```
NSLog(@"Device position : front");
}
}
```

In addition, you can find out the device's model ID and its unique ID.

Device Capture Settings

Different devices have different capabilities; for example, some may support different focus or flash modes; some may support focus on a point of interest.

The following code fragment shows how you can find video input devices that have a torch mode and support a given capture session preset:

If you find multiple devices that meet your criteria, you might let the user choose which one they want to use. To display a description of a device to the user, you can use its localizedName property.

You use the various different features in similar ways. There are constants to specify a particular mode, and you can ask a device whether it supports a particular mode. In several cases, you can observe a property to be notified when a feature is changing. In all cases, you should lock the device before changing the mode of a particular feature, as described in Configuring a Device (page 62).

Note: Focus point of interest and exposure point of interest are mutually exclusive, as are focus mode and exposure mode.

Focus Modes

There are three focus modes:

- AVCaptureFocusModeLocked: The focal position is fixed.
 This is useful when you want to allow the user to compose a scene then lock the focus.
- AVCaptureFocusModeAutoFocus: The camera does a single scan focus then reverts to locked.
 This is suitable for a situation where you want to select a particular item on which to focus and then maintain focus on that item even if it is not the center of the scene.
- AVCaptureFocusModeContinuousAutoFocus: The camera continuously autofocuses as needed.

You use the isFocusModeSupported: method to determine whether a device supports a given focus mode, then set the mode using the focusMode property.

In addition, a device may support a focus point of interest. You test for support using focusPointOfInterestSupported. If it's supported, you set the focal point using focusPointOfInterest. You pass a CGPoint where $\{0,0\}$ represents the top left of the picture area, and $\{1,1\}$ represents the bottom right in landscape mode with the home button on the right — this applies even if the device is in portrait mode.

You can use the adjustingFocus property to determine whether a device is currently focusing. You can observe the property using key-value observing to be notified when a device starts and stops focusing.

If you change the focus mode settings, you can return them to the default configuration as follows:

```
if ([currentDevice isFocusModeSupported:AVCaptureFocusModeContinuousAutoFocus]) {
    CGPoint autofocusPoint = CGPointMake(0.5f, 0.5f);
    [currentDevice setFocusPointOfInterest:autofocusPoint];
    [currentDevice setFocusMode:AVCaptureFocusModeContinuousAutoFocus];
}
```

Exposure Modes

There are two exposure modes:

- AVCaptureExposureModeContinuousAutoExposure: The device automatically adjusts the exposure level as needed.
- AVCaptureExposureModeLocked: The exposure level is fixed at its current level.

You use the isExposureModeSupported: method to determine whether a device supports a given exposure mode, then set the mode using the exposureMode property.

In addition, a device may support an exposure point of interest. You test for support using exposurePointOfInterestSupported. If it's supported, you set the exposure point using exposurePointOfInterest. You pass a CGPoint where $\{\emptyset,\emptyset\}$ represents the top left of the picture area, and $\{1,1\}$ represents the bottom right in landscape mode with the home button on the right — this applies even if the device is in portrait mode.

You can use the adjustingExposure property to determine whether a device is currently changing its exposure setting. You can observe the property using key-value observing to be notified when a device starts and stops changing its exposure setting.

If you change the exposure settings, you can return them to the default configuration as follows:

```
if ([currentDevice
isExposureModeSupported:AVCaptureExposureModeContinuousAutoExposure]) {
    CGPoint exposurePoint = CGPointMake(0.5f, 0.5f);
    [currentDevice setExposurePointOfInterest:exposurePoint];
    [currentDevice setExposureMode:AVCaptureExposureModeContinuousAutoExposure];
}
```

Flash Modes

There are three flash modes:

- AVCaptureFlashModeOff: The flash will never fire.
- AVCaptureFlashModeOn: The flash will always fire.
- AVCaptureFlashModeAuto: The flash will fire dependent on the ambient light conditions.

You use hasFlash to determine whether a device has a flash. If that method returns YES, you then use the isFlashModeSupported: method, passing the desired mode to determine whether a device supports a given flash mode, then set the mode using the flashMode property.

Torch Mode

In torch mode, the flash is continuously enabled at a low power to illuminate a video capture. There are three torch modes:

- AVCaptureTorchModeOff: The torch is always off.
- AVCaptureTorchModeOn: The torch is always on.

AVCaptureTorchModeAuto: The torch is automatically switched on and off as needed.

You use has Torch to determine whether a device has a flash. You use the isTorchModeSupported: method to determine whether a device supports a given flash mode, then set the mode using the torchMode property.

For devices with a torch, the torch only turns on if the device is associated with a running capture session.

Video Stabilization

Cinematic video stabilization is available for connections that operate on video, depending on the specific device hardware. Even so, not all source formats and video resolutions are supported.

Enabling cinematic video stabilization may also introduce additional latency into the video capture pipeline. To detect when video stabilization is in use, use the videoStabilizationEnabled property. The enablesVideoStabilizationWhenAvailable property allows an application to automatically enable video stabilization if it is supported by the camera. By default automatic stabilization is disabled due to the above limitations.

White Balance

There are two white balance modes:

- AVCaptureWhiteBalanceModeLocked: The white balance mode is fixed.
- AVCaptureWhiteBalanceModeContinuousAutoWhiteBalance: The camera continuously adjusts the
 white balance as needed.

You use the isWhiteBalanceModeSupported: method to determine whether a device supports a given white balance mode, then set the mode using the whiteBalanceMode property.

You can use the adjustingWhiteBalance property to determine whether a device is currently changing its white balance setting. You can observe the property using key-value observing to be notified when a device starts and stops changing its white balance setting.

Setting Device Orientation

You set the desired orientation on a AVCaptureConnection to specify how you want the images oriented in the AVCaptureOutput (AVCaptureMovieFileOutput, AVCaptureStillImageOutput and AVCaptureVideoDataOutput) for the connection.

Use the AVCaptureConnectionsupportsVideoOrientation property to determine whether the device supports changing the orientation of the video, and the videoOrientation property to specify how you want the images oriented in the output port. Listing 4-1 shows how to set the orientation for a AVCaptureConnection to AVCaptureVideoOrientationLandscapeLeft:

Listing 4-1 Setting the orientation of a capture connection

```
AVCaptureConnection *captureConnection = <#A capture connection#>;
if ([captureConnection isVideoOrientationSupported])
{
    AVCaptureVideoOrientation orientation = AVCaptureVideoOrientationLandscapeLeft;
    [captureConnection setVideoOrientation:orientation];
}
```

Configuring a Device

To set capture properties on a device, you must first acquire a lock on the device using lockForConfiguration:. This avoids making changes that may be incompatible with settings in other applications. The following code fragment illustrates how to approach changing the focus mode on a device by first determining whether the mode is supported, then attempting to lock the device for reconfiguration. The focus mode is changed only if the lock is obtained, and the lock is released immediately afterward.

```
if ([device isFocusModeSupported:AVCaptureFocusModeLocked]) {
    NSError *error = nil;
    if ([device lockForConfiguration:&error]) {
        device.focusMode = AVCaptureFocusModeLocked;
        [device unlockForConfiguration];
    }
    else {
        // Respond to the failure as appropriate.
```

You should hold the device lock only if you need the settable device properties to remain unchanged. Holding the device lock unnecessarily may degrade capture quality in other applications sharing the device.

Switching Between Devices

Sometimes you may want to allow users to switch between input devices—for example, switching from using the front-facing to to the back-facing camera. To avoid pauses or stuttering, you can reconfigure a session while it is running, however you should use beginConfiguration and commitConfiguration to bracket your configuration changes:

```
AVCaptureSession *session = <#A capture session#>;
[session beginConfiguration];
[session removeInput:frontFacingCameraDeviceInput];
[session addInput:backFacingCameraDeviceInput];
[session commitConfiguration];
```

When the outermost commitConfiguration is invoked, all the changes are made together. This ensures a smooth transition.

Use Capture Inputs to Add a Capture Device to a Session

To add a capture device to a capture session, you use an instance of AVCaptureDeviceInput (a concrete subclass of the abstract AVCaptureInput class). The capture device input manages the device's ports.

```
NSError *error;
AVCaptureDeviceInput *input =
        [AVCaptureDeviceInput deviceInputWithDevice:device error:&error];
if (!input) {
        // Handle the error appropriately.
}
```

You add inputs to a session using addInput:. If appropriate, you can check whether a capture input is compatible with an existing session using canAddInput:.

```
AVCaptureSession *captureSession = <#Get a capture session#>;
AVCaptureDeviceInput *captureDeviceInput = <#Get a capture device input#>;
if ([captureSession canAddInput:captureDeviceInput]) {
    [captureSession addInput:captureDeviceInput];
```

```
}
else {
    // Handle the failure.
}
```

See Configuring a Session (page 54) for more details on how you might reconfigure a running session.

An AVCaptureInput vends one or more streams of media data. For example, input devices can provide both audio and video data. Each media stream provided by an input is represented by an AVCaptureInputPort object. A capture session uses an AVCaptureConnection object to define the mapping between a set of AVCaptureInputPort objects and a single AVCaptureOutput.

Use Capture Outputs to Get Output from a Session

To get output from a capture session, you add one or more outputs. An output is an instance of a concrete subclass of AVCaptureOutput. You use:

- AVCaptureMovieFileOutput to output to a movie file
- AVCaptureVideoDataOutput if you want to process frames from the video being captured, for example, to create your own custom view layer
- AVCaptureAudioDataOutput if you want to process the audio data being captured
- AVCaptureStillImageOutput if you want to capture still images with accompanying metadata

You add outputs to a capture session using addOutput:. You check whether a capture output is compatible with an existing session using canAddOutput:. You can add and remove outputs as required while the session is running.

```
AVCaptureSession *captureSession = <#Get a capture session#>;
AVCaptureMovieFileOutput *movieOutput = <#Create and configure a movie output#>;
if ([captureSession canAddOutput:movieOutput]) {
     [captureSession addOutput:movieOutput];
}
else {
    // Handle the failure.
}
```

Saving to a Movie File

You save movie data to a file using an AVCaptureMovieFileOutput object. (AVCaptureMovieFileOutput is a concrete subclass of AVCaptureFileOutput, which defines much of the basic behavior.) You can configure various aspects of the movie file output, such as the maximum duration of a recording, or its maximum file size. You can also prohibit recording if there is less than a given amount of disk space left.

```
AVCaptureMovieFileOutput *aMovieFileOutput = [[AVCaptureMovieFileOutput alloc]
init];

CMTime maxDuration = <#Create a CMTime to represent the maximum duration#>;

aMovieFileOutput.maxRecordedDuration = maxDuration;

aMovieFileOutput.minFreeDiskSpaceLimit = <#An appropriate minimum given the quality of the movie format and the duration#>;
```

The resolution and bit rate for the output depend on the capture session's sessionPreset. The video encoding is typically H.264 and audio encoding is typically AAC. The actual values vary by device.

Starting a Recording

You start recording a QuickTime movie using startRecordingToOutputFileURL: recordingDelegate:. You need to supply a file-based URL and a delegate. The URL must not identify an existing file, because the movie file output does not overwrite existing resources. You must also have permission to write to the specified location. The delegate must conform to the AVCaptureFileOutputRecordingDelegate protocol, and must implement the

captureOutput:didFinishRecordingToOutputFileAtURL:fromConnections:error: method.

```
AVCaptureMovieFileOutput *aMovieFileOutput = <#Get a movie file output#>;

NSURL *fileURL = <#A file URL that identifies the output location#>;

[aMovieFileOutput startRecordingToOutputFileURL:fileURL recordingDelegate:<#The delegate#>];
```

In the implementation of

captureOutput:didFinishRecordingToOutputFileAtURL:fromConnections:error:,the delegate might write the resulting movie to the Camera Roll album. It should also check for any errors that might have occurred.

Ensuring That the File Was Written Successfully

To determine whether the file was saved successfully, in the implementation of captureOutput:didFinishRecordingToOutputFileAtURL:fromConnections:error: you check not only the error but also the value of the AVErrorRecordingSuccessfullyFinishedKey in the error's user info dictionary:

You should check the value of the AVErrorRecordingSuccessfullyFinishedKeykey in the user info dictionary of the error, because the file might have been saved successfully, even though you got an error. The error might indicate that one of your recording constraints was reached—for example, AVErrorMaximumDurationReached or AVErrorMaximumFileSizeReached. Other reasons the recording might stop are:

- The disk is full—AVErrorDiskFull
- The recording device was disconnected—AVErrorDeviceWasDisconnected
- The session was interrupted (for example, a phone call was received)—AVErrorSessionWasInterrupted

Adding Metadata to a File

You can set metadata for the movie file at any time, even while recording. This is useful for situations where the information is not available when the recording starts, as may be the case with location information. Metadata for a file output is represented by an array of AVMetadataItem objects; you use an instance of its mutable subclass, AVMutableMetadataItem, to create metadata of your own.

```
AVCaptureMovieFileOutput *aMovieFileOutput = <#Get a movie file output#>;
NSArray *existingMetadataArray = aMovieFileOutput.metadata;
NSMutableArray *newMetadataArray = nil;
if (existingMetadataArray) {
    newMetadataArray = [existingMetadataArray mutableCopy];
}
else {
    newMetadataArray = [[NSMutableArray alloc] init];
}
AVMutableMetadataItem *item = [[AVMutableMetadataItem alloc] init];
item.keySpace = AVMetadataKeySpaceCommon;
item.key = AVMetadataCommonKeyLocation;
CLLocation *location - <#The location to set#>;
item.value = [NSString stringWithFormat:@"%+08.4lf%+09.4lf/"
    location.coordinate.latitude, location.coordinate.longitude];
[newMetadataArray addObject:item];
aMovieFileOutput.metadata = newMetadataArray;
```

Processing Frames of Video

An AVCaptureVideoDataOutput object uses delegation to vend video frames. You set the delegate using setSampleBufferDelegate: queue:. In addition to setting the delegate, you specify a serial queue on which they delegate methods are invoked. You must use a serial queue to ensure that frames are delivered to the delegate in the proper order. You can use the queue to modify the priority given to delivering and processing the video frames. See *SquareCam* for a sample implementation.

The frames are presented in the delegate method,

captureOutput:didOutputSampleBuffer:fromConnection:, as instances of the CMSampleBufferRef opaque type (see Representations of Media (page 110)). By default, the buffers are emitted in the camera's most efficient format. You can use the videoSettings property to specify a custom output format. The video settings property is a dictionary; currently, the only supported key is kCVPixelBufferPixelFormatTypeKey. The recommended pixel formats are returned by the availableVideoCVPixelFormatTypes property, and the availableVideoCodecTypes property returns the supported values. Both Core Graphics and OpenGL work well with the BGRA format:

```
AVCaptureVideoDataOutput *videoDataOutput = [AVCaptureVideoDataOutput new];
NSDictionary *newSettings =
                @{ (NSString *)kCVPixelBufferPixelFormatTypeKey :
@(kCVPixelFormatType_32BGRA) };
videoDataOutput.videoSettings = newSettings;
 // discard if the data output queue is blocked (as we process the still image
[videoDataOutput setAlwaysDiscardsLateVideoFrames:YES];)
// create a serial dispatch queue used for the sample buffer delegate as well as
when a still image is captured
// a serial dispatch queue must be used to guarantee that video frames will be
delivered in order
// see the header doc for setSampleBufferDelegate:queue: for more information
videoDataOutputQueue = dispatch_queue_create("VideoDataOutputQueue",
DISPATCH_QUEUE_SERIAL);
[videoDataOutput setSampleBufferDelegate:self gueue:videoDataOutputQueue];
AVCaptureSession *captureSession = <#The Capture Session#>;
if ( [captureSession canAddOutput:videoDataOutput] )
     [captureSession addOutput:videoDataOutput];
```

Performance Considerations for Processing Video

You should set the session output to the lowest practical resolution for your application. Setting the output to a higher resolution than necessary wastes processing cycles and needlessly consumes power.

You must ensure that your implementation of

captureOutput:didOutputSampleBuffer:fromConnection: is able to process a sample buffer within the amount of time allotted to a frame. If it takes too long and you hold onto the video frames, AV Foundation stops delivering frames, not only to your delegate but also to other outputs such as a preview layer.

You can use the capture video data output's minFrameDuration property to be sure you have enough time to process a frame—at the cost of having a lower frame rate than would otherwise be the case. You might also make sure that the alwaysDiscardsLateVideoFrames property is set to YES (the default). This ensures that any late video frames are dropped rather than handed to you for processing. Alternatively, if you are recording and it doesn't matter if the output fames are a little late and you would *prefer* to get all of them, you can set the property value to NO. This does not mean that frames will not be dropped (that is, frames may still be dropped), but that they may not be dropped as early, or as efficiently.

Capturing Still Images

You use an AVCaptureStillImageOutput output if you want to capture still images with accompanying metadata. The resolution of the image depends on the preset for the session, as well as the device.

Pixel and Encoding Formats

Different devices support different image formats. You can find out what pixel and codec types are supported by a device using availableImageDataCVPixelFormatTypes and availableImageDataCodecTypes respectively. Each method returns an array of the supported values for the specific device. You set the outputSettings dictionary to specify the image format you want, for example:

```
AVCaptureStillImageOutput *stillImageOutput = [[AVCaptureStillImageOutput alloc]
init];

NSDictionary *outputSettings = @{ AVVideoCodecKey : AVVideoCodecJPEG};

[stillImageOutput setOutputSettings:outputSettings];
```

If you want to capture a JPEG image, you should typically not specify your own compression format. Instead, you should let the still image output do the compression for you, since its compression is hardware-accelerated. If you need a data representation of the image, you can use <code>jpegStillImageNSDataRepresentation:</code> to get an NSData object without recompressing the data, even if you modify the image's metadata.

Capturing an Image

When you want to capture an image, you send the output a

captureStillImageAsynchronouslyFromConnection:completionHandler: message. The first argument is the connection you want to use for the capture. You need to look for the connection whose input port is collecting video:

```
AVCaptureConnection *videoConnection = nil;
for (AVCaptureConnection *connection in stillImageOutput.connections) {
    for (AVCaptureInputPort *port in [connection inputPorts]) {
        if ([[port mediaType] isEqual:AVMediaTypeVideo] ) {
            videoConnection = connection;
            break;
        }
    }
    if (videoConnection) { break; }
}
```

The second argument to captureStillImageAsynchronouslyFromConnection: completionHandler: is a block that takes two arguments: a CMSampleBuffer opaque type containing the image data, and an error. The sample buffer itself may contain metadata, such as an EXIF dictionary, as an attachment. You can modify the attachments if you want, but note the optimization for JPEG images discussed in Pixel and Encoding Formats (page 69).

Showing the User What's Being Recorded

You can provide the user with a preview of what's being recorded by the camera (using a preview layer) or by the microphone (by monitoring the audio channel).

Video Preview

You can provide the user with a preview of what's being recorded using an AVCaptureVideoPreviewLayer object. AVCaptureVideoPreviewLayer is a subclass of CALayer (see Core Animation Programming Guide. You don't need any outputs to show the preview.

Using the AVCaptureVideoDataOutput class provides the client application with the ability to access the video pixels before they are presented to the user.

Unlike a capture output, a video preview layer maintains a strong reference to the session with which it is associated. This is to ensure that the session is not deallocated while the layer is attempting to display video. This is reflected in the way you initialize a preview layer:

```
AVCaptureSession *captureSession = <#Get a capture session#>;

CALayer *viewLayer = <#Get a layer from the view in which you want to present the preview#>;

AVCaptureVideoPreviewLayer *captureVideoPreviewLayer = [[AVCaptureVideoPreviewLayer alloc] initWithSession:captureSession];

[viewLayer addSublayer:captureVideoPreviewLayer];
```

In general, the preview layer behaves like any other CALayer object in the render tree (see *Core Animation Programming Guide*). You can scale the image and perform transformations, rotations, and so on just as you would any layer. One difference is that you may need to set the layer's orientation property to specify how it should rotate images coming from the camera. In addition, you can test for device support for video mirroring by querying the supportsVideoMirroring property. You can set the videoMirrored property as required, although when the automaticallyAdjustsVideoMirroring property is set to YES (the default), the mirroring value is automatically set based on the configuration of the session.

Video Gravity Modes

The preview layer supports three gravity modes that you set using videoGravity:

- AVLayerVideoGravityResizeAspect: This preserves the aspect ratio, leaving black bars where the video does not fill the available screen area.
- AVLayerVideoGravityResizeAspectFill: This preserves the aspect ratio, but fills the available screen area, cropping the video when necessary.
- AVLayerVideoGravityResize: This simply stretches the video to fill the available screen area, even if doing so distorts the image.

Using "Tap to Focus" with a Preview

You need to take care when implementing tap-to-focus in conjunction with a preview layer. You must account for the preview orientation and gravity of the layer, and for the possibility that the preview may be mirrored. See the sample code project *AVCam for iOS* for an implementation of this functionality.

Showing Audio Levels

To monitor the average and peak power levels in an audio channel in a capture connection, you use an AVCaptureAudioChannel object. Audio levels are not key-value observable, so you must poll for updated levels as often as you want to update your user interface (for example, 10 times a second).

```
AVCaptureAudioDataOutput *audioDataOutput = <#Get the audio data output#>;
NSArray *connections = audioDataOutput.connections;
if ([connections count] > 0) {
    // There should be only one connection to an AVCaptureAudioDataOutput.
    AVCaptureConnection *connection = [connections objectAtIndex:0];

NSArray *audioChannels = connection.audioChannels;

for (AVCaptureAudioChannel *channel in audioChannels) {
    float avg = channel.averagePowerLevel;
    float peak = channel.peakHoldLevel;
    // Update the level meter user interface.
}

}
```

Putting It All Together: Capturing Video Frames as Ullmage Objects

This brief code example to illustrates how you can capture video and convert the frames you get to UIImage objects. It shows you how to:

- Create an AVCaptureSession object to coordinate the flow of data from an AV input device to an output
- Find the AVCaptureDevice object for the input type you want
- Create an AVCaptureDeviceInput object for the device
- Create an AVCaptureVideoDataOutput object to produce video frames
- Implement a delegate for the AVCaptureVideoDataOutput object to process video frames

Implement a function to convert the CMSampleBuffer received by the delegate into a UIImage object

Note: To focus on the most relevant code, this example omits several aspects of a complete application, including memory management. To use AV Foundation, you are expected to have enough experience with Cocoa to be able to infer the missing pieces.

Create and Configure a Capture Session

You use an AVCaptureSession object to coordinate the flow of data from an AV input device to an output. Create a session, and configure it to produce medium-resolution video frames.

```
AVCaptureSession *session = [[AVCaptureSession alloc] init];
session.sessionPreset = AVCaptureSessionPresetMedium;
```

Create and Configure the Device and Device Input

Capture devices are represented by AVCaptureDevice objects; the class provides methods to retrieve an object for the input type you want. A device has one or more ports, configured using an AVCaptureInput object. Typically, you use the capture input in its default configuration.

Find a video capture device, then create a device input with the device and add it to the session. If an appropriate device can not be located, then the deviceInputWithDevice:error: method will return an error by reference.

```
AVCaptureDevice *device =
        [AVCaptureDevice defaultDeviceWithMediaType:AVMediaTypeVideo];

NSError *error = nil;
AVCaptureDeviceInput *input =
        [AVCaptureDeviceInput deviceInputWithDevice:device error:&error];
if (!input) {
        // Handle the error appropriately.
}
[session addInput:input];
```

Create and Configure the Video Data Output

You use an AVCaptureVideoDataOutput object to process uncompressed frames from the video being captured. You typically configure several aspects of an output. For video, for example, you can specify the pixel format using the videoSettings property and cap the frame rate by setting the minFrameDuration property.

Create and configure an output for video data and add it to the session; cap the frame rate to 15 fps by setting the minFrameDuration property to 1/15 second:

The data output object uses delegation to vend the video frames. The delegate must adopt the AVCaptureVideoDataOutputSampleBufferDelegate protocol. When you set the data output's delegate, you must also provide a queue on which callbacks should be invoked.

```
dispatch_queue_t queue = dispatch_queue_create("MyQueue", NULL);
[output setSampleBufferDelegate:self queue:queue];
dispatch_release(queue);
```

You use the queue to modify the priority given to delivering and processing the video frames.

Implement the Sample Buffer Delegate Method

In the delegate class, implement the method

(captureOutput:didOutputSampleBuffer:fromConnection:) that is called when a sample buffer is written. The video data output object delivers frames as CMSampleBuffer opaque types, so you need to convert from the CMSampleBuffer opaque type to a UIImage object. The function for this operation is shown in Converting CMSampleBuffer to a UIImage Object (page 111).

```
UIImage *image = imageFromSampleBuffer(sampleBuffer);
// Add your code here that uses the image.
}
```

Remember that the delegate method is invoked on the queue you specified in setSampleBufferDelegate: queue:; if you want to update the user interface, you must invoke any relevant code on the main thread.

Starting and Stopping Recording

After configuring the capture session, you should ensure that the camera has permission to record according to the user's preferences.

```
NSString *mediaType = AVMediaTypeVideo;
[AVCaptureDevice requestAccessForMediaType:mediaType completionHandler:^(BOOL
granted) {
    if (granted)
    {
        //Granted access to mediaType
        [self setDeviceAuthorized:YES];
    }
    else
        //Not granted access to mediaType
        dispatch_async(dispatch_get_main_queue(), ^{
        [[[UIAlertView alloc] initWithTitle:@"AVCam!"
                                    message:@"AVCam doesn't have permission to use
 Camera, please change privacy settings"
                                    delegate:self
                          cancelButtonTitle:@"OK"
                          otherButtonTitles:nil] show];
                [self setDeviceAuthorized:NO];
        });
    }
}];
```

If the camera session is configured and the user has approved access to the camera (and if required, the microphone), send a startRunning message to start the recording.

Important: The startRunning method is a blocking call which can take some time, therefore you should perform session setup on a serial queue so that the main queue isn't blocked (which keeps the UI responsive). See *AVCam for iOS* for the canonical implementation example.

[session startRunning];

To stop recording, you send the session a stopRunning message.

High Frame Rate Video Capture

iOS 7.0 introduces high frame rate video capture support (also referred to as "SloMo" video) on selected hardware. The full AVFoundation framework supports high frame rate content.

You determine the capture capabilities of a device using the AVCaptureDeviceFormat class. This class has methods that return the supported media types, frame rates, field of view, maximum zoom factor, whether video stabilization is supported, and more.

- Capture supports full 720p (1280 x 720 pixels) resolution at 60 frames per second (fps) including video stabilization and droppable P-frames (a feature of H264 encoded movies, which allow the movies to play back smoothly even on slower and older hardware.)
- Playback has enhanced audio support for slow and fast playback, allowing the time pitch of the audio can be preserved at slower or faster speeds.
- Editing has full support for scaled edits in mutable compositions.
- Export provides two options when supporting 60 fps movies. The variable frame rate, slow or fast motion, can be preserved, or the movie and be converted to an arbitrary slower frame rate such as 30 frames per second.

The SloPoke sample code demonstrates the AVFoundation support for fast video capture, determining whether hardware supports high frame rate video capture, playback using various rates and time pitch algorithms, and editing (including setting time scales for portions of a composition).

Playback

An instance of AVPlayer manages most of the playback speed automatically by setting the setRate: method value. The value is used as a multiplier for the playback speed. A value of 1.0 causes normal playback, 0.5 plays back at half speed, 5.0 plays back five times faster than normal, and so on.

The AVPlayerItem object supports the audioTimePitchAlgorithm property. This property allows you to specify how audio is played when the movie is played at various frame rates using the Time Pitch Algorithm Settings constants.

The following table shows the supported time pitch algorithms, the quality, whether the algorithm causes the audio to snap to specific frame rates, and the frame rate range that each algorithm supports.

| Time pitch algorithm | Quality | Snaps to specific frame rate | Rate range |
|--|--|---------------------------------------|--|
| AVAudioTimePitch- AlgorithmLowQuality- ZeroLatency | Low quality, suitable for fast-forward, rewind, or low quality voice. | YES | 0.5, 0.666667, 0.8, 1.0, 1.25, 1.5, 2.0 rates. |
| AVAudioTimePitch- AlgorithmTimeDomain | Modest quality, less expensive computationally, suitable for voice. | NO | 0.5–2x rates. |
| AVAudioTimePitch- AlgorithmSpectral | Highest quality, most expensive computationally, preserves the pitch of the original item. | NO | 1/32–32 rates. |
| AVAudioTimePitch- AlgorithmVarispeed | High-quality playback with no pitch correction. | NO | 1/32–32 rates. |

Editing

When editing, you use the AVMutableComposition class to build temporal edits.

- Create a new AVMutableComposition instance using the composition class method.
- Insert your video asset using the insertTimeRange:ofAsset:atTime:error: method.
- Set the time scale of a portion of the composition using scaleTimeRange:toDuration:

Export

Exporting 60 fps video uses the AVAssetExportSession class to export an asset. The content can be exported using two techniques:

- Use the AVAssetExportPresetPassthrough preset to avoid reencoding the movie. It retimes the media with the sections of the media tagged as section 60 fps, section slowed down, or section sped up.
- Use a constant frame rate export for maximum playback compatibility. Set the frameDuration property of the video composition to 30 fps. You can also specify the time pitch by using setting the export session's audioTimePitchAlgorithm property.

Recording

You capture high frame rate video using the AVCaptureMovieFileOutput class, which automatically supports high frame rate recording. It will automatically select the correct H264 pitch level and bit rate.

To do custom recording, you must use the AVAssetWriter class, which requires some additional setup.

assetWriterInput.expectsMediaDataInRealTime=YES;

This setting ensures that the capture can keep up with the incoming data.

Export

Objective-CSwift

To read and write audiovisual assets, you must use the export APIs provided by the AVFoundation framework. The AVAssetExportSession class provides an interface for simple exporting needs, such as modifying the file format or trimming the length of an asset (see Trimming and Transcoding a Movie (page 19)). For more in-depth exporting needs, use the AVAssetReader and AVAssetWriter classes.

Use an AVAssetReader when you want to perform an operation on the contents of an asset. For example, you might read the audio track of an asset to produce a visual representation of the waveform. To produce an asset from media such as sample buffers or still images, use an AVAssetWriter object.

Note: The asset reader and writer classes are not intended to be used for real-time processing. In fact, an asset reader cannot even be used for reading from a real-time source like an HTTP live stream. However, if you are using an asset writer with a real-time data source, such as an AVCaptureOutput object, set the expectsMediaDataInRealTime property of your asset writer's inputs to YES. Setting this property to YES for a non-real-time data source will result in your files not being interleaved properly.

Reading an Asset

Each AVAssetReader object can be associated only with a single asset at a time, but this asset may contain multiple tracks. For this reason, you must assign concrete subclasses of the AVAssetReaderOutput class to your asset reader before you begin reading in order to configure how the media data is read. There are three concrete subclasses of the AVAssetReaderOutput base class that you can use for your asset reading needs: AVAssetReaderTrackOutput, AVAssetReaderAudioMixOutput, and AVAssetReaderVideoCompositionOutput.

Creating the Asset Reader

All you need to initialize an AVAssetReader object is the asset that you want to read.

```
NSError *outError;
AVAsset *someAsset = <#AVAsset that you want to read#>;
```

```
AVAssetReader *assetReader = [AVAssetReader assetReaderWithAsset:someAsset
error:&outError];
BOOL success = (assetReader != nil);
```

Note: Always check that the asset reader returned to you is non-nil to ensure that the asset reader was initialized successfully. Otherwise, the error parameter (outError in the previous example) will contain the relevant error information.

Setting Up the Asset Reader Outputs

After you have created your asset reader, set up at least one output to receive the media data being read. When setting up your outputs, be sure to set the alwaysCopiesSampleData property to NO. In this way, you reap the benefits of performance improvements. In all of the examples within this chapter, this property could and should be set to NO.

If you want only to read media data from one or more tracks and potentially convert that data to a different format, use the AVAssetReaderTrackOutput class, using a single track output object for each AVAssetTrack object that you want to read from your asset. To decompress an audio track to Linear PCM with an asset reader, you set up your track output as follows:

```
AVAssetTrack *audioTrack to read.

AVAssetTrack *audioTrack = [[localAsset tracksWithMediaType:AVMediaTypeAudio] objectAtIndex:0];

// Decompression settings for Linear PCM

NSDictionary *decompressionAudioSettings = @{ AVFormatIDKey : [NSNumber numberWithUnsignedInt:kAudioFormatLinearPCM] };

// Create the output with the audio track and decompression settings.

AVAssetReaderOutput *trackOutput = [AVAssetReaderTrackOutput assetReaderTrackOutputWithTrack:audioTrack outputSettings:decompressionAudioSettings];

// Add the output to the reader if possible.

if ([assetReader canAddOutput:trackOutput])

[assetReader addOutput:trackOutput];
```

Note: To read the media data from a specific asset track in the format in which it was stored, pass nil to the outputSettings parameter.

You use the AVAssetReaderAudioMixOutput and AVAssetReaderVideoCompositionOutput classes to read media data that has been mixed or composited together using an AVAudioMix object or AVVideoComposition object, respectively. Typically, these outputs are used when your asset reader is reading from an AVComposition object.

With a single audio mix output, you can read multiple audio tracks from your asset that have been mixed together using an AVAudioMix object. To specify how the audio tracks are mixed, assign the mix to the AVAssetReaderAudioMixOutput object after initialization. The following code displays how to create an audio mix output with all of the audio tracks from your asset, decompress the audio tracks to Linear PCM, and assign an audio mix object to the output. For details on how to configure an audio mix, see Editing (page 37).

```
AVAudioMix *audioMix = <#An AVAudioMix that specifies how the audio tracks from
the AVAsset are mixed#>;
// Assumes that assetReader was initialized with an AVComposition object.
AVComposition *composition = (AVComposition *)assetReader.asset;
// Get the audio tracks to read.
NSArray *audioTracks = [composition tracksWithMediaType:AVMediaTypeAudio];
// Get the decompression settings for Linear PCM.
NSDictionary *decompressionAudioSettings = @{ AVFormatIDKey : [NSNumber
numberWithUnsignedInt:kAudioFormatLinearPCM] };
// Create the audio mix output with the audio tracks and decompression setttings.
AVAssetReaderOutput *audioMixOutput = [AVAssetReaderAudioMixOutput
assetReaderAudioMixOutputWithAudioTracks:audioTracks
audioSettings:decompressionAudioSettings];
// Associate the audio mix used to mix the audio tracks being read with the output.
audioMixOutput.audioMix = audioMix;
// Add the output to the reader if possible.
if ([assetReader canAddOutput:audioMixOutput])
    [assetReader addOutput:audioMixOutput];
```

Note: Passing nil for the audioSettings parameter tells the asset reader to return samples in a convenient uncompressed format. The same is true for the AVAssetReaderVideoCompositionOutput class.

The video composition output behaves in much the same way: You can read multiple video tracks from your asset that have been composited together using an AVVideoComposition object. To read the media data from multiple composited video tracks and decompress it to ARGB, set up your output as follows:

```
AVVideoComposition *videoComposition = <#An AVVideoComposition that specifies how
 the video tracks from the AVAsset are composited#>;
// Assumes assetReader was initialized with an AVComposition.
AVComposition *composition = (AVComposition *)assetReader.asset;
// Get the video tracks to read.
NSArray *videoTracks = [composition tracksWithMediaType:AVMediaTypeVideo];
// Decompression settings for ARGB.
NSDictionary *decompressionVideoSettings = @{ (id)kCVPixelBufferPixelFormatTypeKey
 : [NSNumber numberWithUnsignedInt:kCVPixelFormatType_32ARGB],
(id)kCVPixelBufferIOSurfacePropertiesKey : [NSDictionary dictionary] };
// Create the video composition output with the video tracks and decompression
setttings.
AVAssetReaderOutput *videoCompositionOutput = [AVAssetReaderVideoCompositionOutput
 assetReaderVideoCompositionOutputWithVideoTracks:videoTracks
videoSettings:decompressionVideoSettings];
// Associate the video composition used to composite the video tracks being read
with the output.
videoCompositionOutput.videoComposition = videoComposition;
// Add the output to the reader if possible.
if ([assetReader canAddOutput:videoCompositionOutput])
    [assetReader addOutput:videoCompositionOutput];
```

Reading the Asset's Media Data

To start reading after setting up all of the outputs you need, call the startReading method on your asset reader. Next, retrieve the media data individually from each output using the copyNextSampleBuffer method. To start up an asset reader with a single output and read all of its media samples, do the following:

```
// Start the asset reader up.
[self.assetReader startReading];
```

```
B00L done = N0;
while (!done)
{
  // Copy the next sample buffer from the reader output.
  CMSampleBufferRef sampleBuffer = [self.assetReaderOutput copyNextSampleBuffer];
  if (sampleBuffer)
  {
    // Do something with sampleBuffer here.
    CFRelease(sampleBuffer);
    sampleBuffer = NULL;
  }
  else
  {
    // Find out why the asset reader output couldn't copy another sample buffer.
    if (self.assetReader.status == AVAssetReaderStatusFailed)
      NSError *failureError = self.assetReader.error;
      // Handle the error here.
    }
    else
      // The asset reader output has read all of its samples.
      done = YES;
    }
  }
}
```

Writing an Asset

The AVAssetWriter class to write media data from multiple sources to a single file of a specified file format. You don't need to associate your asset writer object with a specific asset, but you must use a separate asset writer for each output file that you want to create. Because an asset writer can write media data from multiple sources, you must create an AVAssetWriterInput object for each individual track that you want to write to

the output file. Each AVAssetWriterInput object expects to receive data in the form of CMSampleBufferRef objects, but if you want to append CVPixelBufferRef objects to your asset writer input, use the AVAssetWriterInputPixelBufferAdaptor class.

Creating the Asset Writer

To create an asset writer, specify the URL for the output file and the desired file type. The following code displays how to initialize an asset writer to create a QuickTime movie:

Setting Up the Asset Writer Inputs

For your asset writer to be able to write media data, you must set up at least one asset writer input. For example, if your source of media data is already vending media samples as CMSampleBufferRef objects, just use the AVAssetWriterInput class. To set up an asset writer input that compresses audio media data to 128 kbps AAC and connect it to your asset writer, do the following:

```
// Configure the channel layout as stereo.
AudioChannelLayout stereoChannelLayout = {
    .mChannelLayoutTag = kAudioChannelLayoutTag_Stereo,
    .mChannelBitmap = 0,
    .mNumberChannelDescriptions = 0
};

// Convert the channel layout object to an NSData object.

NSData *channelLayoutAsData = [NSData dataWithBytes:&stereoChannelLayout length:offsetof(AudioChannelLayout, mChannelDescriptions)];

// Get the compression settings for 128 kbps AAC.

NSDictionary *compressionAudioSettings = @{
```

```
AVFormatIDKey
                         : [NSNumber numberWithUnsignedInt:kAudioFormatMPEG4AAC],
    AVEncoderBitRateKey : [NSNumber numberWithInteger:128000],
    AVSampleRateKey
                          : [NSNumber numberWithInteger:44100],
    AVChannelLayoutKey
                          : channelLayoutAsData,
    AVNumberOfChannelsKey: [NSNumber numberWithUnsignedInteger:2]
};
// Create the asset writer input with the compression settings and specify the
media type as audio.
AVAssetWriterInput *assetWriterInput = [AVAssetWriterInput
assetWriterInputWithMediaType:AVMediaTypeAudio
outputSettings:compressionAudioSettings];
// Add the input to the writer if possible.
if ([assetWriter canAddInput:assetWriterInput])
    [assetWriter addInput:assetWriterInput];
```

Note: If you want the media data to be written in the format in which it was stored, pass nil in the outputSettings parameter. Pass nil only if the asset writer was initialized with a fileType of AVFileTypeQuickTimeMovie.

Your asset writer input can optionally include some metadata or specify a different transform for a particular track using the metadata and transform properties respectively. For an asset writer input whose data source is a video track, you can maintain the video's original transform in the output file by doing the following:

```
AVAsset *videoAsset = <#AVAsset with at least one video track#>;
AVAssetTrack *videoAssetTrack = [[videoAsset tracksWithMediaType:AVMediaTypeVideo]
  objectAtIndex:0];
assetWriterInput.transform = videoAssetTrack.preferredTransform;
```

Note: Set the metadata and transform properties before you begin writing with your asset writer for them to take effect.

When writing media data to the output file, sometimes you may want to allocate pixel buffers. To do so, use the AVAssetWriterInputPixelBufferAdaptor class. For greatest efficiency, instead of adding pixel buffers that were allocated using a separate pool, use the pixel buffer pool provided by the pixel buffer adaptor. The following code creates a pixel buffer object working in the RGB domain that will use CGImage objects to create its pixel buffers.

```
NSDictionary *pixelBufferAttributes = @{
    kCVPixelBufferCGImageCompatibilityKey : [NSNumber numberWithBool:YES],
    kCVPixelBufferCGBitmapContextCompatibilityKey : [NSNumber numberWithBool:YES],
    kCVPixelBufferPixelFormatTypeKey : [NSNumber
numberWithInt:kCVPixelFormatType_32ARGB]
};
AVAssetWriterInputPixelBufferAdaptor *inputPixelBufferAdaptor =
[AVAssetWriterInputPixelBufferAdaptor
assetWriterInputPixelBufferAdaptorWithAssetWriterInput:self.assetWriterInput
sourcePixelBufferAttributes:pixelBufferAttributes];
```

Note: All AVAssetWriterInputPixelBufferAdaptor objects must be connected to a single asset writer input. That asset writer input must accept media data of type AVMediaTypeVideo.

Writing Media Data

When you have configured all of the inputs needed for your asset writer, you are ready to begin writing media data. As you did with the asset reader, initiate the writing process with a call to the startWriting method. You then need to start a sample-writing session with a call to the startSessionAtSourceTime: method. All writing done by an asset writer has to occur within one of these sessions and the time range of each session defines the time range of media data included from within the source. For example, if your source is an asset reader that is supplying media data read from an AVAsset object and you don't want to include media data from the first half of the asset, you would do the following:

```
CMTime halfAssetDuration = CMTimeMultiplyByFloat64(self.asset.duration, 0.5);
[self.assetWriter startSessionAtSourceTime:halfAssetDuration];
//Implementation continues.
```

Normally, to end a writing session you must call the endSessionAtSourceTime: method. However, if your writing session goes right up to the end of your file, you can end the writing session simply by calling the finishWriting method. To start up an asset writer with a single input and write all of its media data, do the following:

```
// Prepare the asset writer for writing.
[self.assetWriter startWriting];
// Start a sample-writing session.
[self.assetWriter startSessionAtSourceTime:kCMTimeZero];
// Specify the block to execute when the asset writer is ready for media data and
the queue to call it on.
[self.assetWriterInput requestMediaDataWhenReadyOnQueue:myInputSerialQueue
usingBlock:^{
     while ([self.assetWriterInput isReadyForMoreMediaData])
     {
          // Get the next sample buffer.
         CMSampleBufferRef nextSampleBuffer = [self copyNextSampleBufferToWrite];
          if (nextSampleBuffer)
          {
               // If it exists, append the next sample buffer to the output file.
               [self.assetWriterInput appendSampleBuffer:nextSampleBuffer];
               CFRelease(nextSampleBuffer);
               nextSampleBuffer = nil;
          }
          else
          {
              // Assume that lack of a next sample buffer means the sample buffer
source is out of samples and mark the input as finished.
               [self.assetWriterInput markAsFinished];
               break;
          }
     }
}];
```

The copyNextSampleBufferToWrite method in the code above is simply a stub. The location of this stub is where you would need to insert some logic to return CMSampleBufferRef objects representing the media data that you want to write. One possible source of sample buffers is an asset reader output.

Reencoding Assets

You can use an asset reader and asset writer object in tandem to convert an asset from one representation to another. Using these objects, you have more control over the conversion than you do with an AVAssetExportSession object. For example, you can choose which of the tracks you want to be represented in the output file, specify your own output format, or modify the asset during the conversion process. The first step in this process is just to set up your asset reader outputs and asset writer inputs as desired. After your asset reader and writer are fully configured, you start up both of them with calls to the startReading and startWriting methods, respectively. The following code snippet displays how to use a single asset writer input to write media data supplied by a single asset reader output:

```
NSString *serializationQueueDescription = [NSString stringWithFormat:@"%@
serialization queue", self];
// Create a serialization queue for reading and writing.
dispatch_queue_t serializationQueue =
dispatch_queue_create([serializationQueueDescription UTF8String], NULL);
// Specify the block to execute when the asset writer is ready for media data and
 the queue to call it on.
[self.assetWriterInput requestMediaDataWhenReadyOnQueue:serializationQueue
usingBlock:^{
     while ([self.assetWriterInput isReadyForMoreMediaData])
          // Get the asset reader output's next sample buffer.
          CMSampleBufferRef sampleBuffer = [self.assetReaderOutput
copyNextSampleBuffer];
          if (sampleBuffer != NULL)
               // If it exists, append this sample buffer to the output file.
               BOOL success = [self.assetWriterInput
appendSampleBuffer:sampleBuffer];
               CFRelease(sampleBuffer);
               sampleBuffer = NULL;
               // Check for errors that may have occurred when appending the new
sample buffer.
             if (!success && self.assetWriter.status == AVAssetWriterStatusFailed)
               {
                    NSError *failureError = self.assetWriter.error;
```

```
//Handle the error.
               }
          }
          else
               // If the next sample buffer doesn't exist, find out why the asset
 reader output couldn't vend another one.
               if (self.assetReader.status == AVAssetReaderStatusFailed)
                    NSError *failureError = self.assetReader.error;
                    //Handle the error here.
               }
               else
               {
                   // The asset reader output must have vended all of its samples.
Mark the input as finished.
                    [self.assetWriterInput markAsFinished];
                    break;
               }
          }
     }
}];
```

Putting It All Together: Using an Asset Reader and Writer in Tandem to Reencode an Asset

This brief code example illustrates how to use an asset reader and writer to reencode the first video and audio track of an asset into a new file. It shows how to:

- Use serialization queues to handle the asynchronous nature of reading and writing audiovisual data
- Initialize an asset reader and configure two asset reader outputs, one for audio and one for video
- Initialize an asset writer and configure two asset writer inputs, one for audio and one for video
- Use an asset reader to asynchronously supply media data to an asset writer through two different output/input combinations
- Use a dispatch group to be notified of completion of the reencoding process

Allow a user to cancel the reencoding process once it has begun

Note: To focus on the most relevant code, this example omits several aspects of a complete application. To use AVFoundation, you are expected to have enough experience with Cocoa to be able to infer the missing pieces.

Handling the Initial Setup

Before you create your asset reader and writer and configure their outputs and inputs, you need to handle some initial setup. The first part of this setup involves creating three separate serialization queues to coordinate the reading and writing process.

```
NSString *serializationQueueDescription = [NSString stringWithFormat:@"%@
serialization queue", self];

// Create the main serialization queue.
self.mainSerializationQueue = dispatch_queue_create([serializationQueueDescription
UTF8String], NULL);

NSString *rwAudioSerializationQueueDescription = [NSString stringWithFormat:@"%@
rw audio serialization queue", self];

// Create the serialization queue to use for reading and writing the audio data.
self.rwAudioSerializationQueue =
dispatch_queue_create([rwAudioSerializationQueueDescription UTF8String], NULL);
NSString *rwVideoSerializationQueueDescription = [NSString stringWithFormat:@"%@
rw video serialization queue", self];

// Create the serialization queue to use for reading and writing the video data.
self.rwVideoSerializationQueue =
dispatch_queue_create([rwVideoSerializationQueueDescription UTF8String], NULL);
```

The main serialization queue is used to coordinate the starting and stopping of the asset reader and writer (perhaps due to cancellation) and the other two serialization queues are used to serialize the reading and writing by each output/input combination with a potential cancellation.

Now that you have some serialization queues, load the tracks of your asset and begin the reencoding process.

```
self.asset = <#AVAsset that you want to reencode#>;
self.cancelled = NO;
```

```
self.outputURL = <#NSURL representing desired output URL for file generated by
asset writer#>;
// Asynchronously load the tracks of the asset you want to read.
[self.asset loadValuesAsynchronouslyForKeys:@[@"tracks"] completionHandler:^{
     // Once the tracks have finished loading, dispatch the work to the main
serialization queue.
     dispatch async(self.mainSerializationQueue, ^{
         // Due to asynchronous nature, check to see if user has already cancelled.
          if (self.cancelled)
               return:
          BOOL success = YES;
          NSError *localError = nil;
          // Check for success of loading the assets tracks.
          success = ([self.asset statusOfValueForKey:@"tracks" error:&localError]
 == AVKeyValueStatusLoaded);
          if (success)
              // If the tracks loaded successfully, make sure that no file exists
 at the output path for the asset writer.
               NSFileManager *fm = [NSFileManager defaultManager];
               NSString *localOutputPath = [self.outputURL path];
               if ([fm fileExistsAtPath:localOutputPath])
                    success = [fm removeItemAtPath:localOutputPath
error:&localError];
          }
          if (success)
               success = [self setupAssetReaderAndAssetWriter:&localError];
          if (success)
               success = [self startAssetReaderAndWriter:&localError];
          if (!success)
               [self readingAndWritingDidFinishSuccessfully:success
withError:localError];
     });
}];
```

When the track loading process finishes, whether successfully or not, the rest of the work is dispatched to the main serialization queue to ensure that all of this work is serialized with a potential cancellation. Now all that's left is to implement the cancellation process and the three custom methods at the end of the previous code listing.

Initializing the Asset Reader and Writer

The custom setupAssetReaderAndAssetWriter: method initializes the reader and writer and configures two output/input combinations, one for an audio track and one for a video track. In this example, the audio is decompressed to Linear PCM using the asset reader and compressed back to 128 kbps AAC using the asset writer. The video is decompressed to YUV using the asset reader and compressed to H.264 using the asset writer.

```
- (B00L)setupAssetReaderAndAssetWriter:(NSError **)outError
{
     // Create and initialize the asset reader.
     self.assetReader = [[AVAssetReader alloc] initWithAsset:self.asset
error:outError];
     BOOL success = (self.assetReader != nil);
     if (success)
         // If the asset reader was successfully initialized, do the same for the
 asset writer.
          self.assetWriter = [[AVAssetWriter alloc] initWithURL:self.outputURL
fileType:AVFileTypeQuickTimeMovie error:outError];
          success = (self.assetWriter != nil);
     }
     if (success)
         // If the reader and writer were successfully initialized, grab the audio
 and video asset tracks that will be used.
          AVAssetTrack *assetAudioTrack = nil, *assetVideoTrack = nil;
        NSArray *audioTracks = [self.asset tracksWithMediaType:AVMediaTypeAudio];
          if ([audioTracks count] > 0)
               assetAudioTrack = [audioTracks objectAtIndex:0];
        NSArray *videoTracks = [self.asset tracksWithMediaType:AVMediaTypeVideo];
          if ([videoTracks count] > 0)
```

```
assetVideoTrack = [videoTracks objectAtIndex:0];
          if (assetAudioTrack)
             // If there is an audio track to read, set the decompression settings
to Linear PCM and create the asset reader output.
              NSDictionary *decompressionAudioSettings = @{ AVFormatIDKey :
[NSNumber numberWithUnsignedInt:kAudioFormatLinearPCM] };
               self.assetReaderAudioOutput = [AVAssetReaderTrackOutput
assetReaderTrackOutputWithTrack:assetAudioTrack
outputSettings:decompressionAudioSettings];
               [self.assetReader addOutput:self.assetReaderAudioOutput];
              // Then, set the compression settings to 128kbps AAC and create the
asset writer input.
              AudioChannelLayout stereoChannelLayout = {
                    .mChannelLayoutTag = kAudioChannelLayoutTag_Stereo,
                    .mChannelBitmap = 0,
                    .mNumberChannelDescriptions = 0
               };
              NSData *channelLayoutAsData = [NSData
dataWithBytes:&stereoChannelLayout length:offsetof(AudioChannelLayout,
mChannelDescriptions)];
              NSDictionary *compressionAudioSettings = @{
                    AVFormatIDKey
                                          : [NSNumber
numberWithUnsignedInt:kAudioFormatMPEG4AAC],
                    AVEncoderBitRateKey : [NSNumber numberWithInteger:128000],
                   AVSampleRateKey
                                        : [NSNumber numberWithInteger:44100],
                    AVChannelLayoutKey
                                         : channelLayoutAsData,
                   AVNumberOfChannelsKey: [NSNumber numberWithUnsignedInteger:2]
              };
               self.assetWriterAudioInput = [AVAssetWriterInput
assetWriterInputWithMediaType:[assetAudioTrack mediaType]
outputSettings:compressionAudioSettings];
               [self.assetWriter addInput:self.assetWriterAudioInput];
         }
         if (assetVideoTrack)
          {
```

```
// If there is a video track to read, set the decompression settings
for YUV and create the asset reader output.
              NSDictionary *decompressionVideoSettings = @{
                    (id)kCVPixelBufferPixelFormatTypeKey
                                                            : [NSNumber
numberWithUnsignedInt:kCVPixelFormatType_422YpCbCr8],
                    (id)kCVPixelBufferIOSurfacePropertiesKey : [NSDictionary
dictionary]
               };
               self.assetReaderVideoOutput = [AVAssetReaderTrackOutput
assetReaderTrackOutputWithTrack:assetVideoTrack
outputSettings:decompressionVideoSettings];
               [self.assetReader addOutput:self.assetReaderVideoOutput];
               CMFormatDescriptionRef formatDescription = NULL;
              // Grab the video format descriptions from the video track and grab
the first one if it exists.
              NSArray *videoFormatDescriptions = [assetVideoTrack
formatDescriptions];
               if ([videoFormatDescriptions count] > 0)
                    formatDescription = (__bridge
CMFormatDescriptionRef)[formatDescriptions objectAtIndex:0];
               CGSize trackDimensions = {
                    .width = 0.0,
                    .height = 0.0,
               };
               // If the video track had a format description, grab the track
dimensions from there. Otherwise, grab them direcly from the track itself.
               if (formatDescription)
                    trackDimensions =
CMVideoFormatDescriptionGetPresentationDimensions(formatDescription, false, false);
               else
                    trackDimensions = [assetVideoTrack naturalSize];
              NSDictionary *compressionSettings = nil;
              // If the video track had a format description, attempt to grab the
clean aperture settings and pixel aspect ratio used by the video.
               if (formatDescription)
               {
                   NSDictionary *cleanAperture = nil;
                   NSDictionary *pixelAspectRatio = nil;
```

```
CFDictionaryRef cleanApertureFromCMFormatDescription =
CMFormatDescriptionGetExtension(formatDescription,
kCMFormatDescriptionExtension_CleanAperture);
                    if (cleanApertureFromCMFormatDescription)
                         cleanAperture = @{
                              AVVideoCleanApertureWidthKey
(id)CFDictionaryGetValue(cleanApertureFromCMFormatDescription,
kCMFormatDescriptionKey_CleanApertureWidth),
                              AVVideoCleanApertureHeightKey
(id)CFDictionaryGetValue(cleanApertureFromCMFormatDescription,
kCMFormatDescriptionKey_CleanApertureHeight),
                              AVVideoCleanApertureHorizontalOffsetKey:
(id)CFDictionaryGetValue(cleanApertureFromCMFormatDescription,
kCMFormatDescriptionKey_CleanApertureHorizontalOffset),
                              AVVideoCleanApertureVerticalOffsetKey :
(id)CFDictionaryGetValue(cleanApertureFromCMFormatDescription,
kCMFormatDescriptionKey_CleanApertureVerticalOffset)
                         };
                    }
                    CFDictionaryRef pixelAspectRatioFromCMFormatDescription =
CMFormatDescriptionGetExtension(formatDescription,
kCMFormatDescriptionExtension_PixelAspectRatio);
                    if (pixelAspectRatioFromCMFormatDescription)
                    {
                         pixelAspectRatio = @{
                              AVVideoPixelAspectRatioHorizontalSpacingKey:
(id)CFDictionaryGetValue(pixelAspectRatioFromCMFormatDescription,
kCMFormatDescriptionKey_PixelAspectRatioHorizontalSpacing),
                              AVVideoPixelAspectRatioVerticalSpacingKey :
(id)CFDictionaryGetValue(pixelAspectRatioFromCMFormatDescription,
kCMFormatDescriptionKey_PixelAspectRatioVerticalSpacing)
                         };
                    // Add whichever settings we could grab from the format
description to the compression settings dictionary.
                    if (cleanAperture || pixelAspectRatio)
                    {
                         NSMutableDictionary *mutableCompressionSettings =
[NSMutableDictionary dictionary];
                         if (cleanAperture)
```

```
[mutableCompressionSettings setObject:cleanAperture
 forKey:AVVideoCleanApertureKey];
                         if (pixelAspectRatio)
                           [mutableCompressionSettings setObject:pixelAspectRatio
 forKey:AVVideoPixelAspectRatioKey];
                         compressionSettings = mutableCompressionSettings;
                    }
               }
               // Create the video settings dictionary for H.264.
               NSMutableDictionary *videoSettings = (NSMutableDictionary *) @{
                    AVVideoCodecKey : AVVideoCodecH264,
                    AVVideoWidthKey : [NSNumber
numberWithDouble:trackDimensions.width],
                    AVVideoHeightKey: [NSNumber
numberWithDouble:trackDimensions.height]
               };
               // Put the compression settings into the video settings dictionary
 if we were able to grab them.
               if (compressionSettings)
                    [videoSettings setObject:compressionSettings
forKey:AVVideoCompressionPropertiesKey];
               // Create the asset writer input and add it to the asset writer.
               self.assetWriterVideoInput = [AVAssetWriterInput
assetWriterInputWithMediaType:[videoTrack mediaType] outputSettings:videoSettings];
               [self.assetWriter addInput:self.assetWriterVideoInput];
          }
     }
     return success;
}
```

Reencoding the Asset

Provided that the asset reader and writer are successfully initialized and configured, the startAssetReaderAndWriter: method described in Handling the Initial Setup (page 90) is called. This method is where the actual reading and writing of the asset takes place.

```
- (B00L)startAssetReaderAndWriter:(NSError **)outError
{
```

```
BOOL success = YES;
     // Attempt to start the asset reader.
     success = [self.assetReader startReading];
     if (!success)
          *outError = [self.assetReader error];
     if (success)
     {
         // If the reader started successfully, attempt to start the asset writer.
          success = [self.assetWriter startWriting];
          if (!success)
               *outError = [self.assetWriter error];
     }
     if (success)
     {
          // If the asset reader and writer both started successfully, create the
dispatch group where the reencoding will take place and start a sample-writing
session.
          self.dispatchGroup = dispatch_group_create();
          [self.assetWriter startSessionAtSourceTime:kCMTimeZero];
          self.audioFinished = NO:
          self.videoFinished = NO;
          if (self.assetWriterAudioInput)
               // If there is audio to reencode, enter the dispatch group before
beginning the work.
               dispatch_group_enter(self.dispatchGroup);
               // Specify the block to execute when the asset writer is ready for
audio media data, and specify the queue to call it on.
               [self.assetWriterAudioInput
requestMediaDataWhenReadyOnQueue:self.rwAudioSerializationQueue usingBlock:^{
                    // Because the block is called asynchronously, check to see
whether its task is complete.
                    if (self.audioFinished)
                         return;
                    BOOL completedOrFailed = NO;
```

```
// If the task isn't complete yet, make sure that the input
is actually ready for more media data.
                    while ([self.assetWriterAudioInput isReadyForMoreMediaData]
&& !completedOrFailed)
                        // Get the next audio sample buffer, and append it to the
output file.
                         CMSampleBufferRef sampleBuffer =
[self.assetReaderAudioOutput copyNextSampleBuffer];
                         if (sampleBuffer != NULL)
                         {
                              BOOL success = [self.assetWriterAudioInput
appendSampleBuffer:sampleBuffer];
                              CFRelease(sampleBuffer);
                              sampleBuffer = NULL;
                              completedOrFailed = !success;
                         }
                         else
                         {
                              completedOrFailed = YES;
                         }
                    }
                    if (completedOrFailed)
                         // Mark the input as finished, but only if we haven't
already done so, and then leave the dispatch group (since the audio work has
finished).
                         BOOL oldFinished = self.audioFinished;
                         self.audioFinished = YES;
                         if (oldFinished == NO)
                         {
                               [self.assetWriterAudioInput markAsFinished];
                         }
                         dispatch_group_leave(self.dispatchGroup);
                    }
               }];
          }
```

```
if (self.assetWriterVideoInput)
               // If we had video to reencode, enter the dispatch group before
beginning the work.
               dispatch_group_enter(self.dispatchGroup);
               // Specify the block to execute when the asset writer is ready for
 video media data, and specify the queue to call it on.
               [self.assetWriterVideoInput
requestMediaDataWhenReadyOnQueue:self.rwVideoSerializationQueue usingBlock:^{
                    // Because the block is called asynchronously, check to see
whether its task is complete.
                    if (self.videoFinished)
                         return;
                    BOOL completedOrFailed = NO;
                    // If the task isn't complete yet, make sure that the input
is actually ready for more media data.
                    while ([self.assetWriterVideoInput isReadyForMoreMediaData]
&& !completedOrFailed)
                        // Get the next video sample buffer, and append it to the
 output file.
                         CMSampleBufferRef sampleBuffer =
[self.assetReaderVideoOutput copyNextSampleBuffer];
                         if (sampleBuffer != NULL)
                         {
                              BOOL success = [self.assetWriterVideoInput
appendSampleBuffer:sampleBuffer];
                              CFRelease(sampleBuffer);
                              sampleBuffer = NULL;
                              completedOrFailed = !success;
                         }
                         else
                         {
                              completedOrFailed = YES;
                         }
                    }
                    if (completedOrFailed)
```

```
{
                         // Mark the input as finished, but only if we haven't
already done so, and then leave the dispatch group (since the video work has
finished).
                         BOOL oldFinished = self.videoFinished;
                         self.videoFinished = YES;
                         if (oldFinished == NO)
                         {
                               [self.assetWriterVideoInput markAsFinished];
                         }
                         dispatch_group_leave(self.dispatchGroup);
                    }
               }];
          }
          // Set up the notification that the dispatch group will send when the
audio and video work have both finished.
          dispatch_group_notify(self.dispatchGroup, self.mainSerializationQueue,
^{
               BOOL finalSuccess = YES;
               NSError *finalError = nil;
               // Check to see if the work has finished due to cancellation.
               if (self.cancelled)
               {
                    // If so, cancel the reader and writer.
                    [self.assetReader cancelReading];
                    [self.assetWriter cancelWriting];
               }
               else
               {
                   // If cancellation didn't occur, first make sure that the asset
 reader didn't fail.
                    if ([self.assetReader status] == AVAssetReaderStatusFailed)
                         finalSuccess = NO;
                         finalError = [self.assetReader error];
                    }
```

```
// If the asset reader didn't fail, attempt to stop the asset
 writer and check for any errors.
                    if (finalSuccess)
                         finalSuccess = [self.assetWriter finishWriting];
                         if (!finalSuccess)
                              finalError = [self.assetWriter error];
                    }
               }
              // Call the method to handle completion, and pass in the appropriate
 parameters to indicate whether reencoding was successful.
               [self readingAndWritingDidFinishSuccessfully:finalSuccess
withError:finalError];
          });
     }
     // Return success here to indicate whether the asset reader and writer were
started successfully.
     return success;
}
```

During reencoding, the audio and video tracks are asynchronously handled on individual serialization queues to increase the overall performance of the process, but both queues are contained within the same dispatch group. By placing the work for each track within the same dispatch group, the group can send a notification when all of the work is done and the success of the reencoding process can be determined.

Handling Completion

To handle the completion of the reading and writing process, the

readingAndWritingDidFinishSuccessfully: method is called—with parameters indicating whether or not the reencoding completed successfully. If the process didn't finish successfully, the asset reader and writer are both canceled and any UI related tasks are dispatched to the main queue.

```
- (void)readingAndWritingDidFinishSuccessfully:(B00L)success withError:(NSError
*)error
{
    if (!success)
    {
```

```
// If the reencoding process failed, we need to cancel the asset reader
and writer.
          [self.assetReader cancelReading];
          [self.assetWriter cancelWriting];
          dispatch_async(dispatch_get_main_queue(), ^{
               // Handle any UI tasks here related to failure.
          });
     }
     else
     {
          // Reencoding was successful, reset booleans.
          self.cancelled = NO;
          self.videoFinished = NO;
          self.audioFinished = NO;
          dispatch_async(dispatch_get_main_queue(), ^{
               // Handle any UI tasks here related to success.
          });
    }
}
```

Handling Cancellation

Using multiple serialization queues, you can allow the user of your app to cancel the reencoding process with ease. On the main serialization queue, messages are asynchronously sent to each of the asset reencoding serialization queues to cancel their reading and writing. When these two serialization queues complete their cancellation, the dispatch group sends a notification to the main serialization queue where the cancelled property is set to YES. You might associate the cancel method from the following code listing with a button on your UI.

```
// Handle cancellation asynchronously again, but this time serialize
it with the audio queue.
               dispatch async(self.rwAudioSerializationQueue, ^{
                   // Update the Boolean property indicating the task is complete
and mark the input as finished if it hasn't already been marked as such.
                    BOOL oldFinished = self.audioFinished;
                    self.audioFinished = YES;
                    if (oldFinished == NO)
                         [self.assetWriterAudioInput markAsFinished];
                    }
                    // Leave the dispatch group since the audio work is finished
now.
                    dispatch_group_leave(self.dispatchGroup);
               });
          }
          if (self.assetWriterVideoInput)
             // Handle cancellation asynchronously again, but this time serialize
it with the video queue.
               dispatch_async(self.rwVideoSerializationQueue, ^{
                   // Update the Boolean property indicating the task is complete
and mark the input as finished if it hasn't already been marked as such.
                    BOOL oldFinished = self.videoFinished;
                    self.videoFinished = YES;
                    if (oldFinished == NO)
                         [self.assetWriterVideoInput markAsFinished];
                    // Leave the dispatch group, since the video work is finished
now.
                    dispatch group leave(self.dispatchGroup);
               });
          }
          // Set the cancelled Boolean property to YES to cancel any work on the
main queue as well.
```

```
self.cancelled = YES;
});
}
```

Asset Output Settings Assistant

The AVOutputSettingsAssistant class aids in creating output-settings dictionaries for an asset reader or writer. This makes setup much simpler, especially for high frame rate H264 movies that have a number of specific presets. Listing 5-1 shows an example that uses the output settings assistant to use the settings assistant.

Listing 5-1 AVOutputSettingsAssistant sample

```
AVOutputSettingsAssistant *outputSettingsAssistant = [AVOutputSettingsAssistant
outputSettingsAssistantWithPreset:<some preset>];
CMFormatDescriptionRef audioFormat = [self getAudioFormat];
if (audioFormat != NULL)
    [outputSettingsAssistant
setSourceAudioFormat:(CMAudioFormatDescriptionRef)audioFormat];
CMFormatDescriptionRef videoFormat = [self getVideoFormat];
if (videoFormat != NULL)
    [outputSettingsAssistant
setSourceVideoFormat:(CMVideoFormatDescriptionRef)videoFormat];
CMTime assetMinVideoFrameDuration = [self getMinFrameDuration];
CMTime averageFrameDuration = [self getAvgFrameDuration]
[outputSettingsAssistant setSourceVideoAverageFrameDuration:averageFrameDuration];
[outputSettingsAssistant setSourceVideoMinFrameDuration:assetMinVideoFrameDuration];
AVAssetWriter *assetWriter = [AVAssetWriter assetWriterWithURL:<some URL>
fileType:[outputSettingsAssistant outputFileType] error:NULL];
AVAssetWriterInput *audioInput = [AVAssetWriterInput
assetWriterInputWithMediaType:AVMediaTypeAudio
outputSettings:[outputSettingsAssistant audioSettings] sourceFormatHint:audioFormat];
```

AVAssetWriterInput *videoInput = [AVAssetWriterInput
assetWriterInputWithMediaType:AVMediaTypeVideo
outputSettings:[outputSettingsAssistant videoSettings] sourceFormatHint:videoFormat];


Time and Media Representations

Time-based audiovisual data, such as a movie file or a video stream, is represented in the AV Foundation framework by AVAsset. Its structure dictates much of the framework works. Several low-level data structures that AV Foundation uses to represent time and media such as sample buffers come from the Core Media framework.

Representation of Assets

AVAsset is the core class in the AV Foundation framework. It provides a format-independent abstraction of time-based audiovisual data, such as a movie file or a video stream. The primary relationships are shown in Figure 6-1. In many cases, you work with one of its subclasses: You use the composition subclasses when you create new assets (see Editing (page 10)), and you use AVURLAsset to create a new asset instance from media at a given URL (including assets from the MPMedia framework or the Asset Library framework—see Using Assets (page 13)).


Figure 6-1 AVAsset provides an abstraction of time-based audiovisual data



An asset contains a collection of tracks that are intended to be presented or processed together, each of a uniform media type, including (but not limited to) audio, video, text, closed captions, and subtitles. The asset object provides information about whole resource, such as its duration or title, as well as hints for presentation, such as its natural size. Assets may also have metadata, represented by instances of AVMetadataItem.

A track is represented by an instance of AVAssetTrack, as shown in Figure 6-2. In a typical simple case, one track represents the audio component and another represents the video component; in a complex composition, there may be multiple overlapping tracks of audio and video.

Figure 6-2 AVAssetTrack



A track has a number of properties, such as its type (video or audio), visual and/or audible characteristics (as appropriate), metadata, and timeline (expressed in terms of its parent asset). A track also has an array of format descriptions. The array contains CMFormatDescription objects (see CMFormatDescriptionRef), each of which describes the format of media samples referenced by the track. A track that contains uniform media (for example, all encoded using to the same settings) will provide an array with a count of 1.

A track may itself be divided into segments, represented by instances of AVAssetTrackSegment. A segment is a time mapping from the source to the asset track timeline.

Representations of Time

Time in AV Foundation is represented by primitive structures from the Core Media framework.

CMTime Represents a Length of Time

CMTime is a C structure that represents time as a rational number, with a numerator (an int64_t value), and a denominator (an int32_t timescale). Conceptually, the timescale specifies the fraction of a second each unit in the numerator occupies. Thus if the timescale is 4, each unit represents a quarter of a second; if the timescale is 10, each unit represents a tenth of a second, and so on. You frequently use a timescale of 600, because this is a multiple of several commonly used frame rates: 24 fps for film, 30 fps for NTSC (used for TV in North America and Japan), and 25 fps for PAL (used for TV in Europe). Using a timescale of 600, you can exactly represent any number of frames in these systems.

In addition to a simple time value, a CMTime structure can represent nonnumeric values: +infinity, -infinity, and indefinite. It can also indicate whether the time been rounded at some point, and it maintains an epoch number.

Using CMTime

You create a time using CMTimeMake or one of the related functions such as CMTimeMakeWithSeconds (which allows you to create a time using a float value and specify a preferred timescale). There are several functions for time-based arithmetic and for comparing times, as illustrated in the following example:

```
CMTime time1 = CMTimeMake(200, 2); // 200 half-seconds
CMTime time2 = CMTimeMake(400, 4); // 400 quarter-seconds

// time1 and time2 both represent 100 seconds, but using different timescales.
if (CMTimeCompare(time1, time2) == 0) {
    NSLog(@"time1 and time2 are the same");
}

Float64 float64Seconds = 200.0 / 3;
CMTime time3 = CMTimeMakeWithSeconds(float64Seconds , 3); // 66.66... third-seconds
time3 = CMTimeMultiply(time3, 3);
// time3 now represents 200 seconds; next subtract time1 (100 seconds).
time3 = CMTimeSubtract(time3, time1);
CMTimeShow(time3);

if (CMTIME_COMPARE_INLINE(time2, ==, time3)) {
    NSLog(@"time2 and time3 are the same");
}
```

For a list of all the available functions, see CMTime Reference.

Special Values of CMTime

Core Media provides constants for special values: kCMTimeZero, kCMTimeInvalid,

kCMTimePositiveInfinity, and kCMTimeNegativeInfinity. There are many ways in which a CMTime structure can, for example, represent a time that is invalid. To test whether a CMTime is valid, or a nonnumeric value, you should use an appropriate macro, such as CMTIME_IS_INVALID, CMTIME_IS_POSITIVE_INFINITY, or CMTIME_IS_INDEFINITE.

```
CMTime myTime = <#Get a CMTime#>;
if (CMTIME_IS_INVALID(myTime)) {
```

```
// Perhaps treat this as an error; display a suitable alert to the user.
}
```

You should not compare the value of an arbitrary CMTime structure with kCMTimeInvalid.

Representing CMTime as an Object

If you need to use CMTime structures in annotations or Core Foundation containers, you can convert a CMTime structure to and from a CFDictionary opaque type (see CFDictionaryRef) using the CMTimeCopyAsDictionary and CMTimeMakeFromDictionary functions, respectively. You can also get a string representation of a CMTime structure using the CMTimeCopyDescription function.

Epochs

The epoch number of a CMTime structure is usually set to 0, but you can use it to distinguish unrelated timelines. For example, the epoch could be incremented through each cycle using a presentation loop, to differentiate between time N in loop 0 and time N in loop 1.

CMTimeRange Represents a Time Range

CMTimeRange is a C structure that has a start time and duration, both expressed as CMTime structures. A time range does not include the time that is the start time plus the duration.

You create a time range using CMTimeRangeMake or CMTimeRangeFromTimeToTime. There are constraints on the value of the CMTime epochs:

- CMTimeRange structures cannot span different epochs.
- The epoch in a CMTime structure that represents a timestamp may be nonzero, but you can only perform range operations (such as CMTimeRangeGetUnion) on ranges whose start fields have the same epoch.
- The epoch in a CMTime structure that represents a duration should always be 0, and the value must be nonnegative.

Working with Time Ranges

Core Media provides functions you can use to determine whether a time range contains a given time or other time range, to determine whether two time ranges are equal, and to calculate unions and intersections of time ranges, such as CMTimeRangeContainsTime, CMTimeRangeEqual, CMTimeRangeContainsTimeRange, and CMTimeRangeGetUnion.

Given that a time range does not include the time that is the start time plus the duration, the following expression always evaluates to false:

```
CMTimeRangeContainsTime(range, CMTimeRangeGetEnd(range))
```

For a list of all the available functions, see CMTimeRange Reference.

Special Values of CMTimeRange

Core Media provides constants for a zero-length range and an invalid range, kCMTimeRangeZero and kCMTimeRangeInvalid, respectively. There are many ways, though in which a CMTimeRange structure can be invalid, or zero—or indefinite (if one of the CMTime structures is indefinite. If you need to test whether a CMTimeRange structure is valid, zero, or indefinite, you should use an appropriate macro: CMTIMERANGE_IS_VALID, CMTIMERANGE_IS_INVALID, CMTIMERANGE_IS_EMPTY, or CMTIMERANGE_IS_EMPTY.

```
CMTimeRange myTimeRange = <#Get a CMTimeRange#>;
if (CMTIMERANGE_IS_EMPTY(myTimeRange)) {
    // The time range is zero.
}
```

You should not compare the value of an arbitrary CMTimeRange structure with kCMTimeRangeInvalid.

Representing a CMTimeRange Structure as an Object

If you need to use CMTimeRange structures in annotations or Core Foundation containers, you can convert a CMTimeRange structure to and from a CFDictionary opaque type (see CFDictionaryRef) using CMTimeRangeCopyAsDictionary and CMTimeRangeMakeFromDictionary, respectively. You can also get a string representation of a CMTime structure using the CMTimeRangeCopyDescription function.

Representations of Media

Video data and its associated metadata are represented in AV Foundation by opaque objects from the Core Media framework. Core Media represents video data using CMSampleBuffer (see CMSampleBufferRef). CMSampleBuffer is a Core Foundation-style opaque type; an instance contains the sample buffer for a frame of video data as a Core Video pixel buffer (see CVPixelBufferRef). You access the pixel buffer from a sample buffer using CMSampleBufferGetImageBuffer:

```
CVPixelBufferRef pixelBuffer = CMSampleBufferGetImageBuffer(<#A CMSampleBuffer#>);
```

From the pixel buffer, you can access the actual video data. For an example, see Converting CMSampleBuffer to a Ullmage Object (page 111).

In addition to the video data, you can retrieve a number of other aspects of the video frame:

- **Timing information**. You get accurate timestamps for both the original presentation time and the decode time using CMSampleBufferGetPresentationTimeStamp and CMSampleBufferGetDecodeTimeStamp respectively.
- Format information. The format information is encapsulated in a CMFormatDescription object (see CMFormatDescriptionRef). From the format description, you can get for example the pixel type and video dimensions using CMVideoFormatDescriptionGetCodecType and CMVideoFormatDescriptionGetDimensions respectively.
- **Metadata**. Metadata are stored in a dictionary as an *attachment*. You use CMGetAttachment to retrieve the dictionary:

```
CMSampleBufferRef sampleBuffer = <#Get a sample buffer#>;
CFDictionaryRef metadataDictionary =
        CMGetAttachment(sampleBuffer, CFSTR("MetadataDictionary", NULL);
if (metadataDictionary) {
        // Do something with the metadata.
}
```

Converting CMSampleBuffer to a Ullmage Object

The following code shows how you can convert a CMSampleBuffer to a UIImage object. You should consider your requirements carefully before using it. Performing the conversion is a comparatively expensive operation. It is appropriate to, for example, create a still image from a frame of video data taken every second or so. You should not use this as a means to manipulate every frame of video coming from a capture device in real time.

```
// Create a UIImage from sample buffer data
- (UIImage *) imageFromSampleBuffer:(CMSampleBufferRef) sampleBuffer
{
    // Get a CMSampleBuffer's Core Video image buffer for the media data
    CVImageBufferRef imageBuffer = CMSampleBufferGetImageBuffer(sampleBuffer);
    // Lock the base address of the pixel buffer
    CVPixelBufferLockBaseAddress(imageBuffer, 0);
```

```
// Get the number of bytes per row for the pixel buffer
   void *baseAddress = CVPixelBufferGetBaseAddress(imageBuffer);
   // Get the number of bytes per row for the pixel buffer
   size_t bytesPerRow = CVPixelBufferGetBytesPerRow(imageBuffer);
   // Get the pixel buffer width and height
   size_t width = CVPixelBufferGetWidth(imageBuffer);
   size_t height = CVPixelBufferGetHeight(imageBuffer);
   // Create a device-dependent RGB color space
   CGColorSpaceRef colorSpace = CGColorSpaceCreateDeviceRGB();
   // Create a bitmap graphics context with the sample buffer data
   CGContextRef context = CGBitmapContextCreate(baseAddress, width, height, 8,
      bytesPerRow, colorSpace, kCGBitmapByteOrder32Little |
kCGImageAlphaPremultipliedFirst);
   // Create a Quartz image from the pixel data in the bitmap graphics context
   CGImageRef quartzImage = CGBitmapContextCreateImage(context);
   // Unlock the pixel buffer
   CVPixelBufferUnlockBaseAddress(imageBuffer,0);
   // Free up the context and color space
   CGContextRelease(context);
   CGColorSpaceRelease(colorSpace);
   // Create an image object from the Quartz image
   UIImage *image = [UIImage imageWithCGImage:quartzImage];
   // Release the Quartz image
   CGImageRelease(quartzImage);
    return (image);
}
```

Document Revision History

This table describes the changes to AVFoundation Programming Guide.

| Date | Notes |
|------------|---|
| 2015-06-30 | Small organizational changes were made. |
| 2015-07-03 | Updated About AV Foundation to add names to AV Foundation stacks on iOS and OS X. Added links to the camera examples. |
| 2014-11-18 | Updated About AV Foundation to add names to AV Foundation stacks on iOS and OS X. Added links to the camera examples. |
| 2014-03-10 | Updated for iOS 7.0 and OS X v10.9. |
| 2013-10-22 | Clarified use of CMSampleBufferGetImageBuffer. |
| 2013-08-08 | Added a new chapter centered around the editing API provided by the AV Foundation framework. |
| 2011-10-12 | Updated for iOS5 to include references to release notes. |
| 2011-04-28 | First release for OS X v10.7. |
| 2010-09-08 | Expanded Playback and Metadata chapters. |
| 2010-08-16 | First version of a document that describes a low-level framework you use to play, inspect, create, edit, capture, and transcode media assets. |

Apple Inc. Copyright © 2015 Apple Inc. All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Inc., with the following exceptions: Any person is hereby authorized to store documentation on a single computer or device for personal use only and to print copies of documentation for personal use provided that the documentation contains Apple's copyright notice.

No licenses, express or implied, are granted with respect to any of the technology described in this document. Apple retains all intellectual property rights associated with the technology described in this document. This document is intended to assist application developers to develop applications only for Apple-branded products.

Apple Inc. 1 Infinite Loop Cupertino, CA 95014 408-996-1010

Apple, the Apple logo, Aperture, Cocoa, iPad, iPhone, iPod, Objective-C, OS X, Quartz, and QuickTime are trademarks of Apple Inc., registered in the U.S. and other countries.

IOS is a trademark or registered trademark of Cisco in the U.S. and other countries and is used under license.

OpenGL is a registered trademark of Silicon Graphics, Inc.

Times is a registered trademark of Heidelberger Druckmaschinen AG, available from Linotype Library GmbH.

APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS DOCUMENT, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS DOCUMENT IS PROVIDED "AS IS," AND YOU, THE READER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT, ERROR OR INACCURACY IN THIS DOCUMENT, even if advised of the possibility of such damages.

Some jurisdictions do not allow the exclusion of implied warranties or liability, so the above exclusion may not apply to you.