

Sistemas Operativos 1

Unidad 9 – Administración de Memoria

Prof. Dr. Alejandro Zunino ISISTAN - CONICET



Introducción

- La administración de memoria se ocupa de:
 - llevar un registro de las partes de la memoria que están ocupadas y libres
 - asignar espacio a los procesos



1) Reubicación

- El Sistema Operativo puede reubicar procesos en memoria (swapping, compactación)
 - un proceso podría ocupar diferentes lugares de memoria durante su tiempo de vida:
- Los programas no deberían estar atados a direcciones fija de memoria











Administración de Memoria

- Objetivos
- Requerimientos
- Asignación contigua
- Introducción a Paginación



Objetivos y Requerimientos

- El objetivo es permitir que la mayor cantidad posible de procesos estén en memoria:
 - más procesos sugiere... mayor utilización de CPU
- Requerimientos:
 - 1) Reubicación
 - 2) Protección
 - 3) Memoria compartida
 - 4) Organización lógica
 - 5) Organización física



2) Protección

- Los procesos no deberían ser capaces de acceder a áreas de memoria pertenecientes a otros procesos sin permiso:
 - No es posible verificar las direcciones que los programas generan en tiempo de compilación o carga debido a que podría haber reubicación.
 - La verificación debe realizarse durante la ejecución (x hardware)



3) Memoria Compartida

- Permitir a varios procesos acceder a una porción de memoria común sin sacrificar la protección:
 - Ej: para compartir una biblioteca con funciones comunes a varios procesos.
 - Ej: para compartir datos



5) Organización Física

- La memoria externa es el medio donde se perduran los programas y datos, mientras que la memoria principal alberga a los programas y datos en uso:
 - El movimiento de información entre esos dos niveles de memoria es una de las responsabilidades de la administración de memoria.
 - Podría ser ineficiente dejar esto en manos del programador






4) Organización Lógica

- La memoria es un arreglo de bytes
- Sin embargo, los programadores desarrollan módulos con diferentes características:
 - · módulos de código: sólo lectura
 - módulos de datos: sólo lectura o lectura/escritura
 - módulos privados
 - módulos públicos
- El SO/hardware deberían proveer soporte para módulos

Direcciones Lógicas y Físicas

 Las direcciones de memoria generadas por un proceso no pueden ser siempre fijas (por la <u>reubicación</u>)





 Se resuelve <u>ocultando la verdadera ubicación</u> de los procesos en memoria.


Ejemplo: Reubicación con Registro Base


- Las direcciones físicas se calculan "al vuelo" conforme se ejecutan los procesos.
- Para que la performance sea adecuada la traducción debe ser hecha por hardware






















...se Ligan sus Instrucciones y Datos a Direcciones de Memoria...


- En tiempo de compilación
 - si la dirección de memoria inicial se conoce a priori... (sin MMU)
 - se debe recompilar si cambia la dirección...
- En tiempo de carga:
 - código relativo (sin MMU)
 - durante la carga se resuelven las direcciones relativas sumándoles un valor (cargador)... puede ser lento
- En tiempo de ejecución
 - se retrasa hasta la ejecución para permitir que los procesos puedan reubicarse
 - requiere de hardware (MMU) (+ \$\$\$)






























Particiones Fijas: Conclusiones

- Baja utilización de memoria:
 - Una partición por proceso
 - Fragmentación interna
- Qué pasa si un proceso crece?




Asignación de Espacio: Particiones Variables

- First-fit:
 - asigna el primer hueco con espacio suficiente
- Next-fit:
 - misma lógica que el anterior, pero busca desde el último hueco asignado
- Best-fit:
 - asigna el menor de los huecos con espacio suficiente
 - debe recorrer toda la lista
- Worst-fit:
 - asigna el mayor de los huecos con espacio suficiente
 - debe recorrer toda la lista



Particiones Variables: Conclusiones


- Baja utilización de memoria:
 - · Fragmentación externa
 - · Compactación...
 - Qué pasa si un proceso crece?





Particiones Variables

- Cuando se crea un proceso se le asigna un área libre de memoria con el tamaño suficiente para contenerlo
 - el área asignada es la partición
 - el tamaño y número de particiones es variable







Asignación de Espacio: Particiones Variables

- First-fit tiende a asignar memoria en la parte baja (o alta):
 - tiende a crear menos fragmentación que Next-fit
- Best-fit tiende a generar muchos huecos pequeños:
 - mucha fragmentación
- First-fit y next-fit son generalmente utilizados



Introducción a Paginación








Paginación: Conclusiones

- El SO gana mayor libertad para organizar la memoria:
 - no es necesario que la asignación sea contigua
- Desaparece la fragmentación externa
- · Aún hay fragmentación interna
 - ej: de una página de 4 KB sólo se usan 3 KB
- · La tabla ocupa memoria...
- Velocidad???

Dividir la memoria en física en bloques de tamaño fijo llamados marcos (frames) de 1KB, 2KB, 4KB... Dividir la memoria lógica en bloques del mismo tamaño llamados páginas Traducir entre páginas y marcos









Implementation of Page Table

Page table is kept in main memory

- Page-table base register (PTBR) points to the page table
- Page-table length register (PRLR) indicates its size
- In this scheme every data/instruction access requires two memory accesses. One for the page table and one for the data/instruction.
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)
- Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide address-space protection for that process





Associative Memory

Associative memory – parallel search

Page #	Frame #

- Address translation (A', A'')
 - If A' is in associative register, get frame # out.
 - Otherwise get frame # from page table in memory



Effective Access Time

- Associative Lookup = ε time unit
- Assume memory cycle time is 1 microsecond
- Hit ratio percentage of times that a page number is found in the associative registers; ration related to number of associative registers.
- Hit ratio = α
- Effective Access Time (EAT)

EAT =
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$

= $2 + \varepsilon - \alpha$



Memory Protection

- Memory protection implemented by associating protection bit with each frame.
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page.
 - "invalid" indicates that the page is not in the process' logical address space.



Shared Pages


- Shared code
 - One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems).
 - Shared code must appear in same location in the logical address space of all processes.
- Private code and data
 - Each process keeps a separate copy of the code and data.
 - The pages for the private code and data can appear anywhere in the logical address space.




Page tables can get HUGE

- Consider a 32-bit logical address space as on modern computers
 - Page size of 4 KB (2¹²)
 - Page table would have 1 million entries (2³² / 2¹²)
 - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
 - That amount of memory used to cost a lot
 - Don't want to allocate that contiguously in main memory











Hierarchical Page Tables

- Break up the logical address space into multiple page tables.
- A simple technique is a two-level page table.



Address-Translation Scheme

 Address-translation scheme for a two-level 32-bit paging architecture





64-bit Logical Address Space

- But in the following example the 2nd outer page table is still 2³⁴ bytes in size
- And possibly 4 memory access to get to one physical memory location

outer page	inner page offs		set
p_1	p_2 d		d
42	10	1	2
2nd outer page	outer page	inner page	offset
p_1	p_2	p_3	d
32	10	10	12



Two-Level Paging Example

- A logical address (on 32-bit machine with 1K page size) is divided into:
 - a page number consisting of 22 bits.
 - a page offset consisting of 10 bits.
- Since the page table is paged, the page number is further divided into:
 - a 12-bit page number.
 - a 10-bit page offset.
- Thus, a logical address is as follows:




where p₁ is an index into the outer page table, and p₂ is the displacement within the page of the outer table.



64-bit Logical Address Space

- If page size is 4 KB (2¹²)
 - Then page table has 2⁵² entries
 - If two level scheme, inner page tables could be 2¹⁰ 4-byte entries
 - · Address would look like





- Outer page table has 2⁴² entries or 16384 GB
- One solution is to add a 2nd outer page table




Hashed Page Tables

- Common in address spaces > 32 bits.
- The virtual page number is hashed into a page table. This page table contains a chain of elements hashing to the same location.
- Virtual page numbers are compared in this chain searching for a match. If a match is found, the corresponding physical frame is extracted.











- One entry for each real page of memory.
- Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page.
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs.
- Use hash table to limit the search to one or at most a few — page-table entries.








Segmentation Architecture

- Logical address consists of a two tuple: <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory.
 - *limit* specifies the length of the segment.
- Segment-table base register (STBR) points to the segment table's location in memory.
- Segment-table length register (STLR) indicates number of segments used by a program;
- segment number s is legal if s < STLR.



Segmentation Architecture (Cont.)


- Protection. With each entry in segment table associate:
 - validation bit = 0 ⇒ illegal segment
 - read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level.
- Since segments vary in length, memory allocation is a dynamic storage-allocation problem.
- A segmentation example is shown in the following diagram






Segmentation Architecture (Cont.)

- Relocation.
 - dynamic
 - by segment table
- Sharing.
 - shared segments
 - same segment number
- · Allocation.
 - first fit/best fit
 - · external fragmentation







- Supports both segmentation and segmentation with paging
- CPU generates logical address
 - · Given to segmentation unit
 - Which produces linear addresses
 - · Linear address given to paging unit
 - Which generates physical address in main memory
 - Paging units form equivalent of MMU

