# Module IN3031 / INM378 **Digital Signal Processing** and Audio Programming

Tillman Weyde

LONDON

t.e.weyde@city.ac.uk








IN3031 / INM378 Digital Signal Processing and Audio Programming

# Sound and Hearing in Space

- Speed of Sound (vs) approx. 340 m/s
- Wavelength (λ)
  - \_ wavelength = speed \* period = speed / frequency
- · Sound intensity decreases with distance (see next slide), called Distance Roll-Off in programming
- · Air absorbs energy over distance, acting as a low-pass filter
- · In games, a band-pass filter is often used to make sounds seem more distant





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 7

# **Doppler Effect**

- · Doppler Effect changes frequency for moving sources
  - $_{\rm fp} = f \, vs/(vs-vr)$
  - with fp: perceived frequency,
  - f: frequency, vr: velocity relative to the listener (positive = approaching)
  - \_ Example: car moves with 68 m/s producing a 300 Hz sound. fp for a stationary listener in front of the car is

300 Hz \* 340/340-68 = 300 Hz \*5/4 = 375 Hz



Digital Signal Processing and Audio Program Lecture 6 / Slide 5

# **Directional Hearing and** Localisation

- Directional hearing is based mostly on binaural hearing
  - Interaural Intensity Differences (IID)
  - Interaural Time Differences (ITD)
  - \_ IID and ITD vary over frequencies.
- · IID and ITD give only information on left-right
  - \_ front-back and high-low are detected through head-related transfer functions (head shape, pinna)
- Room reflection
  - \_ absorbing and reflecting objects give clues for source location



IN3031 / INM378 Digital Signal Processing and Audio Programming
Lecture 6 / Slide 8

# **FMOD Audio Programming** and 3D Rendering



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 6

# **Intensity and Distance**

- Intensity is power (energy per time) per area, measured in Watts/Meter<sup>2</sup>
- 0 dB Sound Pressure Level defined as 10<sup>-12</sup> W/m<sup>2</sup> (~threshold of hearing)
- · Intensity decreases as the square of distance
- · Power increases as the square of amplitude
- Example: 60dB SPL at 1m means 40dB SPL at 10m (10-fold distance -> 100-fold decrease -> -20dB)



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 9

# Loading and Playing a Sound

Load a sound:

// set the Volume

FMOD::Sound \*sound; result = system->createSound(filename, FMOD LOOP OFF, 0, &sound); FmodErrorCheck(result);

Create a Channel object and play the sound

FMOD::Channel channel = null; result = system->playSound(sound, NULL, false, &channel);

• channel now has the channel where sound is played

```
result = channel->setVolume(0.8f);
```

# **Creating DSP Objects**

· To create an oscillator and set its parameters: FMOD::DSP \*osc;

```
system->createDSPByType(FMOD DSP TYPE OSCILLATOR, &osc);
osc->setParameterFloat(FMOD DSP OSCILLATOR RATE, 440);
// 0 = sine. 1 = square. 2 = sawup.
// 3 = sawdown. 4 = triangle. 5 = noise.
osc->setParameterInt(FMOD DSP OSCILLATOR TYPE, 1);
```



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 13

# **Transforming and Updating 3D Positions**

Transformation of OpenGL vectors to FMOD vectors:

FMOD VECTOR fmodVec = FMOD VECTOR(); fmodVec.x = glVec3.x; fmodVec.y = glVec3.y; fmodVec.z =

· Make this ^ into a converter function for ease: e.g.

void ToFMODVector(glm::vec3 &glVec3, FMOD VECTOR \*fmodVec)

Transform position vectors

ToFMODVector(camera->GetPosition(), &camPos);

· Update the listener position:

```
system->set3DListenerAttributes(0, &camPos, NULL, NULL,
  NULL);
system->update();
```



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 16

# **DSP Playback in 3D**

- Start playing the oscillator (preferably paused): system->playDSP(dsp, NULL, false, &channel);
- Then assign 3D properties to the channel as inthe previous slide
- · Adjusting the minDistance can ensure audibility: channel->set3DMinMaxDistance(200f, 100000f);



# **Using DSP Objects**

To play an oscillator:

```
system->playDSP(dsp, NULL, false, &channel);
```

 ... or to insert a DSP processor into the signal flow sequence at the DSP chain head:

```
channel->addDSP(FMOD CHANNELCONTROL DSP HEAD,
   dsp);
```



IN3031 / INM378 Digital Signal Processing and Audio Programmi Lecture 6 / Slide 14

# **Positioning 3D Sound**

· Create position and velocity vectors:

```
FMOD VECTOR pos1 = FMOD VECTOR();
pos1.x = -10f; pos1.y = 0f; pos1.z = 0f;
FMOD VECTOR vel1 = new FMOD VECTOR();
vel1.x = 0f; vel1.y = 0f; vel1.z = 0f;
```

· And set channel attributes:

```
channel->setMode(FMOD 3D);
channel->set3DAttributes(&pos1, &vel1);
```



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 17

# FMOD 3D **Modelling and Occlusion**

#### 3D Sound with FMOD

- · Set up the FMOD systems 3D settings: system->set3DSettings(doppler, distFactor, distRolloff);
- · Where:
  - \_ doppler scales the intensity of the doppler effect
- \_ distFactor determines the length of an FMOD unit (1
- \_ distRolloff scales the distance roll-off (1 is like real world)



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 15

# **3D Sound Playback**

· Create a sound:

```
system->createSound(filename,
   FMOD LOOP OFF, 0, & sound);
```

... play it:

```
system->playSound(sound, NULL, false, &channel);
```

• ... and set the channel's 3D attributes as in the previous slide



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 18

#### 3D in FMOD

- Recap:
  - FMOD has its own 3D coordinate system and model
  - \_ Need to coordinate
    - listener positions and velocities
    - · sound source positions and velocities
    - objects in 3D that occlude or obstruct sound

IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 19

# **Simulating Acoustics**

 Reflection and conduction change sound on its way from source to listener.

· Reflection: Echo, Reverb

· Conduction: Distance roll-off


Complex effects: Occlusion, Obstruction




IN3031 / INM378
Digital Signal Processing and Audio Programming

#### **Occlusion**

- Obstruction: obstacle blocks direct path between sound source and listener.
- Occlusion: occluder blocks all paths from the source to the listener.







IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 25

Real-time DSP Circular Buffers FMOD Custom DSP Programming



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 20

# **Positioning 3D Sound**

· Create position and velocity vectors:

FMOD\_VECTOR pos1 = {-10.0f, 0.0f, 0.0f}; FMOD VECTOR vel1 = {0.0f, 0.0f, 0.0f};

· And set channel attributes:

channel->setMode(FMOD\_3D);
channel->set3DAttributes(&pos1, &vel1);



Digital Signal Processing and Audio Programming
Lecture 8 / Slide 23

# **Creating 3D Geometry Objects for Occlusion**

#### First, convert your polygon to FMOD format:

```
FMOD_VECTOR wallPoly[4];
ToFMODVector(v1, &wallPoly[0]);
ToFMODVector(v2, &wallPoly[0]);
ToFMODVector(v3, &wallPoly[0]);
ToFMODVector(v4, &wallPoly[0]);
```



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 26

# **Custom FMOD DSPs**

- · DSP inserts
  - For whole system (all channels):

system->addDSP()

\_ For specific channel

channel->addDSP()





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 21

# Transforming and Updating 3D Positions

#### Transformation of OpenGL vectors to FMOD vectors:

```
FMOD_VECTOR fmodVec = FMOD_VECTOR();
fmodVec.x = glVec3.x; fmodVec.y = glVec3.y; fmodVec.z =
glVec3.z;
```

· Make this ^ into a converter function for ease: e.g.

```
void ToFMODVector(glm::vec3 &glVec3, FMOD_VECTOR *fmodVec)
```

Transform position vectors

ToFMODVector(camera->GetPosition(), &camPos);

Update the listener position:

```
system->set3DListenerAttributes(0, &camPos, NULL, NULL,
    NULL);
system->update();
```



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 24

# **Creating 3D Geometry Objects for Occlusion**

#### Then, create the object in FMOD's system

```
FMOD::Geometry *geometry;
system->createGeometry(1, 4, &geometry);
int polyIndex = 0;
// these numbers control direct, and reverb occlusion settings (0-1)
geometry->addPolygon(1.0f, 1.0f, TRUE, 4, wallPoly, &polyIndex);
FMOD_VECTOR wallPosition;
ToFMODVector(position, &wallPosition);
geometry->setPosition(&wallPosition);
geometry->setActive(TRUE);
```



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 27

# **Creating a custom DSP**

Digital Signal Processing and Audio Programming Lecture 6 / Slide 28

### **Custom DSP callback**

```
FMOD_RESULT F_CALLBACK_DSPCallback(FMOD_DSP_STATE *dsp_state,
    float *inbuffer, float *outbuffer,
    unsigned int length, int inchannels, int *outchannels)
             (unsigned int samp = 0; samp < length; samp++)</pre>
             for (int chan = 0; chan < *outchannels; chan++)</pre>
                    outbuffer[(samp * *outchannels) + chan] =
   inbuffer[(samp * inchannels) + chan];
                                                                                              Example
                                                                                               2 channel inbuffer
};
```



CITY UNIVERSITY

IN3031 / INM378 Digital Signal Processing and Audio Programming
Lecture 6 / Slide 31

#### Circular Buffer

- · Goal: continuous buffering of incoming data in linear array
- · Address the buffer:

pos % buffer length






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 34

#### **Circular Buffer**

```
CircBuffer cBuffer = new CircBuffer(4);
Cbuffer->Put(4.0);
```






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 29

# Creating a Delay effect

- Echo adds a delayed signal to the original input
- · Both delayed and original signal are scaled to stay in range, with  $0 \le \alpha \le 1$
- Signal flow diagram of the effect:






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 32

x[t-k]

#### **Circular Buffer**

· Minimise buffer maintenance costs

· Address the buffer: pos % buffer.length



• tail % length points to write position





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 35

#### **Circular Buffer**

```
CircBuffer cBuffer = new CircBuffer(4);
Cbuffer->Put(4);
Cbuffer->Put(2);
```






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 30

# Accessing x[t-k]

- · Buffer the input signal for a time at least equal to the sample delay time k
- Then access x[t-k] from the buffer





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 33

#### **Circular Buffer**

CircBuffer \*cBuffer = new CircBuffer(4);





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 36

#### Circular Buffer

```
CircBuffer cBuffer = new CircBuffer(4);
Cbuffer->Put(4);
Cbuffer->Put(2);
Cbuffer->Put(5);
```







INI3031 / INIM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 39

#### Circular Buffer

CircBuffer cBuffer = new CircBuffer(4); Cbuffer->Put(4); Cbuffer->Put(2); Cbuffer->Put(5); Cbuffer->Put(7);



tail: 4



LONDON

CITY UNIV

CITY UNIVERSITY

IN3031 / INM378 Digital Signal Processing and Audio Programming
Lecture 6 / Slide 40

#### **Circular Buffer**

cBuffer->AtPosition(2); // returns: 5 cBuffer->AtPosition(4): // returns: 0






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 43

#### **Echo effect**


- · Echo adds a delayed signal to the original input
- · Both delayed and original signal are scaled to stay in range
- · Signal flow diagram of the effect:





#### **Circular Buffer**

CircBuffer cBuffer = new CircBuffer(4); Cbuffer->Put(4); Cbuffer->Put(2); Cbuffer->Put(5); Cbuffer->Put(7); Cbuffer->Put(0);




tail: 5



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 41

#### Circular Buffer

cBuffer->AtPosition(2); // returns: 5 cBuffer->AtPosition(4): // returns: 0 cBuffer->AtPosition(6);




tail: 5



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 44

# Feedback delay

- There is also a feedback version of the delay: The output is **fed back** into the buffer!
- · Simplified signal flow diagram of the effect:



(Leen

#### Circular Buffer

cBuffer->AtPosition(2); // returns: 5






IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 42

#### Circular Buffer

cBuffer->AtPosition(2); // returns: 5 cBuffer->AtPosition(4); // returns: 0 cBuffer->AtPosition(6); // throws Exception! Why?







IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 6 / Slide 45

# Frequency analysis in FMOD

```
// create FFT DSP object
DSP * fft;
system->createDSPByType (FMOD DSP TYPE FFT, &fft);
// define spectrum length and window
fft->setParameterInt(FMOD DSP FFT WINDOWSIZE, 1024);
Fft->setParameterInt(FMOD DSP FFT WINDOWTYPE,
    FMOD_DSP_FFT_WINDOW_HANNING);
// get spectrum data
FMOD DSP PARAMETER FFT *fftData;
fft-getParameterData(FMOD DSP FFT SPECTRUMDATA,
    (void **)fftData);
```

# Reading

· FMOD Studio Low-level API tutorials on DSP architecture and usage

#### Game Audio Workflow



IN3031 / INM378 Digital Signal Processing and Audio Programming

#### · FMOD Studio supports to

- · FMOD event model
  - \_ high level interface to programmers, leaving audio matters mostly to the sound designer



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 52

### **FMOD Event Parameters**

**FMOD API Event Model** 

- Parameters control the sound
- · Parameter values are set by the game
- · Designer defines event's reaction to parameters
  - \_ Sound mix/crossfades
  - \_ Effects: Volume, Pictch, Reverb, Chorus, ....
  - Auto-pitch (pitch changes)
  - \_ Randomisation



IN3031 / INM378 Digital Signal Processing and Audio Programming

#### **FMOD Event Model**

- · High level model to support sound and interaction design for games
- - \_ define, manage, package, test and optimise sound 'events' with parameters



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 53

# **FMOD Studio: Event Parameters**

EQ settings



#### **Game Audio Workflow**

- Audio producers → audio programmers
- · Audio producers:
  - \_ recording engineers
  - \_ sound designer, voice artists, composers and musicians
- Interface
  - \_ FMOD Studio (Designer) for producers
  - \_ FMOD Studio low level API for programmers



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 51

# **FMOD Studio: Event Editor**





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 54

# **FMOD Studio: Event Parameters**

Cross-Fading







Digital Signal Processing and Audio Programming

# LONDON

# Music in Games



IN3031 / INM378 Digital Signal Processing and Audio Programming

IN3031 / INM378

Digital Signal Processing and Audio Programming

# Beat, Metre, and Metrical **Hierarchies**

- Introduction
- Beat and Metre
- Metrical Stress Patterns and Time Signatures
- Even, odd, and compound metres
- MIDI Time Signature

CITY UNIVERSITY

LONDON

Computing a Metrical Hierarchy





IN3031 / INM378 Digital Signal Processing and Audio Programming

# **Music and Time**



- · Musical time is structured:
  - \_ the beat (or pulse) creates a (mostly) regular grid
  - \_ Metre creates regular beats groups with internal structure

#### Interactive Music

- · Games have no fixed progression of events
  - Music needs to be adaptable. Approaches:
    - · Write different pieces of music: only possible to a limited extent
    - Loop parts of the music: common approach
  - Adaptation
    - · Horizontal re-sequencing (different sequences of looped sound material)
    - Vertical re-orchestration (different combinations layered sounds)

CITY UNIVERSITY LONDON

INI3031 / INIM378 Digital Signal Processing and Audio Programming

#### Introduction




#### Beat



- Most music has a perceived beat or pulse
  - a succession of stressed point in time (beats)
  - beats have approximately equal durations between them (isochronous sequence)
- The frequency of beats is called the tempo
  - tempo is defined in BPM (beats per minute)
  - tempos are typically in the range 50-200BPM

#### Musical Structure



- · Loops and layers should (normally) create a coherent musical structure in
  - \_ Time (metre and rhythm, horizontal)
  - \_ Frequency (harmony, vertical)



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 6

#### Introduction

- How do dancers synchronise with the music?
- How do musicians synchronise when they play together?



- . This by done by using patterns in time
- Musical beat and metre organise these patterns



IN3031 / INM378 Digital Signal Processing and Audio Programming
Lecture 8 / Slide 63

# **Beat Perception**

- The beat is inferred in the perception of music
  - · a perfectly isochronous sequence of notes evokes a beat unequivocally



- a very irregular sequence evokes no beat perception
- · composers and musicians use this differently (e.g. classical vs. jazz)
- · Beat perception is related to movement (dance music, work songs, ...)







IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 64

# Beats and Musical Organisation

- Notes can occur aligned to the beat, but at a higher or lower rate
- The temporal organisation music is based on stressed and unstressed notes

**Common Time Signatures** 



2/4

4/4

CITY UNIVERSITY

LONDON

IN3031 / INM378 Digital Signal Processing and Audio Programming

IN3031 / INM378

Digital Signal Processing and Audio Programming Lecture 8 / Slide 70

# CITY UNIVERSITY LONDON

IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 65

#### **Common Patterns**

- Beats are grouped in patterns
- one stressed (downbeat) one light (upbeat), (stress is indicated by dots over the note)



- This is even perceived when a completely uniform isochronous sequence is played



IN3031 / INM378
Digital Signal Processing and Audio Programming

# **Metrical Levels**

- Levels of stress in a time signature





IN3031 / INM378
Digital Signal Processing and Audio Programming

# Well known example



# **Metrical Organisation**



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 66

#### Metre

- The distribution of strong and weak times in time is called the metre of the music
- The repeated pattern represents usually one *bar* (brit.) or *measure* (am.), delimited by vertical *barlines*
- In music notation, the metre is usually indicated by the *time signature*
- time signature is written as a fraction x/y
  - x is the number of beats per measure
  - y indicates that a beat has 1/y duration



IN3031 / INM378
Digital Signal Processing and Audio Programming

# **Anacrusis/Upbeat**

- The first measure may be incomplete





IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 72

### **Compound meters**

- A measure can have irregular subdivisions e.g. 3+2+2 / 8
- Examples:
   Bulgarian dances
   Jazz ('Take Five', Latin Rhythms)



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 73

# Musical Instrument Digital Interface (MIDI)

- A hardware, messaging and file format standard, introduced in 1982
- · Binary format, most messages are 8-bit
- · Modelled after western music theory
- Now ubiquitous in digital and (some) analogue instruments
- Other messaging formats are available: CV, Open Sound Control, MIDI HD (in development), some ad-hoc solutions



IN3031 / INM378
Digital Signal Processing and Audio Programming

# **Loops and Metre**

- The metrical structure is normally maintained during loop playback.
- Common loop sizes are 4, 8 or 16 bars (although sometimes musical structures have different values, e.g. 'Eleanor Rigby' by the Beatles has a 5 bar structure)



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 79

# **MIDI vs Audio in Loops**

- Audio
  - can have superior quality (e.g. recorded human performance)
  - \_ costly and lossy change of pitch/tempo
  - \_ changing individual notes hardly possible
  - → careful planning needed, good for final production
- MIDI
  - very flexible (easy to change tempo, pitch, notes)
  - → can experiment, good for developing a soundtrack



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 74

# **MIDI Time Signature**

MIDI Standard Files (0) Meta Message

Time signature of th nn/2<sup>dd</sup>

eg: 6/8 would be specified using nn=6, dd=3
The parameter cc is the number of MIDI Clocks per metronome tick.

The parameter co is the number of MIDI Clocks per metronome tick. Normally, there are 24 MIDI Clocks per quarter note. However, some software allows this to be set by the user. The parameter bb defines this in terms of the number of 1/32 notes which make up the usual 24 MIDI Clocks (the 'standard' ouarter note).

- nn Time signature, numerator
- dd Time signature, denominator expressed as a power of 2.
- eg a denominator of 4 is expressed as dd=2
- cc MIDI Clocks per metronome tick
- bb Number of 1/32 notes per 24 MIDI clocks (8 is standard)



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 77

# **Loops and Harmony**

- Harmony describes the sounding of several (pitched) notes together
- In harmonic contexts, some notes sound consonant, others sound dissonant/inappropriate.
- Layered music loops need common harmonic structure (not true for sound loops)
- Each layer in the same harmonic pattern ensures they are musically 'compatible'



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 80

### **FMOD for Game Music**

- Supports
  - Loop
  - Synchronisation based on beats and bars
  - Conditional transitions and repetitions
- Used to be separate FMOD Music system, now integrated with Studio Event system



IN3031 / INM378 Digital Signal Processing and Audio Programming Lecture 8 / Slide 75

# A MIDI Example

(24 ticks per quarter note)

- 0 NoteOn 80 127
- 24 TimeSig 4 2 24 8
- 24 NoteOn 80 0 <-- (a.k.a NoteOff)
- 24 NoteOn 80 127
- 36 NoteOn 60 127
- 48 NoteOn 60 0
- 48 NoteOn 60 127
- 66 NoteOn 60 0
- 72 NoteOn 80 127
- 96 NoteOn 80 0



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 78

#### MIDI vs Audio

- · MIDI representation
  - \_ used mostly in music production
- used to be applied in Games directly
- · MIDI is symbolic representation
  - \_ Advantages:
    - · independent tempo and pitch
    - · easy to modify for musicians
    - low data volume
  - Disadvantages
    - sound quality (depends on used sound library)



IN3031 / INM378
Digital Signal Processing and Audio Programming
Lecture 8 / Slide 81

#### Interactive Music in FMOD

• FMOD Designer interface (a bit like UML)





# **Interactive Music in FMOD**

 The new FMOD Studio interface (more like Spaghetti code)

