
PREPARED FOR AUREOLE — HRMS ADMINISTRATORS

Dynamic Setup Guide

Approvals, Access, Servers & WiFi

A plain-language guide to everything an admin can change in HRMS without touching code: who can do what (RBAC), who approves what (approval templates), which servers people can reach, which WiFi networks are trusted, and the other settings that are configurable.



PREPARED BY	PREPARED FOR	DATE	VERSION
BeForth	Aureole — HRMS administrators	October 2026	1.0

support@beforth.in · +91 97661 83834
Nashik, Maharashtra, India · beforth.in

Document information

ITEM	DETAIL
Document title	Dynamic Setup Guide: Approvals, Access, Servers & WiFi
Prepared by	BeForth
Prepared for	Aureole — HRMS administrators
Date	October 2026
Version	1.0

HOW TO READ THIS DOCUMENT

Part 1 gives the big picture. Parts 2 to 6 each cover one area and can be read on their own. Part 7 lists smaller settings, and Part 8 is a quick checklist.

Contents

1 The Big Picture 4
- 1.1 What is configurable 4
- 1.2 How the pieces fit together 5

2 Roles & Permissions (RBAC) 6
- 2.1 The vocabulary 6
- 2.2 How HRMS decides yes or no 6
- 2.3 The default roles 6
- 2.4 Giving access, step by step 7
- 2.5 Building your own role 7

3 The Permission Catalog 9
- 3.1 People & Organization 9
- 3.2 Leave, Attendance & Resignation 9
- 3.3 Recruitment & Onboarding 10
- 3.4 DSR and Expenses 10
- 3.5 Service 10
- 3.6 Marketing 11
- 3.7 Administration 11

4 Approval Templates 13
- 4.1 The three building blocks 13
- 4.2 Which requests can have templates 13
- 4.3 Who gets picked as approver 13
- 4.4 The built-in default chain 14
- 4.5 Setting up a chain, step by step 14
- 4.6 Who may change templates 15
- 4.7 For other systems 15

5 Servers 16
- 5.1 Adding a server 16
- 5.2 Choosing who can connect 16
- 5.3 Switching off and removing 16
- 5.4 Server permissions at a glance 17
- 5.5 What TunnelGate calls 17

6 WiFi Access Control 18
- 6.1 Adding a WiFi network 18
- 6.2 SSID only, or pinned to one access point 18
- 6.3 The on and off switch 18
- 6.4 Exempting a person 19
- 6.5 How TunnelGate checks 19

7 Other Things You Can Change 20

8 Quick Checklists 21
- 8.1 A new person joins 21
- 8.2 A person leaves or changes role 21
- 8.3 Things worth remembering 21

1 The Big Picture


HRMS is built so that most day-to-day rules are **settings, not code**. An administrator can change who sees a page, who approves a leave request, which servers an employee can open, and which office WiFi is trusted, all from the browser. Nobody has to edit code or restart anything.

This guide explains each of those controls in simple terms, where to find it, and what happens behind the scenes.

1.1 What is configurable

AREA	WHAT YOU CONTROL	WHERE IN HRMS
Roles and permissions	Who can see and do what	Admin > RBAC > Roles / Permissions / User Roles
Approval templates	Who approves a request, and in how many levels	Workflows > Approval Templates
Template mapping	Which template applies to which person, department or role	Leave > Template Mapping
Servers	Which servers exist and which employees may connect	Admin > Servers
WiFi access	Which office WiFi networks are trusted for server access	Settings > WiFi Access Control
Geofence locations	Where employees may mark attendance from	Settings > Geofence Locations
Company settings	Company profile and shared dropdown values	Settings > Company
Email settings	Outgoing email account and email templates	Settings > Email
Intranet apps	The tiles shown in the app launcher	Intranet > Apps

1.2 How the pieces fit together



Who can do what, and who approves it

THREE QUESTIONS, THREE SETTINGS

Can you do it? is answered by roles and permissions. **Who must approve it?** is answered by approval templates. **Can you connect from here?** is answered by server access and the WiFi whitelist.

2 Roles & Permissions (RBAC)

RBAC means Role Based Access Control. Instead of deciding for each person what they can click, you give them a role, and the role carries a bundle of permissions.

2.1 The vocabulary

Permission	One single ability, written as `module.action`, for example `leave.view` or `server.manage`.
Role	A named bundle of permissions, for example HR Manager.
User role	The link that gives a person a role. One person can hold more than one.
Direct permission	A single permission given to one person outside any role. It can have an expiry date.
Level	A number from 1 (view only) up to 4 or 5 (admin) that shows how powerful a permission or role is.
Superuser	A built-in super administrator. Passes every check automatically.

2.2 How HRMS decides yes or no

Every protected page and button asks the same question. The answer is found in this order, and the first yes wins.

1. Not logged in? The answer is no.
2. Superuser? The answer is yes, always.
3. Does the person have this permission given directly, and has it not expired? Then yes.
4. Does any of the person's active roles include this permission? Then yes.
5. Otherwise the answer is no.

> DEPARTMENT SCOPE
> Passing the permission check is not always enough. A role can be limited to one department or team, so a person may be allowed to view leave but only for their own department's data.

2.3 The default roles


These are created automatically when the permission catalog is seeded. They can be edited, and new roles can be added.

ROLE	TYPE	LEVEL	IN SIMPLE TERMS
Administrator / Super Admin	admin	4	Everything, including RBAC and settings
HR Manager	hr	3	People, leave, attendance, recruitment, onboarding, resignation
Manager	manager	2	Team view, attendance marking, DSR and expense approval views
Employee	employee	1	Own leave, attendance check-in, own DSR and expenses
Marketing Manager	marketing_manager	3	The full marketing module plus DSR and expenses

> EXAMPLE · GIVING SOMEONE ACCESS
> Priya in Accounts needs to see the server list but is not an administrator. Do not make her an admin. Give her the single permission `server.view`, and nothing else changes for her.

2.4 Giving access, step by step

1. Open Admin > RBAC > User Roles and pick the person.
2. Add a role, or open that person's permissions and add a single permission. Set an expiry date if the access is temporary.
3. Role and permission changes are not instant for everyone. They are sent as a request and wait for someone with `rbac.approve_assignments`.
4. The approver opens Pending Requests and approves or rejects, one request or a whole batch at a time.
5. After approval the access is live straight away. The change is written to the audit log.



How an access change is approved

2.5 Building your own role

1. Admin > RBAC > Roles > Create. Give it a clear name and a type.
2. Open the role's permissions and tick what it should be able to do.

3. Assign the role to people as in 2.4.

> **NEVER JUDGE BY ROLE NAME**
>
> HRMS checks permissions, not role names. Renaming a role never removes access, and a new role works the moment its permissions are ticked. The one exception is the fallback approval chain in Part 4, which looks at the role types `hr`, `manager` and `ceo`.

3 The Permission Catalog

Every permission has a code, a short description and a level. The tables below list them by module. Codes are the exact text shown in the Permissions screen.

3.1 People & Organization

CODE	WHAT IT ALLOWS	LEVEL
`employee.view`	See the employee list and details	1
`employee.create` / `employee.edit`	Add or change employees	2
`employee.delete`	Delete employees	3
`employee.import` / `employee.export`	Bulk import or export	2/1
`reports.employee`	Headcount reports by department and designation	1
`org.view_departments` / `org.view_designations`	See departments and designations	1
`org.manage_departments` / `org.manage_designations`	Create and edit them	3
`holiday.view`	See the holiday calendar	1
`holiday.manage` / `manage_years` / `manage_weekly_offs`	Maintain holidays, years and weekly offs	3

3.2 Leave, Attendance & Resignation

CODE	WHAT IT ALLOWS	LEVEL
`leave.view`	See own leave applications	1
`leave.create`	Apply for leave	2
`leave.view_all`	See every employee's leave and its approval history	1
`leave.apply_on_behalf`	Apply for someone else	2
`leave.dashboard`	Leave dashboard and live roster	1
`leave.balances_view` / `leave.balances_edit`	See or import leave balances	1/2
`attendance.view` / `attendance.checkin`	See own records, check in and out	1
`attendance.view_all` / `attendance.mark`	See everyone's attendance, mark for others	2
`attendance.edit`	Edit attendance records	3
`attendance.manage_comp_off`	Manage comp-off	2
`resignation.view` / `resignation.submit`	See and submit own resignation	1

`resignation.view_all` / `manage_handover`	See all, manage handover	2
`resignation.approve` / `resignation.reject`	Decide a resignation	3

3.3 Recruitment & Onboarding

CODE	WHAT IT ALLOWS	LEVEL
`recruitment.view` / `view_applicants`	See job openings and applicants	1
`recruitment.create_job` / `edit_job`	Create and edit openings	2
`recruitment.delete_job`	Delete openings	3
`recruitment.create_applicant` / `manage_applicants` / `send_emails`	Add, update status, email applicants	2
`recruitment.induct_applicant`	Turn an applicant into an employee	3
`onboarding.view`	See onboarding form submissions	1
`onboarding.send`	Email the onboarding form	2
`onboarding.approve`	Approve submissions into the employee profile	3
`onboarding_policy.view` / `create` / `edit` / `delete`	Policies shown in the onboarding form	1/2/3/4

3.4 DSR and Expenses

CODE	WHAT IT ALLOWS	LEVEL
`dsr.indoor_view` / `create` / `edit`	Own indoor daily service report	1
`dsr.indoor_delete`	Delete an indoor DSR	2
`dsr.outdoor_view`	See outdoor DSR	1
`dsr.outdoor_create` / `edit` / `delete`	Manage outdoor DSR	2
`dsr.view_all`	See every employee's DSRs	2
`dsr.view_submissions`	Who has submitted, daily, weekly, monthly	2
`dsr.assign_task`	Log a DSR under another employee's name	2
`expense_report.view` / `create` / `edit`	Own daily expense voucher	1
`expense_report.view_all`	See all vouchers and approve or reject them	2
`expense_report.delete`	Delete a voucher	2

3.5 Service

CODE	WHAT IT ALLOWS	LEVEL

`service.view` / `view_departments`	See the Service section	1
`service.create_contract` / `edit_contract`	Maintenance contracts	2
`service.delete_contract` / `service.delete`	Delete contracts and records	3
`service.manage_visit` / `manage_report`	Visits and service reports	2
`service.manage_work_order`	Create and edit work orders	2
`service.approve_work_order`	Approve or reopen a work order	3
`service.manage_dispatch`	Store dispatch and proofs	2
`service.create_complaint` / `manage_complaint`	Raise and manage complaints	2
`service.approve_complaint` / `reopen` / `close`	Approve, reopen, close complaints	3

3.6 Marketing

PATTERN	WHAT IT ALLOWS	LEVEL
`marketing.view_X`	See the list (contact, customer, lead, domain, region, plant, organization, campaign, events, report, myteam, visiting_card_contact)	1
`marketing.create_X` / `edit_X`	Add or change that item	2
`marketing.delete_X`	Delete that item	3
`marketing.assign_employee_region` / `assign_dashboard`	Assign people to regions, assign dashboards	2
`marketing.create_report`	Submit own plans and reports	2
`marketing.admin`	Full marketing access	4

3.7 Administration

CODE	WHAT IT ALLOWS	LEVEL
`rbac.view_roles` / `view_permissions` / `view_domain_tab`	See roles, permissions, Domain tab	1
`rbac.assign_roles`	Request a role assignment	3
`rbac.assign_permissions`	Request a permission assignment	4
`rbac.approve_assignments`	Approve or reject those requests	4
`rbac.manage_roles` / `manage_permissions`	Create and edit roles and permissions	4
`settings.view`	See system settings	1
`settings.manage_templates`	Edit email templates	2
`settings.manage_email`	Configure outgoing email	3

`settings.manage_company` / `geofencing`	Company settings, geofence locations	4
`settings.wifi_networks`	Manage the WiFi whitelist	4
`settings.wifi_bypass`	Exempt a person from the WiFi check	4
`workflow.view` / `create` / `edit` / `delete`	Workflows	1/2/2/3
`workflow.approval_template_builder` / `approval_template_edit`	Approval templates and mapping	4
`forms.view` / `create` / `edit` / `delete`	Forms	1/2/2/3
`forms.response_view` / `edit` / `delete`	Form responses	1/2/3
`server.view`	See the server list and look up others' access	2
`server.manage` / `server.assign_access`	Add servers, choose who can use them	3
`server.access_all`	Reach every server with no individual grant	4
`intranet.view` / `intranet.manage`	See or edit the app launcher	1/3
`presence.view_users`	See who is online	1

NEW PERMISSIONS

A permission is only usable once it exists in the catalog. New codes follow the `module.action` pattern and are added to the seed command, then seeded with `python manage.py create_all_permissions`, which is safe to run again.

4 Approval Templates

An approval template answers one question: when this person submits something, who must approve it, and in what order. Leave, attendance, expenses, daily reports, marketing and service work orders can each have their own chain.

4.1 The three building blocks

Approval template

A named chain, for example Senior Flow. It has a category and optionally a limit on how many levels are needed.

Step

One level in the chain. Level 1 is asked first, then level 2, and so on. Each step names one approver.

Mapping (route)

The rule that says this template applies to this person, this department or this role, for this kind of request.


4.2 Which requests can have templates

TEMPLATE CATEGORY	USED FOR
Leave Management	Leave requests
Attendance	Attendance corrections
Marketing	Marketing approvals
Expense	Daily expense vouchers
Daily Service Report	DSR approvals
Service Work Order	Work order approvals

4.3 Who gets picked as approver

When someone submits a request, HRMS looks for a mapping in this order and stops at the first one it finds.

1. A mapping set for that exact employee.
2. Otherwise a mapping set for the employee's department.
3. Otherwise a mapping set for the employee's role.
4. Otherwise the built-in default chain.



Finding the approver

> **A FOUND MAPPING IS FINAL**
> Once a mapping is found it is used completely. If the template has no step for the next level, the chain simply ends and the request is approved. HRMS does not fall back to the default chain.

4.4 The built-in default chain

Used only when no mapping matches.

WHO SUBMITS	LEVEL 1	LEVEL 2
Regular employee	Their department manager	An HR user
Manager	The CEO, or else the first superuser	None

4.5 Setting up a chain, step by step

1. Open Workflows > Approval Templates and choose New.
2. Give it a name, pick the category, and add the steps. Level 1 first, then level 2, each with an approver.
3. Optionally set Levels needed. If you configure three steps but set it to two, only two are used.
4. Save, then open Assign (or Leave > Template Mapping for bulk changes).
5. Choose who it applies to: employees, a department, or a role.
6. Check Active Mappings, a read-only page, to confirm who is covered.

EXAMPLE · TWO-LEVEL LEAVE APPROVAL FOR SERVICE TEAM

Template Service Leave has level 1 as the Service team lead and level 2 as the HR Manager. Map it to the Service department for Leave. Every leave request from anyone in Service now goes to the team lead first and then to HR. A single employee in Service can still get their own mapping, which wins over the department's.

ONE TEMPLATE PER CATEGORY PER TARGET

A person, department or role cannot be given two templates of the same category at once. Remove the old assignment first.

4.6 Who may change templates

Both permissions below are level 4, so by default only administrators.

- `workflow.approval_template_builder` opens the builder and mapping pages.
- `workflow.approval_template_edit` allows editing and deleting templates.

4.7 For other systems

Other apps can read the resolved chain for any user over the API. They can read it but not change it.

ITEM	DETAIL
Endpoint	`GET /api/rbac/approval-templates/?username=jane`
Authentication	`Authorization: Token` (get one from `POST /api/rbac/login/`)
Returns	For each request type, the template, its steps and whether it is custom or the system default
Not available	Creating or editing templates over the API

5 Servers

HRMS keeps a directory of servers (RDP by default) and a list of which employees may connect to each one. The TunnelGate app asks HRMS which servers a person is allowed to see.

> **ADDRESSES ONLY, NEVER PASSWORDS**
> HRMS stores the server's address and nothing else. People sign in on the server itself. There is nowhere in HRMS to type a server password.

5.1 Adding a server

1. Open Admin > Servers and choose Add. This needs `server.manage`.
2. Enter a display name such as Accounts RDP.
3. Enter the host: a name or IP only, for example `rdp-128.example.com` or `192.168.1.102`. No port, no `http://`, no spaces. It is stored in lower case and must be unique.
4. Choose the protocol (RDP, SSH, VNC or Other) and add a short description.
5. Save. The server is active straight away.

5.2 Choosing who can connect

1. Open the server and choose Access. This needs `server.assign_access`.
2. Tick the employees who may use it and save.

PERSON	WHAT THEY SEE THROUGH THE API
Employee with a grant	Only the servers they were granted
Superuser	Every active server
Holder of `server.access_all`	Every active server, with no grants needed
Employee with no grant	Nothing

5.3 Switching off and removing

- **Deactivate:** hides the server from the API but keeps its access list. Reactivate later and everyone is back.
- **Delete:** removes the server and all its access rows for good.
- Access is per person. Department or role based access is not supported.

5.4 Server permissions at a glance

CODE	LEVEL	MEANING
`server.view`	2	See the list and use the look-up-another-user API
`server.manage`	3	Add, edit, activate, deactivate, delete
`server.assign_access`	3	Choose who can use each server
`server.access_all`	4	Unrestricted access to every server

> **NOBODY HAS THESE BY DEFAULT**
> The server permissions are not attached to any default role. Until someone assigns them, only superusers can manage servers.

5.5 What TunnelGate calls

CALL	WHO MAY USE IT	RETURNS
`GET /api/rbac/my-servers/`	Any logged-in user	Servers that user can reach
`GET /api/rbac/servers/?username=jane`	A service account with `server.view`	Servers that named user can reach

6 WiFi Access Control

This feature lets administrators decide which office WiFi networks are trusted. HRMS keeps the list and answers one question: is this network allowed? It does not watch or block any traffic itself. The TunnelGate app detects the user's WiFi and asks HRMS before granting access.

6.1 Adding a WiFi network

1. Open Settings > WiFi Access Control. This needs `settings.wifi_networks` .
2. Choose Add Network.
3. Name: a label for people, such as Head Office or Branch 2.
4. SSID: the exact WiFi name people see on their device.
5. BSSID, optional: the access point's MAC address, written `AA:BB:CC:DD:EE:FF` . HRMS checks the format and converts it to capitals.
6. Leave Active ticked and save.

6.2 SSID only, or pinned to one access point

SETUP	HOW IT MATCHES	WHEN TO USE IT
SSID only (BSSID left blank)	Any router broadcasting that name is accepted	Simple setups where you trust the name
SSID with BSSID	Both the name and the exact router must match	Stops a fake hotspot using your WiFi name

> ADD AS MANY AS YOU NEED
> Head office, each branch and a guest network can all be listed. The first match wins. Switching a network to inactive removes it from checks without deleting it.

6.3 The on and off switch


At the top of the same page is **Enforce WiFi Restriction for Server Access**. It is off by default.

SWITCH	WHAT HRMS ANSWERS
Off	Always allowed. No matching is done at all. Safe for testing TunnelGate first.
On, with networks listed	Allowed only if the current network matches one entry
On, with no networks listed	Denied, with a message to contact the administrator

6.4 Exempting a person

A person holding `settings.wifi_bypass` skips the WiFi check entirely. Superusers are exempt too. Use this sparingly, for example for people who must connect from home.

6.5 How TunnelGate checks



The WiFi check

- TunnelGate calls `POST /api/rbac/wifi-networks/validate/` with the `ssid` and optional `bssid`.
- If HRMS cannot be reached, TunnelGate should deny. Failing open defeats the purpose.
- TunnelGate should remember an allow decision for 30 to 60 seconds and check again as soon as the network changes.
- Use a dedicated service account for TunnelGate, never a real employee's login.

7 Other Things You Can Change

Smaller settings that follow the same idea: change it in the browser, no code needed.

Geofence locations

Add plant or office locations with a map point and an allowed range. Attendance check-ins are matched against them. Needs `settings.geofencing`.

Company settings

Company profile, logo and shared dropdown values used across forms. Needs `settings.manage_company`.

Email settings and templates

Outgoing email account and the wording of system emails. Needs `settings.manage_email` and `settings.manage_templates`.

Departments and designations

The organisation structure that approval mappings and scopes refer to. Needs `org.manage_departments` and `org.manage_designations`.

Holidays and weekly offs

Holiday calendar by year and weekly off pattern. Needs the `holiday.manage` permissions.

Intranet apps

Tiles in the app launcher with name, link, icon, colour and order. Can be switched on or off. Needs `intranet.manage`.

Forms and workflows

Custom forms and multi-step workflows built in the browser. Needs `forms.*` and `workflow.*` permissions.

Onboarding policies

The policies new joiners see in the public onboarding form. Needs `onboarding_policy.*`.

8 Quick Checklists

8.1 A new person joins

1. Create the employee. The login and the basic Employee role are created automatically.
2. Check Active Mappings that their department or role has the right approval templates.
3. Give extra roles or single permissions only if needed, then have them approved.
4. Grant server access and, if needed, note any WiFi exemption.

8.2 A person leaves or changes role

1. Remove or replace their role in User Roles. Remove any direct permissions.
2. Remove their server access grants.
3. If they are named as an approver in any template, replace them there first. Otherwise requests may reach someone who has left.

8.3 Things worth remembering

- Everyone's access is decided by permissions, so adjust permissions rather than creating special cases.
- A role or permission change waits for approval and then applies immediately.
- An approval mapping always beats the default chain, even if the template is short.
- Servers are by person, WiFi is by network, and the two are independent switches.
- Every change is recorded in the audit log, so you can always see who changed what.

FOR BEFORTH

Authorized Signatory

FOR AUREOLE

Authorized Signatory