9.4. LABS



Exercise 9.3: Enforce TLS/SSL for IMAP in dovecot Solution 9.3

- 1. Edit the configuration file and require ssl.
 - On **CentOS**: Edit the file /etc/dovecot/conf.d/10-ssl.conf and add or edit these line:

```
ssl = required
```

- On OpenSUSE:
 - (a) Add or edit the file /etc/dovecot/conf.d/10-ssl.conf and make sure these lines exist:

```
ssl = required
ssl_cert = </etc/ssl/certs/dovecot.pem
ssl_key = </etc/ssl/private/dovecot.pem</pre>
```

- (b) Generate a self-signed certificate for IMAP.
 - # cd /usr/share/doc/packages/dovecot/
 # ./mkcert.sh
- On **Ubuntu** and **Debian**:
 - (a) Edit the file /etc/dovecot/conf.d/10-ssl.conf and change the lines:

```
ssl = required
ssl_cert = </etc/dovecot/dovecot.pem
ssl_key = </etc/dovecot/private/dovecot.pem</pre>
```

(b) Generate a self-signed certificate for IMAP.

```
# cd /usr/share/dovecot
# ./mkcert.sh
```

2. Restart dovecot: and test your mutt command again.

```
# systemctl restart dovecot
$ mutt -f imap://student@<IP_ADDRESS>/
```

LFS211: V_2017-12-01

