
# Mise en place et utilisation du protocole VTP sur Cisco Packet Tracer

Le **VTP** (**VLAN Trunking Protocol**) est un protocole Cisco utilisé pour simplifier la gestion des VLANs (Virtual LANs) dans un réseau composé de plusieurs switches. Il permet de centraliser la création, la modification et la suppression des VLANs sur un switch principal (appelé *serveur VTP*) et de répliquer automatiquement ces informations sur les autres switches du réseau (appelés *clients VTP*). Ainsi, il n'est plus nécessaire de configurer les VLANs manuellement sur chaque switch.

Dans **Cisco Packet Tracer**, le VTP est utilisé pour simuler un réseau structuré et cohérent. On configure un switch comme *serveur VTP*, où les VLANs sont définis. Les autres switches, configurés en *clients VTP*, reçoivent automatiquement les informations sur les VLANs via les liaisons *trunk* entre eux. Cela permet de gagner du temps et d'éviter les erreurs de configuration dans les environnements comportant plusieurs switches.

L'utilisation du protocole VTP dans Cisco Packet Tracer est utile pour comprendre comment automatiser la gestion des VLANs dans un réseau étendu. Cela permet de rendre la configuration plus efficace, surtout dans les réseaux d'entreprise, où le nombre de VLANs et de switches peut rapidement devenir difficile à gérer manuellement.

#### Infrastructure



# Configuration des ports du switch principal

On va maintenant configurer le « Switch3 », on va dans « CLI » :



Et on marque ces commandes :

CMD : enable CMD : conf t CMD : int fa0/1

CMD: switchport mode trunk

CMD: int fa0/2

CMD: switchport mode trunk

CMD : exit CMD : exit

```
SwitchSenable
SwitchSeonf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int fa0/1
Switch(config-if)#switchport mode trunk

Switch(config-if)#switchport mode trunk

Switch(config-if)#int fa0/2
Switch(config-if)#int fa0/2
Switch(config-if)#int fa0/2
Switch(config-if)#switchport mode trunk

Switch(config-if)#exit
Switch(config-if)#exit
Switch(config)#exit
Switch(sonfig)#exit
Switch(sonfig)#swit
Switch(sonfig)#swit
Switch(sonfig)#swit
Switch(sonfig)#swit
Switch#
```

#### **Configuration VTP Server**

Puis celle-ci sur le même switch :

CMD: show vtp status

CMD : conf t

CMD: vtp mode server

CMD : vtp domain VTPserver

CMD: exit

CMD: show vtp status

# **Configuration VTP Client**

On va maintenant configurer le « Switch2 », on va dans « CLI » :



Et on marque ces commandes :

CMD: en

CMD: show int trunk

CMD : conf t

CMD: vtp mode client

CMD: exit

CMD: show vtp status

```
Switchéshow int trunk
Port Mode Encapsulation Status Native vian
Pa0/1 auto n-802.1q trunking 1
Port Vians allowed on trunk
Pa0/1 1-1005
Port Vians allowed and active in management domain
Pa0/1 1
Pent Vians in spanning tree forwarding state and not pruned
Pa0/1 1

Switchésonf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch (config) evep mode client
Switch (config) evep mode client
Switch (config) exit Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch (config) exit
Switch exit (config) exit
```

## **Configuration VTP Transparent**

On va maintenant configurer le « Switch4 », on va dans « CLI » :



Et on marque ces commandes :

CMD: en

CMD: show int trunk

CMD : conf t CMD : int f0/2

CMD: switchport mode trunk

CMD : exit

CMD: vtp mode transparent

CMD: exit

CMD : show vtp status

#### **Configuration VTP Client**

On va maintenant configurer le « Switch5 », on va dans « CLI » :



#### Et on marque ces commandes :

CMD: en

CMD: show int trunk

CMD : conf t

CMD: vtp mode client

CMD: exit

CMD: show vtp status

```
SwitchSehow int trunk
Fort Mode Encapsulation Status Native vian
Fa0/1 auto n-802.iq trunking 1

Port Vians allowed on trunk
Fa0/1 1-1005

Fort Vians allowed and active in management domain
Fa0/1 1

Fort Vians in spanning tree forwarding state and not pruned
Fa0/1 1

Switch$conft 1

Switch$conft 1

Switch$conft 2

Switch$conft 2

Switch$conft 3

Switch$conft 3

Switch$conft 4

Enter configuration commands, one per line. End with CNTL/Z.

Switch$conft 5

Switch$conft 6

Switch$conft 9

Swit
```

## Création d'un VLAN dans le VTP Server

On quitte le « Switch5 », pour aller sur le « Switch3 », on va dans « CLI » et on marque :

CMD : conf t CMD : vlan 10

CMD: name production

CMD : exit CMD : exit

CMD: show vtp status

On voit que « Configuration Revision » est maintenant à 2

#### Afficher le VLAN dans les autres switches

On quitte le « Switch3 », pour aller sur le « Switch2 », on va dans « CLI » et on marque :

CMD : show vtp status CMD : show vlan

On voit que « Configuration Revision » est maintenant à 2 et que notre VLAN 10 production est bien retranscrit sur notre switch :

On quitte le « Switch2 », pour aller sur le « Switch4 », on va dans « CLI » et on marque :

CMD : show vtp status CMD : show vlan

On voit que « Configuration Revision » est toujours à 0 et que notre VLAN 10 production n'apparait pas sur notre switch :

```
| Description | Section |
```

On quitte le « Switch4 », pour aller sur le « Switch5 », on va dans « CLI » et on marque :

CMD : show vtp status CMD : show vlan

On voit que « Configuration Revision » est maintenant à 2 et que notre VLAN 10 production est bien retranscrit sur notre switch :

```
| Description |
```

On remarque que tous les Switch configuré en VTP client on les meme configuration que le switch configuré en VTP SERVER, et que le VTP TRANSPARENT est bien transparent, puisqu'il ne fait que la liaison ici entre le switch 3 et le switch 5

### Suppression d'un VLAN et changement de mode VTP

Maintenant, on va supprimer le cable qui relie le « Switch2 » au « Switch3 », et on marquer ces commandes sur le « Switch2 » :

CMD: conf t

CMD: vtp mode server

CMD: no vlan 10

CMD : exit CMD : conf t

CMD: vtp mode client

```
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode server
Setting device to VTP SERVER mode.
Switch(config)#no vlan 10
Switch(config)#exit
Switch#
%SYS-5-CONFIG_I: Configured from console by console
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#vtp mode client
Setting device to VTP CLIENT mode.
Switch(config)#
```

Puis on remet le cable qui relie le « Switch2 » au « Switch3 », et on marque ces commandes sur le « Switch2 » :

CMD: exit

CMD: show vlan

On remarque que le VLAN 10 production n'apparait pas malgré le fait que le « Switch2 » qui est configuré en tant que VTP CLIENT est relié au « Switch3 » en tant que VTP SERVER :

```
Switch(config) #exit
Switch8
SV$5-5-CONFIG_I: Configured from console by console

Svitch8show vlan

VLAN Name

Status Ports

1 default active Fa0/2, Fa0/3, Fa0/4, Fa0/5
Fa0/6, Fa0/10, Fa0/11, Fa0/12, Fa0/13
Fa0/14, Fa0/15, Fa0/16, Fa0/17
Fa0/18, Fa0/19, Fa0/22, Fa0/23, Fa0/24, Gig0/1
Gig0/2

1002 fddi-default active
1003 token-ring-default active
1004 fddinet-default active
1005 trnet-default active
1005 trnet-default active
1005 trnet-default active
100105 trnet-default active
100105 trnet-default active
1003 tdd 101002 1500 - - - 0 0
1002 fddi 101002 1500 - - - 0 0
1002 fddi 101004 1500 - - - 0 0
1003 tr 101003 1500 - - - 0 0
1004 fddet 101004 1500 - - - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fddet 101004 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fddet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fddet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fdmet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fdmet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1004 fdmet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1005 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1007 trnet 101005 1500 - - 1 ieee - 0 0
1008 trnet 101005 1500 - - 1 ieee - 0 0
1008 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005 1500 - - 1 ieee - 0 0
1006 trnet 101005
```

#### Cependant, on remarque que la « Configuration Revision » est maintenant à 3 :

On quitte le « Switch2 », pour aller sur le « Switch5 », on va dans « CLI » et on marque :

CMD: en

CMD: show vlan

CMD: show vip status

On remarque que on obtient le même résultat au niveau des deux switches configurés en tant que VTP CLIENT

	:h>en										
Swite	h#sho	w vlan									
	Name				Stat		Ports				
	defau				act	ive Fa Fa Fa Fa Fa	0/2, 0/6, 0/10, 0/14, 0/18,	Fa0/3, Fa Fa0/7, Fa Fa0/11, Fa0/15, Fa0/19, Fa0/23,	0/4, Fat 0/8, Fat Fa0/12, Fa0/16, Fa0/20,	0/5 0/9 Fa0/13 Fa0/17	
1002	fddi-	default			act		907 1				
	token-ring-default					active					
	fddinet-default					active					
		-default			act:						
		SAID						BrdgMode			
		100001	1500		-	-	-	-	0	0	
			1500		-	-	-		0	0	
			1500		-	-	-		0	0	
			1500		-		ieee		0	0	
1005	trnet	101005	1500	-	-	-	ibm	-	0	0	
		SAID									
		N VLANs									
Prima	ry Se		e		Ports						
Prima	iry Se	condary Type	e		Ports						
Prima	ry Se	condary Type	e		Ports						
Prima  Swite	ry Se	condary Type	e		Ports						
Prima Swite Swite VTP V	nry Se	w vtp statum	e		1 to 2						
Prima Swite Swite VTP V	nry Se	condary Type	e		1 to 2 1 VTPserve						
Prima Swite Swite VTP V VTP I	nry Second	w vtp status n capable n running Name	e s		1 to 2 1 VTPserve	d					
Prima Swite Swite VTP V VTP I VTP I	ary Secondary Se	w vtp status n capable n running	e s	:	1 to 2 1 VTPserve Disable	d d					
Prima Switc Switc VTP V VTP I VTP I VTP I	h# show version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version versio	w vtp statum n capable n running Name g Mode Generation	e s	:	1 to 2 1 VTPserve Disable Disable	d d 28.0000					
Prima Switc Switc VTP V VTP I VTP I VTP I	h# show version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version version versio	w vtp status n capable n running Name	e s	:	1 to 2 1 VTPserve Disable Disable	d d 28.0000	0:28:	48			
Prima Switc Switc VTP V VTP I VTP I VTP I VTP I Confi	hry Second of the state of the	w vtp statu: n capable n running Name g Mode Seneration ion last mod	e s	:	1 to 2 1 VTPserve Disable Disable	d d 28.0000	0:28:	48			
Prima Switc Switc VTP V VTP I VTP I VTP I Confi	h#showersion Oomain Pruninn Fraps Ge ID Lgurat	w vtp statum n capable n running Name J Mode Generation ion last mod	e s	by 0.0	1 to 2 1 VTPserve Disable Disable 0000.D3:	3 28.0000 3-1-93 0	0:28:	48			
Prima Switc Switc VTP V VTP I VTP I Devic	h# h#shoo Version Version Version Prunine Fraps (ce ID lgurat:	w vtp status w vtp status n capable n running Name g Mode Generation ion last mod NN:	e s dified	by 0.0	1 to 2 1 VTPserve Disablee Disablee 0000.D3:	3 28.0000 3-1-93 0	0:28:	48			
Prima Switc Switc VTP V VTP I VTP I VTP I Devic Confi	ch# ch#shor version comain runine rraps ( cigurat: cigurat coperat.	w vtp statum n capable n running Name g Mode Generation ion last mode NN:	e s dified	by 0.0	1 to 2 1 VTPserve Disable Disable 00D0.D3: .0.0 at	3 28.0000 3-1-93 0	0:28:	48			
Prima Switc	h# show we shave the show we s	condary Type w vtp status n capable n running Name g Mode Seneration ion last mod AN : ing Mode ANs support existing VL	e dified ed loca	by 0.0	1 to 2 1 VTPserve Disablee 00D0.D3: .0.0 at	3 28.0000 3-1-93 0	0:28:	48			
Prima Switc Switc Switc VTP V VTP I VTP I VTP I Confi	h# show we shave the show we s	w vtp statum n capable n running Name g Mode Generation ion last mode NN:	e dified ed loca	by 0.0	1 to 2 1 VTPserve Disable Disable 0000.D3: .0.0 at : Client : 255 : 5	d d 28.0000 3-1-93 0		48	2 0x0E	D×7E	