

AVAROS Quick Start

OVOS Assistant for Sustainable Manufacturing · Version 0.1.1

1. Requirements

- Linux server or workstation
- Docker Engine 26+ and Docker Compose v2
- 4 GB RAM minimum and 10 GB free disk space
- One available host port for the Web UI

2. Install

```
unzip avaros-dia-v0.1.1.zip
cd avaros-dia-v0.1.1
bash scripts/prepare-env.sh
docker compose up -d --build
docker compose ps
```

Open **http://localhost:8080** and enter the AVAROS_WEB_API_KEY stored in the private `.env` file.

If port 8080 is occupied

Edit `.env` before starting:

```
AVAROS_WEB_PORT=9090
HIVEMIND_WS_URL=auto
```

Then open **http://localhost:9090**. Voice automatically follows the selected Web UI port.

Do not set the browser HiveMind URL to a Docker service name. Keep `HIVEMIND_WS_URL=auto` for local, LAN, and proxied deployments.

3. Try the demo platform

```
docker compose --profile demo up -d
```

Wizard field	Value
Profile name	demo

API URL	http://demo-platform:8090
Authentication	Bearer token
Token	Any non-empty test value

4. Configure your platform

The guided wizard covers:

1. Platform endpoint and authentication
2. Connection testing
3. Asset registration and aliases
4. Platform resource linking
5. Metric mapping and validation
6. Voice-intent activation
7. Optional PREVENTION analytics

Use a platform URL reachable from inside Docker. A service running in another container must not be configured as `localhost`.

5. Verify and troubleshoot

```
curl http://localhost:8080/health
docker compose ps
docker compose logs --tail=200 avaros-web-ui hivemind avaros
```

Replace 8080 with your configured `AVAROS_WEB_PORT`.

6. Completely reset the test installation

Remove AVAROS containers, networks, volumes, and locally built images:

```
bash scripts/uninstall.sh
```

On a disposable machine, also remove every image referenced by AVAROS and delete the extracted release directory:

```
bash scripts/uninstall.sh --all-images
cd ..
rm -rf avaros-dia-v0.1.1
```

`--all-images` may remove images shared with another Docker Compose project. Use it only on a dedicated test machine.

Documentation included in the ZIP

See `README.md` and `user-docs/` for installation, configuration, operations, security, troubleshooting, voice commands, PREVENTION integration, and SME replication guidance.

