

# UI INSTRUCTIONS FOR AI AGENTS

Assets/Game/New UI/

JunkLite UI setup. Read this before creating or editing any UI or in-world text.

## 1. TEXT STACK

Inventory and all HUD menus use TextMesh Pro UGUI (TextMeshProUGUI / TMP\_Text) on Unity UI canvases. That is the standard for every new screen, card, button, tooltip, and overlay.

Use 3D TextMeshPro (not UGUI) only when there is no canvas: floating world numbers, damage popups, labels parented to a mesh. World-space canvases still use TextMeshProUGUI. Do not use Unity UI.Text, legacy TextMesh, or UI Toolkit.

## 2. FONTS (files in Assets/Game/New UI/Fonts/)

World interactables and any in-world text that is not HUD: PLAY.

TMP asset: Play-Regular SDF.asset source: Play-Regular.ttf

Main HUD titles, cards, submenus: ZUUME EDGE.

TMP asset: ZuumeEdge-Regular SDF.asset source: ZuumeEdge-Regular.ttf

All other HUD text (body, labels, hints, stats): SATOSHI.

TMP asset: Satoshi-Variable SDF TMP.asset source: Satoshi-Variable.ttf

Do not use Lekton, Clash Display, Bebas Neue, LiberationSans, or TMP samples.

Satoshi-Variable SDF.asset is Unity TextCore, not TextMesh Pro. Ignore it for TMP.

## 3. DEFAULT FONT MATERIAL (mandatory)

Only use Assets/Game/New UI/Default Font Material.mat for font/text style.

It is bland overlay TMP: no glow, outline, underlay, fog, or pattern shaders.

World pickup prompts were rendering a foggy LiberationSans material; overlay avoids volumetric fog on in-world text.

Do NOT assign Default Font Material as the only material on a TMP component.

Its atlas slot is empty. Assign the correct TMP font asset, then copy this material shader and bland settings onto the font atlas material (keep \_MainTex).

Runtime: UIFonts.ApplyWorld, ApplyHudTitle, ApplyHudBody, ApplyWorldTree.

Catalog: Assets/Game/New UI/Resources/UIFontCatalog.asset

Never use TMP\_Settings.defaultFontAsset.

## 4. PATHS AND REBUILD

UI root: Assets/Game/New UI/

Helper: Assets/Game/Scripts/UI/UIFonts.cs

If glyphs are missing: JunkLite > UI > Rebuild New UI Font Assets