EE 102 Week 4, Lecture 1 (Fall 2025)

Instructor: Ayush Pandey

Date: September 22, 2025

1 Goals for today

To understand how to compute the output of a linear-time invariant system given any general input signal that is applied to the system.

2 Representing signals using impulses

We have discussed the three fundamental signals: the unit step, the unit impulse, and the complex exponential. What's common about all three of these functions? Why are these three signals so special? The answer is that these three signals can be used to represent any arbitrary signal (well, almost any!) — especially the signals that we come across in engineering practice. In the previous lectures, we have discussed how to write general signals only by using unit steps and complex exponentials. We have also briefly discussed how the definition of the unit impulse (in the sense of distributions), is in fact, a definition that says that each signal is made up of its samples at each time point and the impulse is the function that does the sampling. Let's try to break this down further with some examples.

2.1 Discrete-time step using impulse

To help you build intuition for this concept, consider a signal in discrete-time. For example, the unit step signal u[n] is defined as

$$u[n] = \begin{cases} 1, & n \ge 0 \\ 0, & n < 0 \end{cases}$$

which can be visualized as a train of unit impulses as shown in Figure 1. It is clear that it is a signal that is made up of many impulses (see pop quiz below).

Pop Quiz 2.1: Check your understanding!

In discrete-time, write the unit step signal u[n] as a sum of scaled and shifted unit impulses $\delta[n]$.

Solution on page 7




Figure 1: Unit step signal u[n] visualized as a train of unit impulses.

We see that the unit step can be viewed as many impulses (one impulse at each time point). This is also true for every other signal — the simplest way to break down a signal is to view it as a sample at each time point. The unit impulse helps us pick out the samples at each time point so that we can write the logic above formally. A visualization of this idea is shown in Figure 2.

2.2 Impulse as a sampler in continuous-time

Recall the sampling property of the impulse in continuous-time:

$$\int_{-\infty}^{\infty} x(t)\delta(t-t_0)dt = x(t_0).$$

This property tells us that the impulse function $\delta(t-t_0)$ acts as a sampler that picks out the value of the signal x(t) at the specific time $t=t_0$. This means that we can represent any continuous-time signal x(t) as an integral of scaled and shifted impulses.

2.3 Example: Representing a sinusoidal signal using impulses

Let's work through this with a specific example of a sinusoidal signal: $x(t) = \sin(t)$. We can write $\sin(0)$ as

$$\sin(0) = \int_{-\infty}^{\infty} \sin(\tau)\delta(\tau - 0)d\tau.$$




Figure 2: Visualization of the running sum representation of the unit step signal u[n] as a sum of shifted impulses.

Similarly, we can write $\sin(t_1)$ for any arbitrary time t_1 as

$$\sin(t_1) = \int_{-\infty}^{\infty} \sin(\tau) \delta(\tau - t_1) d\tau.$$

This means that we can represent the entire signal sin(t) as an integral of scaled and shifted impulses:

$$\sin(t) = \int_{-\infty}^{\infty} \sin(\tau) \delta(\tau - t) d\tau.$$

Now, this might seem trivial or even circular! But the key insight here is that we are expressing the signal as a continuous superposition of impulses, each weighted by the value of the signal at that point in time.

2.4 General representation of signals using impulses

In general, any continuous-time signal x(t) can be represented using impulses. Let's visualize an arbitrary signal x(t) and see how it can be decomposed into impulses at each time point

(see Figure 3).




Figure 3: Impulse samplers drawn as arrows from the time axis to the signal x(t) (arrowheads at the curve).

At each point, the impulse signal can be written by shifting the impulse to that point and scaling it by the value of the signal at that point. Therefore, we start with $\delta(t)$ as the impulse at t=0. To get the impulse at an arbitrary time $t=\tau$, we shift the impulse to that point, which gives us $\delta(t-\tau)$. To scale this impulse by the value of the signal at that point, we multiply it by $x(\tau)$, resulting in $x(\tau)\delta(t-\tau)$. So, we have

$$x(t) = \int_{-\infty}^{\infty} x(\tau)\delta(t-\tau)d\tau.$$

3 General output of an LTI system using impulse response

We finally get to the main goal of this lecture. Our goal is to compute the output of systems given any arbitrary input signal. This is very important because in practice, we often encounter signals that are not as simple as the unit step or the complex exponential. We need a systematic way to compute the output of a system for any input signal. Think about the following examples, where we might want to compute the output of a system:

• An audio signal (your recorded voice singing a song, for example) that needs to be filtered to remove noise. How would you represent your filtered signal mathematically (to be able to analyze and report back its properties to your music producer!)?

- For an integrated circuit, you might want to compute the output voltage of a circuit given an arbitrary input voltage signal (in real-world, the voltage signal is never a perfect sinusoid!).
- In communications, you might want to compute the output of a communication channel given an arbitrary input signal (for example, a modulated signal carrying information).

To achieve all of the above, we start by describing the impulse response of the system.

3.1 Impulse response of an LTI system

We define the impulse response of a system as the output of the system when the input is an impulse signal. In continuous-time, if the system input is $\delta(t)$, then we call the output of this system, the impulse response and denote it as h(t) (see Figure 4). Now, the question




Figure 4: Impulse response of a system: output h(t) when input is $\delta(t)$. What is the output for a general input x(t)?

is, what is the output of the system when the input is an arbitrary signal x(t)?

Pop Quiz 3.1: Check your understanding!

What is the output of the system for a shifted impulse input $\delta(t-\tau)$? Do you need additional assumptions about the system to answer this question?

Solution on page 7

Pop Quiz 3.2: Check your understanding!

What is the output of the system for a scaled impulse $k\delta(t)$? Do you need additional assumptions about the system to answer this question?

Solution on page 7

We start by writing the output of the system for a shifted and scaled impulse input. That is, if the input is $x(\tau)\delta(t-\tau)$, then the output will be $x(\tau)h(t-\tau)$ (only if, of course, the system is linear and time-invariant!). Now, we can write the output of the system for an arbitrary input x(t) (see Figure 5) by using the integral representation of the input signal using impulses: So, using the integral representation of the input signal, we can write the

$$x(\tau)\delta(t-\tau)$$
 System: H $\rightarrow x(\tau)h(t-\tau)$

Figure 5: Impulse response of a system: output h(t) when input is $\delta(t)$. What is the output for a general input x(t)?

output of the system as

$$y(t) = \int_{-\infty}^{\infty} x(\tau)h(t-\tau)d\tau.$$

This integral is called the convolution integral, and it is denoted by the symbol *. Therefore, we can write the output of the system as

$$y(t) = x(t) * h(t).$$

Pop Quiz 3.3: Check your understanding!

Write the discrete-time version of the convolution integral.

Solution on page 7

4 Virtual manipulatives to understand convolution

In the next lecture, we will use virtual manipulatives to understand convolution better. We will also discuss some properties of convolution and how to compute convolution using graphical methods (with many practical examples!).

Pop Quiz Solutions

Pop Quiz 2.1: Solution(s)

Notice that for any given value of n, the unit step u[n] is equal to 1 if $n \geq 0$ and 0 otherwise. This means that the unit step can be viewed as a sum of all the unit impulses $\delta[k]$ for k from $-\infty$ to n. So, we can write

$$u[n] = \sum_{k=-\infty}^{n} \delta[k]$$

for all $n \in \mathbb{Z}$. To represent the signal in terms of the general impulse $\delta[n]$, we can write:

$$u[n] = \sum_{k=0}^{\infty} \delta[n-k].$$

You can see that for any given n, the sum will only include the impulses from k = 0 to k = n, which corresponds to the definition of the unit step.

Pop Quiz 3.1: Solution(s)

To answer this question, we need to assume that the system is time-invariant. This means that if the input is shifted in time, the output will also be shifted by the same amount. Therefore, if the input is $\delta(t-\tau)$, the output will be $h(t-\tau)$.

Pop Quiz 3.2: Solution(s)

To answer this question, we need to assume that the system is linear. This means that if the input is scaled by a constant factor, the output will also be scaled by the same factor. Therefore, if the input is $k\delta(t)$, the output will be kh(t).

Pop Quiz 3.3: Solution(s)

In discrete-time, the convolution integral becomes a sum. Therefore, we can write the output of the system as

$$y[n] = \sum_{k=-\infty}^{\infty} x[k]h[n-k].$$

This sum is called the convolution sum, and it is also denoted by the symbol *.