Rave Generation

presents



LC480

User Manual

1. Overview

LC480 is a reverb and effects processor modeled on the Lexicon 480L digital effects system. It recreates the 480L's programs, 205 in 21 banks: halls, rooms, plates, random halls and ambience, delays and effects, pitch and Doppler, samplers, dynamics, EQ and test signals.

Our own panel puts it all under the mouse: a program browser with every bank, page windows that put a program's parameters on six faders, and input and output trims.

2. Signal Flow

INPUT → INPUT TRIM → PROGRAM → OUTPUT TRIM → OUTPUT

The program sets the balance of dry signal and effect itself; most programs have a MIX parameter for it.

LC480 runs at your project's sample rate. It delays its output by 17 samples and reports this to your DAW, so its delay compensation keeps every track in time.

3. The Panel

BANKS

The 21 bank keys. Click one to list its programs below; its light shows which bank is listed.

PROGRAMS

The listed bank's programs. Click one to load it with its factory settings; the running program is lit. The output mutes for a moment while a new program starts. Programs of the same family, two halls for example, take over from each other without the mute.

Display

Shows the running program, its bank and program number, and the page on the faders. While you move a fader it shows that parameter's full name and value.

Arrows

Load the previous or the next program.

Headroom

The input level, left and right, from -24 to +12, where 0 is 12 dB below full scale. Set INPUT so the +12 and ovld lights stay off: ovld means the input clips.

INPUT and OUTPUT

INPUT (-24 to +12 dB, default 0 dB) sets the level into the program. OUTPUT (-24 to +24 dB, default 0 dB) sets the level of everything LC480 puts out. Both keep their setting when you change programs.

PAGES

A program has up to five pages of six parameters. Each window names its page's parameters; click a window to put that page on the faders. The page on the faders is lit.

Faders

The six faders set the parameters of the page on show. The line above them shows each parameter's short name and value. Drag a fader to change its value.

The key under a fader shows that parameter in the display. Press it again for vernier, fine adjustment with FINE in the display, and a third time to leave.

Some programs have a key in place of a parameter, such as TAP PLAY on the Doppler programs and RECORD and PLAY on the samplers. Its key under the fader presses it.

Hints

The line at the bottom of the panel explains the control under the mouse. The i button at its right end shows or hides it.

Menu Bar

Undo and Redo; the panel's opacity, 0% to 100%, to see the DAW behind it; the interface size, 70% to 200%; and the preset menu, which loads and saves presets and copies and pastes them between instances.

Activation

Until LC480 is activated, its output mutes for 1 second in every 6. Paste your license key into the box on the panel, then move any control to activate it.

4. Automation

In your DAW's automation list:

Parameter	Controls
Program	The running program
Param 1 to 6	The faders of page 1, left to right
Param 7 to 30	Pages 2 to 5, six each
Input	INPUT, -24 to +12 dB
Output	OUTPUT, -24 to +24 dB

A program change brings the program's factory settings with it when made on the panel; automated, the Param values in your project stay as they are.

5. Programs

Every bank with its programs, numbered as in the program list.

Bank	Programs
1 HALLS	1 LARGE HALL, 2 LARGE+STAGE, 3 MEDIUM HALL, 4 MEDIUM+STAGE, 5 SMALL HALL, 6 SMALL+STAGE, 7 LARGE CHURCH, 8 SMALL CHURCH, 9 JAZZ HALL, 10 AUTO PARK
2 ROOMS	1 MUSIC CLUB, 2 LARGE ROOM, 3 MEDIUM ROOM, 4 SMALL ROOM, 5 VERY SMALL, 6 LG WOOD ROOM, 7 SM WOOD ROOM, 8 LARGE CHAMB., 9 SMALL CHAMB., 10 SMALL&BRIGHT
3 WILD SPACES	1 BRICK WALL, 2 BUCKRAM, 3 BIG BOTTOM, 4 10W-40, 5 20W-50, 6 METALLICA, 7 SILICA BEADS, 8 INSIDE OUT, 9 RICOCHET, 10 VAROOM
4 PLATES	1 A PLATE, 2 SNARE PLATE, 3 SMALL PLATE, 4 THIN PLATE, 5 FAT PLATE
5 EFFECTS	1 ILLUSION, 2 SURFIN, 3 VOC WHISPERS, 4 DOUBLER, 5 BACK SLAP, 6 REBOUND, 7 GIT IT WET, 8 SUDDEN STOP, 9 IN THE PAST, 10 TREMELO L&R
6 TWIN DELAYS	1 4-VCE DOUBLE, 2 DOUBLE DELAY, 3 4-BOUNCE DLY, 4 PITTERPATTER, 5 X-PAN DOUBLE, 6 DELAY CAVE, 7 CIRCLES, 8 THERE & BACK, 9 SOFT ROLLER, 10 ON AND ON

Bank	Programs
7 SAMPLERS	1 STEREO 3S, 2 MONO 6S, 3 MONO 3S, 4 DUAL RATE CH, 5 FWD&REV 1.5, 6 STEREO DRUM, 7 DUAL RC DRUM, 8 FWD&REV DRUM, 9 STERE0 RC10, 10 MONO RC20
8 PITCH, DOPPLER	1 PITCH CHANGE, 2 PITCH CHORUS, 3 1% UP 1% DWN, 4 BARBER POLE, 5 HALF STEPS, 6 STAIR CASE, 7 XPRES SUBWAY, 8 INDY CORNER, 9 AIRPORT LAND, 10 AIRPORT TKOF
9 MASTERING	1 THE IN_OUT, 2 STEREO ADJST, 3 PONS ADJUST, 4 MS DECODE, 5 INVERT L-R, 6 CHANNEL SWAP, 7 ST PARAM EQ, 8 60 HZ NOTCH, 9 MON PARAM EQ, 10 PANORAMA
10 COMPRESSOR	1 2.00=1 COMP, 2 6.24=1 COMP, 3 18.28=1 COMP, 4 TRANSFER, 5 VOX EASY, 6 FM, 7 NAILED, 8 NOISE GATE, 9 2-SLP MACH A, 10 2-SLP MACH B
11 RANDOM HALLS	1 LARGE RHALL, 2 LG RHALL+STG, 3 MEDIUM RHALL, 4 MED RHAL+STG, 5 SMALL RHALL, 6 SM RHALL+STG, 7 LARGE RCHRCH, 8 SMALL RCHRCH, 9 JAZZ RHALL, 10 AUTO PARK R
12 RANDOM SPACES	1 MUSIC CLUB R, 2 LARGE ROOM R, 3 MEDUM ROOM R, 4 SMALL ROOM R, 5 VERY SMALL R, 6 LARGE CHMB R, 7 SMALL CHMB R, 8 SM&BRIGHT R, 9 CHOROUS ROOM, 10 WET & TACKY
13 AMBIENCE	1 VERY LG AMB, 2 LG AMBIENCE, 3 MED AMBIENCE, 4 SM AMBIENCE, 5 STRONG AMB., 6 HEAVY AMB., 7 AMB. HALL, 8 ANNOUNCER, 9 CLOSET, 10 GATED AMB.
14 POST AMBIENCE	1 CAR INTERIOR, 2 LIVING ROOM, 3 BATHROOM, 4 KITCHEN AMB., 5 KELLARS CELL, 6 SMALL FOLEY, 7 WAREHOUSE, 8 AIRHEAD, 9 DIAL IT UP, 10 REVERB TAIL
15 PRIME TIME 3	1 PRIME CHORUS, 2 PRIME SLAP, 3 BOUNCE GLIDE, 4 SWIRLS, 5 HEAVY DETUNE, 6 SHAKE IT UP, 7 WOWZA, 8 WOWZA 2, 9 VOCALZ, 10 PRIME FLANGE
16 FREQ. STUFF	1 MIX FINISH, 2 BG VOCALS, 3 DRUMS, 4 AC GUITARS, 5 BASS THUMP, 6 CARBON MIC, 7 SAXOPHONE, 8 HORN BLAST, 9 SOFTENER, 10 SOME FUZZ
17 TEST & REF	1 100HZ -12DB, 2 500HZ -17DB, 3 500HZ -12DB, 4 1KHZ -17DB, 5 1KHZ -12DB, 6 10KHZ -12DB, 7 30HZ SLATE, 8 A-440 TUNER, 9 PINK NOISE, 10 BINAURAL SIM
18 CONCERT HALL	1 CONCERT HALL, 2 MEDIUM HALL, 3 SMALL HALL, 4 GOLD HALL, 5 GUITAR HALL, 6 REGGAE HALL, 7 REFLEX HALL, 8 BRIGHT HALL, 9 DARK HALL, 10 OLIVERS WELL

Bank	Programs
19 RICH PLATES	1 LARGE PLATE, 2 DRUM PLATE, 3 VOCAL PLATE, 4 VOX PLATE #2, 5 SLAP PLATE, 6 GUITAR PLATE, 7 SHORT PLATE, 8 HORN PLATE, 9 ECHO PLATE, 10 SILVER PLATE
20 6 VOICE CHORUS	1 WOOWOO, 2 6VC KORUS, 3 3VC CHORUS, 4 4VC CHORUS, 5 EKOZ+KORUS, 6 VOCAL CHORUS, 7 SOFT ECHOES, 8 HARD ECHOES, 9 CANYON KORUS, 10 TUFF STUFF
21 MULTI BAND	1 CLOSET, 2 TELEPHONE, 3 PHARTAGE, 4 STADIUM, 5 DOWNSTAIRS, 6 BANDSWEEP, 7 BASS ECHOES, 8 BAND BOUNCE, 9 WHISPERS, 10 EMPTY STAGE

Support

For technical support, updates, and additional information:

Website: ravegeneration.io

Email: support@ravegeneration.io

© 2026 Rave Generation. All rights reserved.

All product names, trademarks and registered trademarks are the property of their respective owners. Names are used only to identify hardware and software studied during the development of this plugin, and do not imply any affiliation with, endorsement by, sponsorship by or licensing from the trademark holders.