Rave Generation

presents



Multiband Processor

User Manual

1. Overview

Multiband Processor is a recreation of the multiband compressor from Steinberg's Cubase SX and Nuendo. It splits your signal into up to five frequency bands and gives each band its own level and its own compression curve, which you draw. The bands are then added back together, followed by the output level and a soft clipper.

Two controls are new: AMOUNT sets how much of the processing you hear, and ZERO LATENCY removes the delay for recording and live use. At their defaults the plugin produces the same output as the original.

2. Signal Flow

INPUT → BAND SPLIT → LEVEL → CURVE → SUM → OUTPUT → SOFTCLIP

Each band has its own LEVEL and CURVE. LEVEL comes before the curve, so turning a band up also drives it harder into its curve. Each band's compressor reacts to the louder of the two channels and treats both alike, so the stereo image stays in place. With every curve straight and every LEVEL at 0 dB, the bands add up to the input unchanged.

The plugin delays the sound by three times your DAW's buffer size plus about 4 ms, as the original did, and reports this to your DAW, so its delay compensation keeps every track in time. ZERO LATENCY removes this delay.

3. The Panel

FREQUENCY BANDS

Parameter	Range	Description
BAND LEVEL	-12 to +12 dB	Drag the diamond in the middle of a band up or down. Turns the band up or down before its curve. Default 0 dB.
CROSSOVER	20 Hz to 12 kHz	Drag a diamond on the floor sideways to move the split between two bands. Defaults 256 Hz, 2048 Hz, 6000 Hz and 10000 Hz.

Click a band to select it. The strip at the top shows the value of the handle under the mouse.

CHARACTERISTICS

The curve of the selected band: input level across, output level up. On the diagonal a level comes out as it went in; where the curve runs above the diagonal, that level comes out louder, below it, quieter. The orange dot shows where the signal is on the curve right now. The strip at the top shows IN, OUT and GAIN of the signal, or of the point under the mouse.

Parameter	Range	Description
POINT	Anywhere	Drag a point to shape the curve.
END POINT	Up to 0 dB	The point on the right edge: the output level for a 0 dB input. Drag it up or down. Default 0 dB.
POINTS	2 to 8	How many points the selected band's curve has, both ends included. 2, the default, is a straight line.

BANDS

Parameter	Range	Description
BANDS	1 to 5	How many bands the signal is split into. Default 3.
BAND	1 to 5	The selected band: the one shown in CHARACTERISTICS and played by SOLO. Clicking a band in FREQUENCY BANDS selects it too.
SOLO	Off, On	Plays only the selected band. Default Off.

MODE AND OUTPUT

Parameter	Range	Description
MODE	Complex, Classic	Classic uses one fast compressor stage. Complex uses a slower stage followed by a fast one. Default Complex.
SOFTCLIP	Off, On	Rounds off peaks after OUTPUT, so the signal never goes above 0 dBFS. A clean signal comes out 1.4 dB lower. Default Off.
ZERO LATENCY	Off, On	Removes the delay, for recording and live use. The bands then shift in phase near the crossovers, so the sound is close to the original but not identical. Default Off.
AMOUNT	0 to 100%	How much of the curves, band levels and OUTPUT you hear. At 0% the signal passes unchanged; SOFTCLIP still works when it is on. Default 100%.
OUTPUT	-12 to +12 dB	Level after the bands are added together. Default 0 dB.

Knobs

Hold Shift while dragging AMOUNT or OUTPUT for fine adjustment. Right-click a knob to return it to its default (Alt+click works too, Option+click on macOS); double-click it to type a value.

Hints

Hover over a control to read what it does in the bar at the bottom of the window. The (i) icon at the top right turns the hints on and off.

Menu Bar

Undo and Redo; the panel's opacity, 0% to 100%, to see the DAW behind it; the interface size, 70% to 200%; and the preset menu, which browses, loads and saves presets and copies and pastes them between instances.

Support

For technical support, updates, and additional information:

Website: ravegeneration.io

Email: support@ravegeneration.io

© 2026 Rave Generation. All rights reserved.

All product names, trademarks and registered trademarks are the property of their respective owners. Names are used for identification purposes only and do not imply any affiliation with or endorsement by the trademark holders.