Rave Generation

presents



Quadrabank

User Manual

1. Overview

Quadrabank is a recreation of the Quadrafuzz from Steinberg's Cubase SX and Nuendo. It splits your signal into four frequency bands and distorts each band on its own, so low and high notes do not smear into each other the way they do in a single distortion. Each band has its own drive into the distortion and its own level after it; the bands are then added back together.

Three controls are new: AMOUNT blends the distortion with the clean bands, SOFTCLIP keeps the output under 0 dBFS, and the CLIP light shows when the output goes over it. At their defaults the plugin produces the same output as the original.

2. Signal Flow & Panel

INPUT → GAIN → BAND SPLIT → DRIVE → SHAPE → BAND LEVEL → SUM → OUTPUT → SOFTCLIP

GAIN drives all four bands at once; each band's DRIVE then sets how hard that band goes into the distortion curve chosen with SHAPE. The band knobs, LOW, LOW MID, HIGH MID and HIGH, set each band's level after its distortion. AMOUNT mixes each band's distortion with the same band played clean.

The plugin adds no delay.

BANDS

Parameter	Range	Description
LOW, LOW MID, HIGH MID, HIGH	-12 to +12 dB	Each band's level after its distortion. Default 0 dB.

FREQUENCY DISPLAY

Parameter	Range	Description
DRIVE	-20 to +20 dB	Drag the diamond in the middle of a band up or down. How hard the band is driven into its distortion curve. Default 0 dB.
EDGE	25 Hz to 22 kHz	Drag a diamond on the floor sideways. The inner edges move the split between two bands; the outer two set where the lowest band starts and the highest band ends. Defaults 25 Hz, 136 Hz, 742 Hz, 4046 Hz and 22050 Hz.
SOLO	Off, On	Plays only the selected band and lights it in the display. Default Off.

Click a band to select it. The strip at the top shows the value of the handle under the mouse.

SHAPE

Parameter	Range	Description
SHAPE	1 to 5	The distortion curve, the same for all four bands. 1 is the gentlest, 5 the hardest. Default 1.

GAIN, AMOUNT AND OUTPUT

Parameter	Range	Description
GAIN	-20 to +20 dB	Level into all four bands: more GAIN drives every band harder. Default 0 dB.
AMOUNT	0 to 100%	How much distortion you hear in each band. At 0% the bands play clean at their knob levels, and GAIN, DRIVE and SHAPE do nothing. Default 100%.
OUTPUT	-20 to +20 dB	Level after the four bands are added together. Default 0 dB.
SOFTCLIP	Off, On	Rounds off peaks after OUTPUT, so the signal never goes above 0 dBFS. A clean signal comes out 1.4 dB lower. Default Off.
OVER	Light	Lights when a band is driven past the end of its curve, where it clips flat.
CLIP	Light	Lights when the output goes over 0 dBFS. With SOFTCLIP on it stays dark.

Knobs

Hold Shift while dragging a knob for fine adjustment. Right-click a knob to return it to its default (Alt+click works too, Option+click on macOS); double-click it to type a value.

Hints

Hover over a control to read what it does in the bar at the bottom of the window. The (i) icon at the top right turns the hints on and off.

Menu Bar

Undo and Redo; the panel's opacity, 0% to 100%, to see the DAW behind it; the interface size, 70% to 200%; and the preset menu, which browses, loads and saves presets and copies and pastes them between instances.

Support

For technical support, updates, and additional information:

Website: ravegeneration.io

Email: support@ravegeneration.io

© 2026 Rave Generation. All rights reserved.

All product names, trademarks and registered trademarks are the property of their respective owners. Names are used for identification purposes only and do not imply any affiliation with or endorsement by the trademark holders.