Vocal To Choir

User Manual

AI Choir Generator



Turn a sung vocal into a choir with your words and timing.

In this manual

Getting started 2

Capture and choir settings 3

Rendering and using your choir 4

1 Overview

Vocal To Choir turns a sung vocal into a choir. You choose the lines the choir sings (the melody itself, an octave up or down, a third or a fifth above or below), how many singers sing each line and how they sing. The choir sings your words with your timing.

It runs as an effect on the vocal track. It listens while the song plays, or you load a WAV file, and renders the choir on your computer. Every line becomes its own audio file that you drag into your song.

2 Requirements

Windows 10 or 11 (64-bit), or a Mac with Apple silicon (M1 or later) and macOS 14 or later.

The engine. Vocal To Choir needs its Engine folder (about 1 GB) in Documents\Rave Generation\Vocal To Choir. On a Mac, run **Install Vocal To Choir Engine** once to put it there. If it is missing, the status display says where it belongs.

A graphics card. Rendering is fastest on a graphics card that supports DirectX 12, of any brand; built-in graphics work too. Without one, Vocal To Choir renders on the processor, which takes several times longer. On a Mac it uses the Mac's own graphics and Neural Engine. It picks the fastest option by itself.

3 Quick Start

1 Insert the effect

Insert Vocal To Choir as an effect on your vocal track.

2 Capture your vocal

Press **LISTEN** and play the part you want the choir on. Press **LISTEN** again when the part is over.

3 Create the choir

Press **CREATE**. The status display shows the progress.

4 Preview the result

When it reads Done, the choir plays along with the song (**PREVIEW**).

5 Add the audio to your song

Drag **ALL**, or a single line, from **DRAG INTO YOUR SONG** onto a track, at the very start of the song.

4 The Panel

Capture

LISTEN records the vocal while the song plays, together with where it is in the song; up to 9 minutes. Only what you play is used. **LOAD** opens a WAV file instead, or drop a WAV on the display. The display shows what was captured and the key it heard.

Settings

Setting	Choices	Description
KEY	Auto, C to B	Auto finds the key in the vocal. When two keys fit the notes equally, the display names both. Pick the key by hand if harmonies land on wrong notes.
SCALE	Major, Minor	Major or minor, for a key you pick.
STYLE	6 styles	How the singers sing (section 5).
VOICES / LINE	2, 3, 4, 6	Singers per line, each a different voice. More voices make a bigger choir and take longer to render.
QUALITY	Draft, Normal, High	Draft renders faster. High takes about twice as long as Normal.
LEVEL	-24 to +12 dB	Preview volume. The files keep their own level.

Lines

Every line that is on becomes its own file. **UNISON** and **OCT DOWN** are on at first: they fit any key.

Line	Sings
OCT UP	the melody an octave higher
UNISON	the melody
OCT DOWN	the melody an octave lower
3RD UP, 5TH UP	a third or a fifth above the melody, in the key
3RD DOWN, 5TH DOWN	a third or a fifth below the melody, in the key

Sound

These knobs work on the finished choir. After a render, a change to **WIDTH**, **ROOM**, **LOW CUT** or **BRIGHTNESS** takes about a second: press **CREATE** again. A change to **TIMING** renders the choir again.

Knob	Range	Description
TIMING	0 to 150 ms	How loosely the singers come in, phrase by phrase. At 0 every singer keeps one timing all the way through. Default: 40 ms.
WIDTH	0 to 100 %	Where the singers stand. 100 = every singer fully left or right, with different singers on each side; 0 = all in the middle. Default: 100 %.
ROOM	0 to 100 %	A room around the choir. 0 = dry. The files get 2 s extra for the room to fade out. Default: 35 %.
LOW CUT	20 to 400 Hz	Removes the low end below this frequency. 20 Hz = off, the default.
BRIGHTNESS	0 to 10 dB	Lifts the highs above 6 kHz. 0 dB = off, the default.

Rendering and using your choir

Render

CREATE renders every line that is on; its LED lights while it works. Press it again to cancel. Change a setting after a render and the status reads **Settings changed: press CREATE to hear it.**

Preview

PREVIEW plays the choir under your vocal, at its place in the song. It works for a **LISTEN** take; for a loaded WAV, drag the files in.

Drag into your song

ALL is the whole choir, the other tiles one line each. A tile lights up when its file is ready; drag it onto a track.

Files from a **LISTEN** take start at the beginning of the song, so drop them at 0:00 and they line up with your vocal. Files from a loaded WAV start where the WAV starts: drop them where that vocal clip starts.

Every render is also saved in Documents\Rave Generation\Vocal To Choir\Renders, one folder per render.

Hints

Hover over a control to read what it does in the bar at the bottom of the window. The (i) icon at the top right turns the hints on and off.

5 Styles

Style	How the singers sing
Normal	plain and steady
Pop/Gospel	belted, full voice
Soft/Airy/Breathy	breathy
Classical	with vibrato
Soft/Quiet	softly
Loud	loudly, with power

6 Tips

Use a dry, solo vocal: reverb, doubles or backing vocals in the source end up in every voice.

Support

For technical support, updates, and additional information:

ravegeneration.io | support@ravegeneration.io

© 2026 Rave Generation. All rights reserved.