EEE3535-02 Fall 2024

Assignment 2: System Call and Process

Due: Sunday, Oct. 13, 2024, 11:59PM

1 Introduction

- The objective of this assignment is to add a new system call to xv6-riscv that probes processes and prints their information, including process ID, execution state, runtime, number of open files, and program name.
- In the Linux terminal, the ps command prints the information of active processes, including process ID, controlling terminal, CPU time, and command name. You may append options to print more detailed process information, such as ps -af.

- While the ps program in Linux uses a file to record and read process states, we will use a system call in xv6-riscv to implement similar functionality.
- This assignment mainly consists of two parts: implementing i) the ps user program and iii) the new pstate syscall in the kernel.
- The following shows the expected output of the ps program in xv6-riscv. It prints the process ID (PID), parent process ID (PPID), execution state, elapsed runtime, number of open files, and program name of active processes. More explanations will be provided in the next section.

```
$ ps
PID
        PPID
                State
                         Runtime
                                     OFiles Name
                                     3
1
        Ω
                S
                         0:0.7
                                              init
2
                S
                         0:0.5
                                     3
                                              sh
        1
3
                Χ
                         0:0.0
                                     3
                                              ps
```

2 Implementation

• To begin the assignment, go to the xv6-riscv/ directory, download syscall.sh, and run the script to update xv6-riscv.

```
$ cd xv6-riscv/
$ wget https://casl.yonsei.ac.kr/teaching/eee3535/syscall.sh
$ chmod +x syscall.sh
$ ./syscall.sh
```

• Once the update is done, you can run the new user program called ps. Since the program is largely empty in the skeleton code, nothing will be printed.

```
$ make qemu

...

qemu-system-riscv64 -machine virt -bios none -kernel kernel/kernel -m 128M -smp 1
-nographic -global virtio-mmio.force-legacy=false -drive file=fs.img,if=none,
format=raw,id=x0 -device virtio-blk-device,drive=x0,bus=virtio-mmio-bus.0

EEE3535 Operating Systems: booting xv6-riscv kernel
```

```
EEE3535 Operating Systems: starting sh \$ ps \$
```

• The following shows the skeleton code of user/ps.c.

```
#include "kernel/types.h"
#include "kernel/stat.h"
#include "user/user.h"
// A xv6-riscv syscall can take up to six arguments.
#define max_args 6
// Print a help message.
void print_help(int argc, char **argv) {
  fprintf(2, "%s <options: pid or S/R/X/Z>%s\n",
             argv[0], argc > 7 ? ": too many args" : "");
int main(int argc, char **argv) {
  // Print a help message.
  if(argc > 7) { print_help(argc, argv); exit(1); }
  // Argument vector
  int args[max_args];
 memset(args, 0, max_args * sizeof(int));
  /★ Assignment 2: System Call and Process
     Convert the char inputs of argv[] to integers in args[].
     In this skeleton code, args[] is initialized to zeros,
     so technically no arguments are passed to the pstate() syscall. \star/
  // Call the pstate() syscall.
  int ret = pstate(args[0], args[1], args[2], args[3], args[4], args[5]);
  if(ret) { fprintf(2, "pstate failed\n"); exit(1); }
  exit(0);
```

- Near the end of main(), pstate() is the new system call you will have to implement for this assignment.
- The syscall is defined as int pstate(int, ...) in user/user.h, which can take one or more int arguments. xv6-riscv allows passing up to six arguments to a system call.
- The basics of pstate() are already added to various files in kernel/ and user/ directories, so you do not need to worry about how to enable the new syscall; it is already enabled but does nothing at this moment.
- If you are not familiar with main() taking inputs, have a look at the example below to understand what int argc and char **argv are about. This code example has nothing to do with xv6-riscv.

```
/* arg.c */
include <stdio.h>
int main(int argc, char **argv) {
  printf("argc = %d\n", argc);
  for(unsigned i = 0; i < argc; i++) {
    printf("argv[%u] = %s\n", i, argv[i]);
  }
  return 0;
}</pre>
```

• Compiling and executing the arg.c code gives the following output. The result shows that int argc is the number of arguments in the run command, and char **argv is the array of char pointers, each pointing to a character string.

```
$ gcc -o arg arg.c
$ ./arg input1 input2 input3
argc = 4
argv[0] = ./arg
argv[1] = input1
argv[2] = input2
argv[3] = input3
```

- We will later revisit ps.c to discuss what needs to be passed to the input argument of pstate().
- Where are the system calls, and how are they implemented in xv6-riscv?
- Since several basic system calls, such as getpid(), are already implemented in xv6-riscv, find the getpid-related codes in the kernel/directory.

```
$ grep -n getpid *
syscall.c:93:extern uint64 sys_getpid(void);
syscall.c:118:[SYS_getpid] sys_getpid,
syscall.h:12:#define SYS_getpid 11
sysproc.c:19:sys_getpid(void)
```

- Open the syscall.h, syscall.c, and sysproc.c files to learn how getpid() is implemented. You can also find pstate-related lines near getpid in these files.
- Since process ID is a part of the information that the new pstate() syscall has to collect, take a look at how getpid() retrieves it.
- A process ID is stored in a process control block (PCB), which is defined as struct proc at the end of proc.h. The struct has int pid to save the process ID. The getpid() syscall simply reads its value.
- Who sets the process ID? Presumably, it is set when a process is created.
- Process creation occurs in the allocproc() function of proc.c. In the function, p->pid = allocpid() assigns an ID to a new process.
- You just learned that a process is created in allocproc(). This must be a good place to record the start time of the new process because pstate() needs to print the elapsed runtime of the process.
- In this assignment, the elapsed runtime will be measured simply as the time difference between the process creation and the pstate() call.
- How can we get the time information in xv6-riscv?
- It is impossible to get the exact time, but an approximate value can be obtained by reading ticks, which is defined in defs.h and globally available in the kernel.
- This variable is incremented every 100ms after xv6-riscv is booted up. For instance, ticks == 7 means that the current time is about 0.7 seconds since the kernel launch. Using ticks, you can trace the elapsed runtime of a process at 100ms granularity.
- When printing the runtime, display it in the format of 1:23.4, meaning 1 minute and 23.4 seconds have passed since the process was created.
- The PCB also contains enum procstate state, struct proc *parent, struct file *ofile[NOFILE], and char name[16], indicating the process state (e.g., RUNNABLE, SLEEPING), pointer to the parent process, pointer to open files, and program name (e.g., sh, grep), respectively.

- Process states are defined as enum procstate {UNUSED, USED, SLEEPING, RUNNABLE, RUNNING, ZOMBIE} right above struct procin proc.h.
 - UNUSED: If a process state is UNUSED, this does not represent a valid process. xv6-riscv creates a process list simply as a static array defined as struct proc proc[NPROC] in proc.c, where NPROC is 64. It means that xv6-riscv can have only up to 64 processes at a time. UNUSED is to indicate an entry in the proc[] array that is currently not in use.
 - USED: When a process is newly created, its state is initially set to USED. Then, the state is soon changed to
 RUNNABLE. It is technically impossible to observe a process in a USED state, so the pstate() syscall will
 not trace which processes are in USED states.
 - SLEEPING: If a process is SLEEPING, it is blocked until some conditions are met to resume its execution.
 - RUNNABLE: This state indicates that a process is runnable and waiting for a job scheduler to give it a chance to use the CPU.
 - RUNNING: A process is running. Since xv6-riscv in this assignment is configured to use a single CPU, the only running process when pstate() is called must be the ps program itself.
 - ZOMBIE: Lastly, this state indicates that a process is done and being terminated. A process finishes its
 execution by calling the exit() syscall, and it finally gets deallocated via freeproc() in proc.c. The
 ZOMBIE state is very short but observable.
- In the PCB (i.e., struct procin kernel/proc.h), struct file *ofile[NOFILE] is an array of pointers to open files. NOFILE is the maximum number of files that a process can have. By counting the number of non-zero pointers in the array, you can find the number of open files for each process.
- It is tedious for pstate() to simply print the information of all active processes. So, let us go back to user/ps.c and add some options to the program.
- A ps command may be associated with options to print the information of processes only in certain states.
- For instance, ps S prints the information of processes in **S**LEEPING states only. Similarly, R, X, and Z options are for **R**UNNABLE, RUNNING (EXECUTING), and **Z**OMBIE states, respectively.
- You can also set multiple states, such as ps S R, to display processes in either SLEEPING or RUNNABLE states. The following shows a few examples with state options.

| \$ ps X | | | | | |
|---------|------|-------|---------|--------|------|
| PID | PPID | State | Runtime | OFiles | Name |
| 4 | 2 | X | 0:0.1 | 3 | ps |
| | | | | | |
| \$ ps S | | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:6.7 | 3 | init |
| 2 | 1 | S | 0:6.5 | 3 | sh |
| | | | | | |
| \$ ps S | X | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:9.5 | 3 | init |
| 2 | 1 | S | 0:9.3 | 3 | sh |
| 6 | 2 | X | 0:0.0 | 3 | ps |
| | | | | | |

- Another option is to specify process IDs to print. For instance, ps 1 only prints the process whose pid is 1. You may also specify multiple process IDs, such as ps 1 2 or ps 5 1 2. If a specified process ID is invalid, ps simply ignores it.
- The following shows a few examples with specified process IDs.

| \$ ps 1 PID 1 | PPID 0 | State S | Runtime 0:12.1 | OFiles | Name init |
|---------------------|-----------|------------|----------------|--------|--------------|
| \$ ps 8 | 2 | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 2 | 1 | S | 0:14.8 | 3 | sh |
| 8 | 2 | X | 0:0.1 | 3 | ps |
| \$ ps 9 | 1 3 | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:19.4 | 3 | init |
| 9 | 2 | X | 0:0.0 | 3 | ps |
| | | | | | |

• How about using a combination of both state and process ID options? Let the ps program print processes that satisfy any conditions. For instance, ps X 2 prints the information of processes that are either in a RUNNING state or have the process ID of 2. It is also possible that no processes meet the specified conditions.

| \$ ps X | 2 | | | | |
|---------|------|-------|---------|--------|------|
| PID | PPID | State | Runtime | OFiles | Name |
| 2 | 1 | S | 0:25.8 | 3 | sh |
| 10 | 2 | X | 0:0.0 | 3 | ps |
| | | | | | _ |
| \$ ps S | Z 11 | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:29.6 | 3 | init |
| 2 | 1 | S | 0:29.5 | 3 | sh |
| 11 | 2 | X | 0:0.0 | 3 | ps |
| | | | | | |
| \$ ps Z | R 3 | | | | |
| PID | PPID | State | Runtime | OFiles | Name |

- By allowing the ps program to take multiple state and/or process ID options in a run command, you must be able to pass them to the pstate() syscall.
- The pstate() syscall is defined as int pstate(int, ...) in user/user.h, which takes one or more integers as input arguments. xv6-riscv supports passing up to six arguments to a syscall, and the case of having more than six arguments is already screened in user/ps.c.
- Suppose a run command is ps R X 15 2, which should print the information of processes in either the RUNNABLE or RUNNING states or having pid of 15 or 2.
- argc of main() in this case should be 5, where argv[0] = ps, argv[1] = R, argv[2] = X, argv[3] = 15, and argv[4] = 2. Since 15 and 2 are characters, you should convert them to integers using atoi() defined in user/ulib.c.
- How should you handle the state options of R and X, which are not integers? Since the number of process states is finite (i.e., only four states of S, R, X, Z), a possible solution is to encode them into negative integers. Process IDs are always positive integers, so encoding the process states into negative numbers will not conflict with process IDs. Use your own encoding method to translate the process states into integers.
- Then, the input arguments of pstate() can have three cases. If an argument is a positive number, it is a process ID. A negative number means a process state. If an argument is zero, it indicates the end of the options, similar to the null-terminated argv[] array of an execvp() call.
- Make the ps program in user/ps.c also do basic error checking for input arguments to screen invalid options, such as ps A -5 # 1+2; A is not a valid state option, -5 is not a valid process ID, # and + are invalid characters.
- For an invalid run command, call print_help() to display the help message and then exit as follows.

```
ps A -5 # 1+2
ps <options: pid or S/R/X/Z>
```

- The invocation of pstate() in the skeleton code is over-specified with six arguments regardless of whether there are actually six options.
- Calling the pstate() syscall traps into usertrap() in kernel/trap.c via a trampoline routine in kernel/trampoline.S. After looking up the trap table via syscall() in kernel/syscall.c, it will reach the uint64 sys_pstate(void) function at the bottom of kernel/sysproc.c.
- The input arguments of the pstate() sycall can be retrieved by using argint(), which reads RISC-V function argument registers from a0 (or x10) to a5 (or x15). Take a look at other syscalls taking several input arguments as a reference. argint() is defined in kernel/syscall.c.
- While sequentially reading CPU registers from a0 to a5, encountering a zero value indicates that there are no more arguments passed to the pstate() syscall. Otherwise, the sixth argument should be the last one.
- Once all the input arguments are retrieved in sys_pstate(), the syscall should search the process list (i.e., struct proc proc[NPROC]) to find if there are any matching processes.
- Print out a header line and the information of the matching processes.
- If the syscall is done without errors, return 0. Otherwise, a non-zero return value will indicate an error.

3 Validation

- When printing the result of ps, follow the formatting rules.
 - 1. **Header**: The first line must be a header in the format of PID PPID State Runtime Name. Separate each column by a single tab in the header and process information rows.
 - 2. **State**: A process state must be printed as a single uppercase character; S for SLEEPING, R for RUNNABLE, X for RUNNING, and Z for ZOMBIE states. Do not use other expressions.
 - 3. **Runtime**: The time must be printed in the 1:23.4 format as explained earlier.
- After launching xv6-riscv, execute the usertests program in the background with an & symbol at the end of the command.
- usertests will run for several minutes and create thousands of processes. However, you will see only a handful of them at each ps invocation. Concurrent execution of multiple processes (e.g., sh, usertests, ps) may mess up the ordering of printf results, but this is normal and expected.
- Your assignment will be graded based on the following five cases, but they are not the exact and only ones that will be on the test. Your code should be able to handle other similar common-sense situations.

Simple ps command: \$ usertests&

```
usertests starting
. . .
$ ps
PID
        PPID
                State
                         Runtime
                                      OFiles Name
1
        0
                S
                         0:3.8
                                      3
                                              init
2
        1
                S
                         0:3.7
                                      3
                                              sh
5
        4
                R
                         0:1.9
                                     4
                                              usertests
4
        1
                S
                         0:1.9
                                      4
                                              usertests
6
        2
                Χ
                         0:0.7
                                      3
                                              ps
```

2. ps with state options:

| \$ ps X R | | | | | |
|--------------|-----------|-------------|---------------------------|-------------|-------------------------|
| PID | PPID | State | Runtime | OFiles | Name |
| 36 | 4 | R | 0:2.2 | 3 | usertests |
| 59 | 36 | R | 0:0.1 | 3 | usertests |
| 56 | 2 | X | 0:0.3 | 3 | ps |
| | | | | | |
| \$ ps F | R S X Z | | | | |
| | | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| PID 1 | PPID O | State S | Runtime 0:26.1 | OFiles 3 | Name init |
| | | | | | |
| 1 | | S | 0:26.1 | 3 | init |
| 1 2 | 0 | S S | 0:26.1 0:26.0 | 3 | init sh |
| 1 2 36 | 0 | S S R | 0:26.1 0:26.0 0:7.2 | 3 3 3 | init sh usertests |

3. ps with process ID options:

| \$ ps : | 1 | | | | |
|---------|---------|-------|---------|--------|-----------|
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:31.2 | 3 | init |
| | | | | | |
| \$ ps 4 | 4 1 2 3 | | | | |
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | S | 0:32.8 | 3 | init |
| 2 | 1 | S | 0:32.7 | 3 | sh |
| 4 | 1 | S | 0:30.9 | 3 | usertests |

4. ps with mixed state and process ID options:

| \$ ps S | 1 2 R | | | | |
|---------|-------|-------|---------|--------|-----------|
| PID | PPID | State | Runtime | OFiles | Name |
| 1 | 0 | R | 0:43.2 | 3 | init |
| 2 | 1 | S | 0:43.1 | 3 | sh |
| 3047 | 4 | S | 0:3.2 | 3 | usertests |
| 4 | 1 | S | 0:39.5 | 3 | usertests |

5. ps with invalid options:

```
$ ps -5 A
ps <options: pid or S/R/X/Z>
$ ps 1+5 R S Z
ps <options: pid or S/R/X/Z>
```

4 Submission

• In the xv6-riscv/ directory, run the tar.sh script to create a tar file named after your student ID (e.g., 2024143535).

```
$ ./tar.sh
$ ls
2024143535.tar kernel LICENSE Makefile mkfs README tar.sh user
```

• Upload this tar file (e.g., 2024143535.tar) on LearnUs. Do not rename the file.

5 Grading Rules

• The following is the general guideline for grading. A 30-point scale will be used for this assignment. The minimum score is zero, and negative scores will not be given. Grading rules are subject to change; a grader may add extra rules without notice for the fair evaluation of students' efforts.

- -5 points: The tar file includes extra tags such as a student name, hw2, etc.
- **-5 points:** The code has insufficient comments. Comments in the skeleton code do not count. You must clearly explain what each part of your code does.
- **-6 points each:** The validation section has five test cases. Each failed test will lose 6 points.
- **-30 points:** No or late submission.

Final grade = F: The submitted tar file is copied from someone else. All students involved in the incidents will get "F" for the final grade.

- Your teaching assistant (TA) will grade your assignments. If you think your assignment score is incorrect, discuss your concerns with the TA. Always be courteous when contacting the TA. If no agreement is reached between you and the TA, escalate the case to the instructor to review your assignment. Refer to the course website for the contact information of the TA and the instructor: https://casl.yonsei.ac.kr/eee3535
- Arguing for partial credits for no valid reasons will be considered as a cheating attempt and lose the assignment score.