


Multimedia Systems

Assistant professor Daniel Hofman, PhD

Associate professor Josip Knezović, PhD



MPEG coder





Types of redundance

- Spatial redundancy
 - Natural visual data (images) correlation among neighbouring elements
- Temporal redundancy
 - Moving objects in adjacent visual images (frames)
 - Stationary scene
- Movements:
 - Magnifications/reductions (zoom)
 - Rotations
 - Translations



Intra and inter-block compression

- Intra-block compression
 - Removal of high frequency information that the human eye cannot recognize
 - Same as image compression (JPEG) as explained beforehand
- Inter-block compression
 - Reducing temporal redundancy
- Basis: Characteristics of the human visual system (HVS)



Interblock compression

- Often, individual parts of the image within a string change very little or are even unchanged
- Picture background often doesn't change



- There's not much change between adjacent sequence images
 - parts of the image are repeated temporal redundancy
- Changing parts can be analysed as movements describing changes

Temporal redundancy





Temporal redundancy (2)

Department of Control and Computer Engineering





Temporal redundancy (3)





Estimation and compensation of movements

- Motion Estimation (ME):
 - Extract parts of a picture (motion segmentation)
 - Describing movements (estimate)
 - Running in encoder
- Motion Compensation (MC):
 - Use motion estimation results
 - Running in a decoder




Estimation and compensation of movements (2)

- Implementation:
 - Block: Segmentation into rectangular parts of pre-set dimensions (block-based motion estimation)
 - Each movement is translational (movement) vector)



Estimation and compensation of movements (3)

- Motion estimation algorithms for each block calculate the corresponding movement vector
- The vector shows the source of the block in the previous image before moving to the position in the current image






Estimation and compensation of movements (4)





Motion estimation

 For more efficient processing to assess movements, component Y is sufficient





Distance criterion

- The measure of similarity between the two blocks is the distance criterion
- Motion estimation is reduced to optimising the distance criterion as a criterion function
- Algorithms in a defined search area seek to find the minimum criterion function
 - Change of the picture in this location is the smallest
 - Movement of the reference block along the motion vector



Distance criterion (2)

- Some possible distance criterion of two blocks:
 - Mean Squared Error (MSE) computationally demanding

$$MSE(x, y; d_x, d_y) = \frac{1}{MN} \sum_{i=0}^{M-1} \sum_{j=0}^{N-1} \left[Y(x+i, y+j, t_1) - Y(x+d_x+i, y+d_y+j, t_0) \right]^2$$

Mean Absolute Deviation (MAD) – widely accepted

$$MAD(x, y; d_x, d_y) = \frac{1}{MN} \sum_{i=0}^{M-1} \sum_{j=0}^{N-1} |Y(x+i, y+j, t_1) - Y(x+d_x+i, y+d_y+j, t_0)|$$

Number of matching picture elements (MPC)

$$MPC(x, y; d_x, d_y) = \frac{1}{MN} \sum_{i=0}^{M-1} \sum_{j=0}^{N-1} T[Y(x+i, y+j, t_1), Y(x+d_x+i, y+d_y+j, t_0)]$$



Motion estimation algorithms

- Depending on the search method, we distinguish between:
 - Full Search Algorithm
 - searches all points within the search area
 - computationally very demanding
 - gives the best possible result
 - Incomplete (fast, advanced) algorithms
 - The search area can be:
 - unalterable
 - adaptable




Full Search Algorithm

- Very demanding algorithm for computer resources:
 - Calculation of one Mean Absolute Deviation (MAD):
 - Data retrieval (very demanding)
 - For block 16x16: 256 subtractions + 1 offset (dividing by 256)
 - If the offset area is +-8 in both dimensions:
 - (2*8+1)*(2*8+1)*(256+retreival)=73984 + retrievals
 - Finding the minimum
 - For one picture 1280x1024
 - 5120*73984=378 798 080 + retrievals
 - For 30 pictures per second: 1,1*1010 additions/s



Full Search Algorithm (2)

Department of Control and Computer Engineering





Full Search Algorithm (3)

- Optimal result but unfortunately in practice difficult to apply
- It is used mainly only by circuitry designs of the algorithm
- The need for fast algorithms
 - Benefits: less operations necessary
 - Disadvantages: larger differences to be encoded and thus the output amount of data is higher (lower degree of compression)
 - The quality of some algorithms is satisfactory and close to full searchalgorithm
 - Problems with movement types (explained later)




Fast algorithms

- Fast, advanced search algorithms direct search depending on the value of the distance criterion
- Some examples:
 - Logarithmic Search (LOG)
 - Three-step search (3SS)
 - Orthogonal search (ORT)
 - Block-based gradient descent algorithm (BBGDS)




Three-step search (3SS)



- 0. N = 3
- Compute SAE(0,0)
- 2. Set $S=2^{(N-1)}$ (step size)
- 3. Compute SAE on 2^N locs
- 4. Select loc with min SAE
- 5. Set S=S/2
- 6. Repeat [3:5] until S=1
- Each step 9 points for calculations
- Number of points: 9+8+8 = 25 (FS: 15*15 = 225)




Orthogonal search (ORT)



- 0. S = Step size (d/2 = 8/2)= 4
- 1. Compute SAE on 2 horizontal loc displaced S from origin
- 2. Select new origin
- 3. Repeat [1:2] vertically
- 4. Select loc with min SAE
- 5. Set S=S/2
- 6. Repeat [1:5] until S=1

Number of points: 3 + 2 + 2 + 2 + 2 = 13

Logarithmic Search (LOG)



- 0. Step size = S(d/2) = 4
- 1. Search (0,0)
- 2. Search 4 loc S pixels away (horiz and vert.)
- 3. New origin = best match (BM)
- 4. If BM is in center: S = S/2
- 5. If S=1: goto 6, else 2
- 6. Search 8 loc arround BM and select BM

Number of searches: Depends on data




BBGDS algorithm (Gradient Descent Search)

•Centered search pattern with 9 dots with

S=1 search step

•Number of searches not defined ⁶


- •Fnd of Search:
 - BM is in the center.
 - Window Edge
- •Good for small movements





Distribution of movement vectors

- The view indicates evenly distributed movement vectors between two sequence images
- Vectors are mostly short centered vector distribution - typical for real-life sequences






Distribution of movement vectors (2)

 Counting vectors for all possible component pairs (x,y) throughout the sequence gives relative vector frequencies

The efficiency of the algorithm can be increased if the observed centered probability distribution of vectors is taken into account, more attention should be paid to the center of the search area





Examples of algorithm comparison

- Parameters that determine the effectiveness of the algorithm:
 - the overall measure of disruption (distance criterium) after the movement assessment should be as small as possible (better compression)
 - the total number of test points should also be as low as possible (higher speed)
- We need an compromise between compression
 ⇔ speed
- Example of three sequences containing different types of movements:
 - "City View" evenly arranged and small movement
 - "Car Jump" located and high movement
 - "Troops" uniformly arranged and large movement



Comparison of search algorithms

- <u>City view sequence</u> uniformly arranged small movements (throughout the frame)
- Car jump sequence located and large movements (movements localized in part of the frame)
- Troops sequence evenly distributed and large movements (all over the frame)

Implementation - Example

 The compression standard does not specify movement assessment procedures


 The quality of the application depends significantly on how the movement is assessed



Results (1)

Department of Control and Computer Engineering

• "City View" sequence - number of test points:




- Centered Distribution: BBGDS Best
- ORT and 3SS constant and relatively large number of test points



Results (2)

Department of Control and Computer Engineering

• "Car Jump" sequence - number of test points:




- Localized growing change: BBGDS and LOG produce underperformance as the disorder grows
- ORT better than 3SS, constant despite disruption



Results (3)

Department of Control and Computer Engineering

• "Troops" sequence - number of test points:



- Many complex movements: BBGDS bad for higher average displacement vector length
- LOG very good according to both criteria



Results (4)

- The effectiveness of a particular algorithm depends on the type of movement contained
- An effective procedure will heuristically select the most suitable algorithm based on the type of movement: adaptive algorithms



Performance

- With this, we briefly analyzed some of the most demanding algorithms when processing and compressing multimedia data
- We also saw the principle complexity of calculation without going into too much detail

 The question arises as to how to effectively perform such algorithms




Optimizations

- Let's remind ourselves from the last lecture to some core optimization groups
 - Reduce calculation accuracy
 - Development of equivalent mathematical algorithms with less complexity
 - Change the program's development environment
 - Change the program's performance environment
 - Change the system architecture on which the algorithms are run



Basic ways to SW support for MM





Performance


 You must be aware that a program written in Java or e.g. C# is running more slowly than programs that have been translated into target processor code

 Additionally: higher programming languages generate slower code than the one written in combination with the assembler



Comparison Java, C#, C++


Department of Control and Computer Engineering



Department of Control and Computer Engineering



MM Basic CPU Support Modes



Standard CPU


- If we recall computer architecture then we know that ordinary processors can perform one ALU operation per period
- The operation is the width of the ALU

 In order to speed up performance, we need to pay a lot of attention to data retrieval and loop optimizations



Standard CPU - Memory System

- Memory Hierarchy
- Cache smallest and fastest
- If the program access pattern corresponds to the heuristics of the cache access assembly: high speed
- If not: extremely slow!





Standard CPU - Memory System (2)


- Let's consider multiplying the matrix:
 Multiplication of the matrix
- \bullet A = B x C
- Matrix B: Row Access
- Master C: Column Access

```
for(int i = 0; I < x; i++)
  for(int j = 0; j < y; j++)
    for(k=0; k < z; k++)
        A[i][j] += B[i][k] * C[k][j];</pre>
```



Standard CPU - Memory System (3)

- Sequential retrieves from cache memory are more efficient
- Example: x86 retrieval from cache memory reads 8 bytes (latency) 1 cvcle!!!)
- Access to matrix C does not match the organization of the cache
- Possible solution: Transpose matrix C, matrix multiplication loop will be much more effective





Memory system

```
#define READ(A, x, y, d) A[(x)*(d)+(y)]
   A = (double *) malloc(sizeof(double) *x*v);
   B = (double *)malloc(sizeof(double)*x*z);
   C = (double *)malloc(sizeof(double)*v*z);
   Cx = (double *) malloc(sizeof(double)*v*z);
   for (i = 0; i < v; i++)
     for (k=0; k < z; k++)
       READ(Cx,i,k,z) = READ(C,k,i,v);
   for (i = 0; i < x; i++)
     for (i = 0; i < v; i++)
       for (k=0: k < z: k++)
         READ(A, i, j, y) += READ(B, i, k, z)*READ(Cx, j, k, z);
```

Acceleration approx. 3.5x



Standard CPU

- Performance-oriented libraries:
 - BLAS: Manually optimized library for basic vector and matrix operations (C/assembler)
 - http://www.netlib.org/blas/
 - Intel MKL: Math Kernel Library
 - Library of optimized mathematical functions for x86
 - BLAS, LAPACK, FFT, ...
 - Intel IPP: Integrated Performance Primitives
 - Optimized function library for signal processing, encoding, compression, multimedia
 - Optimized for individual architectures and their MM extension instructions (SSEx)



Standard CPU (2)

- For DSP operations (e.g. DCT), it is extremely useful if the processor has multiplication implemented in hardware and a related command
 - MUL
- Additional significant advantage if there is a multiplying command with addition
 - MLA
 - In examples of calculating DCT, DFT and similar we have most of the "butterfly" operations in which MLA is the basic link




SIMD Support

- SIMD (Single Instruction Multiple Data)
 - Cpu data path architecture that allows multiple data to be processed (less precision in principle) with a single command
 - Basic idea:
 - If we have e.g. 64 bit ALU then it is completely inefficient to process 8 bit data with it
 - Reorganise the ALU in such a way that the work on 8 bit data can be "divided" into multiple ALU



ALU – ordinary and SIMD





MM Extensions

 This (basic) principle serves to significantly speed up the processing of multimedia algorithms

- Examples:
 - Old: VIS, PA-RISC
 - Not so old: MMX, 3DNow!
 - New: SSE4 (Streaming SIMD Extensions 4)





Example - MMX

- Put on the market in 1996 (Pentium with MMX and Pentium II)
- New data type introduced: Packed 64 bit
- Why 64 bits?
 - satisfactory acceleration
 - does not need major interventions on architecture



Example - MMX Data Types






Department of Control and Computer Engineering

- 57 new MMX instructions
- Arithmetic, logical, comparison, ...
- With saturation (signed and unsigned), no saturation
- All instructions except MOVE work on MMX registries
- All instructions work on 16 bit data and only some on 8 and 32 bit
- Disadvantage: Overlap with FP instructions



MMX instructions - Saturation

- Wrap-aroud or saturate
- Extremely useful with MM algorithms





MMX instructions


- The standard function for TV applications is to overlap two images
- It is realized by putting a predefined background on the speaker that the computer replaces with another image
- By regularly calculating very slowly






MMX - Picture Overlay








Phase 2




A and (Complement of Mask)

C and Mask

00000000 11111111	00000000 1111	1111 11111111	00000000	11111111	00000000







SSE – Streaming SIMD Extensions

- Presented in 1999 with Pentium III
- MMX's most important flaws fixed
- 8 brand new 128 bit registers XMM0..XMM7 (another 8, .. XMM15 in 64bit)
- Enabled 128-bit (4x32bit) SIMD FP support:
 - arithmetic, comparison, shuffle, ...
 - Integer SIMD support over 64 bits
 - Over 60 new instructions



SSE4 part of a set of instructions ...

Instruction	Description
PEXTRB r32/m8, xmm, imm8	Extract Byte
PEXTRD r/m32, xmm, imm8	Extract Dword
PEXTRQ r/m64, xmm, imm8	Extract Qword
PEXTRW r/m16, xmm, imm8	Extract Word
PHMINPOSUW xmm1, xmm2/m128	Packed Horizontal Word Minimum
PINSRB xmm1, r32/m8, imm8	Insert Byte
PINSRD xmm1, r/m32, imm8	Insert Dword
PINSRQ xmm1, r/m64, imm8	Insert Qword
PMAXSB xmm1, xmm2/m128	Maximum of Packed Signed Byte Integers
PMAXSD xmm1, xmm2/m128	Maximum of Packed Signed Dword Integers
PMAXUD xmm1, xmm2/m128	Maximum of Packed Unsigned Dword Integers
PMAXUW xmm1, xmm2/m128	Maximum of Packed Unsigned Word Integers
PMINSB xmm1, xmm2/m128	Minimum of Packed Signed Byte Integers
PMINSD xmm1, xmm2/m128	Minimum of Packed Signed Dword Integers
PMINUD xmm1, xmm2/m128	Minimum of Packed Unsigned Dword Integers
PMINUW xmm1, xmm2/m128	Minimum of Packed Unsigned Word Integers
PMOVSXBD xmm1, xmm2/m32	Packed Move with Sign Extend - Byte to Dword
PMOVSXBQ xmm1, xmm2/m16	Packed Move with Sign Extend - Byte to Qword



Example: MPSADBW


 MPSADBW sums the absolute difference of 4 unsigned bytes, selected by bits [0:1] of the immediate byte (third operand), from the source (second operand) with sequential groups of 4 unsigned bytes in the destination operand. The first group of eight sequential groups of bytes from the destination operand (first operand) start at an offset determined by bit 2 of the immediate. The operation is repeated 8 times, each time using the same source input but selecting the next group of 4 bytes starting at the next higher byte in the destination. Fach 16-bit sum is written to dest.



Example: MPSADBW (2)

Department of Control and Computer Engineering

MPSADBW xmm1, xmm2/m128, imm8





Optimization example (BlockMatch4x4)

Unoptimized code

SSE2 optimized

SSE4 optimized




Example of acceleration

Code Sample	Cycles / Block SAD	Speedup		
4x4 Block				
C++	54.84	1.0		
SSE2	4.32	12.7		
Intel SSE4	2.71	20.2		
8x8 Block				
C++	180.55	1.0		
SSE2	25.29	7.1		
Intel SSE4	6.73	26.8		
16x16 Block				
C++	173.01	1.0		
SSE2	71.42	2.4		
Intel SSE4	26.86	6.4		



Acceleration

Department of Control and Computer Engineering





SIMD intrinsics

- Intel Intrinsics Guide
- Functions similar to C
 - Enable intel instructions to be performed
 - MMX, SSEx, AVXx, FMA, KNL, SVML
- Example

```
m128d mm acos pd ( m128d a)
#include "immintrin.h"
CPUID Flags: SSE
```

Compute the inverse cosine of packed doubleprecision (64-bit) floating-point elements in a expressed in radians, and store the results in dst.




SIMD intrinsics (2)


Technology	Header
MMX	mmintrin.h
SSE	xmmintrin.h
SSE2	emmintrin.h
Itanium	ia64intrin.h ia64regs.h




SIMD intrinsics (3)


Department of Control and Computer Engineering







$$C = A[0] * B[0] + A[1] * B[1] + ... + A$$





SIMD conclusion

Department of Control and Computer Engineering

- SIMD extensions bring significant performance improvements
- Unfortunately, using SIMD requires tremendous knowledge and time but results in extremely efficient code
- New versions of SIMD lead to ever better results
- But SIMD also has its limits What next?



Amdahl law


- Execution time of a program P is t
- Part of the program (marked with Q) with ratio p can be parallelized (speed-up) N times
- What is the speed-up of the whole program (U)?

Amdahl law:

$$U = \frac{t}{t'} = \frac{t}{t\left((1-p) + \frac{p}{N}\right)} = \frac{1}{\left(1-p + \frac{p}{N}\right)}$$


If
$$N \to \infty$$

$$U pprox rac{1}{1-p}$$





Amdahl law (2)



P = parallel portion of the process

N = number of processors

 O_N = parallel overhead in using N threads

- Speedup (in croatian Ubrzanje) $U(N) = T_{total}/T_{parallel}(N)$
 - Scalability $S = T_{total} / T_{parallel} (\infty)$
 - Assuming N=∞ I O_N=0
 - Parallel efficiency PE(N) = U(N)/N*100%